

## VSE/ESA Hot Topics

Cyrus Mead IV  
WAVV 2003 Conference  
Winston-Salem NC  
April 25-29, 2003



---

---

---

---

---

---

---

---

## Objectives

- Provide you with useful tips you can take home and use
- Get you to share your tips with the rest of us
  - Note: The topics covered in this presentation assume no vendor products are being used, just a standard IBM VSE/ESA system



---

---

---

---

---

---

---

---

## SIR Command

- AR command SIR
- Produces a System Information Report on the console
- Well known, but undocumented



---

---

---

---

---

---

---

---

## SIR Command Output

```
sir
AR 0015 CPUID = 0000000174900000
AR 0015 PROC-MODE = ESA IPL(250) 14:05:40 03/20/2003
AR 0015 SYSTEM = VSE/ESA 2.6.0 GA 10/29/2001
AR 0015 VSE/AF 6.6.0 GA-LEVEL 10/15/2001
AR 0015 VSE/POWER 6.6.0 DY-BASE 09/19/2001
AR 0015 IPL-PROC = $IPLESA JCL-PROC = $$JCL
AR 0015 SUPVR = $$S$SUPX TURBO-DISPATCHER (30) ACTIVE
AR 0015 HARDWARE COMPRESSION ENABLED
AR 0015 SEC. MGR. = BASIC SECURITY = ONLINE
AR 0015 CPU-ADDR. = 0000(IPL) ACTIVE
AR 0015 ACTIVE = 0011:17:05.774 WAIT = 0695:09:07.051
```



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-4

---

---

---

---

---

---

---

---

---

---

## SIR Command Output

```
AR 0015 PARALLEL= 0004:27:50.744 SPIN = 0000:00:00.000
AR 0015 CPU timings MEASUREMENT INTERVAL 0790:55:01.332
AR 0015 TASKS ATT.= 00047 HIGH-MARK = 00053 MAX = 00180
AR 0015 DYN.PARTS = 00002 HIGH-MARK = 00003 MAX = 00032
AR 0015
AR 0015 COPY-BLKS = 00003 HIGH-MARK = 00043 MAX = 01500
AR 0015 CHANQ USED= 00009 HIGH-MARK = 00013 MAX = 00223
AR 0015 LBL.-SEGM.= 00010 HIGH-MARK = 00011 MAX = 00717
AR 0015 PGIN TOT.= 00000000001 EXP.AVRGE.= 0000000000/SEC
AR 0015 PGOUT TOT.= 0000000000
AR 0015 UNC.= 00000000000 EXP.AVRGE.= 0000000000/SEC
AR 0015 PRE = 00000000000 EXP.AVRGE.= 0000000000/SEC
AR 0015 LOCKS EXT.= 00000000540 LOCKS INT.= 0000002727
AR 0015 FAIL = 00000000040 FAIL = 00000000000
AR 0015 LOCK I/O = 00000000000 LOCK WRITE= 00000000000
AR 0015 1140I READY
```



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-5

---

---

---

---

---

---

---

---

---

---

## SIR COMMAND

- What else will it do?
- Actually, quite a bit.
- Find out with the command SIR ?



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-6

---

---

---

---

---

---

---

---

---

---

## SIR Help

sir ?  
AR 0015 SIR COMMAND HELP  
AR 0015 SIR (<RESET|SYS>) RESET/DISPLAY SYSTEM INFO  
AR 0015 SIR SMF((VSE)=<ON|OFF|cuu-) SUBSYSTEM MEASUREMENT DATA  
AR 0015 SIR MON(=<<id|ON,(NOSYM)|OFF>-(option)) MONITORING DATA  
AR 0015 SIR MIH(=<nnnnnn|ON|OFF>) DISPLAY/CHANGE MIH SETTING  
AR 0015 SIR CHPID(=chpid) DISPLAY CHPID INFORMATION  
AR 0015 SIR VENDOR DISPLAY VENDOR PRODUCT INF  
AR 0015 SIR CRWMSG(=<ON|OFF>) DSPLY/CHANGE CRW MSG-REPORTING



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-7

---

---

---

---

---

---

---

---

---

---

## SIR COMMAND

- SIR SYS displays current counters and SIR RESET resets them
- SIR SMF, when on displays I/O statistics
- SIR MON when activated produces SVC statistics
- SIR MIH displays current setting for MIH  
If can be used to set it ON or OFF and to change the interval.



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-8

---

---

---

---

---

---

---

---

---

---

## SIR COMMAND

- SIR CHPID sounds useful but I haven't tested it (no CHPIDs)
- SIR VENDOR lists vendor products (including IBM) which are registered and any exits in use
- SIR CRWMSG enables or disables channel reporting messages



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-9

---

---

---

---

---

---

---

---

---

---

## SIR Command

- So the SIR command actually allows access to quite a bit of performance related information.
- But before you start depending on it, reflect that SIR is somewhat undocumented and therefore subject to change



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-10

---

---

---

---

---

---

---

---

## Changing Partition Size

- Changing a static partition
  - PSTOP the partition to VSE/POWER

```
pstop f5
AR 0015 1C39I COMMAND PASSED TO VSE/POWER
F5 0001 1Q33I STOPPED F5
F5-0005 1I00D READY FOR COMMUNICATIONS.
```
  - UNBATCH the partition to VSE

```
5 unbatch
```
  - Re-alloc the partition and define default size

```
alloc f5=0m
alloc f5=2m
size f5=1m
```



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-11

---

---

---

---

---

---

---

---

## Changing Partition Size

- Changing a static partition...
- PSTART the partition to VSE/POWER
  - You **must** know in advance the spool devices and classes to specify

```
s F5,h5
AR 0015 1C39I COMMAND PASSED TO VSE/POWER
F1 0001 1R86I PLEASE SPECIFY DEVICES TO BE
SPOOLED
F1-0001 1R50D F5 READER=
1 fec
F1-0001 1R50D F5 PRINTERS=
1 fee
F1-0001 1R50D F5 PUNCHES=
1 fed
F5-0005
```



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-12

---

---

---

---

---

---

---

---

## Changing Partition Size

- Changing a static partition...
- Assign system logical units in the partition

```
5 assgn syslst,fee
F5-0005
5 assgn syspch,fed
F5-0005
5 assgn sysrdr,fec
F5-0005
```



Copyright © 2003 i!lustrO Systems International, LLC

WAVV2003-13

---

---

---

---

---

---

---

---

## Changing Partition Size...

- Changing a static partition...  
Re-establish standard assigns, labels etc

```
5 exec proc=$$jcl
F5 0005 // JOB STARTF5
          DATE 04/22/2003, CLOCK 12/10/22
F5 0005 1N901 EOP WAS FORCED BY EOJ
F5 0005 EOP $$JCL
F5-0005 EOJ STARTF5
          DATE 04/22/2003, CLOCK 12/10/24, DURATION
          00/00/01
```

- You are done! Tedious, wasn't it!



Copyright © 2003 i!lustrO Systems International, LLC

WAVV2003-14

---

---

---

---

---

---

---

---

## Changing Partition Size

- Automating the process for a static partition  
Put a job out in the POWER/VSE RDR queue  
to perform all the above commands with  
DTRATTN i.e.

```
* $$ JOB JNM=ALLOCF4.DISP=H,CLASS=6
// JOB ALLOCF5
// EXEC DTRATTN,PARM='PSTOP F5'
// EXEC DTRATTN,PARM='5 UNBATCH'
etc. etc.
/&
* $$ EOJ
```



Copyright © 2003 i!lustrO Systems International, LLC

WAVV2003-15

---

---

---

---

---

---

---

---

## Changing Partition Size...

- ❑ **Changing a dynamic partition**
- ❑ Using IUI, Update Dynamic Class Table with new data
  - DTR\$DYNC or user-specified suffix
  - Need to change Dynamic Space GETVIS value also?
- ❑ Load updated table

```
pload dync
AR 0015 1C39I COMMAND PASSED TO VSE/POWER
F1 0001 1Q6AI ***** ACTIVE DYNAMIC CLASS TABLE
DTR$DYNC.Z *****
F1 0001 1Q6AI CLS STATE ACT/MAX ALLOC SIZE SP-GETV
F1 0001 1Q6AI C ENAB 0 9 1M 500K 128K STDPREF
F1 0001 1Q6BI DYNAMIC CLASS TABLE LOADED SUCCESSFULLY
```



Copyright © 2003 iIllustrro Systems International, LLC

WAVV2003-16

---

---

---

---

---

---

---

---

## Changing Partition Size...

- Things to think about...
  - ❑ The procedures for changing a static partition are tedious and error prone. They are basically for emergency use only.
  - ❑ Furthermore they are temporary unless you update the IPL procs
  - ❑ In many cases it is easier to just IPL
  - ❑ The procedures for changing a dynamic partition are easier and permanent



Copyright © 2003 iIllustrro Systems International, LLC

WAVV2003-17

---

---

---

---

---

---

---

---

## VSE/POWER

- Little known Autostart SET commands
  - ❑ SET CONFIRM=power command  
Prevents processing of accidentally entered POWER commands

For example: require confirm for "PEND"  
IQZ3D PROCESS PEND? CONFIRM WITH  
'YES' ELSE 'NO'



Copyright © 2003 iIllustrro Systems International, LLC

WAVV2003-18

---

---

---

---

---

---

---

---

## VSE/POWER

- Little known Autostart SET commands...

- SET IR33D=FLUSH|IGNORE

IR333D is issued when incorrect JECL is submitted. The Operator must reenter the entire JECL card correctly (and he generally doesn't know what to enter)

With FLUSH the entire job is flushed and put on hold.

With IGNORE the card is bypassed



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-19

---

---

---

---

---

---

---

---

## VSE/POWER

- Little known Autostart SET commands...

- SET NORUN=YES

Prevents active jobs from running after a system failure. DISP is changed to X during autostart.

Automatic PAUSE is issued for any static partition with a DISP X job.

\* \$\$ JOB NORUN=IGN bypasses this for jobs that you always want to run after a failure, i.e. VTAM



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-20

---

---

---

---

---

---

---

---

## VSE/POWER

- Little known Autostart SET commands...

- SET LONGCMD=power-command

Keeps POWER from accepting short forms of selected commands which may be entered by mistake e.g. "L RDR,ALL"  
Multiple SET LONGCMDs may be specified.

But short form commands can still be used by DTRATTN or other programs



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-21

---

---

---

---

---

---

---

---

## VSE/POWER

- Little known Autostart SET commands...
  - SET AUTONAME=FLUSH|HOLD  
Prevents jobs without valid \* \$\$ JOB or // JOB cards from running.
- They are probably seriously wrong anyway.
- FLUSH deletes the job  
HOLD leaves it in the RDR on hold



Copyright © 2003 iIllustrro Systems International, LLC

WAVV2003-22

---

---

---

---

---

---

---

---

---

---

## VSE POWER...

- Manage queue entries by USER or UINF
    - Valid for PALTER, PDELETE, PHOLD, and PRELEASE commands
- ```
d lst.zwebcnfg,full=yes
AR 0015 1C39I COMMAND PASSED TO VSE/POWER
F1 0001 1R46I LIST QUEUE P D C S PAGES CC FORM B
F1 0001 1R46I ZWBCNFG 03324 3 D A 3 1 TO=(JEL1)
FROM=(JEL1)
F1 0001 D=03/20/2003 U=ABCD 'DBGP=000001 L=0000000
F1 0001 QNUM=00673
d lst.cuinf=abcd
AR 0015 1C39I COMMAND PASSED TO VSE/POWER
F1 0001 1R46I LIST QUEUE P D C S PAGES CC FORM B
F1 0001 1R46I ZWBCNFG 03324 3 D A 3 1 TO=(JEL1)
FROM=(JEL1)
I lst.cuinf=abcd
AR 0015 1C39I COMMAND PASSED TO VSE/POWER
F1 0001 1R88I OK : 1 ENTRY PROCESSED BY L LST,CUINF=ABCD
```



Copyright © 2003 iIllustrro Systems International, LLC

WAVV2003-23

---

---

---

---

---

---

---

---

---

---

## Read-Only DASD volumes

- The supported way to do this is with ADD cuu,dev-type, SHR and the lock file
- This works fine, but can mean lots of I/Os against the lock file
- However there is another undocumented way to get the same result.



Copyright © 2003 iIllustrro Systems International, LLC

WAVV2003-24

---

---

---

---

---

---

---

---

---

---



## Read-Only DASD Volumes...

- ADD cuu,dev-type,READ
  - Prefixes a MODE SET to each CCW string to inhibit writes.
  - Overhead is quite low, but be aware that any program that tries to write on the volume will cancel



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-25

---

---

---

---

---

---

---

---

## Now It's Your TURN

- Does anybody else have any tips they would like to contribute?



Copyright © 2003 iIllustro Systems International, LLC

WAVV2003-26

---

---

---

---

---

---

---

---

This document was created with Win2PDF available at <http://www.daneprairie.com>.  
The unregistered version of Win2PDF is for evaluation or non-commercial use only.