

Automated Tape Allocation Manager
for z/OS and OS/390



User's Guide

Version 1 Release 1

Automated Tape Allocation Manager
for z/OS and OS/390



User's Guide

Version 1 Release 1

Note!

Before using this information and the product it supports, be sure to read the general information under notices.

Second Edition (September 2002)

This edition applies to Version 1, Release 1 of IBM Automated Tape Allocation Manager for z/OS and OS/390 (product number 5697-H62) and to all subsequent releases and modifications until otherwise indicated in new editions.

© Copyright International Business Machines Corporation 2001. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About this book	v	Job Activity report	28
Who should read this book	v	Display columns for Job Activity report	29
Conventions and terminology used in this book	v	Allocation Activity report	30
How this book is organized	v	Display columns for Allocation Activity report ...	31
		Failed Allocations report	32
		Display columns for Failed Allocations report ...	32
Summary of Changes	vii		
Chapter 1. Automated Tape Allocation Manager	1	Appendix A. Operator Commands	35
		Display Commands	35
		Dynamic Configuration Commands	36
Chapter 2. Configuring Automated Tape Allocation Manager	3	Appendix B. The ATAM PARMLIB Member .	39
Customization summary	3	Entering tape selection and exclusion commands	39
Customizing Automated Tape Allocation Manager ...	3	Sample PARMLIB member	39
Step 1: Check requirements	3	Syntax rules	39
Step 2: Create the VSAM control file	4	Specifying the member name read by ATAM at start-up .	40
Step 3: Create the log file	5	Common Questions	40
Step 4: Customize and initiate the started task JCL .	5		
Step 5: Access Automated Tape Allocation Manager	6	Appendix C. VTS load balancing exit ...	41
Step 6: Configure MVS system parameters	9	Modifying storage class and group names	41
Step 7: Configure Automated Tape Allocation Manager	11	Disabling VTS load balancing	43
Step 8: Stop and restart the started task	13		
		Appendix D. Volser-to-Unit Preferencing Exit	45
Chapter 3. Current Allocation Status ...	15	Modify ATH#VALD	45
Accessing the Current Status screen	15	Assemble and link ATH#VALD	45
Display fields	16	Enabling ATH#VALD for use	45
Line command	17	Disabling ATH#VALD	45
Optional commands	18		
Reviewing allocation activity	19	Appendix E. Error Messages from ISPF .	47
Display fields	19		
Optional commands	20	Appendix F. Error Messages from the ATAM Started Task	51
Chapter 4. Activity Reporting	23	Appendix G. Notices	57
Common Fields	23	Trademarks	59
Common Commands	23		
FIND	23	Index	61
SORT	24		
PRINT	24		
Accessing the Activity Reporting option	25		
All Activity report	26		
Display columns for All Activity report	26		

About this book

This book describes how to use Automated Tape Allocation Manager for z/OS and OS/390 to maximize usage of costly tape units across images to minimize wait time and maximize availability. The book contains detailed information, such as field descriptions, sample JCL, and line commands, to help the user of Automated Tape Allocation Manager to fully benefit from the use of this product.

Who should read this book

The *Automated Tape Allocation Manager User's Guide* is intended for systems programmers and administrators who understand the issues relating to sharing system resources and offline storage. The authors of this book assume that the readers are data processing professionals familiar with MVS and its conventions.

Conventions and terminology used in this book

In this book, Automated Tape Allocation Manager for z/OS and OS/390 is referred to as "Automated Tape Allocation Manager" or simply as "ATAM" where the context makes the meaning clear. Other conventions include:

- Monospaced font - Identifies example code and line commands
- **Bold font** - Identifies the names of fields

How this book is organized

This book is divided into the following chapters:

- Chapter 1, *Automated Tape Allocation Manager*, provides a general description of how ATAM can benefit your organization.
- Chapter 2, *Configuring Automated Tape Allocation Manager*, walks through all of the steps that must be performed to customize ATAM for your environment.
- Chapter 3, *Current Allocation Status*, explains how to use the Current Status option to check the level of activity of your tape drives.
- Chapter 4, *Activity Reporting*, describes the reports you can use to monitor tape drive activities.
- *Appendices*. There are several appendices that provide supplemental material for operator commands, the PARMLIB, VTS load balancing, VOLSER-to-unit preferencing, LRU device selection, and error messages.

Summary of Changes

Changes made for this edition of the book include:

- *LRU Device Selection.* ATAM now uses a process referred to as *Least Recently Used device selection* to select the tape unit to be varied online. Essentially, the tape unit that has been dormant the longest will be the first that ATAM will attempt to use. This ensures that all available tape units are used for requests, not just a few.

Least Recently Used (LRU) device selection operates by tracking the date and time that each tape unit under the control of ATAM was utilized, meaning:

- the last date and time the tape device was successfully varied online
- the last date and time the tape device was varied offline
- the last date and time a failure occurred when attempting to vary the tape device online.

By tracking all of these events, the ATAM started task can sort this date and time information to determine which tape unit to vary online when a request for a tape unit is received. The tape unit that has been dormant the longest will be the first unit that ATAM will try to use. If it is not available, ATAM will attempt to use the next one in the sorted list, and so on.

- *PARMLIB member.* The ATAM PARMLIB member allows you to create a script of valid ATAM commands that can be executed each time you start the ATAM started task. This enables you to customize ATAM to fit your particular tape unit environment. Refer to Appendix B, “The ATAM PARMLIB Member” on page 39 for details.
- *VTS load balancing.* With ATAM’s VTS load balancing feature, all of the VTS libraries are used, not just the last library. This is accomplished through ATAM’s STORCLAS ACS exit that uses a unique storage class name for each VTS library. Refer to Appendix C, “VTS load balancing exit” on page 41 for details.
- *New message command.* The “R=” command enables you to specify a message that ATAM is to automatically respond to and the reply that is to be issued, without specifying an offset number. Refer to Appendix A, “Operator Commands” on page 35 for details.
- *Volser-to-unit preferencing.* Now you can restrict one or more series of VOLSER ID’s to a specific set of tape units. Refer to Appendix D, “Volser-to-Unit Preferencing Exit” on page 45 for details.

Chapter 1. Automated Tape Allocation Manager

Getting the most out of your investment in tape drives is important to every MVS shop. You want your equipment to be up and running 24 x 7, and you want the most productive use of your drives. What you do not want is a backlog of job requests while waiting for tape drives that are sitting idle simply because they have not been freed for use. Also you do not want your drives sitting idle while owned by one MVS image when, at the same time, a job waits on another image.

Automated Tape Allocation Manager, referred to as "ATAM," solves these problems and more by handling tape unit allocations across multiple MVS images. It does so in direct response to actual user and job requests. ATAM continually checks the tape units which it has been configured to manage, and looks for opportunities to vary offline those units that are no longer in use. By doing this, ATAM frees the devices for use as new requests come in for tape units. ATAM also works the request side of tape management by instantly responding to requests for tape unit allocations without any required operator intervention.

ATAM is completely flexible and can fit any MVS environment. Tuning and configuration parameters can be established that fit your environment. They can also be dynamically changed to accommodate changes in work load and priorities without any need to undergo an outage in the product's operation. A complete set of ISPF-based panels is provided that enables you to easily establish your ATAM configuration. These panels include online help to ease the setup procedure.

From a reporting standpoint, ATAM also provides many advantages. Available reports include:

- All recorded tape unit activity
- Tape activity by job and step
- Usage by tape unit
- A record of failed automatic allocations

These reports can be tailored by the use of common commands, such as SORT, FIND, and PRINT.

In addition to detailed reporting, you also have the ability, through the ISPF interface, to quickly and easily access the state of your tape units and ATAM. The Current Status display provides you a quick and easy way to see what is in use, what is idle, and how it is being used.

With the detailed reports, as well as the ability to easily look at your current status, you have the information you need to assess if your tape units are being fully utilized. The detailed reports can tell you when a tape drive was allocated to a job and if the job had to wait for a drive. With this detail, you can not only respond to your customers quickly, but you can also see bottlenecks and configure accordingly.

The bottom line is that ATAM streamlines and automates your tape unit management, and reduces or eliminates the need for operator intervention in tape unit allocation. It optimizes the availability of your hardware and promotes efficiency. It does not force a method for "doing business" on you, but rather is flexible enough to tailor to meet your specific requirements. Most of all, it shortens the return on investment (ROI) in your hardware.

Chapter 2. Configuring Automated Tape Allocation Manager

Follow the installation instructions in the Program Directory. Once you have installed Automated Tape Allocation Manager for z/OS and OS/390, referred to as "ATAM" in this chapter, you must customize it before you can use it.

Customization summary

After you install ATAM, you must tailor some files for your system. The following steps configure your system.

Step	Description	Reference
1	Check the microcode level and authority requirements for the load library.	"Step 1: Check requirements"
2	Create the VSAM control file.	"Step 2: Create the VSAM control file" on page 4
3	Create the log file.	"Step 3: Create the log file" on page 5
4	Customize and initiate the started task JCL.	"Step 4: Customize and initiate the started task JCL" on page 5
5	Run the CLIST to go to the main menu.	"Step 5: Access Automated Tape Allocation Manager" on page 6
6	Specify each MVS system and libraries.	"Step 6: Configure MVS system parameters" on page 9"
7	Specify parameters for each MVS system.	"Step 7: Configure Automated Tape Allocation Manager" on page 11
8	Stop and restart the started task.	"Step 8: Stop and restart the started task" on page 13

Customizing Automated Tape Allocation Manager

After you have installed ATAM, follow these steps to tailor some of the files for your system.

Step 1: Check requirements

Before using ATAM, check to ensure that the following requirements have been met:

- The load library containing ATAM must be APF authorized.
- If you are using the Virtual Tape Server (VTS) make sure your microcode level is current. If you have a problem using VTS with ATAM, it may be due to an older level of microcode. Contact IBM for information on the current microcode level.
- Make sure the devices you want ATAM to manage are defined as auto-switchblade.

Contact your systems administrator if you encounter difficulties starting ATAM.

Step 2: Create the VSAM control file

You must create a VSAM control file for each MVS image where ATAM will be running. The control file holds the configuration information for ATAM. To create a VSAM control file, edit member ATHCNTFL in your SATHSAMP library and submit it. This JCL creates the configuration VSAM file. The sample JCL and instructions for changing it are shown below:

```
//STEP1 EXEC PGM=IDCAMS
//SYSPRINT DD SYSOUT=*
//SYSOUT DD SYSOUT=*
//SYSUT1 DD *
DUMMY RECORD TO SATISFY VSAM REQUIREMENT FOR A NON-EMPTY INITIAL FILE.
/*
//SYSIN DD *
DELETE 'ATH.V1R1.CONTROL'

SET MAXCC = 0

DEFINE CLUSTER -
    ( NAME ('ATH.V1R1.CONTROL') -
    CYLINDERS (1 1) -
    SHAREOPTIONS (2 3) -
    INDEXED -
    RECORDSIZE (1024 1024) -
    KEYS (32 0) -
    REUSE ) -
    DATA ( NAME ('ATH.V1R1.CONTROL.DATA')) -
    INDEX ( NAME ('ATH.V1R1.CONTROL.INDEX'))

REPRO INFILE(SYSUT1) OUTDATASET('ATH.V1R1.CONTROL') REUSE
```

JCL Portion	Modification
NAME	Change the highlevel qualifier in the CONTROL data set name to meet your site's standards. In the example, the data set name is ATH.V1R1.CONTROL, where ATH.V1R1 is the highlevel qualifier.
DATA	Change the highlevel qualifier in the DATA data set name to meet your site's standards. In the example, the data set name is ATH.V1R1.CONTROL.DATA, where ATH.V1R1 is the highlevel qualifier.

JCL Portion	Modification
INDEX	Change the highlevel qualifier in the INDEX data set name to meet your site's standards. In the example, the data set name is ATH.V1R1.CONTROL.INDEX, where ATH.V1R1 is the highlevel qualifier.
OUTDATASET	Use the same highlevel qualifier and data set name that you entered for the NAME line. In the example, the data set name is ATH.V1R1.CONTROL, where ATH.V1R1 is the highlevel qualifier.

Note: If ATAM is controlling tape drives that are shared among multiple MVS systems, control files and log files can be placed on a common DASD that is shared among all of the systems that use the tape drives. The only criteria is that there must be an ATAM started task for each MVS image (OS/390 or z/OS).

Step 3: Create the log file

A log file is required for ATAM. The JCL for generating the log file is in member ATHLOGF in the SATHSAMP library. The sample JCL and instructions for changing it are shown below:

```
//LOGF EXEC PGM=IEFBR14
//LOGFILE DD DSN=ATH.V1R1.LOGFILE,DISP=(NEW,CATLG,DELETE),RECFM=FB,
// UNIT=SYSDA,LRECL=260,BLKSIZE=27820,SPACE=(27820,(200,50))
```

JCL Portion	Modification
LOGFILE DD DSN	Type the data set name of the log file, changing the highlevel qualifier to meet your site's naming standards. In the sample JCL, the data set name is ATH.V1R1.LOGFILE, where ATH.V1R1 is the highlevel qualifier.
UNIT	Type the unit name. In the example, the unit is SYSDA.

Step 4: Customize and initiate the started task JCL

The sample JCL procedure for the started task is in the highlevel.SATHSAMP library, member name ATHPROC. Edit this member and add it to MVS for started tasks initiation. The default procedure name is ATHPROC. The sample JCL is shown below:

```
//ATAM EXEC PGM=ATH#MAIN,TIME=1440
//STEPLIB DD DSN=ATH.V1R1.SATHLOAD,DISP=SHR
//LOGFILE DD DSN=ATH.V1R1.LOGFILE,DISP=SHR
//ATHPARMS DD DSN=ATH.V1R1.CONTROL,DISP=SHR
```

You must customize the sample JCL to work in your environment. The changes are:

JCL Portion	Modification
STEPLIB DD	<p>Type the data set name of the installed load library for ATAM. If you do not specify a load library, the default is SATHLOAD. In the sample JCL, the data set name is ATH.V1R1.SATHLOAD.</p> <p>Note: Check that the highlevel qualifier listed here is the same as the highlevel qualifier used in the VSAM control file and the log file.</p>
LOGFILE DD	<p>Type the data set name of the log file. In the sample JCL, the data set name is ATH.V1R1.LOGFILE.</p> <p>Note: The LOGFILE data set may have been allocated when ATAM was installed. If not, create the LOGFILE by following the instructions in “Step 3: Create the log file” on page 5.</p>
ATHPARMS DD	<p>Type the data set name of the ATHPARMS. In the sample JCL, the data set name is ATH.V1R1.CONTROL.</p> <p>Note: The ATHPARMS data set may have been allocated when ATAM was installed. If not, create the data set by following the instructions in “Step 2: Create the VSAM control file” on page 4.</p>

When you are finished with customizing the JCL for the started task, you are ready to configure ATAM for its first use as described in the following sections.

Note: Do not attempt to start the started task until you have completed the configuration process, including specifying an Exit Library, or the started task will fail.

Step 5: Access Automated Tape Allocation Manager

To access ATAM, run the CLIST. However, you must first tailor the two CLISTs found in the SATHSAMP library, which are ATH and ATHCLIST, to work in your environment. The sample CLIST is shown below along with instructions on how to change it.

The sample CLIST in the ATH member of SATHSAMP is the following:

```

PROC 0 CLISTLIB(ATH.V1R1.SATHSAMP)

CONTROL NOMSG

FREE FILE(ATHCLIST)

CONTROL MSG

ALLOC FILE(ATHCLIST) DATASET('&CLISTLIB') SHR REU

ALTLIB ACTIVATE APPLICATION(CLIST) FILE(ATHCLIST)

```



```
ISPEXEC SELECT CMD(ATHCLIST) NEWAPPL(ATH) PASSLIB
```

```
ALLLIB DEACTIVATE APPLICATION(CLIST)
```

```
FREE FILE(ATHCLIST)
```

CLIST Line	Modification
PROC 0 CLISTLIB()	<p>Type the high level qualifier of your installed ATAM libraries, followed by the name of the sample library. In the sample CLIST, the PROC line is:</p> <pre>PROC 0 CLISTLIB(ATH.V1R1.SATHSAMP)</pre> <p>In this example, ATH.V1R1 is the highlevel qualifier and SATHSAMP is the sample library.</p> <p>Note: The high level qualifier used in the CLIST must match the one used with the VSAM control data set, the ATAM load library, and the log file.</p>

The second sample CLIST, ATHCLIST, is shown below:

```
PROC 0 PRDLIB(ATH.V1R1)
```

```
CONTROL NOMSG
```

```
FREE FILE(ATHPARMS)
```

```
FREE FILE(LOGFILE)
```

```
CONTROL MSG
```

```
ISPEXEC LIBDEF ISPMLIB DATASET ID('&PRDLIB..SATHMENU') COND STACK
```

```
ISPEXEC LIBDEF ISPLLIB DATASET ID('&PRDLIB..SATHPENU') COND STACK
```

```
ISPEXEC LIBDEF ISPLLIB DATASET ID('&PRDLIB..SATHLOAD') COND STACK
```

```
ALLOC FILE(ATHPARMS) DA('ATH.V1R1.CONTROL') SHR REUSE
```

```
ALLOC FILE(LOGFILE) DA('ATH.V1R1.LOGFILE') SHR REUSE
```

```
ATH$MAIN
```

You must customize the sample CLIST to work in your environment. The changes are:

CLIST Line	Modification
PROC 0 PRDLIB	Type the high level qualifier in between the parentheses. The sample CLIST uses ATH.V1R1 for the highlevel qualifier. Note: The high level qualifier used in the CLIST must match the one used with the VSAM control data set, and with the ATAM load library and log file.
ATHPARMS	Type the data set name of the VSAM control file in between the parentheses. In the sample CLIST, the line containing the ATHPARMS data set is ALLOC FILE(ATHPARMS) DA(ATH.V1R1.CONTROL), where ATH.V1R1 is the highlevel qualifier.
LOGFILE	Type the data set name of the log file in between the parentheses. In the sample CLIST, the line containing the LOGFILE data set is ALLOC FILE(LOGFILE) DA(ATH.V1R1.LOGFILE), where ATH.V1R1 is the highlevel qualifier. Note: The LOGFILE referred to in the CLIST is the LOGFILE that the started task for ATAM uses to record its activity. The LOGFILE in the CLIST is usually the same one used listed in the started task. If not, the LOGFILE must be concatenated with the other previously allocated log files.

When you are done modifying the ATHCLIST member, copy this member to your system CLIST library.

When you run the CLIST, the ATAM main menu appears. The main menu is shown below:

```

ATH$MAIN ----- Automated Tape Allocation Manager for z/OS and OS/390 -----
Option ==> _____

      1 Current Status                               User ID: myuserid
      2 Activity Reporting                           Date...: 2001/12/14
      S Setup and Configuration                       Release: V1R1

      A About Automated Tape Allocation Manager
      X Exit Automated Tape Allocation Manager

```

Step 6: Configure MVS system parameters

The first time you run ATAM, you must set some general MVS configuration options, then provide specific parameters for each MVS image on which ATAM will operate. These configuration settings control the way that ATAM runs and how it varies tape devices on and offline. You can control your tape allocation activity, tailoring your methods to meet your specific needs.

To configure general MVS options, follow these steps:

1. Type **S** and press Enter to access the ATAM Setup screen.

```
-----ATAM Setup-----
Command ==>

Control Dataset Name ==> ATP.SAMPLE.CONTROL

MVS Info:

MVS System ID      ==> ABCD      (1-4 Character System ID)

Valid command selection values are:

1: MVS Specific Information
2: ATAM Configuration Parameters
```

2. Type an **MVS System ID** as described below:

Field	Description
Control Dataset Name	(Display only) This is the name of the control data set that was established at installation. You cannot change this field.
MVS System ID	Type the one- to four-character ID of the MVS system on which you want to perform tape allocation activities.

Command line values

Type a valid code in the Command line to display one of the lower level screens. Valid values are:

Value	Description
1	Type 1 to enter information specific to a particular MVS system, including the load library information.
2	Type 2 to enter information for tape allocation processing, such as the amount of time or the number of times to perform activities.

MVS specific information

To update information for a specific MVS system, type **1** in the Command line on the ATAM Setup screen and press Enter. The Update Parameters for MVS System *ssid* screen appears.

```

----- Update Parameters for MVS System ABCD -----
Command ==>

Enter or Update Specific MVS Parameters :

ATAM Parameter Member   ==>
Exit Load Library       ==>
  
```

Enter the following MVS system parameters:

Parameter	Description
ATAM Parameter Member	Type the one- to eight-character name of the PARMLIB member that contains optional startup commands for ATAM. The member name in the sample JCL is ATHPARMS. You must provide a name in this field even if the member does not exist. If a member does exist, it must be located in a data set available to the current PARMLIB concatenation. Note: For more information on the PARMLIB member, refer to Appendix B, "The ATAM PARMLIB Member" on page 39.
EXIT Load Library	Type the data set name of the load library that contains the ATAM exit. This is usually the same load library that is used in the STEPLIB DD in the started task JCL for ATAM. The default name for the EXIT Load Library field is SATHLOAD. In the sample JCL for the started task, member ATHPROC, the STEPLIB DD data set name is highlevel.SATHLOAD.

Note: You must specify an EXIT load library and press Enter to update the control file *before* you start the started task. Otherwise, the started task will fail to start.

Press Enter, then PF3 to exit this screen and return to the ATAM Setup screen.

Step 7: Configure Automated Tape Allocation Manager

To enter parameters for ATAM, type **2** in the Command line on the ATAM Setup screen and press Enter. The ATAM Configuration screen appears.

```

ATHPNL2  V1R1 ----- ATAM Configuration ----- 2002/07/17 15:05:14.90
Option ==> _____

MVS ID: RS01
-----

Operational Mode: 1 1) Active 2) Passive
-----

Offline Unit Polling Interval..... 030 Seconds
Online Unit Polling Interval..... 005 Seconds
Online Unit Iteration Count..... 0056 Iterations
Reconfiguration Termination Limit..... 015 Dynamic Changes
Vary Online Wait Time..... 030 Seconds
Vary Online Maximum Attempts..... 0020 Attempts

Surround WTOR Responses in Quotes..... (Y or N)

Press ENTER to save, END to exit.

```

This screen allows you to tailor the process for allocating tape drives. There are several options you can specify to customize how tape drives are varied online or offline.

Operational parameter

The **Operational Mode** field allows you to set the method for allocation that you want ATAM to perform. Select one of the following modes:

Operational Mode	Description
Active	Type 1 to indicate that you want ATAM to automatically vary tape drives online in response to demands for tape drive units.

Operational Mode	Description
Passive	Type 2 to indicate that you want ATAM to continually check for drives that are not being used and return them to "free" status (selectable and unallocated). In passive mode, ATAM will not attempt to vary a tape unit online.

ATAM configuration parameters

The ATAM configuration parameters are described below. The first time you use this screen, the default values appear in the fields.

Parameter	Description
Offline Unit Polling Interval	Enter a number between 001 and 999 to indicate the number of seconds to wait between attempts to see if a device is available to be varied offline or is still offline. The default is 30 seconds.
Online Unit Polling Interval	Enter a number between 000 and 999 to indicate the number of seconds to wait between attempts to vary an online device to offline. The default is 5 seconds.
Online Unit Iteration Count	Enter a number between 0000 and 9999 to indicate the number of times to attempt to see if a device can be varied offline. The default is 5 iterations. Note: It is recommended that you do not type a value of 0 for this parameter, but instead, code the value that fits your environment. If you type a 0 value in this field, ATAM will continue to attempt to find a device until it succeeds or until the started task is ended.
Reconfiguration Termination Limit	Enter a number between 001 and 999 to indicate the number of times that ATAM will tolerate dynamic IOCF reconfigurations before terminating the started task. The purpose of this limit is to conserve ECSA memory. The default limit is 15 dynamic changes.
Vary Online Wait Time	Enter a number between 000 and 999 to indicate the number of seconds that ATAM must wait between attempts to find an available tape unit, and then vary the device online. The default is 30 seconds.
Vary Online Maximum Attempts	Enter a number between 0000 and 9999 to indicate the maximum number of times that ATAM will attempt to find an available device for a job, and then vary the device online for that job. The default is 20 attempts. Note: It is recommended that you do not type a value of 0 for this parameter, but instead, code the value that fits your environment. If you type a 0 value in this field, ATAM will continue to attempt to find a device until it succeeds or until the started task is ended.
Surround WTOR Responses in Quotes	Type Y to display quote marks (") around write-to-operator messages. Otherwise, type N. The default is Y, surround responses with quotes.

Press Enter, then PF3 to exit this screen and return to the ATAM Setup screen.

If you want to return to the default settings for ATAM, type the DEFAULT, or DEF, command in the Option line. This returns the settings for the ATAM Configuration screen to their defaults.

Additional MVS Images

If you want to run ATAM on additional MVS images, you must specify customization information for each MVS image. To do this, repeat the customization process for each MVS image, starting with “Step 6: Configure MVS system parameters” on page 9 and continuing onto “Step 7: Configure Automated Tape Allocation Manager” on page 11. When you have finished customizing all the MVS images on which you want to use ATAM, go to “Step 8: Stop and restart the started task”.

Step 8: Stop and restart the started task

Once you have set your configuration parameters on the ATAM Configuration screen, you must stop and restart the started task for those settings to take effect.

To stop the started task, issue the following MVS Purge command:

```
P ATH
```

This command assumes that you kept the name of the started task as provided in the sample JCL. If you changed the name of the started task, you must use that name in the MVS Purge command to stop the task.

Notes:

1. If you decide not to stop the started task, the new configuration settings will take effect the next time the started task is stopped and started.
2. Avoid using the MVS FORCE command to terminate ATAM. Unpredictable results may occur otherwise, including the termination of active MVS systems.

To restart the started task, issue the following MVS Start command:

```
S ATH
```

Notes:

1. If the started task fails to start, check to ensure that you specified an EXIT load library on the MVS Parameters screen (option S.1 from the ATAM main menu), then press Enter to update the control file. The started task requires the name of the EXIT load library.
2. The same control file is used for both the ISPF started task and the ATAM started task.

How the started task works with Automated Tape Allocation Manager

ATAM requires a started task component that runs in its own address space. The started task establishes and provides the operating environment required by ATAM.

Note: If this started task is not available, there will be no automatic allocation of tape units.

The started task does not cause activity to occur or undesirable resource use. Once active, it services requests from users of ATAM. The majority of its activity is spent waiting for requests of this nature.

IPLs and the automatic started task

You should set up the ATAM started task to start automatically when MVS is IPLed. You can do this by adding the appropriate command to the COMMAND member within SYS1.PARMLIB. You may need to consult your MVS support personnel to use this automatic startup.

Note: You need one ATAM started task for each MVS image that is sharing tape devices.

Chapter 3. Current Allocation Status

After you have set the configuration options for your MVS systems, and stopped and restarted the started task, use the **Current Status** option to verify that Automated Tape Allocation Manager, referred to as ATAM, is working as you configured it. The **Current Status** option helps you determine the level of activity that is related to your tape drives, such as:

- the number of tape drives that are varied offline, ready for use
- the number of tape drives that are varied online, but not allocated
- the number of tape drives that are online and allocated
- the current status of each tape drive in your environment.

Accessing the Current Status screen

To access the Current Status screen, type **1** in the Option line of the ATAM main menu and press Enter. The Current Status screen appears, as shown in the following example:

```

Row 1 of 6 ----- Current Status ----- 2001/12/14 08:04:45
Option ==>                                SCROLL ==> PAGE

          ATH Service Task: ATH           Current Status: ACTIVE

          Task Started: 12/14/01         5:25:19

-----
UNITS: Discovered:      38  Selectable:    6  Online:      0
      Allocated:        0   Pending:      0

-----
USAGE:      Allocation Failures:    0  Forced Waits:    0
      Successful Allocations:      1

----- Selectable Units -----
Cmd  Unit  Selectable  Online  Allocated  Pending  Allocations
-   -   -   -   -   -   -
_   0650   Y       N       N       N       0
_   0651   Y       N       N       N       0
_   0652   Y       N       N       N       0
_   0653   Y       N       N       N       0
_   0660   Y       N       N       N       0
_   0690   Y       N       N       N       1

***** Bottom of Data *****

Valid Line Commands: (A-Allocations)

```

To refresh the current status display, simply press Enter. ATAM will obtain the current data available and display it.

Note: Do not type a line command (Cmd column) or a command in the Option line before pressing Enter to refresh the data. Otherwise, ATAM will process the command instead of refreshing the data display.

Display fields

The information on this screen is for display only.

Field	Description
ATH Service Task	The name of the started task used by ATAM for processing.
Current Status	Indicates the status of the started task: <ul style="list-style-type: none"> Active - the started task is running. Inactive - the started task is not running.

Field	Description
Task Started	Indicates the date and time that the started task was initialized. The format for the date is MM/DD/YY and the format for the time is HH:MM:SS.
Units Discovered	Indicates the number of tape units that are actually defined to this MVS system.
Units Selectable:	Indicates the number of tape units that are available for use.
Units Online	Indicates the number of tape units that are currently assigned to a job.
Units Allocated	Indicates the number of tape units that are currently allocated.
Units Pending	Indicates the number of tape units that are allocated for a job, but are not online.
Allocation Failures	Indicates the number of events for which a tape unit could not be automatically allocated.
Forced Waits	Indicates the number of times a tape request was forced to wait for an available tape unit.
Successful Allocations	Indicates the number of events that were successfully allocated.
Unit	Indicates the name of the tape drive.
Selectable	Indicates whether this specific tape drive is currently available for selection.
Online	Indicates whether this specific tape unit is currently online.
Allocated	Indicates whether this specific tape unit is currently allocated to an MVS image.
Pending	Indicates whether this tape unit is pending, but not online.
Allocations	Indicates the number of times this specific tape unit was successfully allocated on this MVS image.

Line command

There is only one valid line command for the Current Status screen:

Line Command	Description
A	Allocation - This provides a display-only screen where you can view the allocation activity for this specific tape unit. For descriptions of the fields on the Allocation Activity screen, refer to "Reviewing allocation activity" on page 19.

Optional commands

In addition to the A line command, there are commands you can enter in the Option line of the Current Status screen to find a string, sort the data, and print the current display. Each of these commands is described below.

FIND

Syntax:

```
FIND string or F string
```

Find the first occurrence of the specified string in the scrollable area of the display.

Example:

```
FIND 652
```

In the example above, the FIND command will look for the text "652" in the scrollable area of the screen. If it finds this text, for example, if "652" is the name of one of your tape units, the FIND command will place the line containing that text at the top of the scrollable area.

SORT

Syntax:

```
SORT UNIT|SELECT|ONLINE|ALLOCATED|PENDING|ALLOCS
```

Sort the rows in the scrollable area by the specified column. The sort keywords are listed in the same order as the columns on the report.

Example:

```
SORT UNIT
```

In the example above, the SORT command will sort the lines in the scrollable area based on the ID in the UNIT column.

PRINT

Syntax:

```
PRINT
```

Print the information in the scrollable area of the screen.

Example:

```
PRINT
```

Reviewing allocation activity

When you type **A** next to a specific tape unit on the Current Status screen and press Enter, the Allocation Activity screen is displayed. This screen contains display-only information about the allocations made to the tape unit you selected on the Current Status screen. The Allocation Activity screen is shown next.

```

Row 1 of 6 ----- Allocation Activity ----- 2001/12/14 09:11:16
Option ==>                                     SCROLL ==> PAGE

-----
Unit  Date      Time      Event      Job Name  Job Step  DDNAME  DSN
0690 12/12/01    4:00:10  ALLOCATE   DAILY001  STEP1    TAPE    DAILY.BKUP
0690 12/13/01    4:00:03  ALLOCATE   DAILY001  STEP1    TAPE    DAILY.BKUP
0690 12/14/01    4:00:04  ALLOCATE   WEEKLY04  STEP1    TAPE    WEEKL.BKUP
0690 12/07/01    4:00:04  ALLOCATE   WEEKLY04  STEP1    TAPE    WEEKL.BKUP
0690 12/08/01    4:00:04  ALLOCATE   DAILY001  STEP1    TAPE    DAILY.BKUP
0690 12/09/01    4:00:05  ALLOCATE   WEEKLY03  STEP1    TAPE    WEEKL.BKUP
***** Bottom of Data *****

```

Display fields

The columns on the Allocation Activity screen contain information that is for display only that you can review. The report columns are described in the following table:

Column	Description
Unit	Indicates the name of the tape unit that was used to satisfy the allocation (only valid for ALLOCATE events).
Date	Indicates the date that the event occurred. The format is MM/DD/YY.
Time	Indicates the time that the event occurred. The format is HH:MM:SS.
Event	Describes what happened for this job. Possible events are: <ul style="list-style-type: none"> ALLOCATE - The tape unit was successfully allocated for the job driving the event. ATAM Start - The started task for ATAM was started. ATAM Term - The started task for ATAM ended normally. FAIL - ATAM could not allocate a tape device for an allocation request. The MVS default option was then invoked. WAIT - An allocation request had to wait for a tape unit to become available. This same request may or may not have failed at a later time.

Column	Description
Job Name	Indicates the name of the job that is driving the request.
Job Step	Indicates the name of the job step within the job that is driving the request.
DDNAME	Indicates the DDNAME within the job step of the job that is driving the request.
DSN	Indicates the name of the data set that is either being read from or written to for this job.

Optional commands

There are three commands you can enter in the Option line of the Allocation Activity screen to find a string, sort the data, and print the current display. Each of these commands is described below.

FIND

Syntax:

FIND string or F string

Find the first occurrence of the specified string in the scrollable area of the display.

Example:

FIND 690

In the example above, the FIND command will look for the text "690" in the scrollable area of the screen. If it finds this text, the FIND command will place the line containing that text at the top of the scrollable area.

SORT

Syntax:

SORT UNIT|DATE|TIME|EVENT|JOB|STEP|DDN|DSNME

Sort the rows in the scrollable area by the specified column. The sort keywords are listed in the same order as the columns on the report. The keywords refer to the following columns:

- UNIT - Sort by the tape unit ID
- DATE - Sort by the Date column
- TIME - Sort by the Time column
- EVENT - Sort by the Event column
- JOB - Sort by the job name
- STEP - Sort by the job step name
- DDN - Sort by the DD name
- DSNME - Sort by the data set name, which is the DSN column

Example:

SORT UNIT

In the example above, the SORT command will sort the lines in the scrollable area based on the ID in the UNIT column.

PRINT

Syntax:

PRINT

Print the information in the scrollable area of the screen.

Example:

PRINT

When you are finished reviewing the allocation activity of this tape drive, press PF3 to return to the Current Status screen. You can either choose another tape drive for which you want to review allocation activity or press PF3 again to return to the main menu.

Chapter 4. Activity Reporting

The **Activity Reporting** option on the Automated Tape Allocation Manager main menu provides several reports to help you monitor tape drive activities. There are four primary reports for you to choose from, which are:

1. All activity
2. Job activity
3. Allocation activity
4. Failed allocations

Each of these reports is described in detail in this chapter. For easier reading, Automated Tape Allocation Manager is referred to as "ATAM" throughout this chapter.

Common Fields

All of the reports have two items at the top of the screen that enable you to navigate the reports: the **SCROLL** field and the **Row N of N** field. These fields are described below.

The **SCROLL** field in the upper right corner works in the same manner as on other ISPF screens. The **SCROLL** field accepts a value or keyword to specify the scroll amount. Valid entries are: PAGE, CSR, MAX, DATA, HALF, or a number. For more details on these SCROLL commands, refer to the IBM manual, *OS/390 Version 2 Release 10.0 ISPF User's Guide, Vol. I (Document #SC34-4791-00)*.

The **Row N of N** area indicates the number of the top row in the current view of the report and the total number of rows in the report. If you page down (F8), the first number will change to the top row of this view, while the second number (total rows) remains the same. This helps you see where you are in the report. If there are no rows for a report (the report is empty), the message "No rows to display" appears in place of the "Row N of N" message.

Common Commands

There are three commands you can type in the Option line on any of the reports to find a string, sort the data, and print the current display. Each of these commands is described below.

FIND

Syntax:

FIND *string* or F *string*

Find the first occurrence of the specified string in the scrollable area of the display.
Example:

FIND 652

In the example above, the FIND command will look for the text "652" in the scrollable area of the screen. If it finds this text, the FIND command will place the line containing that text at the top of the scrollable area.

SORT

Syntax:

```
SORT EVENT|DATE|TIME|UNIT|JOB|STEP|DDN|DSNME
```

Sort the rows in the scrollable area by the specified column. The sort keywords are listed in the same order as the columns on the report. The keywords refer to the following columns:

- EVENT - Sort by the Event column
- DATE - Sort by the Date column
- TIME - Sort by the Time column
- UNIT - Sort by the tape unit ID
- JOB - Sort by the job name
- STEP - Sort by the job step name
- DDN - Sort by the DD name
- DSNME - Sort by the data set name, which is the DSN column

Example:

```
SORT UNIT
```

In the example above, the SORT command will sort the lines in the scrollable area in ascending order based on the ID in the UNIT column. Ascending order is the default.

If you want to change the order to descending order, type a "D" after the column name. This is shown in the following example:

```
SORT UNIT D
```

PRINT

Syntax:

```
PRINT
```

Print the information in the scrollable area of the screen.

Example:

```
PRINT
```

Accessing the Activity Reporting option

To access the **Activity Reporting** screen, type **2** in the Option line of the ATAM main menu and press Enter. A window appears, as shown in the following example:

```

ATH$MAIN ----- Automated Tape Allocation Manager for z/OS and OS/390 -----
Option ==> 2_____

      1 Current Status                               User ID: myuserid
      2 Activity Reporting                           Date...: 2001/12/14
      S +-----+                                     Release: V1R1
        | ----- Select Activity Report ----- |
      A | Option ==>                                 |
      X |                                             |
        |      1 All Activity                         |
        |      2 Job Activity                         |
        |      3 Allocation Activity                 |
        |      4 Failed Allocations                 |
        |                                             |
        |      X Exit Reporting Menu                 |
        |                                             |
        +-----+
  
```

You must type a number in the Option line to choose the report you want to view. Valid choices are:

Value	Description
1	All Activity. View a report listing all of the activities for all of the tape drives.
2	Job Activity. View a report listing all of the activities based on job name.
3	Allocation Activity. View a report listing all of the allocations that occurred for all of the tape drives.
4	Failed Allocations. View a report listing all of the allocations that were requested by jobs, but did not occur or that failed during the job.

All Activity report

To select the All Activity report, type 1 in the Option line of the Select Activity Report window and press Enter. The All Activity screen is displayed. It lists all activities associated with ATAM, and is initially sorted by the Date column. An example of an All Activity report is shown below:

```
Row 1 of 48 ----- All Activity ----- 2001/12/14 12:08:37
Option ==> SCROLL ==> CSR
```

EVENT	Date	Time	Unit	Job Name	Job Step	DDNAME	DSN
ATAM Start	12/07/01	1:32:25	N/A	N/A	N/A	N/A	N/A
ALLOCATE	12/07/01	1:33:05	0651	ABCDE	STEP1	SYSOUT	WXYZ.CRASH
ALLOCATE	12/07/01	1:52:16	0652	ABCDE	STEP1	SYSOUT	WXYZ.TEST.
ALLOCATE	12/07/01	2:46:48	0652	ABCD5	STEP1	SYSOUT	WXYZ.TEST.
ALLOCATE	12/07/01	4:00:04	0690	WEEKLY04	STEP1	TAPE	WEEKL.BKUP
ATAM Start	12/07/01	14:14:54	N/A	N/A	N/A	N/A	N/A
ATAM Term	12/08/01	1:52:58	N/A	N/A	N/A	N/A	N/A
ATAM Start	12/08/01	1:55:28	N/A	N/A	N/A	N/A	N/A
ALLOCATE	12/08/01	4:00:04	0690	DAILY001	STEP1	TAPE	DAILY.BKUP
ATAM Start	12/08/01	12:56:34	N/A	N/A	N/A	N/A	N/A
ATAM Term	12/08/01	13:41:11	N/A	N/A	N/A	N/A	N/A
ATAM Start	12/08/01	13:41:45	N/A	N/A	N/A	N/A	N/A
ALLOCATE	12/08/01	13:42:14	0652	ABCDE	STEP1	SYSOUT	WXYZ.TEST.
ATAM Term	12/08/01	14:05:32	N/A	N/A	N/A	N/A	N/A
ATAM Start	12/08/01	14:59:25	N/A	N/A	N/A	N/A	N/A
ALLOCATE	12/08/01	14:59:55	0652	ABCDE	STEP1	SYSOUT	WXYZ.TEST.
ATAM Term	12/08/01	15:08:07	N/A	N/A	N/A	N/A	N/A
ATAM Start	12/08/01	15:08:32	N/A	N/A	N/A	N/A	N/A

All of the information on this screen is for display only for your review. However, you can enter commands in the Option line to find, sort, and print the data in the scrollable area of the report. For more information on the column headings and the type of data displayed in the report, refer to "Display columns for All Activity report". For information on commands for the Option line, refer to "Common Commands" on page 23.

Display columns for All Activity report

The columns in the All Activity report contain information that is for display only. The report columns are described in the following table.

Column	Description
Event	<p>Describes what happened for this job. Possible events are:</p> <ul style="list-style-type: none"> • ALLOCATE - The tape drive was successfully allocated for the job driving the event. • ATAM Start - The started task for ATAM was started. • ATAM Term - The started task for ATAM ended normally. • FAIL - ATAM could not allocate a tape device for an allocation request. The MVS default option was then invoked. • WAIT - An allocation request had to wait for a tape unit to become available. This same request may or may not have failed at a later time.
Date	Indicates the date that the event occurred. The format is MM/DD/YY.
Time	Indicates the time that the event occurred. The format is HH:MM:SS.
Unit	Indicates the name of the tape drive used to satisfy the allocation (only valid for ALLOCATE events).
Job Name	Indicates the name of the job that is driving the request.
Job Step	Indicates the name of the job step within the job that is driving the request.
DDNAME	Indicates the DDNAME within the job step of the job that is driving the request.
DSN	Indicates the name of the data set that is either being read from or written to for this job.

Job Activity report

To select the Job Activity report, type **2** in the Option line of the Select Activity Report window, and press Enter. The Job Activity screen is displayed. It lists all job activities, and is initially sorted by the job name. An example of a Job Activity report is shown below:

```
Row 1 of 170 ----- Job Activity ----- 2001/12/14 13:25:36
Option ==>                                     SCROLL ==> CSR
-----
```

Job Name	Job Step	Event	Date	Time	Unit	DDNAME	DSN
ABCDE	STEP1	ALLOCATE	12/08/01	17:15:34	0652	SYSOUT	ABCD.TEST.
ABCDE	STEP1	ALLOCATE	12/08/01	17:06:02	0652	SYSOUT	ABCD.TEST.
ABCDE	STEP1	ALLOCATE	12/08/01	15:08:52	0652	SYSOUT	ABCD.TEST.
ABCDE	STEP1	ALLOCATE	12/13/01	1:59:12	0652	SYSOUT	ABCD.TEST.
ABCDE	STEP1	ALLOCATE	12/08/01	17:34:13	0652	SYSOUT	ABCD.TEST.
ABCDE	STEP1	ALLOCATE	12/08/01	17:23:31	0652	SYSOUT	ABCD.TEST.
ABCDE	STEP1	ALLOCATE	12/08/01	14:59:55	0652	SYSOUT	ABCD.TEST.
ABCDE	STEP1	ALLOCATE	12/07/01	1:52:16	0652	SYSOUT	ABCD.TEST.
ABCDE	STEP1	ALLOCATE	12/07/01	1:33:04	0551	SYSOUT	ABCD.CRASH
ABCDE	STEP1	ALLOCATE	12/08/01	13:42:14	0652	SYSOUT	ABCD.TEST.
ABCD5	STEP1	ALLOCATE	12/07/01	2:46:48	0652	SYSOUT	ABCD.TEST.
DAILY001	STEP1	ALLOCATE	12/12/01	4:00:10	0690	TAPE	DAILY.BKUP
DAILY001	STEP1	ALLOCATE	12/13/01	4:00:04	0690	TAPE	DAILY.BKUP
DAILY001	STEP1	ALLOCATE	12/08/01	4:00:04	0690	TAPE	DAILY.BKUP
DAILY003	STEP1	ALLOCATE	12/09/01	4:00:04	0690	TAPE	WEEKL.BKUP
DAILY004	STEP1	ALLOCATE	12/14/01	4:00:04	0690	TAPE	WEEKL.BKUP
DAILY004	STEP1	ALLOCATE	12/07/01	4:00:04	0690	TAPE	WEEKL.BKUP

All of the information on this screen is for display only for your review. However, you can enter commands in the Option line to find, sort, and print the data in the scrollable area of the report. For more information on the column headings and the data displayed in the report, refer to “Display columns for Job Activity report” on page 29. For information on commands for the Option line, refer to “Common Commands” on page 23.

Display columns for Job Activity report

The columns in the Job Activity report contain information that is for display only. The report columns are described in the following table:

Column	Description
Job Name	Indicates the name of the job that is driving the request.
Job Step	Indicates the name of the job step within the job that is driving the request.
Event	Describes what happened for this job. Possible events are: <ul style="list-style-type: none">• ALLOCATE - The tape drive was successfully allocated for the job driving the event.• ATAM Start - The started task for ATAM was started.• ATAM Term - The started task for ATAM ended normally.• FAIL - ATAM could not allocate a tape device for an allocation request. The MVS default option was then invoked.• WAIT - An allocation request had to wait for a tape unit to become available. This same request may or may not have failed at a later time.
Date	Indicates the date that the event occurred. The format is MM/DD/YY.
Time	Indicates the time that the event occurred. The format is HH:MM:SS.
Unit	Indicates the name of the tape drive used to satisfy the allocation (only valid for ALLOCATE events).
DDNAME	Indicates the DDNAME within the job step of the job that is driving the request.
DSN	Indicates the name of the data set that is either being read from or written to for this job.

Allocation Activity report

To view the Allocation Activity report, type **3** in the Option line of the Select Activity Report window, and press Enter. The Allocation Activity screen is displayed. It lists all the jobs with an allocation activity, and is initially sorted by the unit ID. An example of an Allocation Activity report is shown below:

```
Row 1 of 89 ----- Allocation Activity ----- 2001/12/14 13:49:50
Option ==> SCROLL ==> CSR
```

Unit	Date	Time	Event	Job Name	Job Step	DDNAME	DSN
0651	12/07/01	1:33:04	ALLOCATE	ABCDE	STEP1	SYSOUT	ABCD.CRASH
0652	12/08/01	17:15:34	ALLOCATE	ABCDE	STEP1	SYSOUT	ABCD.TEST.
0652	12/08/01	17:06:02	ALLOCATE	ABCDE	STEP1	SYSOUT	ABCD.TEST.
0652	12/08/01	15:08:52	ALLOCATE	ABCDE	STEP1	SYSOUT	ABCD.TEST.
0652	12/13/01	1:59:12	ALLOCATE	ABCDE	STEP1	SYSOUT	ABCD.TEST.
0652	12/08/01	17:34:13	ALLOCATE	ABCDE	STEP1	SYSOUT	ABCD.TEST.
0652	12/08/01	17:23:31	ALLOCATE	ABCDE	STEP1	SYSOUT	ABCD.TEST.
0652	12/07/01	2:46:48	ALLOCATE	ABCD5	STEP1	SYSOUT	ABCD.TEST.
0652	12/07/01	1:52:16	ALLOCATE	ABCDE	STEP1	SYSOUT	ABCD.TEST.
0652	12/08/01	13:42:14	ALLOCATE	ABCDE	STEP1	SYSOUT	ABCD.TEST.
0652	12/08/01	14:59:55	ALLOCATE	ABCDE	STEP1	SYSOUT	ABCD.TEST.
0690	12/14/01	4:00:04	ALLOCATE	WEEKLY04	STEP1	TAPE	WEEKL.BKUP
0690	12/13/01	4:00:04	ALLOCATE	DAILY001	STEP1	TAPE	DAILY.BKUP
0690	12/12/01	4:00:10	ALLOCATE	DAILY001	STEP1	TAPE	DAILY.BKUP
0690	12/08/01	4:00:04	ALLOCATE	DAILY001	STEP1	TAPE	DAILY.BKUP
0690	12/07/01	4:00:04	ALLOCATE	WEEKLY04	STEP1	TAPE	WEEKL.BKUP
0690	12/09/01	4:00:04	ALLOCATE	WEEKLY03	STEP1	TAPE	WEEKL.BKUP

All of the information on this screen is for display only for your review. However, you can enter commands in the Option line to find, sort, and print the data in the scrollable area of the report. For more information on the type of data displayed in the report, refer to "Display columns for Allocation Activity report" on page 31. For information on commands for the Option line, refer to "Common Commands" on page 23.

Display columns for Allocation Activity report

The columns on the Allocation Activity report contain information that is for display only. The information provided on this screen is described in the following table.

Column	Description
Unit	Indicates the name of the tape drive used to satisfy the allocation (only valid for ALLOCATE events).
Date	Indicates the date that the event occurred. The format is MM/DD/YY.
Time	Indicates the time that the event occurred. The format is HH:MM:SS.
Event	Describes what happened for this job. Possible events are: <ul style="list-style-type: none">• ALLOCATE - The tape drive was successfully allocated for the job driving the event.• ATAM Start - The started task for ATAM was started.• ATAM Term - The started task for ATAM ended normally.• FAIL - ATAM could not allocate a tape device for an allocation request. The MVS default option was then invoked.• WAIT - An allocation request had to wait for a tape unit to become available. This same request may or may not have failed at a later time.
Job Name	Indicates the name of the job that is driving the request.
Job Step	Indicates the name of the job step within the job that is driving the request.
DDNAME	Indicates the DDNAME within the job step of the job that is driving the request.
DSN	Indicates the name of the data set that is either being read from or written to for this job.

Failed Allocations report

To select the Failed Allocations report, type 4 in the Option line of the Select Activity Report window, and press Enter. The Failed Allocations screen is displayed. It lists all of the jobs with unsuccessful allocations, and is initially sorted by the job name. An example of a Failed Allocations report is shown below:

```
Row 1 of 2  ----- Failed Allocations -----      2001/12/16  14:23:53
Option  ==>                                     SCROLL ==>  CSR

-----
Job Name  Job Step  Event      Date       Time       Unit  DDNAME  DSN
ABCD5    STEP1    FAIL       12/15/01   13:46:48   0690  SYSOUT  ABCD.TEST
DAILY001 STEP1    FAIL       12/15/01   13:46:48   0690  TAPE    DAILY.BKUP
```

All of the information on this screen is for display only for your review. However, you can enter commands in the Option line to find, sort, and print the data in the scrollable area of the report. For more information on the column headings and the type of data displayed in the report, refer to "Display columns for Failed Allocations report". For information on commands for the Option line, refer to "Common Commands" on page 23.

Display columns for Failed Allocations report

The columns on the Failed Allocations report contain information that is for display only. The information provided on this screen is described in the following table:

Column	Description
Job Name	Indicates the name of the job that is driving the request.
Job Step	Indicates the name of the job step within the job that is driving the request.
Event	Describes what happened for this job. Possible events are: <ul style="list-style-type: none">• ALLOCATE - The tape drive was successfully allocated for the job driving the event.• ATAM Start - The started task for ATAM was started.• ATAM Term - The started task for ATAM ended normally.• FAIL - ATAM could not allocate a tape device for an allocation request. The MVS default option was then invoked.• WAIT - An allocation request had to wait for a tape unit to become available. This same request may or may not have failed at a later time.

Column	Description
Date	Indicates the date that the event occurred. The format is MM/DD/YY.
Time	Indicates the time that the event occurred. The format is HH:MM:SS.
Unit	Indicates the name of the tape drive used to satisfy the allocation (only valid for ALLOCATE events).
DDNAME	Indicates the DDNAME within the job step of the job that is driving the request.
DSN	Indicates the name of the data set that is either being read from or written to for this job.

Appendix A. Operator Commands

Automated Tape Allocation Manager (ATAM) offers several different operator commands that can be used to display the status of ATAM and to dynamically alter the ATAM configuration. All commands are intended to be modifiers of the MVS modify command. For example, refer to the command below:

```
F ATH,L
```

This command displays the list of tape devices known to ATAM on the operator's console. ATAM commands consist of a single-letter command identifier followed by command modifiers, if required. Commands are also divided into two categories:

- Display commands
- Configuration commands

Both types of commands are described in this appendix.

Please note that any dynamic changes made to the ATAM configuration with these commands are not saved between the stop and start cycle of the ATAM started task. If you wish to issue a series of commands for each ATAM started task cycle, you must save the commands in a PARMLIB member. Commands contained in the ATAM PARMLIB member are executed each time ATAM is started. For more information on how to use an ATAM PARMLIB member, refer to Appendix B, "The ATAM PARMLIB Member" on page 39.

Display Commands

Display commands provide information about ATAM on the issuing operator's console. Commands in this category have no effect on the current ATAM configuration.

The table below lists the single-character display commands you can use.

Command	Description
S	Lists the selectable tape units.
L	Lists the status of all tape units.
V	Lists the version of ATAM that is currently running.
T	Displays a list of the currently active ATAM tuning parameters. These are the same parameters you selected on the ATAM configuration panels in the ISPF interface. The tuning parameters are the following: <ul style="list-style-type: none">• T1 = Offline Unit Polling Interval• T2 = Online Unit Polling Interval• T3 = Online Unit Iteration Count• T4 = Reconfiguration Termination Limit• T5 = Vary Online Wait Time• T6 = Vary Online Maximum Attempts Note: For more information on these tuning parameters, refer to "ATAM configuration parameters" on page 12.
W	Displays a list of all WTOR messages being monitored for automated response.

Dynamic Configuration Commands

Configuration commands enable an operator to dynamically reconfigure ATAM without the need to recycle the ATAM started task. A list of the configuration commands is provided below:

Command	Description
S,xxxx	Defines the tape unit as selectable. Replace xxxx with the four-character ID of the tape unit. Once made selectable, a tape unit is available to ATAM for automatic allocation.
S,xxxx-yyyy	Defines a range of tape units that are now selectable to ATAM. Replace xxxx with the low numeric tape unit identifier and replace yyyy with the high numeric tape unit ID. All units between and including the high and low range will be made available.
X,xxxx	Excludes the tape unit identified by xxxx from ATAM's pool of tape units. Once excluded, the designated tape unit can no longer be automatically allocated (varied online) or deallocated (varied offline) by ATAM.
X,xxxx-yyyy	Excludes the range of tape units from xxxx to yyyy from ATAM's pool of tape units from which it can allocate and deallocate. All units in the range of xxxx through yyyy will be excluded.
Tz=nnn	Dynamically changes the applicable ATAM tuning parameter. Replace nnn with the value you wish to use in place of the current value. Modifiers and their meanings are listed below: <ul style="list-style-type: none">• T1 = Offline Unit Polling Interval• T2 = Online Unit Polling Interval• T3 = Online Unit Iteration Count• T4 = Reconfiguration Termination Limit• T5 = Vary Online Wait Time• T6 = Vary Online Maximum Attempts Note: For more information on these tuning parameters, refer to "ATAM configuration parameters" on page 12.

Command	Description
W=msgid,offset,reply	<p>This command enables you to specify a message that ATAM is to automatically respond to when the required tape unit is online and available. You also specify the reply that is to be issued. The parameters are:</p> <ul style="list-style-type: none"> • Msgid is the message number you wish to monitor. • Offset is the exact location, starting with the first character in the message ID, where ATAM can find the unit ID of the target tape. • Reply is the exact reply ATAM is to issue. <p>For example, look at the command and message below:</p> <p>W=XYZ5373I,57,R</p> <p>XYZ5373I Unable to allocate tape drive with device type <i>device ID</i> for tape <i>volume ID</i>. Reply 'C' (cancel), 'R' (retry), or 'W' (wait).</p> <p>When message XYZ5373I is encountered, ATAM will reply with an R whenever the device ID indicated at offset 57 in the ANR message is online and available.</p>
R=msgid,offset,reply	<p>This command is similar to the "W=" command described above, but does not require a unit name or device ID. The "R=" command enables you to specify a message that ATAM is to automatically respond to and the reply that is to be issued. The parameters are:</p> <ul style="list-style-type: none"> • Msgid is the message number you wish to monitor. • Offset is the location, starting with the first character in the message ID, where ATAM can find the matching reply text in the message. For the "R=" command, the location does not have to be exact. ATAM will scan up to seven (7) bytes forward to try and match the text. The offset to the matching string in the message is required so that ATAM will not issue invalid responses. • Reply is the exact reply ATAM is to issue. The reply text must match what is in the message being acted upon (quotes do not count as part of the reply text). <p>For example, look at the command below:</p> <p>R=XYZ238D,20,WAIT</p> <p>This tells ATAM to respond with WAIT each time it encounters an XYZ238D message and that the string WAIT can be found at offset 20 through 27 in the message text.</p>

There are two messages that you can use to assign a response to either "W=" or "R=" commands:

- IEF238D - the default reply is "wait"
- IEF433D- the default reply is "hold"

In addition, ATAM allows you to alter the response issued to these messages.

Appendix B. The ATAM PARMLIB Member

The ATAM PARMLIB member allows you to create a script of valid ATAM commands that can be executed each time you start the ATAM started task. This member provides the ability to further customize ATAM to fit your particular tape unit environment.

Entering tape selection and exclusion commands

There are several commands you can enter in the ATAM PARMLIB member that will be executed each time ATAM is started. For a list of these commands and the command syntax, refer to Appendix A, "Operator Commands" on page 35.

While the default is for ATAM to manage all tape devices, there are two commands you can use to limit which tape units you want ATAM to manage:

- Use the "S" (Select) command to specify which tape devices you want ATAM to manage. ATAM will only manage the tape drives you list after the "S" command.
- Use the "X" (Exclude) command to indicate that you do not want ATAM to manage a specific tape unit.
 - If the "X" command is used by itself (without "S"), ATAM will manage all of your tape devices, except for the one(s) listed in the "X" command.
 - If you use "X" in combination with "S", ATAM will first look at the tape devices you want it to manage (based on the range listed in the "S" command), then ATAM will look to see which of those devices you do not want ATAM to manage (listed in the "X" command).

An example of how to use these two commands is provided below.

Sample PARMLIB member

The following text is an example of how you can combine the "S" and "X" commands to limit the tape devices you want ATAM to manage. Without these commands, the default is for ATAM to manage all of the devices.

```
* COMMANDS ISSUED TO ATAM AT PRODUCT START-UP
*
S,0280-028F    SELECT: MANAGE TAPE DEVICES 0280 THROUGH 028F
X,028D        EXCLUDE: DO NOT MANAGE DEVICE 028D
```

Syntax rules

This section describes the syntax rules you must follow in the PARMLIB member. The rules are listed below:

- A command must start in the first column.
- Only one command per line is processed.
- Each command is terminated by the first blank encountered.
- Comments must be separated from the command by at least one blank.
- Any record with an asterisk (*) in the first column is treated as a comment.

Specifying the member name read by ATAM at start-up

Use the ATAM PARMLIB member to specify which tape devices you want ATAM to manage. If tape device addresses are not specified in the PARMLIB member, ATAM will automatically discover and manage all eligible tape devices that it can find on the system.

To specify the name of the ATAM PARMLIB member, follow these steps:

1. Choose option S, **Setup and Configuration** on the ATAM main menu.
2. Choose option 1 for **MVS Specific Information** on the ATAM Setup screen.
3. On the "Update Parameters for MVS System ssid" screen, type the PARMLIB member name in the **ATAM Parameter Member** field. If you do not type a PARMLIB member name in this field, a default member name of ATPARMxx is assigned, where xx is the major version release number for your release of ATAM. For example, if the major version number of a release is 02, the default PARMLIB member name is ATPARM02

The ATAM PARMLIB member, whether it is one you created or the default member, must exist in your system PARMLIB concatenation when the ATAM task is started. If a PARMLIB member does not exist in this concatenation, ATAM will issue a message, "ATH047E MEMBER xxxxxxxx NOT FOUND IN PARMLIB," and continue processing normally.

Common Questions

This section contains questions and answers that may help you understand more about using PARMLIBs with the ATAM started task.

Q: Can I add a PARMLIB DDname to the ATAM started task JCL to indicate which library I want it to look in for the member?

A: No, ATAM uses Logical Parmlib Support to determine the system PARMLIB concatenation that was specified for your system during the IPL. To identify your system PARMLIB concatenation, issue the following console command:

```
D PARMLIB
```

An example of the response to the "D PARMLIB" command is shown below:

```
IEE251I 11.38.04 PARMLIB DISPLAY 645
PARMLIB DATA SETS SPECIFIED AT IPL
ENTRY  FLAGS  VOLUME  DATA SET
  1      S    OS280T  SYS1.ADCD08.PARMLIB
  2      S    OS39M1  SYS1.PARMLIB
```

One of the PARMLIB data sets listed in the example above must contain the member that was specified in the "ATAM Parameter Member" field (option S.1 from the ATAM main menu). For example, if you typed ATAM001 in the "ATAM Parameter Member" field then member ATAM001 must exist in one of the libraries listed in the output from the "D PARMLIB " command.

Q: If I change the member name in the "ATAM Parameter Member" field (option S.1 from the ATAM main menu), do I have to recycle the ATAM started task?

A: Yes, ATAM only searches for and executes the PARMLIB member contents at product initialization.

Appendix C. VTS load balancing exit

When using z/OS to share two or more DFSMS-managed Virtual Tape Servers (VTS), a problem occurs when identifying which VTS library in the concatenation is specified as the STORGRP. The IBM Allocation Recovery exit, IEF_ALLC_OFFLN, only sees the units of the last library used, not the units of the other VTS libraries. This, in turn, causes Automated Tape Allocation Manager (ATAM) to see only the units from the last library.

With ATAM's VTS load balancing feature, all of the VTS libraries are used, not just the last library. This is accomplished through ATAM's STORCLAS ACS exit that uses a unique storage class name for each VTS library. This exit works in conjunction with your DFSMS STORCLAS and STORGRP ACS routines so that only one library name will be passed to MVS Allocation for a unit assignment. This library assignment will be based on the criteria for VTS load balancing in ATAM's STORCLAS ACS exit routine.

Modifying storage class and group names

To implement VTS load balancing, you need to make changes to the DFSMS STORCLAS and STORGRP ACS routines, then update the ATAM STORCLAS exit with the new storage classes. Follow the steps below:

1. Using DFSMS, define and activate storage class names. You need to define:
 - a. A "generic" storage class name that can be used for any VTS library, such as SCVTS.
 - b. Specific storage class names for each VTS library, such as SCVTS1 for library 1, SCVTS2 for library 2, etc.
2. Update the DFSMS **STORCLAS** ACS routine with these new storage class names. Assign each name using the &STORCLAS variable, such as:

```
&STORCLAS = 'SCVTS'    (any VTS library)
```

```
&STORCLAS = 'SCVTS1'  (VTS library 1)
```

```
&STORCLAS = 'SCVTS2'  (VTS library 2)
```

3. Update the DFSMS **STORGRP** ACS routine so it can test for the ATAM-redirected assignment of the &STORCLAS variable. Perform the following steps to modify the DFSMS STORGRP ACS routine:

- a. Update the &STORCLAS variable with the new storage class names, such as &STORCLAS = 'SCVTS'.

- b. Update the &STORGRP variable with the VTS library you want to associate with each storage class. For example, if VTS library 2 (Lib2) should be associated with storage class 2 (SCVTS2), then the variables may look like this:

```
&STORCLAS='SCVTS2'
```

```
&STORGRP='Lib2'
```

The screen below provides an example of how the STORGRP ACS routine may look when you have updated it with new storage classes and group assignments for three VTS libraries.

```

WHEN (&STORCLAS='SCVTS1') /*ATAM redirected to Library 1*/
DO
  SET &STORGRP='LIB1'
EXIT
END

WHEN (&STORCLAS='SCVTS2') /*ATAM redirected to Library 2*/
DO
  SET &STORGRP='LIB2'
EXIT
END

WHEN (&STORCLAS='SCVTS3') /*ATAM redirected to Library 3*/
DO
  SET &STORGRP='LIB3'
EXIT
END

WHEN (&STORCLAS='SCVTS') /*ATAM not active, use any VTS*/
DO
  SET &STORGRP='LIB1','LIB2','LIB3'
EXIT
END

```

- Next, update the ATAM member, ATH#VTSO, in the highlevel.SAMPLIB library to include the new storage classes. This is the ATAM STORCLAS exit that will perform the VTS load balancing.

Note: An example of the highlevel qualifier for ATAM is ATH.PR0110, but the HLQ is based on how the ATAM product libraries were named at your site.

The instructions for modifying the JCL in ATH#VTSO are listed in the member. A part of the code described in this member is shown below for your reference:

```

*-----*
* CHANGE THE VALUE "SCVTS" TO MATCH YOUR INSTALLATION'S STORCLAS*
* NAME FOR THE STORCLAS THAT TELLS SMS TO SELECT ANY VTS. *
*-----*
VTSB_CLAS      DC  AL2(VTSB_CLAS_NAME#)
VTSB_CLAS_NAME DC  C'SCVTS'          DO NOT EXCEED 8 CHARACTERS
VTSB_CLAS_NAME# EQU *-VTSB_CLAS_NAME
                DS  (8-VTSB_CLAS_NAME#)C
*-----*
* VTS STORCLAS LIBRARY DEFINITION SECTION. *
* ADD YOUR STORCLAS DEFINITIONS TO MATCH THE STORCLAS THAT MATCH*
* EACH LIBRARY. *
*-----*
VTSB_SC# EQU 3          <= CHANGE TO MATCH TOTAL NUMBER IN TABLE
VTSB_LIBRARIES DS OF          START ON FULL WORD BDY
VTSB_SC1      DC  AL2(VTSB_SC1#)
VTSB_SC1_NAME DC  C'SCVTS1'          STORCLAS FOR VTS 1
VTSB_SC1# EQU *-VTSB_SC1_NAME
                DS  (8-VTSB_SC1#)C

VTSB_SC2      DC  AL2(VTSB_SC2#)
VTSB_SC2_NAME DC  C'SCVTS2'          STORCLAS FOR VTS 2
VTSB_SC2# EQU *-VTSB_SC2_NAME
                DS  (8-VTSB_SC2#)C

VTSB_SC3      DC  AL2(VTSB_SC3#)
VTSB_SC3_NAME DC  C'SCVTS3'          STORCLAS FOR VTS 3
VTSB_SC3# EQU *-VTSB_SC3_NAME
                DS  (8-VTSB_SC3#)C

```

The lines in italics in the example show where the storage class name is added to the JCL in ATH#VTSO.

5. When you are done adding the new storage classes to the ATH#VTSO member of `highlevel.SAMPLIB`, assemble and link this JCL, following the instructions in the member.
6. Stop and restart the ATAM started task to recycle the product.

ATAM is now ready to perform VTS load balancing. In actual use, the ATAM exit is run before the DFSMS STORGRP ACS routine to ensure the new storage classes are passed to the STORGRP ACS routine. This allows the STORGRP ACS routine to assign the appropriate library to ensure that all VTS libraries are used.

Disabling VTS load balancing

If you decide you do not want to use VTS load balancing, you can disable ATAM's STORCLAS exit by doing the following:

1. Delete member ATH#VTSO from the `highlevel.LOADLIB` library, which is in the ATAM started task STEPLIB.
Note: The high level qualifier (HLQ) may be ATH.PR00110 or another HLQ assigned by your system administrator when ATAM was installed.
2. Stop and restart the ATAM started task to recycle the product.

These instructions are also listed in the ATH#VTSO member for your reference.

Appendix D. Volser-to-Unit Preferencing Exit

ATAM allows you to restrict the selection of available tape units by specific criteria. Now you can restrict one or more series of VOLSER ID's to a specific set of tape units. For example, if tape VOLSERS 005000 through 009999 are physically located at a remote data center, you can tell ATAM to direct mount requests to the tape device addresses at that data center. This is one example of *volser-to-unit preferencing*.

Modify ATH#VALD

To use volser-to-unit preferencing, you must modify a model ATAM exit, ATH#VALD, in the *highlevel*.SAMPLIB library, where *highlevel* is the highlevel qualifier assigned to the ATAM product libraries by your system administrator. The ATH#VALD member contains instructions on how to modify the member to specify criteria for volser-to-unit preferencing.

Assemble and link ATH#VALD

When you have modified the ATH#VALD member, you must assemble and link edit the module into your *highlevel*.LOADLIB library, where *highlevel* is the highlevel qualifier assigned to the ATAM product libraries by your system administrator.

Another member, \$ASMVALD, in the *highlevel*.SAMPLIB library, contains the JCL to perform the assemble and link edit processes. Refer to \$ASMVALD for instructions on assembling and linking the ATH#VALD member so volser-to-unit preferencing is used whenever ATAM is run.

Note: An ATH#VALD module must be present in the ATAM LOADLIB for volser-to-unit preferencing to work. If you do not want to use this feature, you do not need to put ATH#VALD in the ATAM load library.

Enabling ATH#VALD for use

When you first implement ATH#VALD exit, or whenever you change the exit you already have in place, you must perform the following steps:

1. Stop the ATAM started task.
2. Assemble and link edit your customized ATH#VALD load module into the ATAM load library.
3. Start the ATAM started task.

Disabling ATH#VALD

If you decide not to use volser-to-unit preferencing, you can disable this feature by doing the following:

1. Stop the ATAM started task.
2. Delete the ATH#VALD load module from the ATAM load library.
3. Restart the ATAM started task.

Appendix E. Error Messages from ISPF

The error messages in this appendix are based on issues with ISPF or with entries made on ATAM's screens. For easier reading, "Automated Tape Allocation Manager" is referred to as "ATAM" in this appendix. All messages generated by ATAM have a severity code printed as the last character of the message ID. The severity codes are described in the following table:

Severity Code	Description
I	Information only. No user action required.
W	Warning message. Results may not be as expected.
E	Error message. Some may be user-correctable. Read the User Response to determine the course of action.

ATH001I COPYRIGHT SCREEN

Explanation: This screen lists the copyright information for this product.

User Response: No action required.

ATH002E INVALID SELECTION

Explanation: You have typed an invalid selection in the Option line.

User Response: Type a valid option from the choices listed on this screen, or type X to Exit.

ATH030E INVALID SELECTION

Explanation: You have typed an invalid selection in the line command (Cmd) column.

User Response: Type A in the line command (Cmd) column to select Allocation Activity or type X in the Option line to Exit.

ATH031E TRUNCATION ERROR

Explanation: An internal error occurred while attempting to display the Current Status panel.

User Response: Contact IBM customer support to report the problem.

ATH032E SEVERE ERROR

Explanation: An internal error occurred while attempting to display the current status panel.

User Response: Contact IBM customer support to report the problem.

ATH033E UNEXPECTED RC

Explanation: An internal error occurred, indicated by the return code (RC), while attempting to display the Current Status panel.

User Response: Contact IBM customer support to report the problem.

ATH034E INVALID SELECTION

Explanation: You have typed an invalid selection in the Option line.

User Response: Type a valid entry based on the menu options for this screen.

ATH612E INVALID MODE

Explanation: You have entered an invalid value for the mode.

User Response: Type 1 for Active or 2 for Passive mode.

ATH617I INVALID VALUE

Explanation: The value you typed is not valid for this field because the value is either non-numeric or out of range.

User Response: Type a value that is numeric and within the acceptable range for this field.

ATH901E DATASET NOT FOUND

Explanation: The Rocket Software default load library could not be located.

User Response: Ensure that the load library name is correct.

ATH902E NO MVS SYSTEM NAME

Explanation: An MVS system ID must be typed for processing.

User Response: Type an MVS system name.

ATH904E VSAM OPEN ERROR

Explanation: The specified data set could not be opened for I/O.

User Response: There may be related WTOR messages that were also issued as a result of this error. Attempt to determine the cause of the error from these other messages. If the problem persists, contact IBM customer support.

ATH905E VSAM READ ERROR

Explanation: An unexpected return code from VSAM was encountered while doing a read of the control file.

User Response: There may be related WTOR messages that were also issued as a result of this error. Attempt to determine the cause of the error from these other messages. If the problem persists, contact IBM customer support.

ATH906I RECORD UPDATED

Explanation: An updated record was successfully written to the control file.

User Response: None required.

ATH907E ERROR IN VSAM UPDATE

Explanation: An unexpected return code from VSAM was encountered while doing an update operation of the control file.

User Response: There may be related WTOR messages that were also issued as a result of this error. Attempt to determine the cause of the error from these other messages. If the problem persists, contact IBM customer support.

ATH908I RECORD ADDED

Explanation: A new record was successfully written to the control file.

User Response: None required.

ATH909E INVALID VALUE

Explanation: You have typed an invalid value where ATAM expects a 1 or 2.

User Response: Type 1 or 2 and press Enter.

ATH910E ERROR IN VSAM ADD

Explanation: An unexpected return code from VSAM was encountered while doing an add operation to a control file.

User Response: There may be related WTOR messages that were also issued as a result of this error. Attempt to determine the cause of the error from these other messages. If the problem persists, contact IBM customer support.

ATH911E NO FIND STRING SPECIFIED

Explanation: The (F)IND command was entered, but no parameters were specified.

User Response: Type a string after you type F or FIND.

ATH912I FIND STRING NOT FOUND

Explanation: The string you typed after the (F)IND command could not be found.

User Response: No action required.

ATH913E INVALID PRIMARY COMMAND ENTERED

Explanation: You typed an unknown primary command.

User Response: Type a different, valid command.

ATH914E UNKNOWN COLUMN ENTERED

Explanation: You typed the name of an unknown column when using the SORT command.

User Response: Type the name of a column that exists on this screen after the SORT command.

ATH915E COLUMN UNSORTABLE

Explanation: The SORT command is not supported for this column.

User Response: Type a different column name after the SORT command.

ATH916E COLUMN NOT SPECIFIED

Explanation: SORT column not entered. Column name or number must be specified.

User Response: Type a column name or number after the SORT command so it knows which column to sort.

User Response: Please verify that you entered the proper dataset name and that the data set exists.

ATH940E DATASET NOT FOUND

Explanation: The specified data set could not be located.

Appendix F. Error Messages from the ATAM Started Task

All messages generated by the Automated Tape Allocation Manager (ATAM) started task are listed in this appendix. A description of each message and suggestions on how you can resolve the problem are provided, where possible. For easier reading, "Automated Tape Allocation Manager" is referred to as "ATAM" in this chapter.

All messages have a severity code printed as the last character of the message ID. The severity codes are described in the following table:

Severity Code	Description
I	Information only. No user action required.
W	Warning message. Results may not be as expected.
E	Error message. Some may be user-correctable. Read the User Response to determine the course of action.
D	Operator intervention required.

ATH001I ATAM - ACTIVE MODE - VERSION X.X.XX

Explanation: This message lists the version of ATAM you are using. It also indicates that ATAM has been started in the active processing mode.

User Response: None required.

ATH002I ATAM - PASSIVE MODE - VERSION X.X.XX

Explanation: This message lists the version of ATAM you are using. It also indicates that ATAM has been started in the passive processing mode.

User Response: None required.

ATH003W ATAM DETECTED ANOTHER ACTIVE ATAM ADDRESS-SPACE, TERMINATING THIS TASK

Explanation: The ATAM started task found another active ATAM started task. The started task will terminate after this message is displayed.

User Response: Either use the existing ATAM started task or stop the existing started task and restart ATAM.

ATH004I ATAM MUST BE EXECUTED AS A STARTED TASK

Explanation: The only way to run ATAM is by using a started task.

User Response: Verify the name of the started task for ATAM (ATH was used in the sample JCL for the started task) and try executing the started task, such as S ATH.

ATH005I ATAM INITIALIZATION COMPLETE

Explanation: This message informs you that the initialization process for ATAM is done.

User Response: None required.

ATH006I CONFIGURATION CHANGE DETECTED

Explanation: This message is displayed if a dynamic I/O configuration change is detected by ATAM.

User Response: None required.

ATH007I ATAM RE-INITIALIZATION COMPLETE

Explanation: The re-initialization process is done.

User Response: None required.

ATH008I NO TAPE UNITS DETECTED, ATAM TERMINATING

Explanation: No selectable tape units were discovered on the MVS image. ATAM will terminate after this message is displayed.

User Response: None required.

**ATH009I ATAM TERMINATION
REQUESTED**

Explanation: A normal shutdown of the ATAM started task has begun.

User Response: None required.

**ATH010I ATAM TABLE BUILD LIMIT
EXCEEDED, ATAM TERMINATING**

Explanation: The number of dynamic I/O configuration changes has exceeded the threshold established for ATAM. The ATAM started task will terminate after this message is displayed.

User Response: Please verify that the value for the Reconfiguration Termination Limit in the ATAM configuration is correct, and then restart the ATAM started task.

**ATH011I ATAM WAITING 15 SECONDS
BEFORE TERMINATING**

Explanation: This is for your information.

User Response: None required.

**ATH012E MULTIPLE EXIT ROUTINES
DETECTED, RESULTS MAY BE
UNPREDICTABLE**

Explanation: ATAM detected multiple copies of its allocation module. This is an error. ATAM will generate a diagnostic dump and then terminate.

User Response: Please contact IBM Customer Support.

**ATH013E EXIT ATAM VERSION
INCOMPATIBILITY ERROR, ATM
TERMINATING WITH A
DIAGNOSTIC DUMP**

Explanation: A mixture of ATAM releases and/or maintenance was detected while the ATAM started task was attempting to start. A diagnostic dump will be generated, and the started task will terminate.

User Response: Please verify that all installation or maintenance procedures completed successfully.

ATH014I xx,xxx TAPES DETECTED

Explanation: The xx,xxx refers to the number of tapes discovered on the MVS image.

User Response: None required.

**ATH020E ERROR PROCESSING WTOR
MESSAGE xxxxxxxxxxxxxx**

Explanation: The xxxxxxxxxxxxxx refers to the ID of the message that could not be processed.

User Response: Verify that the W operator command or PARMLIB command was specified correctly.

**ATH021E INVALID WTOR MESSAGE FLAG
COMBINATION DETECTED**

Explanation: An unexpected error occurred while trying to process a WTOR message.

User Response: ATAM will attempt to recover from this error. If this message is received repeatedly, please contact IBM Customer Support for additional diagnostic information.

**ATH022E BAD RETURN CODE FROM
EDTINFO, WTOR PROCESSING
SUSPENDED**

Explanation: An error occurred while attempting to access the table of eligible devices.

User Response: ATAM will attempt to recover from this error. If this message is received repeatedly, please contact IBM Customer Support for additional diagnostic information.

**ATH023E ATAM LOGIC ERROR, DYNAMIC
IODF UPDATE SUSPECTED**

Explanation: ATAM was unable to locate a device. The most likely cause is a dynamic change to the I/O configuration.

User Response: ATAM will attempt to recover from this error. If the message continues to display, please recycle the ATAM started task. If this fails to cure the problem, please contact IBM Customer Support for additional diagnostic information.

**ATH024E ATAM RETURNED NON-TAPE
DEVICE OR AN INTERNAL LOGIC
ERROR HAS OCCURRED**

Explanation: The requested device was not a tape unit.

User Response: Please recycle the ATAM started task. If this fails to cure the problem, please contact IBM Customer Support for additional diagnostic information.

**ATH031W NO BASE CONFIGURATION
FOUND, USING DEFAULTS**

Explanation: You have not entered parameters for this MVS image, so ATAM is using default values for the parameters.

User Response: Select option S, Setup and Configuration, on the ATAM Main Menu to enter parameters for each MVS image on which you want to run ATAM.

ATH032I BASE CONFIGURATION LOADED

Explanation: ATAM is using the parameters you entered through the Setup and Configuration option.

User Response: None required.

ATH033I PASSIVE MODE SELECTED

Explanation: You selected passive mode, which tells ATAM to continually check for drives that are not being used and return them to "free" status (selectable and unallocated). In passive mode, ATAM will not attempt to vary a tape unit online.

User Response: None required.

ATH034I ACTIVE MODE SELECTED

Explanation: You selected active mode, which tells ATAM to automatically vary tape drives online in response to demands for tape drive units.

User Response: None required.

ATH040W UNKNOWN COMMAND: xxxxxx

Explanation: You entered a command that ATAM does not recognize.

User Response: Check the syntax and spelling of this command or type a different command.

ATH041I TAPE LIST: xabc y xbcd y xcde y xdef y

Explanation: This message displays a list of tapes where xabc refers to the tape unit ID and y is one of the following values:

- ? = Not validated
- x = Excluded
- S = Selectable
- P = Pending offline
- O = Online
- A = Allocated

User Response: None required.

ATH042W UNIT xxxx UNKNOWN.

Explanation: The xxxx refers to the invalid tape unit ID. The specified unit is not known to ATAM.

User Response: Use a valid tape unit ID.

ATH043W INVALID RANGE SPECIFIED, ADDRESSES DECREASING.

Explanation: One or both of the values you specified for the range are not valid.

User Response: Change one or both of the values you typed for the range.

ATH044I NO TAPE UNITS DEFINED AS SELECTABLE

Explanation: None of the tape units defined for this MVS image are available for use.

User Response: Contact your systems programmer to define one or tape units as selectable by this MVS image.

ATH045I TIMES: T1=mmm T2=nnn, T3=ooo, T4=ppp.

Explanation: This message tells you the values that are currently set for your tuning parameters. T1 refers to the first tuning parameter, T2 the second parameter, and so on. All of the values are numeric.

- T1=mmm. The Office Unit Polling Interval is set for mmm seconds.
- T2 = nnn. The Online Unit Polling Interval is set to nnn seconds.
- T3 = ooo. The Offline Unit Iteration Count is set to ooo iterations.
- T4 = ppp. The Reconfiguration Termination Limit is set to ppp dynamic changes.

User Response: None required. For more information on the tuning parameters, refer to "ATAM configuration parameters" on page 12.

ATH045I TIMES: T5=mmm T6=nnn, T7=ooo, T8=ppp.

Explanation: This message tells you the values that are currently set for your tuning parameters. T5 refers to the fifth tuning parameter, T6 the sixth parameter, and so on. All of the values are numeric.

- T5 = mmm. The Vary Online Wait Time is set for mmm seconds.
- T6 = nnn. The Vary Online Maximum Attempts is set to nnn attempts.
- T7 and T8 are currently not defined and are reserved for future use.

User Response: None required. For more information on the tuning parameters, refer to "ATAM configuration parameters" on page 12.

ATH046W INVALID SYNTAX: xxxxxx

Explanation: The command contained invalid syntax.

User Response: Re-enter the command using valid syntax.

ATH047E MEMBER ATPARMxx NOT FOUND
IN PARMLIB.

Explanation: The default parmlib member was not found in the current PARMLIB concatenation. ATPARMxx is the name of the default parmlib member for ATAM, where xx is the major version release number for this version of ATAM, such as 02.

User Response: None required.

ATH048I PARMLIB MEMBER xxxxxxxx
COMMAND IS yyyyyy

Explanation: The xxxxxxxx refers to the name of the PARMLIB member, and yyyyyy is the specific command.

User Response: None required.

ATH049W CANNOT SPECIFY A M=XX
COMMAND FROM WITHIN A
PARMLIB MEMBER

Explanation: You placed the M=xx command in the PARMLIB member for ATAM, but this command can only be used as a console command.

User Response: Remove the M=xx command from the PARMLIB member for ATAM.

ATH050I DIAGNOSTIC MESSAGES ARE
BEING SUPPRESSED.

Explanation: This is an informational message.

User Response: None required.

ATH050I DIAGNOSTIC MESSAGES ARE
BEING GENERATED.

Explanation: This is an informational message.

User Response: None required.

ATH051I WTOR MSGID xxxxxxxxxx HAS
REPLY yyyyyyyyyyy AND OFFSET
nnn

Explanation: The xxxxxxxxxx refers to the message ID, the yyyyyyyyyyy indicates the type of reply for this message, and OFFSET nnn refers to the exact location from the start of the message, denoted by msgid, where ATAM can find the tape unit ID.

User Response: None required.

ATH052W WTOR ENTRIES FOR
ALLOCATION TYPE MESSAGES
CANNOT BE UPDATED

Explanation: You cannot modify the established response to the selected message.

User Response: Do not attempt to modify the established response for this message.

ATH058W WTOR MSGID xxxxxxxxxx NOT
DEFINED

Explanation: The specified WTOR message is not defined to ATAM.

User Response: None required.

ATH059I UNIT xxxx SELECT=x,
REASON=xxxx

Explanation: The xxxx refers to the tape unit ID, the x after SELECT represents either Y or N, and the xxxx after REASON indicates why the unit was/was not selected.

User Response: No user action required.

ATH080I ATAM BLOCK DELETED

Explanation: This is an informational message.

User Response: None required.

ATH081I ATAM BLOCK CHAINED FROM
SSCT

Explanation: This is an informational message.

User Response: None required.

ATH082I SELECTABLE FREE ONLINE TAPE
DETECTED

Explanation: This is an informational message.

User Response: None required.

ATH083I VARY OFFLINE ATTEMPTED.

Explanation: This is an informational message.

User Response: None required.

ATH084I VARY ONLINE OF PENDING
OFFLINE UNIT ATTEMPTED.

Explanation: This is an informational message.

User Response: None required.

**ATH085I ALLOCATION TYPE MESSAGES
DETECTED, NO VARY OFFLINES
WILL BE ATTEMPTED.**

Explanation: One or more WTORs requesting allocation of a tape unit have been received, but the request could not be automatically responded to by ATAM. This message will continue to be displayed until a response is provided for all outstanding WTORs. During this time, ATAM will not attempt to vary offline any tape units currently online to the local MVS image. Once all of the WTORs have been cleared, ATAM will return to normal processing.

User Response: Free or add tape units and respond to the WTOR(s).

**ATH090I ESOTERIC xxxxxxxx DETECTED IN
WTOR yyyyyyyyyyy FOR REPLY ID
nnnn**

Explanation: ATAM found the specified ESOTERIC unit name in the WTOR message it is processing. This message is informational only.

User Response: None required.

**ATH091I UNIT MADE AVAILABLE, AND
REPLY ISSUED TO WTOR**

Explanation: This is an informational message.

User Response: None required.

**ATH092I NO DEVICE AVAILABLE TO
SATISFY WTOR REQUEST**

Explanation: No tape units matching the required criteria could be located. Automatic allocation failed, and a WTOR is posted requesting operator intervention.

User Response: Respond to the WTOR that was issued.

**ATH093I STORAGE OBTAINED FOR
EDTINFO WORKAREA**

Explanation: This is an informational message.

User Response: None required.

**ATH094I STORAGE RELEASED FOR
EDTINFO WORKAREA**

Explanation: This is an informational message.

User Response: None required.

**ATH101D JOB xxxxxxxx NEEDS A TAPE,
REPLY C TO CANCEL, M FOR
MANUAL ALLOCATION, W FOR**

**WAIT-NO HOLD OR I FOR
INFORMATION.**

Explanation: ATAM automatic allocation failed for the specified job.

User Response: Respond to the WTOR in line with your site's requirements.

**ATH102W NO SELECTABLE TAPE UNITS
AVAILABLE.**

Explanation: This is an informational message.

User Response: None required.

**ATH103W UNEXPECTED EXIT LOCATION,
ATAM INTERNAL ERROR**

Explanation: ATAM has detected storage that potentially has been disrupted.

User Response: Please contact IBM Customer Support for additional diagnostic assistance.

**ATH104W INVALID DIRECT SSCT ADDRESS,
ATAM INTERNAL ERROR**

Explanation: ATAM has detected storage that potentially has been corrupted.

User Response: Please contact IBM Customer Support for additional diagnostic assistance.

**ATH140I JOB xxxxxxxx, STEP yyyyyyyy,
DDNAME zzzzzzzz REQUIRES AT
LEAST 1 TAPE UNIT**

Explanation: The xxxxxxxx refers to the job name, yyyyyyyy refers to the specific step in the job, and zzzzzzzz refers to the specific DD line in the step that is requesting one or more tape units.

User Response: None required.

**ATH141I ACCEPTABLE OFFLINE UNITS
ARE:**

Explanation: This message appears before a list of offline units.

User Response: None required.

**ATH142I ACCEPTABLE NON-ACCESSIBLE
UNITS ARE:**

Explanation: This message appears before a list of non-accessible units.

User Response: None required.

ATH143I **xabc y xbcd y xcde y xdef y**

Explanation: This is the list of tape units that accompanies another error message. The tape unit IDs are represented by xabc, xbcd, xcde, xdef, and the letter y is one of the following values:

- ? = Not validated
- x = Excluded
- S = Selectable
- P = Pending offline
- O = Online
- A = Allocated

User Response: None required.

ATH190I **ATAM - VERSION x.x.xx**

Explanation: This message lists the version of ATAM that you are using.

User Response: None required.

ATH191I **ATAM REQUESTING WAIT + NOHOLD**

Explanation: This is an informational message.

User Response: None required.

ATH192I **ATAM REQUESTING DEFAULT PROCESSING**

Explanation: This is an informational message.

User Response: None required.

ATH193I **ATAM REQUESTING CHECK OF ONLINE UNIT**

Explanation: This is an informational message.

User Response: None required.

Appendix G. Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10594-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this publication to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is as your own risk.

Licensees of this program who want to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
J74/G4
555 Bailey Avenue

P.O. Box 49023
San Jose, CA 95161-9023
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurement may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

Advanced Peer-to-Peer Networking	GDDM
AIX	IBM
AIX/6000	MVS/ESA
CICS	MVS/XA
CICS/MVS	OfficeVision/VM
CICS/VSE	OS/2
DATABASE 2	PL/I
DB2	PROFS
Distributed Relational Database Architecture	QMF
DRDA	SQL/DS
DXT	Virtual Machine/Enterprise Systems Architecture
	VM/XA
	VSE/ESA

Other company, product, and service names, which may be denoted by a double asterisk (**), may be trademarks or service marks of others.

Index

A

A line command 17
accessing Automated Tape
 Allocation Manager 6
ACS vii, 41
Active operational mode 11
Activity Reporting option 23
Activity Reporting screen 25
All Activity report 26
All Activity screen 26
ALLOCATE event 19, 27, 29, 31,
 32
Allocated field 17
Allocation Activity report 30
Allocation Activity screen 19, 30
allocation line command 17
Allocations
 failures 17
 field 17
 successful 17
ATAM commands, configuration
 36
ATAM Configuration Parameters
 12
ATAM Configuration screen 11
ATAM Parameter Member 10
ATAM parameters 11
ATAM Setup screen 9
ATAM Start event 19, 27, 29, 31,
 32
ATAM Term event 19, 27, 29, 31,
 32
ATH sample JCL 6
ATH#VALD 45
ATH\$ACTV screen 26
ATH\$FALA screen 32
ATH\$JOBA screen 28
ATH\$MAIN screen 8
ATH\$STAT screen 15
ATH\$UNTA screen 19, 30
ATHCLIST sample JCL 7
ATHCNTFL 4
ATHLOGF sample JCL 5
ATHPARMS data set 6
ATHPNL1 screen 10
ATHPNL2 screen 11
ATHPROC sample JCL 5
authorization 3
 microcode level 3

C

CLIST 6
 ATH sample JCL 6
 ATHCLIST sample JCL 7
 LOGFILE 8
commands, dynamic configuration
 36
configuring Automated Tape
 Allocation Manager 9
Control Dataset Name 9
current status 15
Current Status screen 15

D

dataset name 20, 27, 29, 31, 33
Date field 19, 27, 29, 31, 33
date of initialized started task 17
DDNAME field 20, 27, 29, 31, 33
DEFAULT command 13
default settings 13
device selection vii
DSN field 20, 27, 29, 31, 33
dynamic configuration commands
 36
dynamic IOCF reconfigurations 12

E

ECSA memory conservation 12
Event field 19, 27, 29, 31, 32
 ALLOCATE 19, 27, 29, 31, 32
 ATAM Start 19, 27, 29, 31, 32
 ATAM Term 19, 27, 29, 31, 32
 FAIL 19, 27, 29, 31, 32
 WAIT 19, 27, 29, 31, 32
Exclude (X) command 39
EXIT load library 10

F

FAIL event 19, 27, 29, 31, 32
Failed Allocations report 32
Failed Allocations screen 32
failures 17
Forced waits 17

I

IEF238D 37
IEF433D 37

J

JCL
 ATH 6
 ATHCLIST 7
 ATHCNTFL 4
 ATHLOGF 5
 ATHPROC 5
 CLISTs 6
 started task 5
Job Activity report 28
Job Activity screen 28
Job name field 20, 27, 29, 31, 32
Job step field 20, 27, 29, 31, 32

L

line command
 A 17
 allocation 17
load balancing vii, 41
load library 10
log file JCL 5
LOGFILE data set 6
LRU vii

M

Main Menu 8
message processing 37
microcode level 3
MVS System ID 9
MVS system information 10

N

name of started task 16
name of tape drive 17
Notices 57

O

Offline unit polling interval 12
Online field 17
Online unit iteration count 12
Online unit polling interval 12
operational modes
 active 11
 passive 11

P

parameters 10
 ATAM 11
 new 13
 offline unit polling interval 12
 online unit iteration count 12
 online unit polling interval 12
 reconfiguration termination
 limit 12
 restarting the started task 13
 vary online maximum attempts
 12
 vary online wait time 12
PARMLIB 39
Passive operational mode 12
Pending field 17
preferencing, volser-to-unit 45

R

R= command 37
Reconfiguration termination limit
 field 12
reports 25
 all activity 26
 allocation activity 30
 failed allocations 32
 job activity 28
requirements 3

S

sample JCL
 ATH 6
 ATHCLIST 6, 7
 ATHCNTFL 4
 ATHLOGF 5
 ATHPROC 5
sample, PARMLIB member 39
Screens

- Activity Reporting window 25
- all activity 26
- Allocation Activity 19
- allocation activity 30
- ATAM Configuration 11
- ATAM Setup 9
- ATH\$ACTV 26
- ATH\$FALA 32
- ATH\$JOBA 28
- ATH\$MAIN 8
- ATH\$STAT 15
- ATH\$UNTA 19, 30
- ATHPNL1 10
- ATHPNL2 11
- Current Status 15
- Failed Allocations 32
- job activity 28
- main menu 8
- Update Parameters for MVS
 - System 10
- Select (S) command 39
- Selectable field 17
- started task 13
 - customizing 35
 - date initialized 17
 - JCL 5
 - name 16
 - new parameters 13
 - purging 13
 - restarting 13
 - starting 13, 14
 - status 16
 - stopping 13
 - terminating 12
 - time initialized 17
- starting the started task 13
- status
 - current 15
 - started task 16
- STORCLAS vii, 41
- STORGRP vii, 41
- successful allocations field 17

T

- tape drive
 - allocated 17
 - allocations 17
 - name 17
 - online 17
 - pending 17
 - selectable 17
- Task started field 17
- Time field 19, 27, 29, 31, 33
- time of initialized started task 17

U

- Unit field 19, 27, 29, 31, 33
- Units
 - allocated 17
 - discovered 17
 - name 17
 - online 17
 - pending 17
 - selectable 17
- Update Parameters for MVS System
 - screen 10

V

- Vary online maximum attempts 12
- Vary online wait time 12

- volser-to-unit preferencing 45
- VTS vii, 41

W

- W= command 37
- WAIT
 - event 19, 27, 29, 31, 32
 - forced 17
- WTOR rule processing 37

Readers' Comments—We'd Like to Hear from You

Automated Tape Allocation Manager for z/OS and OS/390
User's Guide
Version 1 Release 1

Publication No. SC27-1610-01

Overall, how satisfied are you with the information in this book?

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

How satisfied are you that the information in this book is:

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Complete	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to find	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to understand	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Well organized	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Applicable to your tasks	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Please tell us how we can improve this book:

Thank you for your response. May we contact you? Yes No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

_____ Name	_____ Address
_____ Company or Organization	_____
_____ Phone No.	_____



Cut or Fold
Along Line

Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

International Business Machines Corporation
Department HHX/H3
PO BOX 49023
SAN JOSE CA
U. S. A. 95161-9023



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold
Along Line



Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

SC27-1610-01



