

CICS Universal Client



# Windows Client Administration

*Version 7.1*



CICS Universal Client



# Windows Client Administration

*Version 7.1*

**Note!**

Before using this information and the product it supports, be sure to read the general information under “Notices” on page 155.

**Third Edition (July 2008)**

This edition applies to Version 7.1 of the CICS Universal Client, program number 5724-J09. It will also apply to all subsequent versions, releases, and modifications until otherwise indicated in new editions.

This edition replaces SC34-6369. Technical changes to the text are indicated by a vertical line to the left of the change.

© Copyright International Business Machines Corporation 1996, 2008.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

## About this book. . . . . vii

Installation path. . . . . vii

Information specific to your operating system . . . viii

## What's new on the CICS Universal Client . . . . . ix

## Chapter 1. CICS Universal Client overview . . . . . 1

The external access interfaces (ECI, EPI, ESI). . . . 1

3270 terminal emulation (cicsterm) . . . . . 1

3270 printer support (cicsprnt) . . . . . 2

Client control . . . . . 2

Workload management . . . . . 2

## Chapter 2. Planning your installation . . . 3

Hardware requirements. . . . . 3

Supported software . . . . . 3

    Supported operating systems . . . . . 3

    Supported CICS servers . . . . . 4

    Support for SNA communications . . . . . 4

    Support for TCP/IP communications . . . . . 5

    Support for compilers and application development tools . . . . . 5

    Support for screen readers. . . . . 5

    Support for other tools . . . . . 5

CICS server PTF requirements . . . . . 5

    Terminal Sign-on capability . . . . . 6

    Timeout support . . . . . 6

Communication with CICS servers . . . . . 6

    Restrictions on CICS Transaction Server for iSeries 7

    Why use a particular protocol? . . . . . 7

Server code page support . . . . . 8

## Chapter 3. Installing CICS Universal Client. . . . . 9

Choosing what to install . . . . . 9

Preparing to install CICS Universal Client . . . . 9

Installing with the InstallShield wizard . . . . . 10

Installing from the command line . . . . . 11

Installing silently . . . . . 11

Actions after installation . . . . . 12

    Installing the Java runtime environment. . . . 12

    Verifying the system path. . . . . 12

    Assigning user rights (Windows 2000 service pack 4 or later) . . . . . 13

Adding features after installation . . . . . 13

Removing features . . . . . 13

Updating CICS Universal Client . . . . . 13

Uninstalling the CICS Universal Client . . . . . 14

    Uninstalling from the command line . . . . . 14

    Uninstalling silently . . . . . 14

Diagnosing problems with the installation and

uninstallation logs . . . . . 14

## Chapter 4. Configuring CICS server connections . . . . . 15

Configuring TCP/IP . . . . . 15

    Configuring TCP/IP on CICS Transaction Server

    for z/OS . . . . . 16

    Next steps. . . . . 17

Configuring SNA . . . . . 17

    Overview of SNA connection definitions . . . 18

    Configuring IBM Communications Server for ATI 18

    Defining SNA connections on CICS Transaction

    Server for z/OS . . . . . 22

Configuring named pipes. . . . . 24

Data conversion . . . . . 24

## Chapter 5. Configuring CICS Universal Client . . . . . 25

Before you start to configure your system . . . . 25

    Gathering information. . . . . 25

    Log on with administrator privileges . . . . 25

    Set the JVM . . . . . 26

    Set the time . . . . . 27

Using the Configuration Tool . . . . . 27

    Running the Configuration Tool for a different

    operating system . . . . . 27

    The Configuration Tool interface . . . . . 28

    Configuring the product setting . . . . . 31

    Configuring Client daemon settings . . . . . 31

    Configuring Server settings . . . . . 37

    Configuring the Workload Manager . . . . . 41

    Trace settings. . . . . 45

    Applying your changes to the system . . . . 46

Sample configuration and mapping files. . . . . 46

Editing the configuration file . . . . . 47

    CLIENT section of the configuration file. . . . 47

    SERVER section of the configuration file. . . . 49

    DRIVER section of the configuration file. . . . 50

    LOADMANAGER section of the configuration

    file . . . . . 50

    PRODUCT section of the configuration file. . . 51

Customizing cicsterm . . . . . 51

    Keyboard mapping for cicsterm . . . . . 51

    Customizing the screen colors for cicsterm . . 53

Disabling pop-up windows . . . . . 55

Checking your configuration . . . . . 55

## Chapter 6. Client security. . . . . 57

Client security overview . . . . . 57

Default connection settings . . . . . 57

    Security windows . . . . . 58

ECI security . . . . . 58

EPI terminal security . . . . . 59

    Changing the user ID and password . . . . . 59

Password expiry management . . . . . 59

Sign-on capable and sign-on incapable terminals . 59

    Specifying the sign-on capability of a terminal. . 60

## **Chapter 7. Performance . . . . . 63**

|  |    |
|--|----|
| System considerations . . . . .        | 63 |
| Tracing and performance . . . . .      | 63 |
| Performance monitoring tools . . . . . | 64 |

## **Chapter 8. Operating the Client daemon 65**

|  |    |
|--|----|
| The cicscli command . . . . .  | 65 |
| Starting the Client daemon . . . . .   | 65 |
| Starting connections with additional servers . . . . .                                 | 66 |
| Shutting down the Client daemon normally . . . . .                                     | 66 |
| Shutting down the Client daemon immediately . . . . .                                  | 66 |
| Restarting the Client daemon normally . . . . .  | 66 |
| Restarting the Client daemon immediately . . . . .                                     | 66 |
| Starting client tracing . . . . .  | 67 |
| Specifying the trace components . . . . .  | 67 |
| Stopping client tracing. . . . .   | 67 |
| Setting up security for the Client daemon . . . . .                                    | 68 |
| Displaying information about the version of the Client daemon . . . . .                | 68 |
| Listing the connected servers . . . . .  | 68 |
| Disabling the display of messages from the Client daemon . . . . .                     | 68 |
| Enabling and disabling the display of pop-up messages from the Client daemon . . . . . | 68 |
| Displaying command options for the Client daemon . . . . .                             | 69 |
| Alternative to cicscli.exe . . . . .   | 69 |
| cicscli command reference . . . . .  | 69 |
| Changing the system time . . . . .   | 72 |

## **Chapter 9. Terminal Emulation . . . . . 75**

|  |    |
|--|----|
| Summary of Terminal Emulation commands . . . . . | 75 |
| The cicsterm command . . . . .                   | 75 |
| Using cicsterm . . . . .                         | 75 |
| Stopping a terminal emulator . . . . .           | 76 |
| cicsterm and user exits . . . . .                | 76 |
| cicsterm and RETURN TRANSID IMMEDIATE . . . . .  | 76 |
| cicsterm command reference. . . . .              | 77 |
| Terminal emulator preferences . . . . .          | 79 |
| The cicsprnt command . . . . .                   | 80 |
| Using cicsprnt . . . . .                         | 80 |
| cicsprnt and user exits. . . . .                 | 81 |
| cicsprnt and RETURN TRANSID IMMEDIATE . . . . .  | 81 |
| cicsprnt command reference . . . . .             | 81 |

## **Chapter 10. Using the Workload Manager . . . . . 85**

|   |    |
|---|----|
| Workload Manager overview . . . . .               | 85 |
| Key concepts . . . . .                            | 85 |
| What the Workload Manager needs to know . . . . . | 86 |
| Load balancing algorithms . . . . .               | 88 |
| The round-robin algorithm . . . . .               | 88 |
| The biasing algorithm . . . . .                   | 88 |
| Workload Manager failure recovery . . . . .       | 88 |
| Workload Manager implementation . . . . .         | 89 |
| ECI implementation . . . . .                      | 89 |
| EPI implementation . . . . .                      | 89 |
| Workload Manager installation . . . . .           | 90 |
| Tracing the Workload Manager . . . . .            | 90 |

## **Chapter 11. Problem determination and problem solving. . . . . 91**

|  |     |
|--|-----|
| Problem determination: preliminary checks. . . . . | 91  |
| What to do next . . . . .                          | 91  |
| Problems installing the product. . . . .           | 91  |
| Problems with the Client daemon . . . . .          | 92  |
| Messages . . . . .                                 | 92  |
| Tracing . . . . .                                  | 93  |
| Diagnosing common problems . . . . .               | 98  |
| Telnet clients . . . . .                           | 105 |
| Program support . . . . .                          | 106 |
| Reporting problems . . . . .                       | 106 |
| Documenting problems . . . . .                     | 107 |
| Locating and compiling information. . . . .        | 108 |
| Submitting the documentation. . . . .              | 108 |
| APARs and fixes . . . . .                          | 109 |

## **Chapter 12. Migration . . . . . 111**

|   |     |
|---|-----|
| Migrating to Version 7.1 . . . . .                    | 111 |
| Migration considerations at Version 6 . . . . .       | 112 |
| Supported ECI and EPI versions . . . . .              | 112 |
| Change to maxrequests configuration setting . . . . . | 112 |
| Out-of-process libraries . . . . .                    | 112 |

## **Appendix. Data conversion . . . . . 115**

|                                      |     |
|--------------------------------------|-----|
| Data conversion on Windows . . . . . | 115 |
| Supported conversions . . . . .      | 115 |
| Arabic . . . . .                     | 117 |
| Baltic Rim . . . . .                 | 117 |
| Cyrillic . . . . .                   | 117 |
| Estonian . . . . .                   | 118 |
| Greek . . . . .                      | 118 |
| Hebrew . . . . .                     | 119 |
| Japanese . . . . .                   | 119 |
| Korean . . . . .                     | 120 |
| Latin-1 and Latin-9 . . . . .        | 121 |
| Latin-2 . . . . .                    | 122 |
| Latin-5 . . . . .                    | 123 |
| Simplified Chinese . . . . .         | 123 |
| Traditional Chinese . . . . .        | 124 |
| Vietnamese . . . . .                 | 124 |
| Unicode data . . . . .               | 124 |

## **The product library and related literature . . . . . 127**

|  |     |
|--|-----|
| CICS Universal Client books . . . . .          | 127 |
| Sample configuration documents . . . . .       | 127 |
| Redbooks. . . . .                              | 127 |
| Other Useful Books . . . . .                   | 128 |
| CICS Transaction Server publications . . . . . | 128 |
| Microsoft Windows publications . . . . .       | 128 |
| APPC-related publications . . . . .            | 129 |
| Obtaining books from IBM . . . . .             | 129 |

## **Accessibility features for CICS Universal Client . . . . . 131**

|  |     |
|--|-----|
| Installation . . . . .                     | 131 |
| Documentation. . . . .                     | 131 |
| Configuration Tool accessibility . . . . . | 131 |

|   |     |
|---|-----|
| Components. . . . .                         | 131 |
| Using help . . . . .                        | 131 |
| Keys . . . . .                              | 132 |
| Customizing colors and fonts . . . . .      | 134 |
| Screen readers and pop-up windows . . . . . | 134 |
| cicsterm . . . . .                          | 134 |
| The cicsterm -? command . . . . .           | 135 |

|                           |            |
|---------------------------|------------|
| <b>Glossary . . . . .</b> | <b>137</b> |
|---------------------------|------------|

|                        |            |
|------------------------|------------|
| <b>Index . . . . .</b> | <b>151</b> |
|------------------------|------------|

|                          |            |
|--------------------------|------------|
| <b>Notices . . . . .</b> | <b>155</b> |
|--------------------------|------------|

|                      |     |
|----------------------|-----|
| Trademarks . . . . . | 156 |
|----------------------|-----|

|   |            |
|---|------------|
| <b>Sending your comments to IBM . . . . .</b> | <b>159</b> |
|---|------------|





---

## About this book

This information describes the planning, installation, configuration, and operation of the IBM® CICS® Universal Client product.

You should be familiar with the operating system on which your CICS Universal Client runs.

This information is organized as shown in the following table:

| Topic   | Contents   |
|---|--|
| "What's new on the CICS Universal Client" on page ix                | Functional changes made in this version of CICS Universal Client.  |
| Chapter 1, "CICS Universal Client overview," on page 1              | Overview of CICS Universal Client and the functions it provides.   |
| Chapter 2, "Planning your installation," on page 3                  | Planning your installation, including the hardware and software you need to run CICS Universal Client.         |
| Chapter 3, "Installing CICS Universal Client," on page 9            | How to install CICS Universal Client.  |
| Chapter 4, "Configuring CICS server connections," on page 15        | How to set up communication links between CICS Universal Client and CICS servers.                              |
| Chapter 5, "Configuring CICS Universal Client," on page 25          | How to configure your CICS Universal Client.   |
| Chapter 6, "Client security," on page 57                            | How to provide a user ID and password when connecting to a CICS server.  |
| Chapter 7, "Performance," on page 63                                | How to tune your CICS Universal Client, and other system components, to achieve the best possible performance. |
| Chapter 8, "Operating the Client daemon," on page 65                | How to operate the Client daemon.  |
| Chapter 9, "Terminal Emulation," on page 75                         | How to use the cicsterm and cicsprnt programs.   |
| Chapter 10, "Using the Workload Manager," on page 85                | How to use the Workload Manager part of CICS Universal Client to distribute server workload.                   |
| Chapter 11, "Problem determination and problem solving," on page 91 | Problem determination and problem solving.   |
| Chapter 12, "Migration," on page 111                                | Migrating from an earlier version of CICS Universal Client.  |
| "Data conversion," on page 115                                      | Data conversion when using the Client daemon and a CICS server   |

---

## Installation path

The term <install\_path> is used in file paths to represent the directory where you installed the product. The default location for new installations is:

C:\Program Files\IBM\CICS Universal Client

If you are upgrading, the installation process keeps your existing directory structure.

---

## Information specific to your operating system

Unless otherwise specified, the term *Windows*<sup>®</sup> refers to Windows 2000, Windows 2003, Windows XP, and Windows Vista.

---

## What's new on the CICS Universal Client

CICS Universal Client Version 7.1 delivers extended interoperability in the following areas:

- TCP/IP network optimizations are provided to improve response times for Java clients connecting to CICS through the Gateway daemon.
- Support for fully qualified SNA partner LU names, provides for easier configuration of SNA clients in an APPN network, simplifying the migration of TCP62 connections to Enterprise Extender for customers who continue to require APPC interconnectivity in a TCP/IP network.

### Removed and changed function

For information on removed and changed function, see “Migrating to Version 7.1” on page 111.



---

## Chapter 1. CICS Universal Client overview

The CICS Universal Client enables users to access transactions and programs on the entire family of CICS application servers from their desktop. It can communicate with multiple CICS servers using a variety of protocols; see “Communication with CICS servers” on page 6. You use the Configuration Tool to determine the settings for client operation, and identify the associated servers and protocols used for communication (see “Using the Configuration Tool” on page 27).

---

### The external access interfaces (ECI, EPI, ESI)

The external interfaces allow non-CICS applications to access and update CICS resources by calling CICS programs or by initiating CICS transactions. When used in conjunction with CICS communication, the external interfaces enable non-CICS programs to access and update resources on any CICS system. This method of using the external interfaces supports such activities as the development of graphical user interface (GUI) front ends for CICS applications and it allows the integration of CICS systems and non-CICS systems.

#### External Call Interface (ECI)

The ECI enables a user application to call a CICS program synchronously or asynchronously. It enables the design of new applications to be optimized for client/server operation, with the business logic on the server and the presentation logic on the client.

#### External Presentation Interface (EPI)

The EPI enables a user application to act as a logical 3270 terminal and to control a CICS 3270 application. It enables modern technologies, such as graphical or multimedia interfaces, to be used with traditional CICS 3270 applications.

#### External Security Interface (ESI)

The ESI enables user applications to verify and change passwords for specified user IDs that are managed by an external security manager (ESM) on a CICS server.

For more information on the external access interfaces, see *CICS Transaction Gateway: Programming Guide* and *CICS Transaction Gateway: Programming Reference*.

---

### 3270 terminal emulation (cicsterm)

CICS 3270 terminal emulation enables a CICS Universal Client system to operate as a 3270 display for CICS applications, without needing a separate 3270 emulator product. Multiple CICS 3270 emulation sessions can run to one or more CICS servers.

You can use mapping files to customize the screen color attributes and keyboard settings of the client emulator, for example, to comply with company standard keyboard layouts.

CICS Client terminal definitions are autoinstalled on the CICS server and do not have to be predefined.

---

## 3270 printer support (cicsprnt)

CICS 3270 printer support allows you to define a printer terminal on a CICS Universal Client system. This support enables CICS applications running on a server to send output to a printer attached to the CICS Universal Client.

You can send output to a physical printer attached, for example, to the LPT1 port, or you can specify a command to process the data into a format more suitable for special-purpose printers.

CICS 3270 printer support uses CICS 3270 terminal emulation. Table 1 on page 7 in topic “Communication with CICS servers” on page 6 tells you which CICS servers currently support CICS 3270 emulation and hence CICS 3270 client printer support.

---

## Client control

Commands or icons exist to:

- **Control the client process**

You can:

- Start or stop the client process
- Turn client trace on or off
- Specify the client components to be traced
- Set up security by specifying user IDs and passwords for a CICS server
- List connected servers
- Enable and disable the display of pop-up messages
- Perform controlled restarts of the client process

- **Control terminal emulation**

You can:

- Start and stop the terminal emulator
- Specify the initial transaction
- Define the terminal characteristics
- Specify the name of the keyboard and screen color mapping files
- Define the command used to process print requests
- Specify the name of a file used for appending print requests.

- **Control client printer operation**

You can:

- Start and stop the client printer emulator
- Specify the initial transaction to be run against the client printer
- Define the printer terminal characteristics
- Define the command used to process print requests
- Specify the name of a file used for appending print requests.

---

## Workload management

CICS Universal Client provides *load balancing*, which allows the transaction workload to be distributed across multiple CICS regions or CICS servers.

### **Related information**

“Configuring the Workload Manager” on page 41

Chapter 10, “Using the Workload Manager,” on page 85

---

## Chapter 2. Planning your installation

This information helps you to plan the installation of the CICS Universal Client by listing the hardware and software that you need. The CICS servers to which CICS Universal Client can connect are also listed.

If you are using an earlier version of the product see Chapter 12, “Migration,” on page 111 for a discussion of migration issues.

See the product readme file for any late changes to hardware and software requirements:

- If you are installing from CD, the readme file is README.WIN in the root directory.
- If you downloaded the product, the packaged file that you downloaded contains the product code and the readme file for your operating system.

When you install the CICS Universal Client, the readme file is copied into your installation directory as readme.txt.

---

### Hardware requirements

CICS Universal Client requires the following hardware:

- An IBM eServer™ zSeries® system or S/390® system supported by Linux®
- An Intel® 32-bit system supported by Linux
- An IBM eServer pSeries®, iSeries®, or Open Power™ system supported by Linux
- An IBM eServer pSeries system supported by AIX®
- A Sun SPARC system supported by Sun Solaris
- An HP PA-RISC 1.1 or 2.0 system supported by HP-UX
- An HP Itanium system supported by HP-UX
- An Intel 32-bit system supported by Microsoft® Windows

---

### Supported software

For the latest details about supported software, visit the Web site at <http://www.ibm.com/software/cics/cuc/support>.

The CICS Universal Client works with the following products:

### Supported operating systems

CICS Universal Client is supported on the following operating systems:

- Windows 2000 Professional with service pack 4 minimum service level. CICS Universal Client is supported on 32-bit distributions only.
- Windows XP Professional with service pack 2 minimum service level. CICS Universal Client is supported on 32-bit distributions only.
- Windows Vista Business Edition. CICS Universal Client is supported on 32-bit distributions only.
- Windows Vista Enterprise Edition. CICS Universal Client is supported on 32-bit distributions only.

- Windows Vista Ultimate Edition. CICS Universal Client is supported on 32-bit distributions only.

**Notes:**

- The setting of multiple user interface languages, under Windows 2000 MultiLanguage Version and Windows 2003, is not supported.
- Multiple concurrent users using different user interface languages are not supported. This situation can occur when using Windows XP fast user switching.
- Only the CICS Transaction Gateway, not the CICS Universal Client, is licensed for use with Windows 2000 Terminal Services.

## Supported CICS servers

The CICS Universal Client is supported by the following CICS servers:

- CICS Transaction Server for z/OS® V2.2:
  - Apply APAR PQ92943 and PK17427 for EXCI.
  - Apply APAR PK08496 for mixed-case password support.
  - If connecting over TCP/IP apply APAR PQ75803 and PQ82124.
  - Apply APAR PQ70543 for better recovery for EPI and cicsterm requests made over SNA, after a failure of CICS or the network.
- CICS Transaction Server for z/OS V2.3:
  - Apply APAR PQ92943 and PK17427 for EXCI.
  - Apply APAR PK08496 for mixed-case password support.
  - If connecting over TCP/IP to apply APAR PQ81772 and PQ82124.
- CICS Transaction Server for z/OS V3.1:
  - Apply APAR PK17426 for EXCI.
- CICS Transaction Server for z/OS V3.2:
  - Apply APAR PK51587 for z/OS CICS security violation.
- CICS/VSE 2.3:
  - Apply APAR PQ30169 for EPI support.
- CICS Transaction Server for VSE/ESA™ 1.1.1:
  - If connecting over TCP/IP apply APAR PQ80212 and APAR PQ52342.
  - Apply APAR PQ30170 for EPI support.
- TXSeries® V5.1 (Windows, AIX, Solaris, HP-UX).
- TXSeries V6.0 and V6.1 (AIX and Linux on Intel PRPQ).
- CICS Transaction Server for Windows V5.0.
- CICS Transaction Server for iSeries V5.3 and V5.4..

## Support for SNA communications

Customers wishing to use SNA communications must install one of the following products:

- IBM Communications Server V6.1 for Windows. V6.1.2 is required. There is no Vista support until V6.1.3.
- IBM Personal Communications V5.9 for Windows
- IBM Personal Communications V5.8 for Windows
- Microsoft Host Integration Server 2006



- Microsoft Host Integration Server 2004
- IBM Communications Server remote API Client V6.1.0.3

If you are using Microsoft Host Integration Server, you might need to configure the CICS TG with a Windows domain logon with the appropriate access to the HIS server. If the service does not have the appropriate security access, the following error will be seen in the cicscli.log:

CCL4661E: SNA stack component not loaded or terminated, APPC return code X'F004'.

## Support for TCP/IP communications

The operating system provides TCP/IP support.

## Support for compilers and application development tools

CICS Universal Client supports the following compilers and application development tools:

- Microsoft Visual C++ .NET 2003
- Microsoft Visual C++ 2005
- Visual Basic .NET Standard 2003
- Microsoft Visual Basic 2005
- Micro Focus Net Express V4.0, COBOL compiler for Windows
- IBM COBOL for Windows V6.0, supplied with WebSphere® Developer for z/OS V6.0
- IBM COBOL for Windows V7.0, supplied with WebSphere Developer for z/OS V7.0

CICS Universal Client does not support the use of the COM libraries with Microsoft Transaction Server (MTS) or the MTS component of COM+.

## Support for screen readers

CICS Universal Client supports JAWS, the minimum level supported is V6.0.

## Support for other tools

CICS Universal Client supports the following tools:

- Adobe Acrobat Reader 6.0
- JAWS Screen Reader V6.0. (Version 6.0 is a minimum requirement)
- Citrix Presentation Server V4.0
- Citrix Presentation Server V4.5

---

## CICS server PTF requirements

See the README file for the latest details on APARs and PTFs applicable to the CICS Universal Client.

### Terminal sign-on capability

CICS servers require APAR fixes to support the terminal sign-on capability available in this release of CICS Universal Client; see “Supported software” on page 3 for details of the APAR relating to your CICS server. If the server does not have the required APAR applied and the ‘-a’ option is not specified when the

cicsterm command is issued, the installed terminal will give unpredictable results.

## Timeout support

Any TXSeries or CICS Transaction Server on the Windows and UNIX® operating systems must include the appropriate PTF level to provide complete support for timeouts. See “Supported software” on page 3 for details.

If the server does not have the required APAR applied and the ‘-a’ option is not specified when the cicsterm command is issued, the CTIN transaction abends with code A42B. You see the following:

- The CICS Universal Client displays the message:  
CCL7053E Errors found while communicating with server
- This message is written to cicscli.log:  
CCL3105 Inbound CICS data stream error (CTIN,4, 0)
- On the server, this message is written to CSMT.out:  
ERZ042004E/0112: An invalid request was received from client
- console.msg includes this message:  
ERZ014016E/0036: Transaction CTIN Abend A42B

## Terminal Sign-on capability

CICS servers require APAR fixes to support the terminal sign-on capability function available in this release; see “Supported software” on page 3 for details of the APAR relating to your CICS server. If the server does not have the required APAR applied and the ‘-a’ option is not specified when the cicsterm command is issued, the installed terminal will give unpredictable results.

## Timeout support

Any TXSeries or CICS Transaction Server on the Windows and UNIX operating systems must include the appropriate PTF level to provide complete support for timeouts. See “Supported software” on page 3 for details.

If the server does not have the required APAR applied and the ‘-a’ option is not specified when the cicsterm command is issued, the CTIN transaction abends with code A42B. You see the following:

- The CICS Universal Client displays the message: CCL7053E Errors found while communicating with server
- This message is written to cicscli.log:  
CCL3105 Inbound CICS data stream error (CTIN,4, 0)
- On the server, the message: ERZ042004E/0112: An invalid request was received from client is written to CSMT.out
- console.msg includes this: ERZ014016E/0036: Transaction CTIN Abend A42B

---

## Communication with CICS servers

You can use these protocols to communicate with CICS servers:

### TCP/IP

TCP/IP is a widely used, robust, suite of protocols, particularly useful in connecting heterogeneous networks.

### SNA

The CICS Universal Client uses Advanced Program-to-Program Communication (APPC) to provide SNA LU 6.2 communication. APPC is

an implementation of the SNA LU 6.2 protocol that provides device-independent application-to-application communication over LU 6.2 sessions.

### Local Named Pipe

TXSeries for Windows and CICS Transaction Server for Windows can use the Local Named Pipe protocol to communicate with a CICS Universal Client that is on the same computer, providing a fast communications method independent of any network protocol. Named Pipe Communications are not supported on Windows Vista.

The protocols that you can use for the various client/server connections are shown in Table 1. This table lists the protocols that you can use to connect your CICS Universal Client to your CICS server. It also shows whether EPI emulation and ECI are supported for your combination of CICS server and CICS Universal Client operating system. ● indicates that the protocol or feature is supported; ○ indicates that it is not supported.

Table 1. Protocols and functions supported.

| SERVER   | TCP/IP               | SNA | ECI | EPI<br>See note | ESI |
|--|----------------------|-----|-----|-----------------|-----|
| CICS Transaction Server for z/OS V3.2                | ● (ECI only)         | ●   | ●   | ●               | ●   |
| CICS Transaction Server for z/OS V2.2, V2.3 and V3.1 | ● (ECI only)         | ●   | ●   | ●               | ●   |
| CICS Transaction Server for VSE/ESA V1.1.1           | ● (ECI only)         | ●   | ●   | ●               | ●   |
| CICS/VSE® V2.3                                       | ○                    | ●   | ●   | ●               | ●   |
| TXSeries V5.1, V6.0 and V6.1                         | ● (ECI and EPI only) | ○   | ●   | ●               | ○   |
| CICS Transaction Server for Windows V5.0             | ●                    | ○   | ●   | ●               | ○   |
| CICS Transaction Server for iSeries V5.3             | ●                    | ●   | ●   | ●               | ●   |
| CICS Transaction Server for i5/OS® V5.4              | ●                    | ●   | ●   | ●               | ●   |

**Note:** EPI also incorporates CICS 3270 terminal emulation and CICS 3270 client printer support.

## Restrictions on CICS Transaction Server for iSeries

The following restrictions apply:

- DBCS languages are supported when communicating using ECI but not EPI.
- Sign-on capable terminals are not supported.
- You cannot start the CEDA transaction from a client terminal.
- You cannot use PF1 to obtain CICS online help from a client terminal.

## Why use a particular protocol?

As shown in table Table 1, some protocols can be used only for certain types of client/server connection. Access to 3270-based CICS transactions might require an SNA connection. SNA network connections are the recommended approach,

because they can be routed over IP networks using the SNA Remote API Client or Enterprise Extender and they do not require complex AnyNet<sup>®</sup> definitions.

For information on continuing AnyNet support in z/OS Communications Server, refer to the information in the z/OS Statements of direction announcement, Software Announcement 203-266, dated October 7, 2003, and the z/OS V1.7 preview announcement, Software Announcement 205-034, dated February 15, 2005.

---

## Server code page support

Some CICS servers do not support all the code pages that are supported by the operating system on which CICS Universal Client is running.

If the code page of an ECI application is different from the code page of the server, data conversion must be performed at the CICS server. This restriction applies for EBCDIC CICS servers such as CICS Transaction Server for z/OS. For more information, see “Data conversion,” on page 115, the CICS server documentation, and the Redbook *Java Connectors for CICS*.

---

## Chapter 3. Installing CICS Universal Client

To install CICS Universal Client follow the steps in these topics:

---

### Choosing what to install

You can choose either a complete or custom installation.

#### Complete installation

Installs all features:

- Program files
- Development kit, consisting of the following features:
  - Programming samples (installed to <install\_path>\samples\)
  - Toolkit (includes Javadoc information)

into the default installation directory (see “Installation path” on page vii). The path is updated.

#### Custom installation

To perform a custom installation:

- Select the features to install
- Specify the target drive and directory
- Optionally update the path

For both types of installation:

- All shortcuts are created in the IBM CICS Universal Client folder in the **Start -> Programs** menu for all users.

---

### Preparing to install CICS Universal Client

Before you install CICS Universal Client, perform the following steps as appropriate:

1. Check that your operating system is supported; see “Supported software” on page 3 for supported operating systems.
2. Log on with administrator privileges. Only users with Administrator authority can install and uninstall CICS Universal Client to the C:\Program Files directory. You can have Administrator privileges by being a member of the local Administrators group or by being a domain Administrator. For Windows Vista, elevated authority is required. Alternatively the `cicscli` variable can define the configuration file in a directory that can be accessed by a CICS Transaction gateway administrator.
3. Close down any programs that are running, including the following:
  - Client daemon (issue the `cicscli -x` command)
  - Configuration Tool
4. The installation process can upgrade from the CICS Transaction Gateway V5 or later. Remove any other versions of the CICS Transaction Gateway and CICS Universal Client before installing this product. Remove any beta versions of the product. When a computer is upgraded from a previous version of Windows to Windows Vista, CICS Transaction GatewayCICS Universal Client must be uninstalled prior to the Windows upgrade.

5. If multisession Terminal Services are installed, ensure that your session is correctly configured to install new software. Take one of the following steps:
  - Install using **Add or Remove Programs** on the Control Panel.
  - At a command prompt, type `change user /install` to place the system in install mode. When the installation has finished, type `change user /execute` at the command prompt to return the system to execute mode.
6. If you are migrating from V5.x, and your existing version of the product uses Network Provider Interface (you selected the **Use Windows credentials for security** option on the Server connection panel of the Configuration Tool), take the following steps before you install this version:
  - a. At a command prompt, change to this directory:  
`\Program Files\Common Files\IBM\IBM Integrated Sign On`
  - b. Enter `bthdinst -u CICSCLI`
  - c. Reboot.
7. If you are installing the CICS Universal Client onto a workstation that already has a CICS for Windows server installed, uninstall the CICS Universal Client that is supplied with the CICS for Windows server before you install the CICS Universal Client.

---

## Installing with the InstallShield wizard

Follow these steps to install CICS Universal Client with the InstallShield wizard:

1. Insert the CD into the drive. If installing from a network drive, connect to the drive.
2. From the Control Panel, click **Add/Remove Programs -> Add New Programs**. Click the **CD or Floppy** button.
3. Click **Next**, then type `d:\windows\installer.exe`, where d: is your CD or network drive. A message box informs you that a Java™ virtual machine is being installed. This is used only by the installation and uninstallation processes; refer to the license for restrictions on the use of this JRE. Be prepared for a pause before the next screen is displayed.
4. A welcome screen is displayed. Click **Next**.
5. If you are upgrading, you see the Upgrade warning screen. Click **Next** to continue.
6. The license agreement is displayed. Read the agreements, click the appropriate radio button, and then click **Next**. You must accept all license agreements that are shown to continue the installation. License files are stored in the `<install_path>\license` subdirectory, in plain text format. If you run a console-based installation in a DBCS locale, the License agreement is displayed in English and not the local language. Installation using a Graphical User Interface is not affected.
7. The README file is displayed, giving details of any late changes to the product. Read it and then click **Next**.
8. Choose the type of installation required. Select **Complete** or **Custom** as appropriate, and then click **Next**.  
If you chose a complete installation, go to step 12 on page 11. If you chose a custom installation, continue at step 9.
9. Specify the directory to which you want to install CICS Universal Client. This option is not available if you are upgrading; in that case, CICS Universal Client is installed in the same location as your existing installation.

10. A screen showing the features that can be installed is displayed. Select the check box for each feature that you want to install.
11. Select the appropriate option from the Install Options screen that is displayed:  
**Yes, update the PATH environment variable**  
You are recommended to leave this option selected, to update the system path. If you clear this box you will have to update the path manually.
12. (Resume here if you chose a complete installation in step 8 on page 10.)  
Information about the choices you have made is displayed on your screen. Read the information and then click **Next** to start installing. The installation process keeps you informed of progress.
13. Read the information about configuring the product and click **Finish** to end the installation process.

---

## Installing from the command line

To install from the command line, take the following steps:

1. Insert the CD into the drive. If installing from a network drive, connect to the drive.
2. Issue the following command:  
`d:\windows\installer.exe -console`

where d: is the CD or network drive that contains the installation files.

You cannot cancel a command-line installation after the installer has started to copy files.

---

## Installing silently

You can silently install CICS Universal Client without going through any of the installer screens. The installation process takes its input from a response file; no user input is required. If you do not provide a response file, all default options are used.

### Creating a response file

Use one of the following methods to create a response file:

- Use the supplied sample file `installResponseSamp.txt`. Edit this file as appropriate.
- Create a response file by installing the CICS Universal Client and recording the responses that you enter. Issue the following command:  
`installer.exe -options-record full_path_name\response_file_name`

This command stores your responses in file *response\_file\_name*. Note that there is no space between `-options` and `-record`.

### Using the response file to install silently

To install silently, take the following steps:

1. Make the response file and the install image available to the computer on which the CICS Universal Client is to be installed.
2. Issue the following command:

```
installer.exe -options "full_path_name\response_file_name" -silent -V licenseAccepted=true
```

### Installing silently with no response file

To install silently without using a response file, issue the following command:

```
installer.exe -silent -V licenseAccepted=true
```

All options will take default values.

---

## Actions after installation

After installing CICS Universal Client you may do the following:

### Installing the Java runtime environment

You need Java to run the Configuration Tool.

Install the JRE from the following location:

d:\JRE\Windows

where d: is the CD drive that contains the CD.

### Assigning user rights (Windows 2000 service pack 4 or later)

Service pack 4 for Windows 2000 introduced a new user right "Impersonate a client after authentication".

Users of the CICS Universal Client might need this right; see "Starting clients and terminals" on page 99 for information on how to grant users the right.

#### Related information

"Set the JVM" on page 26

Under Windows, you can have more than one Java Virtual Machine (JVM) installed on a machine. If so, applications must know which one to use. The `ctgjava` command allows you to view or alter the JVM used by the CICS Universal Client. The examples in this information use the dash character (-); you may use either the dash (-) or the forward slash (/).

## Installing the Java runtime environment

You need Java to run the Configuration Tool.

Install the JRE from the following location:

d:\JRE\Windows

where d: is the CD drive that contains the CD.

#### Related information

"Set the JVM" on page 26

Under Windows, you can have more than one Java Virtual Machine (JVM) installed on a machine. If so, applications must know which one to use. The `ctgjava` command allows you to view or alter the JVM used by the CICS Universal Client. The examples in this information use the dash character (-); you may use either the dash (-) or the forward slash (/).

## Verifying the system path

Make sure that an entry for `<install_path>\bin` (the path to the CICS Universal Client executable files) appears before any network directories in your PATH statements.



Because the CICS Universal Client runs as a Windows service, its environment is determined when the system is started and is formed from system environment variables only. The environment used by Windows services is established before the network drives are attached when Windows starts. Consequently, any directory in the system PATH that involves a network drive is not available to Windows services.

Some Windows versions discard the remainder of a PATH if they find a nonexistent directory, and you might have problems running your CICS Universal Client if network directories (or nonexistent local directories) are in your system PATH before the CICS Universal Client executable files paths.

## Assigning user rights (Windows 2000 service pack 4 or later)

Service pack 4 for Windows 2000 introduced a new user right "Impersonate a client after authentication".

Users of the CICS Universal Client might need this right; see "Starting clients and terminals" on page 99 for information on how to grant users the right.

---

## Adding features after installation

To add features after installation:

1. Follow the steps in "Installing with the InstallShield wizard" on page 10 as far as step 8 on page 10.
2. Select **Custom** as the type of installation and select the features that you want to install.
3. Complete the remaining steps in the installation process to add the new features.

---

## Removing features

1. From the Control Panel, click **Add/Remove Programs** → **Change or Remove Programs**.
2. Find IBM CICS Universal Client in the list of programs and click **Change/Remove**.
3. Click **Next** on the Welcome screen.
4. The uninstaller screen is displayed, with all features selected. Leave selected the features that you want to remove; deselect any features that you want to keep. Click **Next**.
5. Read the summary information and then click **Next** to remove the features.
6. Click **Finish** when prompted.

---

## Updating CICS Universal Client

After installing CICS Universal Client, you can update the product or obtain corrective service software ("fixes").

For information about corrective service software, visit the Web site at [www.ibm.com/software/cics/cuc](http://www.ibm.com/software/cics/cuc) and follow the **Support** link.

---

## Uninstalling the CICS Universal Client

To uninstall the CICS Universal Client, take the following steps:

1. Click **Start->Settings->Control Panel-Add/Remove Programs**.
2. Find the CICS Universal Client in the list of programs and then click **Change/Remove**.

### Uninstalling from the command line

Issue the following command:

```
ctguninst -console
```

### Uninstalling silently

Issue the following command:

```
ctguninst [-options "response_file_name"] -silent
```

You do not have to provide a response file. If you do not, the whole product is uninstalled.

## Uninstalling from the command line

Issue the following command:

```
ctguninst -console
```

## Uninstalling silently

Issue the following command:

```
ctguninst [-options "response_file_name"] -silent
```

You do not have to provide a response file. If you do not, the whole product is uninstalled.

---

## Diagnosing problems with the installation and uninstallation logs

Errors and warnings generated during the installation or uninstallation of the CICS Universal Client are recorded in the appropriate log file. The log files, if created, are at the following locations:

### Installation

```
%temp%\cicsucInstall.log
```

### Uninstallation

```
%temp%\cicsucUninstall.log
```

If a log file already exists, any new messages are appended to the end of the file.

Use the log to diagnose any problems that might have caused an installation or uninstallation to fail, especially in silent mode which has no user interaction with the program.

---

## Chapter 4. Configuring CICS server connections

After you have installed the CICS Universal Client and set up your CICS servers for communication, your next step is to set up the communication links between the CICS Universal Client and your CICS servers.

After you have set up your communications links, continue at Chapter 5, “Configuring CICS Universal Client,” on page 25, which tells you how to make the required entries in the configuration file.

### Related information

“Sample configuration documents” on page 127

---

## Configuring TCP/IP

The TCP/IP stack on your local machine should already be correctly configured. Contact your system administrator if you encounter problems.

### Verifying the TCP/IP installation

To verify that the CICS Universal Client can communicate with CICS servers, use the TCP/IP PING command to check the route to the CICS server:

```
ping [machine address | name]
```

To start PING, enter a command like the following:

```
ping 192.113.36.200
```

where 192.113.36.200 is the IP address of your CICS server. If you are using a *Domain Name Server (DNS)*, you can specify the symbolic host name rather than the IP address of the server.

If the statistics message shows a value other than 0% packet loss, it is possible that TCP/IP is not correctly configured:

- Check for TCP/IP definition errors.
- Check the physical connection to the network.

The PING command differs slightly, depending on your operating system. For more information, refer to the documentation supplied with your operating system.

Refer to “TCP/IP settings” on page 39 for information on TCP/IP settings.

### Configuring TCP/IP on CICS Transaction Server for z/OS

CICS Universal Client can send ECI requests over TCP/IP to CICS Transaction Server for z/OS V2.2 and later. To perform this configuration:

1. Set the SIT parameter TCPIP=YES.
2. Install the following:
  - CICS-supplied transient data queue CIEO, in group DFHDCTG
  - Transaction CIEP in group DFHIPECI
  - Program DFHIEP in group DFHIPECI

3. Define the TCP/IP address and host name for the z/OS system. By default they are defined in the PROFILE.TCPIP and TCPIP.DATA data sets.
4. Add a TCP/IP listener to CICS. Use the following CEDA command to define a TCPIPSERVICE in a group:

```
CEDA DEF TCPIPSERVICE(service-name) GROUP(group-name)
```

Ensure that the group in which you define the service is in the startup GRPLIST, so that the listener starts when CICS is started. Key fields are explained as follows:

**POrtnumber**

The port on which the TCP/IP service listens.

**PRotocol**

The protocol of the service is ECI.

**TRansaction**

The transaction that CICS runs to handle incoming ECI requests. Set it to CIEP.

**Backlog**

The number of TCP/IP requests that are queued before TCP/IP starts to request incoming requests.

**Ipaddress**

The IP address (in dotted decimal form) on which the TCPIPSERVICE listens. For configurations with more than one IP stack, specify ANY to make the TCPIPSERVICE listen on all addresses.

**SOcketclose**

Whether CICS should wait before closing the socket after issuing a receive for incoming data on that socket. NO is recommended for ECI connections, to ensure that the connection from the Client daemon always remains open.

**ATtachsec**

Specifies the level of attach-time security required for TCP/IP connections.

5. Use the following command to install the TCPIPSERVICE definition:

```
CEDA INS TCPIPSERVICE(service-name) GROUP(group-name)
```

**Next steps**

1. Use the Configuration Tool to create a server definition; see “The Configuration Tool interface” on page 28.
2. Configure the server definition; see “Configuring Server settings” on page 37.

## Configuring TCP/IP on CICS Transaction Server for z/OS

CICS Universal Client can send ECI requests over TCP/IP to CICS Transaction Server for z/OS V2.2 and later. To perform this configuration:

1. Set the SIT parameter TCPIP=YES.
2. Install the following:
  - CICS-supplied transient data queue CIEO, in group DFHDCTG
  - Transaction CIEP in group DFHIPECI
  - Program DFHIEP in group DFHIPECI
3. Define the TCP/IP address and host name for the z/OS system. By default they are defined in the PROFILE.TCPIP and TCPIP.DATA data sets.

4. Add a TCP/IP listener to CICS. Use the following CEDA command to define a TCPIP SERVICE in a group:

```
CEDA DEF TCPIP SERVICE(service-name) GROUP(group-name)
```

Ensure that the group in which you define the service is in the startup GRPLIST, so that the listener starts when CICS is started. Key fields are explained as follows:

**Portnumber**

The port on which the TCP/IP service listens.

**Protocol**

The protocol of the service is ECI.

**Transaction**

The transaction that CICS runs to handle incoming ECI requests. Set it to CIEP.

**Backlog**

The number of TCP/IP requests that are queued before TCP/IP starts to request incoming requests.

**Ipaddress**

The IP address (in dotted decimal form) on which the TCPIP SERVICE listens. For configurations with more than one IP stack, specify ANY to make the TCPIP SERVICE listen on all addresses.

**Socketclose**

Whether CICS should wait before closing the socket after issuing a receive for incoming data on that socket. NO is recommended for ECI connections, to ensure that the connection from the Client daemon always remains open.

**Attachsec**

Specifies the level of attach-time security required for TCP/IP connections.

5. Use the following command to install the TCPIP SERVICE definition:

```
CEDA INS TCPIP SERVICE(service-name) GROUP(group-name)
```

## Next steps

1. Use the Configuration Tool to create a server definition; see “The Configuration Tool interface” on page 28.
2. Configure the server definition (see “Configuring Server settings” on page 37.)

---

## Configuring SNA

You need to install and configure an SNA communications server, such as IBM Communications Server. To set up communication over SNA define the following in your SNA communications product.

- The **local node characteristics** that are common to all SNA users at the workstation.
- A **local logical unit (LU)** for the CICS Universal Client.
- A **partner logical unit** for each CICS server with which the CICS Universal Client will communicate.
- One or more **modes** to specify sets of session properties that are used in binding SNA sessions.

- A **transaction program (TP)** for the CRSR transaction. You need this if the following apply:
  - The CICS servers support terminal emulation, and
  - You require automatic transaction initiation (ATI) against the CICS Universal Client terminals.

The terms used to describe these definitions vary with the product used to provide support. The terms used above are the ones used by IBM Communications Server.

SNA links to the CICS Universal Client support data synchronization levels (sync levels) 0 and 1.

## Overview of SNA connection definitions

This topic provides an overview on how to configure SNA.

The following sections summarize configuration. Configuration requires action on VTAM®, CICS, the CICS Universal Client, and one of the following:

- Personal Communications
- Communications Server
- Microsoft Host Integration Server

Install and configure only one of these products. If you have more than one product installed on your machine, you might experience unexpected results. Table 2 shows the entries that you need to make. The values in the Example column are taken from the sample configuration documents.

*Table 2. Matching definitions for SNA*

| VTAM                           | CICS     | Personal Communications        | Communications Server          | Microsoft Host Integration Server | Configuration file | Example      |
|--------------------------------|----------|--------------------------------|--------------------------------|-----------------------------------|--------------------|--------------|
| NETID                          | —        | First part of Partner LU name  | First part of Partner LU name  | Network Name                      | Partner LU name    | ABC3XYZ4     |
| PU                             | —        | CP name                        | CP name                        | Control Point Name                | —                  | IYAMR004     |
| LU                             | Netname  | Local LU alias                 | Local LU alias                 | LU Name                           | Local LU name      | IYAMT040     |
| XID                            | —        | Local Node ID                  | Local Node ID                  | Local Node ID                     | —                  | 05D 316DF    |
| Token Ring destination address | —        | Destination address            | Destination address            | Remote Network Address            | —                  | 400045121088 |
| APPL                           | Applid   | Second part of Partner LU name | Second part of Partner LU name | Remote LU Name                    | Partner LU name    | IYCKCTU1     |
| LogMode                        | Modename | Mode name                      | Mode name                      | Mode Name                         | Mode name          | LU62PS       |
| SSCP                           | —        | Adjacent CP name               | —                              | —                                 | —                  | —            |

## Configuring IBM Communications Server for ATI

### SNA using IBM Communications Server

Install Communications Server client on a machine that contains the CICS Universal Client, which in turn communicates with the CICS server through the Communications Server machine.




Figure 1. SNA using IBM Communications Server

For information on installing and configuring Communications Server and Communications Server clients, see the *IBM Communications Server Quick Beginnings*.

Run **Configuration** to configure Global Data and the LU6.2 Server List.

**Setting up the Communications Server (server):** Run SNA Node Configuration to configure SNA support, define a connection and the local LU, partner LU, and mode specified in the configuration file. Configure the local LU to be independent.

If you are using a Communications Server SNA Client, you must select the **SNA API client use** check box in the Local LU 6.2 definition panel.

To enable ATI against CICS Client terminals, define the transaction program CRSR on the Communications Server, whether or not a Communications Server SNA Client is being used:

**TP name**  
CRSR

**Service TP**  
No

**Complete pathname**  
<install\_path>\bin\cclclnt.exe

**Program parameters**  
CRSR

**Conversation type**  
Mapped

**Synchronization level**  
Any

**Conversation security required**  
No

**Receive\_Allocate timeout**  
0

**Incoming allocate timeout**  
Default

**TP instance limit**  
1

**PIP allowed**  
No

**SNA Client**

Yes/No

**Dynamically loaded**

No

**Full duplex support**

No

**Setting up the Communications Server Windows (client):**

To set up the Communications Server Windows (client) you must complete the following actions:

1. Run **Configuration** to configure Global Data and the LU6.2 Server List.
2. To enable ATI against CICS Client terminals, define the transaction program CRSR on the SNA Client:

**TP name**

CRSR

**LU alias**

Alias of the local LU defined for the connection

**Complete pathname**

&lt;install\_path&gt;\bin\cclclnt.exe

Your <install\_path> must not contain spaces; use short file and directory names.

**Program operation**

Attach Manager Started

**Program parameters**

CRSR

**Service TP**

No

**Attach Manager Started**

No

3. Start the Attach Manager.

**Configuring IBM Personal Communications**

To configure and run IBM Personal Communications carry out the following steps:

1. Run SNA Node Configuration to configure SNA support.
2. Define a node, a device, and a connection. Use an adjacent CP type of APPN Node or Back-Level LEN in the connection definition.
3. Define the local LU, partner LU, and mode specified in the configuration file. Configure the local LU to be independent.
4. Start the node from SNA Node Operations before starting a connection from the Client daemon to a server that uses Personal Communications.
5. To enable ATI against CICS client terminals, define the transaction program CRSR:

**TP name**

CRSR

**Service TP**

No



**Complete pathname**

<install\_path>\bin\cclclnt.exe

Your <install\_path> must not contain spaces; use short file and directory names.

**Program parameters**

CRSR

**Conversation type**

Mapped

**Synchronization level**

Any

**Conversation security required**

No

**Receive\_Allocate timeout**

0

**Incoming allocate timeout**

Default

**TP instance limit**

1

**PIP allowed**

No

**SNA Client**

Yes/No

**Dynamically loaded**

No

**Full duplex support**

No

**Running Personal Communications**

Start the IBM Personal Communications node before you start an SNA connection from the Client daemon.

**Running Personal Communications:** Start the IBM Personal Communications node before you start a SNA connection from the Client daemon.

**Microsoft Host Integration Server (SNA Server)**

This topic provides an overview of installing, setting up, and configuring Microsoft Host Integration Server (SNA Server).

**Installing Microsoft Host Integration Server (SNA Server)**

1. Install Host Integration Server client on a machine that contains the CICS Universal Client, which in turn communicates with the CICS server through the Host Integration Server machine. For information on installing and configuring Microsoft Host Integration Server and Host Integration Server clients, see the Microsoft Host Integration Server documentation.
2. To allow workstations using the Windows SNA Client to communicate with other systems, define the LUs used by the client systems as Local APPC LUs to the Host Integration Server workstation.

## Setting up the Host Integration Server Windows client

1. On the Host Integration Server Windows client, enter the following:

### **SNA client mode**

Remote

### **Primary Server**

Name of the Host Integration Server workstation that the client systems using SNA Client will use. This computer name of the Host Integration Server is displayed in both the Host Integration Server Admin **Servers and Connections** window, and in the **Network Settings** control panel dialog box.

2. Run SNABASE.EXE to start the Host Integration Server Client SnaBase. If you do not, the CICS Universal Client cannot communicate with the Host Integration Server.
3. Start the Host Integration Server Windows client.

## Configuration documentation

More information on connecting CICS Transaction Gateway to CICS Transaction Server for z/OS, using Host Integration Server, is in *CICS Transaction Gateway V5 The WebSphere Connector for CICS*.

## Setting up the Host Integration Server Windows client:

1. On the Host Integration Server Windows client, enter the following:

### **SNA client mode**

Remote

### **Primary Server**

Name of the Host Integration Server workstation that the client systems using SNA Client will use. This computer name of the Host Integration Server is displayed in both the Host Integration Server Admin **Servers and Connections** window, and in the **Network Settings** control panel dialog box.

2. Run SNABASE.EXE to start the Host Integration Server Client SnaBase. If you do not, the CICS Universal Client cannot communicate with the Host Integration Server.
3. Start the Host Integration Server Windows client.

**Configuration documentation:** More information on connecting CICS Transaction Gateway to CICS Transaction Server for z/OS, using Host Integration Server, is in *CICS Transaction Gateway V5 The WebSphere Connector for CICS*.

## Defining SNA connections on CICS Transaction Server for z/OS

To define SNA connections from CICS do the following:

1. Specify the SIT parameter ISC=YES.
2. Install CSD groups DFHCLNT and DFHISC.
3. Create and install CICS connection and sessions definitions, as described later in this information.

## Defining the location of the remote system

Define the location of the remote CICS system and the parameters of the connection to it. Use CEDA to set the following:

### **ACcessmsmethod**

Set to Vtam.

### **PRotocol**

Set to Appc.

### **Singlesess**

Set to No.

### **AUTOconnect**

Specify whether CICS is to bind sessions (drive CNOS) when the connection is installed. Set this to Yes.

### **ATTachsec**

This defines the settings for SNA LU6.2 conversation-level security. Set it to one of the following:

- Verify to flow a user ID and password from the CICS Universal Client.
- LOCAL if you do not want to flow a user ID and password.

### **Netname**

Set to the LU name of the partner LU6.2.

If you change and reinstall the CICS connection definition, you must stop and restart the connection.

## Defining CICS sessions

For each CICS connection definition, define one or more session definitions to specify the SNA mode groups to be used within that connection.

### **Connection**

Set to the name of the associated connection definition.

### **MODename**

Specify the mode group as defined in a VTAM LOGMODE. The modename must be unique among the sessions definitions that relate to one connection definition.

### **Protocol**

Set to APPC.

### **MAXimum**

Specify the maximum number of sessions that are to be supported. The first value is the maximum number of sessions that can be supported. The second value specifies the number of contention-winner sessions (CICS-owned sessions). These values are negotiated during change number of sessions (CNOS) flows, when the sessions are actually bound; the negotiated values depend on the settings specified in the partner SNA node.

Set the first value to be at least as big as the MAXREQUESTS parameter in the ctg.ini file, to prevent a bottleneck to throughput. Set the second value to 001, to ensure that START requests are shipped serially from the server to the client.

### **Autoconnect**

Set to determine whether the sessions for this mode group will be bound when the connection is installed. Set it to one of the following:

- Yes to bind only contention-winner sessions
- All to bind all sessions

## Configuring CICS connection autoinstall

Autoinstall of connections is particularly useful when dealing with many similar connections or when you are unsure of the LU names (netnames) to be used. To configure autoinstall of connection definitions:

1. Update the default autoinstall program from DFHZATDX to DFHZATDY, by specifying the SIT parameter AIEXIT=DFHZATDY. Alternatively, write your own autoinstall user-replaceable module based on the samples provided.
2. Configure model definitions. The supplied DFHZATDY autoinstall program uses the template CBPS. CBPS is supplied in DFHAI62 group; copy it to your own group and modify it accordingly. The parameters in the connection definition template are the same as for a static definition (see “Defining the location of the remote system” on page 23), except that the netname is not needed.

The parameters for the sessions definition are the same as those listed in “Defining CICS sessions” on page 23, except that the Connection parameter must refer to the CBPS connection definition.

If you use the supplied connection autoinstall program (DFHZATDY), the connection name generated is based on the last four characters of the Netname. To change the connection name, create your own user-replaceable module from the sample provided in CICSTS22.CICS.SDFHSAMP.

---

## Configuring named pipes

CICS Universal Client can use the Windows named pipes protocol to communicate with TXSeries for Windows and CICS Transaction Server for Windows servers that are on the same computer. This protocol provides a fast communications method independent of any network protocol.

The following definitions are required:

- The CICS server must have a Listener Definition for the **NamedPipe** protocol.
- The **NamedPipeName** attribute must match the Named pipe name setting in the CICS Universal Client configuration. All other attributes can use their default values. Named pipe name must be 6 alphanumeric characters; for example, CICS00.
- The Named pipe name setting in the configuration file must match the **NamedPipeName** attribute in the CICS server Listener Definition. Use the Configuration Tool to select the **NamedPipe** protocol, in the Server panel (see “Configuring Server settings” on page 37). This selection creates the correct settings in the configuration file including a LOCALNP Driver section with DriverName set to CCLCLPIP.

---

## Data conversion

The ECI and EPI allow non-CICS applications running in a client system to access CICS facilities and data managed by a CICS server system. Character data might need to be converted as it is passed between client and server; for example, data is encoded in ASCII on a CICS Universal Client system and in EBCDIC on a CICS mainframe server system. The server system performs data conversion. For more information, see “Data conversion,” on page 115.

---

## Chapter 5. Configuring CICS Universal Client

This information describes how to configure your CICS Universal Client.

### Related information

“Sample configuration documents” on page 127

“Redbooks” on page 127

Chapter 4, “Configuring CICS server connections,” on page 15

---

### Before you start to configure your system

This information covers what you must do before running the Configuration Tool.

In particular, make sure that communication links with your CICS servers are correctly set up; see Chapter 4, “Configuring CICS server connections,” on page 15.

On Windows Vista systems, if an elevated user configures the system, all other users can read from the default location. If a non-elevated user configures the system, the *CICSCLI* environment variable must be used to name the configuration file. Create the directory specified in the *CICSCLI* environment variable if it does not exist. When setting the *CICSCLI* environment variable at a Windows command line, Windows auto-completion adds double quotes around the path value. The double quotes must be removed, for example:

```
CICSCLI=C:\ProgramData\IBM\CICS Universal Client\ctg.ini
```

Windows Vista configuration requires that log files must be identified in the *ctg.ini* file. Log files must be located in a directory that is accessible to the user who runs the Gateway or Client daemon, for example:

```
LOGFILE=C:\ProgramData\IBM\CICS Universal Client\cicscli.log
```

The Windows environment variable *ALLUSERSPROFILE* identifies a directory that is accessible to all users. By default, *ALLUSERSPROFILE* is a hidden directory and the value varies by Windows platform, for example:

```
XP ALLUSERSPROFILE=C:\Documents and Settings\All Users
```

```
VISTA ALLUSERSPROFILE=C:\ProgramData
```

### Gathering information

Have the following information available:

- The protocol you will use to connect to the CICS server (TCP/IP, SNA, or Named Pipe)
- The host name or IP address of the server
- The port number at the server to which the Client daemon should connect

See “Overview of SNA connection definitions” on page 18, for information on matching definitions for SNA.

### Log on with administrator privileges

Before you configure the CICS Universal Client, you must be logged on to the machine with Administrator privileges. You might have Administrator privileges by being a member of the local Administrators group or by being a domain administrator.

## Set the JVM

Under Windows, you can have more than one Java Virtual Machine (JVM) installed on a machine. If so, applications must know which one to use. The `ctgjava` command allows you to view or alter the JVM used by the CICS Universal Client. The examples in this information use the dash character (-); you may use either the dash (-) or the forward slash (/).

### Seeing which JVM is in use

Issue this command to find out which JVM the CICS Universal Client is set to use:  
`ctgjava -v`

### Selecting a JVM automatically

Issue this command to auto configure the JVM for the CICS Universal Client:  
`ctgjava -a`

On Windows Vista to configure Java for CICS Universal Client the `ctgjava` utility must be invoked from an elevated command prompt.

### Setting the JVM

Issue this command to explicitly set the JVM that the CICS Universal Client uses:  
`ctgjava -s=jvmlocation`

where *jvmlocation* is the fully qualified path name of the Java executable file.

If the path name contains spaces, enclose it in quotation marks. For example:  
`ctgjava -s="C:\Program Files\IBM\Java15\bin\java.exe"`

On Windows Vista to configure Java for CICS Universal Client the `ctgjava` utility must be invoked from an elevated command prompt.

### Seeing which JVM is in use

Issue this command to find out which JVM the CICS Universal Client is set to use:  
`ctgjava -v`

### Selecting a JVM automatically

Issue this command to auto-configure the JVM for the CICS Universal Client:  
`ctgjava -a`

On Windows Vista to configure Java for CICS Universal Client the `cgtjava` utility must be invoked from an elevated command prompt.

### Setting the JVM

Issue this command to explicitly set the JVM that the CICS Universal Client uses:  
`ctgjava -s=jvmlocation`

where *jvmlocation* is the fully-qualified path name of the Java executable file.

If the path name contains spaces, enclose it in quotation marks. For example:  
`ctgjava -s="C:\Program Files\IBM\Java15\bin\java.exe"`

On Windows Vista to configure Java for CICS Universal Client the `cgtjava` utility must be invoked from an elevated command prompt.

## Set the time

Ensure that the locale and time zones are set correctly so that time stamps display the time accurately.

---

## Using the Configuration Tool

Use the Configuration Tool to configure the CICS Universal Client.

To start the Configuration Tool, click the shortcut on the Start menu, or enter the `ctgcfg` command.

### Storing configuration details

Configuration details are stored by default in the `ctg.ini` file in the `<install_path>\bin` subdirectory. You are recommended to use the Configuration Tool to update this file.

You can specify a different location for the configuration file, and optionally change its name, by setting the `CICSCLI` environment variable. If this variable is set, at startup the Configuration Tool loads the file referenced by `CICSCLI`. If the Configuration Tool fails to find the configuration file, it creates a file that includes a partial definition for a new server named `A_Server`. You must edit and save this file before use. The tool does not automatically create a directory if the directory referenced by `CICSCLI` does not exist.

The CICS Universal Client log indicates the name and location of the INI file. The CICS Universal Client will not run if a configuration file is not found.

### Mixed case values

The configuration tool allows parameter values to be entered in mixed case and also writes the values as mixed case to the configuration file, `ctg.ini`. For both the Gateway daemon and the Client daemon, some values are folded to upper case at runtime.

## Running the Configuration Tool for a different operating system

Proceed as follows:

1. Install the CICS Universal Client on the workstation on which you want to run the Configuration Tool.
2. To edit an existing configuration, copy `ctg.ini` to the `<install_path>\bin` subdirectory on the workstation, using FTP in ASCII mode.
3. Issue the following command to display help about the Configuration Tool:  
`ctgcfg -?`
4. Issue the following command:  
`ctgcfg -PLAT OSCODE`

where *OSCODE* represents the operating system that the Configuration Tool should emulate, and is one of the values returned by the command that you issued at step 3.

5. Make the required entries and click **Save** to create or update the `ctg.ini` file.
6. Use FTP in ASCII mode to transfer the file to your system.

## The Configuration Tool interface

The screen has four input areas:

1. Menu bar
2. Toolbar
3. Navigation panel
4. Settings panel

A fifth area, the status bar, shows which configuration file and operating system you are using. The status bar is display only.




Figure 2. The Configuration Tool

### Navigation panel

The navigation panel (see Figure 2) allows you to navigate through all the settings in your configuration. The tree has the following root nodes:

#### Client daemon

Contains Workload Manager and subnodes.

#### Workload Manager

Contains two subnodes:

#### Server Groups

Server groups are used to group together CICS server definitions with different port numbers. These server instances are used by the



Workload Manager to balance the workload across CICS servers. Each server group subnode contains the server definitions associated with that server group.

#### **Programs**

Contains a number of subnodes, one for each program associated with the Workload Manager. Each program subnode contains the server definitions with which the program is associated.

#### **CICS servers**

Contains a list of CICS server names and the network protocol used to connect to that server.

### **Menu bar**

The menu bar contains the **File**, **Edit**, **Options**, **Settings**, and **Help** menus.

The **File** menu has the following options:

**New** Creates a new configuration.

**Open** Opens an existing configuration.

**Save** Saves the current configuration. By default, the file name is ctg.ini and is saved to the <install\_path>\bin subdirectory.

#### **Save As**

Allows you to override the default path and name of the configuration file.

**Exit** Exits the Configuration Tool. If you have made any alterations you are asked whether you want to save the configuration.

The **Edit** menu has **Cut**, **Copy** and **Paste** options, which perform the standard text functions.

The **Options** menu has the following options:

#### **Trace Settings**

Displays the Trace Settings dialog.

#### **New Server**

Defines a new server, named A\_Server, that uses the TCP protocol.

#### **Delete Server**

Deletes a server node from the navigation panel.

#### **New Server Group**

Creates a new Server group for the Workload Manager.

#### **Delete Server Group**

Deletes a Server group subnode from the Workload Manager node.

#### **New Program Definition**

Allows you define a new program for use by the Workload Manager.

#### **Delete Program Definition**

Deletes a program subnode.

The **Settings** menu has these options:

**Color** Changes the background color on panels and fields. If you change the color, all fields (except check boxes and radio buttons) take on the same background color as the main panel.

**Font** Changes the typeface, size, style, and color of text. You can also change the color of warning text.

### **Save on exit**

If this menu option is selected, your choices are stored in CTGCFG.INI, for use in future sessions. A copy of CTGCFG.INI is created for each user in the %appdata%\IBM\CTG directory. If this directory cannot be resolved, the Java home directory is used. In this case, CTGCFG.INI is overwritten if another user alters the settings and saves them in the Java home directory.

If the system administrator has designated %appdata%\IBM\CTG as a roaming folder, your preferences are used when you run the Configuration Tool on any computer on the network.

#### **Notes:**

1. The file is not deleted if the CICS Universal Client is uninstalled. It remains on the system unless manually deleted and will be reused if the product is reinstalled.
2. To restore the default settings, close the Configuration Tool, delete file CTGCFG.INI, and then restart the Configuration Tool.
3. When you close the Configuration Tool, a message is displayed if file CTGCFG.INI cannot be written, even if you have deselected the **Save on exit** menu option. Click **OK** to clear the message and close the Configuration Tool.

The **Help** menu has the following options:

#### **Context Help**

Displays online help information according to the current screen context; for example, for a particular configuration setting.

#### **Contents**

Displays the contents list for online help.

#### **Keys Help**

Displays information on keyboard alternatives and other information to help users with a disability to use the software. See also “Accessibility features for CICS Universal Client” on page 131.

**Index** Displays a subject index for online help.

**About** Displays the version number and other information about the Configuration Tool.

### **Toolbar**

The toolbar provides some of the function available from the menu bar in a set of icons. These icons have *hover help*, so that, when you place the cursor over them, a text box describing the option appears.

### **Settings panels**

When you select nodes in the navigation panel, the relevant settings panel is displayed. The settings in these panels correspond to parameters in the ctg.ini file.

On each settings panel, an **Undo Changes** button allows you to undo changes you have made.

## Configuring the product setting

The opening screen of the CICS Universal Client configuration tool displays the product settings panel for the CICS Universal Client.

### APPLID

The APPLID is used to identify the instance of the CICS Universal Client on server connections and tasks in a CICSplex.

Enter up to 8 characters, or leave this field blank. There is no restriction on the characters that can be used in APPLID, but to ensure that the APPLID is valid for use in all scenarios, it is advisable to restrict the characters used to be in the range A through Z, and 0 through 9. The character strings entered are converted to uppercase for SNA and TCP/IP connections.

The name must be unique within the CICS server system. The value of blank automatically generates a name that is guaranteed to be unique.

## Configuring Client daemon settings




Figure 3. Client settings

Select the **Client** node to display the Client Configuration panel. The settings map to the parameters in the CLIENT section of the ctg.ini file. The panel has these tabs:

Resources

Logging

## Default Server

Select the default server from the drop-down list.

## Maximum buffer size

Enter a number of kilobytes, in the range 4 through 32. The default is 32 KB. If you enter a value outside the permitted range, the Configuration Tool warns you. If the value entered is too low, it substitutes the minimum. If the value entered is too high, it substitutes the maximum. If a non-numeric value is present in the configuration file, it substitutes the minimum value.

This value specifies the size of the transmission buffers in which application or terminal data will flow. The value should be large enough to cater for the largest possible COMMAREA or terminal input/output area (TIOA) to be used. The maximum COMMAREA size might be less than the Maximum buffer size, because certain protocols have an overhead of 512 bytes.

Leave this setting at the default unless the CICS Universal Client is running on a machine that is short of memory.

For details of the corresponding entry in the configuration file, see MAXBUFFERSIZE ("CLIENT section of the configuration file" on page 47).

## Terminal exit

Enter a character string of between 1 and 4 characters. The default is EXIT.

The string, when entered at a terminal emulator at any time and place where a transaction name can be entered, causes the terminal emulator to terminate. The string must not contain any blank characters.

The string is case-sensitive. If a terminal emulator has uppercase translation in its CICS terminal definition, enter this string in uppercase.

For details of the corresponding entry in the configuration file, see TERMINALEXIT ("CLIENT section of the configuration file" on page 47).

## Maximum servers

Enter a value in the range 1 through 256. The default is 10. If you enter a value outside the permitted range, the Configuration Tool warns you. If the value entered is too low, it substitutes the minimum. If the value entered is too high, it substitutes the maximum. If a non-numeric value is present in the configuration file, it substitutes the minimum value.

This value specifies the maximum number of servers that can be accessed concurrently from the client.

For details of the corresponding entry in the configuration file, see MAXSERVERS ("CLIENT section of the configuration file" on page 47).

## Maximum requests

Enter a value in the range 1 through 32. The default is 32. If you enter a value outside the permitted range, the Configuration Tool warns you. If the value

entered is too low, it substitutes the minimum. If the value entered is too high, it substitutes the maximum. If a non-numeric value is present in the configuration file, it substitutes the minimum value.

This value specifies the maximum number of concurrent items that might be executing on the Client daemon, where an item is one of:

- A request to install or uninstall a terminal emulator
- A request to install or uninstall an EPI terminal
- A transaction invoked by a terminal
- An ECI unit of work
- An ESI unit of work

It is used to detect runaway conditions where an application could, in error, submit an excessive number of requests to a server. The actual limit might be less than this setting if other operating system limits (for example, memory constraint or communication sessions), come into effect.

For details of the corresponding entry in the configuration file, see MAXREQUESTS ("CLIENT section of the configuration file" on page 47).

## Print command

Enter a character string, from 1 to 256 characters long.

The specified string is a command specific to the operating system under which the CICS Universal Client is running. When a request to print is received, the Client daemon generates a temporary print file with a unique name.

The parameter string is appended with the temporary file name, and the resultant command executed. This allows, for example, print requests to be copied to a file, directed to a local printer, formatted for inclusion into documentation, and so on.

A command file might be necessary to act as an interface between the syntax of the invocation command defined here, and more general operating system syntax. For example, if the desired final command was COPY printfile LPT2, a simple command file would be required to reorder the parameters. It is the responsibility of the Print command to delete the temporary print file after it has finished processing it.

You may specify only a local executable in this field. UNC paths of the type `\\User1\Share\notepad.exe` do not work, due to the system limitations of running executables that are installed on one machine on a different machine.

See also the **Print file** description for more information.

For details of the corresponding entry in the configuration file, see PRINTCOMMAND ("CLIENT section of the configuration file" on page 47).

## Print file

Enter a character string, 1 to 256 characters long.

This option applies only if you make no entry in the **Print command** setting.

The specified string identifies a file to which output from print requests received at the Client daemon is directed. Each print request is appended to the end of the current file.

If both this setting and **Print command** are omitted, the default action is to direct the print data to LPT1.

This setting acts only as a default. The terminal and print emulators provide options to override this value. (See “cicsterm command reference” on page 77 and “cicsprnt command reference” on page 81).

For details of the corresponding entry in the configuration file, see PRINTFILE (“CLIENT section of the configuration file” on page 47).

### Code page identifier override

Enter a value indicating a Coded Character Set Identifier (CCSID) to override your local code page identifier.

Use this setting if your platform has been updated for euro support, and the CICS Server has euro support. For example, for Latin-1 countries, use a CCSID value of 858 to indicate that the code page 850 includes euro support. For code page 1252, specify a CCSID value of 5348.

#### Note:

1. Regardless of the value in the **Code page identifier override** setting, `cicsterm` always displays characters based on the local code page of the workstation.
2. If you use the CCSID to change the code page identifier, data that is already stored on the server might be modified when retrieved by the CICS Universal Client, if it includes characters for which the code points produce different characters.
3. You do not have to supply a CCSID, because you can use the **Use OEM code page** setting to provide support for euro enabled code pages. Any value that you enter in the **Code page identifier override** field overrides the code page value generated using the **Use OEM code page** setting. You might do this, for example, to switch back to code page 850 or 1252 to indicate to the CICS server that the euro should not be used.

For details of the corresponding entry in the configuration file, see CCSID (“CLIENT section of the configuration file” on page 47).

### Server retry interval

Enter a number between 1 and 3600, to specify the time in seconds between attempts by the Client daemon to reconnect to a server. The default is 60 seconds.

When the Client daemon becomes aware that a server to which it was connected is no longer active, it attempts to reconnect to the server one second after it becomes inactive. If it fails it keeps trying, at the interval specified here.

Set the interval to 0 (zero) to disable automatic re-connection attempts.

For details of the corresponding entry in the configuration file, see SRVRETRYINTERVAL (“CLIENT section of the configuration file” on page 47).

### Enable pop-up windows

Select this check box to enable the display of pop-up messages at startup.

You can also change this setting dynamically by using the `-e` and `-n` parameters of the CICSCLI command; see “The cicscli command” on page 65.

For details of the corresponding entry in the configuration file, see ENABLEPOPUPS (“CLIENT section of the configuration file” on page 47).

### Use OEM code page

Select this check box if you want the CICS Universal Client to call the Windows operating system OEM code page function to get the code page identifier (for example, 850). If the workstation is euro-enabled, code page 850 is mapped to 858 within the client to indicate to the CICS Server that the euro symbol can be used.

If you do not select this check box, the CICS Universal Client uses the Windows operating system ACP function to get the ASCII identifier (for example 1252). Use this to provide appropriate conversions for Latin-1, Japanese, Korean and Simplified Chinese systems. If the workstation is euro enabled, code page 1252 is mapped to code page 5348.

For more information on code pages and data conversion, refer to “Data conversion,” on page 115.

For details of the corresponding entry in the configuration file, see USEOEMCP (“CLIENT section of the configuration file” on page 47).

### Log terminal installations and deletions

Select this check box to log server connection and disconnection events.

For details of the corresponding entry in the configuration file, see TERMINSTLOGGING (“CLIENT section of the configuration file” on page 47).

### Error and warning log file

Enter the name of the log file to be used for problem diagnosis.

If not specified, the log file name defaults to cicscli.log in the <install\_path>\bin subdirectory.

Optionally specify a ctglog subdirectory in a directory to which all users have write access. For example:

C:\Documents and Settings\All Users\Application Data\ctglog

All users can read the log file. In a Windows secured environment, consider specifying instead a directory to which users do not have write access, to stop them writing to the log files.

For details of the corresponding entry in the configuration file, see LOGFILE (“CLIENT section of the configuration file” on page 47).

On Windows Vista, log and trace files for the Client daemon process must be defined with a fully qualified file name, for example:

C:\ProgramData\IBM\CICS Universal Client\cicscli.log

On Windows Vista the user who starts CICS Universal Client must have write access to the log files.

### Use the same file for information messages

Clear this check box to send information messages to a separate log.



By default, information messages are logged to the “Error and warning log file” on page 35; clear the Use the same file for information messages check box to enable the “Information log file” field.

This field has no corresponding entry in the configuration file.

### Information log file

Enter the name of the file to which information messages will be logged.

By default, information messages are logged to the “Error and warning log file” on page 35; clear the “Use the same file for information messages” on page 35 field, and then complete this field, to change the destination. If you do not specify a path to the file, the log is created in the following directory:

<install\_path>\bin

For details of the corresponding entry in the configuration file, see LOGFILEINFO (“CLIENT” section of the configuration file” on page 47).

### Changing settings for Client daemon logging

This information describes how to specify a destination for error and other messages from the Client daemon.

By default error, warning, and informational messages are output to the “Error and warning log file” on page 35. Terminal installations and deinstallations are not logged by default. Take the steps below to change the settings.

1. Launch the Configuration Tool and navigate to the **Logging** tab of the **Client daemon** node.
2. Complete the fields on the tab as appropriate. You can choose to:
  - Log terminal installations and deinstallations.
  - Change the name of the Error and warning log file from the default cicscli.log.
  - Specify a different log for information messages.
3. Save the configuration file.

#### Related tasks

“Viewing the information log”

This information describes how to view messages that have been output to the information log.

#### Related information

“Using the Configuration Tool” on page 27

Use the Configuration Tool to configure the CICS Universal Client.

### Viewing the information log

This information describes how to view messages that have been output to the information log.

1. Determine the location of the information log file. By default, information messages are output to the “Error and warning log file” on page 35, but the destination can be changed through the “Information log file” field in the Configuration Tool.
2. View the file using any standard text editor.

#### Related tasks



“Changing settings for Client daemon logging” on page 36  
This information describes how to specify a destination for error and other messages from the Client daemon.

## Configuring Server settings

To configure a new CICS Server, select **New Server** from the **Options** menu, or from the toolbar, or right click on the CICS Servers entry in the Navigation Panel.




Figure 4. Server settings

Select a server in the navigation panel to display the Server connection panel. The settings map to the parameters in a Server section of the configuration file.

Multiple identical server definitions are not permitted in the configuration file of the CICS Universal Client. The combination of fields that identify a server, and must therefore be unique is as follows:

### Protocol

Fields in ctg.ini

### TCP/IP

Hostname or IP address and Port.

This ensures that every connection that the CICS region and the network protocol see is represented by a unique server definition in the configuration file. If you

have existing Client applications that use different server names to send requests to the same CICS region, you need to write a user exit to redirect requests. This is demonstrated in sample user exits `ecix2.c` and `epix2.c`; see `<install_path>\samples\samples.txt`.

### **Server name**

Enter a name of between 1 and 8 characters. This provides a name that is independent of the communications protocol for the server, local to the Client daemon.

Any requests to access the server from ECI, EPI, ESI, or terminal emulators should use this name.

For details of the corresponding entry in the configuration file, see SECTION SERVER ("SERVER section of the configuration file" on page 49).

### **Description**

Enter a description for the server of between 1 and 60 characters. This description is optional.

This description is returned on EPI or ECI list systems calls.

For details of the corresponding entry in the configuration file, see DESCRIPTION ("SERVER section of the configuration file" on page 49).

### **Initial transaction**

Enter a transaction identifier of between 1 and 128 characters.

This string is case-sensitive and identifies the initial transaction (and any parameters) to be run when the terminal emulator connects to the server. If you do not enter anything, no initial transaction is run. The first four characters, or the characters before the first blank in the string are taken as the transaction. The remaining data is passed to the transaction on its invocation.

Ensure that the transaction does not require terminal input.

For details of the corresponding entry in the configuration file, see INITIALTRANSID ("SERVER section of the configuration file" on page 49).

### **Model terminal definition**

Enter a string of between 1 and 16 characters.

The string is case-sensitive and specifies the name of a model terminal definition at the server, identifying the characteristics of terminals to be autoinstalled from the client. If the model cannot be located at the server, or you do not enter anything, a default terminal definition is used. This default is server-specific.

The interpretation of the Model terminal definition setting is server-specific. For example, for a TXSeries for AIX server, the value is 1 to 16 characters, and is the DevType for a CICS terminal definition entry to be used as the model.

For details of the corresponding entry in the configuration file, see MODELTERM ("SERVER section of the configuration file" on page 49).

## Use uppercase security

Select this check box to specify that the CICS Universal Client converts to uppercase any user ID or password from an ECI application or from a user prompt. This setting is disabled by default.

If the UPPERCASESECURITY entry is missing from the configuration file, the default behaviour is for UPPERCASESECURITY to be enabled.

For details of the corresponding entry in the configuration file, see UPPERCASESECURITY ("SERVER section of the configuration file" on page 49).

## Network protocol

Select the protocol to be used for the server connection from the list:

- TCP/IP
- SNA
- Named Pipe

The protocol settings on the panel change according to the protocol you select.

## Server idle timeout (mins)

Enter an integer in the range 1 through 1080, to specify in minutes the period of inactivity after which the connection between the Client daemon and the CICS server is closed. A value of 0 means that no timeout is applied. The default value is 0.

The field is available if one of the following network protocols is selected:

- TCP/IP
- SNA
- Named pipes

The **Server idle timeout (mins)** period is counted from when the number of outstanding conversations (units of work) on the connection is zero. The connection is automatically reestablished when a Client application sends the next ECI, EPI or ESI request.

When a server connection times out, the Client daemon behaves as if the `cicscli -x=<servername>` command had been issued. In particular, any value specified in the "Server retry interval" on page 34 configuration field is ignored, and no attempt is made to reestablish the connection. The Server retry interval setting is re-enabled if the connection is re-established.

For details of the corresponding entry in the configuration file, see SRVIDLETIMEOUT (ctg.ini: SERVER section `sectionserver). If the network protocol for the server in question is not supported for this field, the Client daemon ignores any entry in the configuration file for the **Server idle timeout (mins)** field.

### Related information

"Shutting down the Client daemon normally" on page 66

## TCP/IP settings

**Hostname or IP address:** Enter the character or numeric TCP/IP identifier for the host on which the CICS server is running. For example, `cicssrv2.company.com` (host name) or `192.113.36.200` (IP Address).

Host names are mapped to IP addresses either by the name server or in the hosts system file. It is better to use a host name in case the IP address changes.

The hosts system file is in the %windir%\system32\drivers\etc directory.

For details of the corresponding entry in the configuration file, see NETNAME ("SERVER section of the configuration file" on page 49).

**Port:** Enter a numeric value in the range 0 through 65 535 defining the port number at the server to which the Client daemon should connect. The default value is 0. If you enter a value outside the permitted range, the Configuration Tool warns you. If the value entered is too low, it substitutes the minimum. If the value entered is too high, it substitutes the maximum. If a non-numeric value is present in the configuration file, it substitutes the minimum value.

A value of 0 indicates that the services system file should be used to locate the port number for the CICS service using the TCP protocol.

The services system file is in the %windir%\system32\drivers\etc directory.

If no entry can be located in the services system file, a value of 1435 is assumed. This is the port assigned to the Client daemon in the TCP/IP architecture.

For details of the corresponding entry in the configuration file, see PORT ("SERVER section of the configuration file" on page 49).

**Connection timeout:** Enter a value in the range 0 through 3600, specifying the maximum time in seconds that establishing a connection is allowed to take; the default value of 0 means that no limit is set by the Client daemon. If you enter a value outside the permitted range, the Configuration Tool warns you. If the value entered is too low, it substitutes the minimum. If the value entered is too high, it substitutes the maximum. If a non-numeric value is present in the configuration file, it substitutes the minimum value.

A timeout occurs if connection establishment takes longer than the specified time. The TCP/IP socket is closed and the return code passed back to the client application is either ECI\_ERR\_NO\_CICS or CICS\_EPI\_ERR\_FAILED.

Cleanup processing happens after a timeout only if the server has support for this function installed.

For details of the corresponding entry in the configuration file, see CONNECTTIMEOUT ("SERVER section of the configuration file" on page 49).

**Send TCP/IP KeepAlive packets:** Select this check box if you want TCP/IP to periodically send keepalive messages to the server to check the connection. The CICS Universal Client uses the interval specified by your operating system.

For details of the corresponding entry in the configuration file, see TCPKEEPALIVE ("SERVER section of the configuration file" on page 49).

## SNA settings

**Local LU name:** Enter the **Local LU name** as it is known to the SNA Communications Server.

**On Windows operating systems:**

- If you selected **Use Local LU alias name**, enter an alias name of eight characters or less.
- If you did not select **Use Local LU alias name**, enter an LU name of eight characters or less.

For details of the corresponding entry in the configuration file, see **LOCALLUNAME** (“SERVER section of the configuration file” on page 49).

**Use Local LU alias name:** This option is only available on Windows operating systems. Select the **Use Local LU alias name** box to specify the **Local LU name** is an alias. The default is for the check box not to be selected.

**Partner LU name:** Enter the LU name of the CICS server as it is defined for the SNA network.

- If you selected **Use Partner LU alias name**, enter an alias name of eight characters or less.
- If you did not select **Use Partner LU alias name**, enter a qualified name of up to 17 characters, for example, ABC3XYZ4.PQRS1234

**On Windows operating systems:** You can only have an alias **Partner LU name** when the **Local LU name** is an alias.

**Use Partner LU alias name:** Select the **Use Partner LU alias name** box to specify the **Partner LU name** is an alias.

**On Windows operating systems:** The check box is not selected and is only available if **Use Local LU alias name** is enabled.

**Mode name:** Enter between 1 and 8 characters specifying the mode name to be used when connecting to the server.

Enter \* if you want the mode name to be filled with spaces.

## Named pipe settings

CICS® Transaction Gateway can use the Windows® named pipes protocol to communicate with TXSeries® for Windows and CICS Transaction Server for Windows servers that are on the same computer. However, the Windows® named pipes protocol is not supported on Windows® Vista. Use of the named pipes protocol is deprecated for removal from other Windows® platforms in a future release.

**Named pipe name:** Enter a name of up to six alphanumeric characters that match the **NamedPipeName** attribute specified in the listener definition of the TXSeries or CICS Transaction Server for Windows server.

For details of the corresponding entry in the configuration file, see **NAMEDPIPENAME** (“SERVER section of the configuration file” on page 49).

## Configuring the Workload Manager




Figure 5. Workload Manager settings

To display the Workload Manager settings panel, select the Workload Manager node in the navigation panel. Most settings map to the parameters in the LOADMANAGER section of the ctg.ini file, although the Workload Manager also uses the REGION parameter in the SERVER section.

Read Chapter 10, “Using the Workload Manager,” on page 85, before configuring the Workload Manager. This chapter explains important concepts, such as server groups, and the behaviour of the workload balancing algorithms.

### Enable the Workload Manager

Select this check box to enable the Workload Manager. The default is that the Workload Manager is disabled.

For details of the corresponding entry in the configuration file, see LOADMANAGER (“CLIENT section of the configuration file” on page 47).

### Round robin

Select this radio button to choose a round-robin algorithm for the Workload Manager.

For details of the corresponding entry in the configuration file, see TYPE (“LOADMANAGER section of the configuration file” on page 50).

## Biasing

Select this radio button to choose a biased algorithm for the Workload Manager. The biasing algorithm is selected by default.

For details of the corresponding entry in the configuration file, see TYPE (“LOADMANAGER section of the configuration file” on page 50).

## Region timeout (s)

Enter a value in seconds between 0 and 3600. The default is 60 seconds. If you enter a value outside the permitted range, the Configuration Tool warns you. If the value entered is too low, it substitutes the minimum. If the value entered is too high, it substitutes the maximum. If a non-numeric value is present in the configuration file, it substitutes the minimum value.

When a CICS server (region) is selected as the target of a client request, and that server is unavailable, the server is flagged as invalid, and is no longer included in the list of target regions for requests. The Region timeout (s) value specifies the number of seconds after which an invalid region can once more be included in the list of target regions.

For details of the corresponding entry in the configuration file, see Timeout (“LOADMANAGER section of the configuration file” on page 50).

## Tools menu options for the Workload Manager

Two options on the **Tools** menu allow you to configure server groups and programs. These options are enabled only when you select the Workload Manager node.

**Configuring a server group:** This panel allows you to define which servers belong to a particular server group.

To add a new server group, select the **New Server Group** option, or click the **New Server Group** icon, and enter a name in the **Server group name** field.

To change the members of a server group, select the server group from the tree selection.

- To add a server to a group, select from the **Servers not in server group** list on the right and then select the arrow button (<<).
- To remove a server from a group, select from the **Servers in server group** list and then select the arrow button (>>).

**Manage workload for this server group:** Select this check box to enable workload balancing for servers in the selected server group.

If load balancing is enabled for this server group, the first time an instance of the Client daemon makes a request, it selects a server instance from the server group at random. For the duration of the life of the Client daemon instance, all subsequent requests to that server group are sent to the same server instance.

All servers not assigned to a server group are also considered for workload management, and a server not included in a server group is thought to be in a server group of its own. To stop the Workload Manager from sending requests to a server, do the following:

1. Create a new server group.
2. Add the server to the new server group.



3. Clear the **Manage workload for this server group** check box.

If you disable workload balancing for a particular server group, for any server in that group, the Workload Manager connects only to the server specified in the call; it does not use an algorithm to select the next appropriate server. The Workload Manager does not re-send failed requests to a server that has workload balancing disabled.

## Configuring programs

This panel allows you to define the workload management for a particular program. Workload management for particular programs is available only for ECI. If the round-robin algorithm is selected, you define which servers are valid for the program. If the biasing algorithm is selected, you define which servers are used for biasing. When a program defined to the Workload Manager is used, requests are balanced across CICS servers where the program is defined, according to the biasing on this panel.

- To add a new program definition, click **Tools—>New Program Definition** option, or click the **New Program Definition** icon, and enter a name in the **Program name** field.
- To change a definition, select the program from the tree selection.
- To disable workload management for the program, clear the **Manage workload for this program** check box.
- To add a server to the list of servers for which the program is valid:

### Round-robin algorithm

To add a server to the list of servers for which the program is valid, select from the **Servers not valid for this program** list on the right and then click the arrow (<<).

### Biasing algorithm

To add a server to the list of servers used for biasing, select from the **Servers not used for biasing** list on the right and then click the arrow (<<).

In the **Bias value** field, you can enter a bias value for a server. Enter a number between 0 and 100, to represent the ratio of requests sent to that server, compared to other servers. For example, if two servers have a bias of 75 and 25, program requests are sent in a ratio of 3:1 to the first server. If you enter a value outside the permitted range, the Configuration Tool warns you. If the value entered is too low, it substitutes the minimum. If the value entered is too high, it substitutes the maximum. If a non-numeric value is present in the configuration file, it substitutes the minimum value.

In the **Ratios** fields, percentage bias values for each server are shown. This field contains **Standby** if the bias value is 0, which means use only if no other server is available.

- To remove a server from the list of servers for which the program is valid:

### Round-robin algorithm

To remove a server from the list, select from the **Servers this program is valid on** list on the left and then click the arrow (>>).

### Biasing algorithm

To remove a server from the list, select from the **Servers used for biasing** list on the left and then click the arrow (>>).



## Manage workload for this program

Select this check box if you want to enable workload balancing for the selected program.

If you disable workload balancing for a particular program, the Workload Manager connects to the server specified in the call; it does not use an algorithm to select the next appropriate server.

For details of the corresponding entry in the configuration file, see NOTMANAGED (“LOADMANAGER section of the configuration file” on page 50).

## Trace settings

To configure the trace settings, select the **Trace Settings** option from the **Tools** menu.

### Trace Settings

Select check boxes to specify the components that will be traced when tracing is turned on.

#### Select all Client trace components

Select all Client trace components.

#### Client API level 1

The client API layer (level 1).

#### Client API level 2

The client API layer (level 1 and 2).

#### CICSCLI command line

The cicscli command interface.

#### CICSTERM and CICSPRINT

cicsterm and cicsprnt emulators.

#### CPP classes

The C++ class libraries.

#### Client daemon

The Client daemon.

#### Transport layer

Interprocess communication.

#### Protocol drivers level 1

Protocol drivers (for example, TCP). This traces data sent and received and provides supplementary information about failures.

#### Protocol drivers level 2

This traces internal flows through the protocol drivers and interactions with other software components. This enhanced tracking level currently has the same functionality as level 1.

#### Workload manager

The Workload Manager.

If you enable tracing without specifying the components in either the cicscli command or in ctg.ini, a default set of components is traced:

- Protocol drivers
- The Client daemon

- Client API level 1

Selecting any of the check boxes in the Configuration Tool overrides the default set of components.

For details of the corresponding entry in the configuration file, see TRACE (“CLIENT section of the configuration file” on page 47).

### Client trace file

Enter the path name of a trace file to which Client trace messages will be written, if tracing is enabled.

You do not have to enter an extension for the file name, because a file of type .BIN is always generated (or .WRP if the trace file wraps).

If no path is specified, the trace is written as follows:

```
<install_path>\bin\cicscli.bin
```

On Windows Vista, log and trace files for the Client daemon process must be defined with a fully qualified file name, for example:

```
C:\ProgramData\IBM\CICS Universal Client\cicscli
```

On Windows Vista the user who starts CICS Universal Client must have write access to the log files.

To minimize any performance impact, the trace file is written out in binary format. To read it, convert the file to ASCII using the cicsftrc command.

For details of the corresponding entry in the configuration file, see TRACEFILE (“CLIENT section of the configuration file” on page 47).

### Client trace file wrap size (KB)

Enter a value in the range 0 through 2 000 000.

If you use the memory mapped tracing option (cicscli -b), the size of the trace files is determined by this field, which specifies the total amount of space in KB reserved for trace data files. Subsequent trace entries will continue to be written from the beginning of the file. **Client trace file wrap size (KB)** must be greater than 0 if memory mapped tracing is to be used; the default value of 0 disables wrapping. If its value is between 1 and 99, a value of 100 is used instead to guarantee an adequate minimum trace size.

For details of the corresponding entry in the configuration file, see MAXWRAPSIZE (“CLIENT section of the configuration file” on page 47).

## Applying your changes to the system

You must restart the Client daemon for any changes to the configuration file to take effect.

---

## Sample configuration and mapping files

The following files are supplied in the <install\_path>\bin subdirectory:

### ctgsamp.ini

A sample configuration file. (The default configuration file name is ctg.ini.)

**cicskey.ini**  
The keyboard mapping file.

**cicskeysamp.ini**  
A sample keyboard mapping file.

**cicscol.ini**  
The color mapping file.

**cicscolsamp.ini**  
A sample color mapping file.

It is recommended that you create your own customized versions of these files with different names, because installing service updates might overwrite the files and cause any customization to be lost.

Reference your customized files through the following environment variables:

| <b>File</b> | <b>Environment variable</b> |
|-------------|-----------------------------|
|-------------|-----------------------------|

|                           |         |
|---------------------------|---------|
| <b>configuration file</b> | CICSCLI |
|---------------------------|---------|

|                              |         |
|------------------------------|---------|
| <b>keyboard mapping file</b> | CICSKEY |
|------------------------------|---------|

|                           |         |
|---------------------------|---------|
| <b>color mapping file</b> | CICSCOL |
|---------------------------|---------|

Use the **System** icon in the **Control Panel** to set these environment variables.

---

## Editing the configuration file

The default name for the configuration file is `ctg.ini`. This configuration file name can be changed to another name if required. A sample configuration file is supplied: `<install_path>\bin\ctgsamp.ini`. To create a new configuration, copy this file to `<install_path>\bin\ctg.ini` and edit the copy.

The configuration file is a text file consisting of a number of sections. Each section starts with `SECTION <NAME>` as the first entry on a line, and ends with `ENDSECTION`.

This information maps entries in the configuration file to the corresponding fields in the Configuration Tool. For an explanation of the fields see the Configuration chapter in the Administration book.

If you use the number sign (#) character to denote a comment, either:

- place it at the start of a line; or
- precede it by a space or tab character

because some valid names (for example `modename`) can start with the # character.

## CLIENT section of the configuration file

The CLIENT section of the configuration file defines the Client daemon settings.

There must be one CLIENT section of the configuration file. Entries correspond to fields in the Client Configuration and Trace settings panels of the Configuration Tool. The section name also stores the value entered in the Application ID field of the Configuration Tool.

Table 3. SECTION CLIENT

| Entry in the INI file | Configuration Tool field  |
|-----------------------|---|
| SECTION CLIENT        | The Application ID entry is deprecated, it has been replaced by the "APPLID" on page 31 parameter which now takes precedence. Existing configuration files with the Application ID parameter set are still supported for compatibility with earlier versions.<br><b>Note:</b> SECTION CLIENT must be set to * when creating a new configuration file. |
| CCSID                 | "Code page identifier override" on page 34  |
| ENABLEPOPUPS          | "Enable pop-up windows" on page 34. Set to Y to enable, or N to disable.  |
| LOGFILE               | "Error and warning log file" on page 35   |
| LOGFILEINFO           | "Information log file" on page 36   |
| MAXBUFFERSIZE         | "Maximum buffer size" on page 32  |
| MAXREQUESTS           | "Maximum requests" on page 32   |
| MAXSERVERS            | "Maximum servers" on page 32  |
| MAXWRAPSIZE           | "Client trace file wrap size (KB)" on page 46   |
| PRINTCOMMAND          | "Print command" on page 33  |
| PRINTFILE             | "Print file" on page 33   |
| SRVRETRYINTERVAL      | "Server retry interval" on page 34  |
| TERMINALEXIT          | "Terminal exit" on page 32  |
| TERMINSTLOGGING       | "Log terminal installations and deletions" on page 35   |
| TRACEFILE             | "Client trace file" on page 46  |
| USEOEMCP              | "Use OEM code page" on page 35. Set to Y to enable the field, otherwise set to N.   |
| LOADMANAGER           | "Enable the Workload Manager" on page 42 (on the Workload Manager settings panel in the Configuration Tool.) Set this to Y to enable workload management, otherwise set to N.   |
| TRACE                 | A comma-separated list of components to trace, as entered on the "Trace Settings" on page 45 panel. Possible entries are as follows:  |
| ALL                   | Trace everything  |
| API                   | Client API level 1  |
| API.2                 | Client API level 2 (also traces level 1)  |
| TRN                   | Transport layer   |
| DRV                   | Protocol drivers level 1  |
| DRV.2                 | Protocol drivers level 2 (also traces level 1)  |
| CLI                   | CICSCLI command line  |
| CCL                   | Client daemon   |
| EMU                   | CICSTERM and CICSPRINT  |
| LMG                   | Workload manager  |
| CPP                   | CPP classes   |

## SERVER section of the configuration file

The SERVER section of the configuration file defines a server to which the Client daemon may connect.

There may be more than one SERVER section. The first server listed is the default. The section name also stores the value entered in the **Server name** field of the Configuration Tool.

Table 4. SECTION SERVER

| Entry in the INI file | Configuration Tool field   |
|-----------------------|--|
| SECTION SERVER        | "Server name" on page 38   |
| DESCRIPTION           | "Description" on page 38   |
| INITIALTRANSID        | "Initial transaction" on page 38   |
| MODELTERM             | "Model terminal definition" on page 38   |
| REGION                | To assign the server to a Workload Manager server group, enter the name of the server group here, for example<br>REGION=MYGROUP<br><br>Otherwise, omit the entry.  |
| UPPERCASESECURITY     | "Use uppercase security" on page 39. Set to <b>Y</b> to enable, otherwise set to <b>N</b> .  |
| PROTOCOL              | Network protocol. Valid entries are SNA, TCP/IP, or LOCALNP (Named pipe). The Network protocol must correspond to an entry in the DRIVER section; see "DRIVER section of the configuration file" on page 50. |

Other entries in this section depend upon the protocol selected.

Table 5. SECTION SERVER: additional entries for the TCP protocol

| Entry in the INI file | Configuration Tool field   |
|-----------------------|--|
| NETNAME               | "Hostname or IP address" on page 39  |
| PORT                  | "Port" on page 40  |
| CONNECTTIMEOUT        | "Connection timeout" on page 40  |
| SRVIDLETIMEOUT        | "Server idle timeout (mins)" on page 39  |
| TCPKEEPALIVE          | "Send TCP/IP KeepAlive packets" on page 40. Set to <b>Y</b> to enable, otherwise set to <b>N</b> . |

Table 6. SECTION SERVER: additional entries for the SNA protocol

| Entry in the INI file | Configuration Tool field   |
|-----------------------|--|
| LOCALLUNAME           | "Local LU name" on page 40   |
| LUALIASNAMES          | "Use Local LU alias name" on page 41. Set to <b>Y</b> to enable, otherwise set to <b>N</b> . This setting applies only to Windows operating systems.   |
| NETNAME               | "Partner LU name" on page 41   |
| PARTNERLUALIAS        | "Use Partner LU alias name" on page 41. Set to <b>Y</b> to enable, otherwise set to <b>N</b> . On Windows operating systems this option should only be set to <b>Y</b> when LOCALLUALIAS is also set to <b>Y</b> . |
| MODENAME              | "Mode name" on page 41   |

Table 6. SECTION SERVER: additional entries for the SNA protocol (continued)

| Entry in the INI file | Configuration Tool field                |
|-----------------------|---|
| SRVIDLETIMEOUT        | "Server idle timeout (mins)" on page 39 |

Table 7. SECTION SERVER: additional entry for the LOCALNP protocol

| Entry in the INI file | Configuration Tool field     |
|-----------------------|------------------------------|
| NAMEDPIPENAME         | "Named pipe name" on page 41 |

## DRIVER section of the configuration file

This DRIVER section of the configuration file defines a communications protocol DLL used to communicate with a server.

There should be one DRIVER section for each Network protocol used with your servers; see "SERVER section of the configuration file" on page 49. Entries take the following form:

```
SECTION DRIVER=<protocol>
    DRIVERNAME=<DLL>
ENDSECTION
```

Table 8. DRIVER section

| Valid entries for <protocol> | Corresponding <DLL> |
|------------------------------|---------------------|
| SNA                          | CCLWNTSN            |
| TCPIP                        | CCLWNTIP            |
| LOCALNP                      | CCLCLPIP            |

The DRIVER section has no corresponding section in the Configuration Tool. The Configuration Tool automatically selects the correct protocol drivers.

## LOADMANAGER section of the configuration file

The LOADMANAGER section of the configuration file defines Workload Manager settings and is only present if you enable the Workload Manager.

Entries in this section take the following form:

```
SECTION LOADMANAGER
    TYPE=[0|1]
    Timeout=<timeinseconds>
    BIAS=<program>;<server1>:1;<servergroup1>:3;...
    NOTMANAGED=<servergroup2>
ENDSECTION
```

Figure 6. LOADMANAGER section example

Table 9. SECTION LOADMANAGER

| Entry in the INI file | Meaning  |
|-----------------------|--|
| TYPE                  | Defines the type of algorithm used. <ul style="list-style-type: none"> <li>• Enter 0 for "Round robin" on page 42.</li> <li>• Enter 1 for "Biasing" on page 43.</li> </ul> |
| Timeout               | Corresponds to the "Region timeout (s)" on page 43 field in the Configuration Tool.  |

Table 9. SECTION LOADMANAGER (continued)

| Entry in the INI file | Meaning   |
|-----------------------|---|
| BIAS                  | <p>Create a line like this for each program for which workload management is enabled.</p> <ul style="list-style-type: none"> <li>The first entry is the program, terminated by a semicolon. In Figure 6 on page 50, this is <i>&lt;program&gt;</i>.</li> <li>This is followed by a list of servers or server groups used for biasing. Entries take the following form:<br/><i>&lt;server&gt;:&lt;Bias value&gt;</i></li> </ul> <p>Enter 0 for the Bias value if you selected the Round robin algorithm.</p> |
| NOTMANAGED            | <p>Equivalent to clearing the “<b>Manage workload for this program</b>” on page 45 check box in the Configuration Tool. Create a separate entry for each server group that is to be excluded from workload management.</p>  |

## PRODUCT section of the configuration file

The PRODUCT section of the configuration file defines the APPLID for the Client daemon.

Table 10. SECTION PRODUCT

| Entry in the INI file | Configuration Tool field  |
|-----------------------|---|
| SECTION=Product       |   |
| APPLID                | <p>Enter an alphanumeric identifier, in the range A-Z and 0-9, up to 8 characters in length. This identifies the client connection to the Gateway daemon. The APPLID is not case sensitive.</p> |

The following template shows the INI file definition:

```
SECTION=Product
  APPLID = cccccccc

ENDSECTION
```

## Customizing cicsterm

The following topics cover customizing cicsterm for keyboard mapping and screen colors.

### Keyboard mapping for cicsterm

The keyboard mapping for terminal emulator operation is defined in a keyboard mapping file. A sample key mapping file is supplied with your CICS Universal Client; see “Sample configuration and mapping files” on page 46 for details. It is recommended that you create your own customized mapping file.

The keyboard mapping file can be specified by:

- The -k option of the cicsterm command, which identifies a keyboard mapping file with a particular terminal (see “cicsterm command reference” on page 77).
- The CICSKEY environment variable. For example:

```
SET CICSKEY=C:\custom\mykeys.ini
```

See your operating system documentation for other ways of setting this environment variable.

If you do not specify otherwise, a file name of cicskey.ini in the <install\_path>\bin subdirectory is assumed.

You can change the keyboard mapping file at any time, although changes do not take effect until the next time the terminal emulator is started.

### Keyboard mapping file syntax

This section describes the syntax of the keyboard mapping file. A statement must be provided for each key that is needed, because there are no default assignments (except for the alphabetic and numeric keys). There is no case sensitivity. Each binding must be on a separate line, and of the following form:

```
BIND 3270function [modifier+] key [;comment|#comment]
```

For example, to map the 3270 function EraseEof to the Ctrl+Delete keys pressed together the binding is as follows:

```
bind      EraseEof          Ctrl+Delete ;erase to end of field
```

### The keyboard mapping file

In the mapping file, *3270function* can be any one of the following:

|               |             |      |      |
|---------------|-------------|------|------|
| backspace     | pa1         | pf1  | pf13 |
| backtab       | pa2         | pf2  | pf14 |
| clear         | pa3         | pf3  | pf15 |
| cursor down   |             | pf4  | pf16 |
| cursor left   | printscreen | pf5  | pf17 |
| cursor right  | reset       | pf6  | pf18 |
| cursor select | tab         | pf7  | pf19 |
| cursor up     |             | pf8  | pf20 |
| delete        | ignore      | pf9  | pf21 |
| enter         |             | pf10 | pf22 |
| erase eof     |             | pf11 | pf23 |
| erase input   |             | pf12 | pf24 |
| home          |             |      |      |
| insert        |             |      |      |
| newline       |             |      |      |

The value of *ignore* is provided to permit unwanted control keys on the keyboard to be ignored. (Unexpected glyphs are not generated.)

The *Modifier* can be any one of:

Alt  
Ctrl  
Shift

The *Key* can be any one of the keys shown in Table 11, (but some combinations of modifier+key are not supported — see “Key combinations” on page 53):

Table 11. Keys that you can map

| Group         | Keys                                   |
|---------------|--|
| Escape key    | Escape                                 |
| Function keys | f1 f2 f3 f4 f5 f6 f7 f8 f9 f10 f11 f12 |
| Numeric keys  | 0 1 2 3 4 5 6 7 8 9                    |



Table 11. Keys that you can map (continued)

| Group           | Keys  |
|-----------------|---|
| Alphabetic keys | a b c d e f g h i j k l m<br>n o p q r s t u v w x y z  |
| Tab key         | Tab   |
| Movement keys   | newline backspace<br>insert home pageup<br>delete end pagedown<br>up left down right  |
| Keypad keys     | keypad/ keypad* keypad-<br>keypad7 keypad8 keypad9<br>keypad4 keypad5 keypad6 keypad+<br>keypad1 keypad2 keypad3<br>keypad0 keypad. keypadenter |

In addition, the following key mappings are allowed:

|            |             |
|------------|-------------|
| bind Clear | Pause       |
| bind Reset | Scroll Lock |

**Key combinations:** The following combinations of modifier and key can be mapped:

**No modifier**

All keys available for mapping.

**Alt modifier**

Only function keys, numeric keys, movement keys, and alphabetic keys can be mapped.

**Ctrl modifier**

Only function keys, movement keys, alphabetic keys, tab key, and keypad keys can be mapped.

**Shift modifier**

Only function keys, numeric keys, tab key, and alphabetic keys can be mapped.

**Note:** All modifier and key combinations that are not pre-empted by Windows can be mapped.

## Customizing the screen colors for cicsterm

Screen colors and attributes are defined in a color mapping file. A sample is provided for you to tailor; see “Sample configuration and mapping files” on page 46 for details. It is recommended that you create your own customized mapping file.

The color mapping file can be identified by either of these methods:

- The -c option of the cicsterm command, which identifies a color mapping file with a particular server.
- The CICSCOL environment variable: For example:

```
SET CICSCOL=C:\custom\mycols.ini
```

You can also set this environment variable through the **System** icon in the Control Panel.

If you do not specify otherwise, a file name of `cicscol.ini` in the `<install_path>\bin` subdirectory is assumed.

A color mapping file provides alternative representations in hardware environments where it is not possible exactly to replicate 3270 screen attributes, for example, blinking or underscore. The color mapping file therefore defines how 3270 screen attributes are emulated on the client hardware.

If the color mapping file specifies a mapping for an attribute, this mapping is used even if the hardware upon which the CICS Universal Client is running actually supports the screen attribute.

If an application requests a 3270 field to be displayed with, for example, underscore, and no emulation setting has been specified, and the hardware cannot display underscore, the field is displayed without any highlighting at all.

The color mapping file is optional. However, for most hardware environments a mapping file is required if blinking or underscore support is required by the emulator.

You can change the color mapping file at any time, although changes do not take effect until the next time the terminal emulator is started.

### Color mapping syntax

The syntax of the color mapping file is as follows. Each binding must be on a separate line, in this form:

```
BIND 3270attrib fg_color[/bg_color] [;comment|#comment]
```

Specifying a space between `fg_color` and `/bg_color` causes `bg_color` to be ignored.

The file is not case-sensitive.

### The color mapping file

In the color mapping file, *3270attrib* can be any one of the following:

```
normal_protected    intensified_protected
normal_unprotected  intensified_unprotected

default    blinking_default    underscored_default
blue       blinking_blue       underscored_blue
green      blinking_green      underscored_green
cyan       blinking_cyan       underscored_cyan
red         blinking_red        underscored_red
magenta    blinking_magenta    underscored_magenta
white       blinking_white      underscored_white
yellow      blinking_yellow     underscored_yellow

default_highlight

operator_information_area
```

Each of *fg\_color* and *bg\_color* (foreground color and background color) can be any one of the following:

|         |               |
|---------|---------------|
| black   | light_gray    |
| blue    | light_blue    |
| brown   | yellow        |
| cyan    | light_cyan    |
| green   | light_green   |
| magenta | light_magenta |
| red     | light_red     |
| gray    | white         |

If *bg\_color* is omitted, a default value of black is taken.

---

## Disabling pop-up windows

Enabling and disabling pop-up windows on CICS Universal Client for Windows.

The Client daemon interacts with the desktop, and displays pop-up message windows by default.

To disable pop-up message windows, run the Configuration Tool and deselect the 'Enable pop-up windows' field on the Client daemon resources panel.

---

## Checking your configuration

After you have configured your system, check that it is configured correctly.

1. Start the CICS Universal Client.
2. Run one of the sample programs supplied. See file `samples.txt`, in the `<install_path>\bin` subdirectory, for details, including compilation instructions and information on compiler considerations.

### Related information

"Starting the Client daemon" on page 65



---

## Chapter 6. Client security

This information describes how to provide a user ID and password when connecting to a CICS server.

---

### Client security overview

CICS servers might require the Client daemon to supply a user ID and password before they permit the following:

- A client connection
- Terminals to be installed
- Transactions to be run

This depends on the server and protocol security settings. The user ID and password are sent to the server of the transaction attach request for each conversation. A user ID and password are also required when a sign-on transaction is invoked on a sign-on capable terminal. In this instance, the user ID and password are flowed to the server as part of the 3270 data stream.

User IDs and passwords must not contain DBCS characters.

If no user ID is passed by a CICS Universal Client user application, and no default is set by the CICS Universal Client, the transaction is run using the mainframe CICS server's default user ID and password if the **Usedfltuser** parameter on the CICS server connection definition is set to Yes. If this parameter is set to No, security is enforced by the host CICS server and a user ID and password will need to be supplied. In each case, transactions execute in the server with the authorities assigned to the user ID authenticated.

Because the Client daemon has no security manager, it does not support user ID authentication. Configure your CICS server client connections so that incoming attach requests must specify a user ID and password. For mainframe servers, specify **AttachSec = Verify** in the CICS connection definition. **AttachSec = Identify**, which indicates that a user ID, but not password, is required, is **not** supported for client connections.

---

### Default connection settings

The Client daemon maintains a default user ID and password for each server connection, which can be set by any of the following methods:

- CICSCLI security commands:  
`cicscli -c=servername -u=userid -p=password`
- From C use the ESI function **CICS\_SetDefaultSecurity**.
- From C++, use the **makeSecurityDefault** method of the **CclConn** or **CclTerminal** class.
- From COM, use the **MakeSecurityDefault** method of the **Connect** or **Terminal** COM class.
- Through a Client daemon security window; see "Security windows" on page 58.

These default values are used when required on all subsequent transaction requests for that server, provided that no values have been passed on the ECI request itself, or have been set for the specific EPI terminal against which the transaction will run.

**Note:** If the Client daemon is running in an environment where it survives user logoff, for example, as a Windows service, the default user ID and password values entered by the current user are retained even when that user logs off, and are subsequently reused as required.

## Security windows

The Client daemon will display a security window to allow the user to enter a user ID and password if **ALL** of the following are true:

- The Enable pop-up windows field in the Configuration Tool is selected; see “Enable pop-up windows” on page 34.
- The client is not running as a service, or is running as a service that is enabled to interact with the desktop.
- The server requires that a user ID and password are flowed in the transaction attach request.
- No default security has yet been set for the server connection **or** default security has been set but the settings produce a security error on the server, for example, password expired.
- The transaction being invoked by the client is CCIN (client install) or CTIN (terminal install).
- A terminal user ID and password have not been supplied on a terminal install request.

Values entered via a security window, once verified, are used to set the default user ID and password values for that server connection.

Security windows are not displayed directly by ECI or EPI transaction requests, although they can be prompted by these requests, if the request causes a server connection to be established, or a terminal to be installed.

---

## ECI security

An application can provide a user ID and password on an ECI request; these values override any default values set for the server connection.

### **C programs**

Set `eci_userid` and `eci_password` or `eci_userid2` and `eci_password2` in the ECI parameter block.

### **C++ programs**

Set the `userid` and `password` parameters when constructing a server connection object - `CclConn`.

### **COM programs**

Set the `userid` and `password` via the `Details` method on the `Connect` object.

---

## EPI terminal security

The Client daemon also maintains a user ID and password for each installed terminal. These values override any default values set for the server connection. .

Terminal security is normally required only if using sign-on incapable terminals.

### Changing the user ID and password

The user ID and password may be changed at any time, as follows:

- C programs:  
Set `UserId` and `Password` in the `CICS_EpiAttributes_t` structure on a `CICS_EpiAddExTerminal` call. Or, use the EPI function `CICS_EpiSetSecurity`. This call would typically be used to change the terminal security settings if, for example, the user's password had expired.
- C++ programs:  
Set the `userid` and `password` parameters when constructing a `CclTerminal` class object. Or, use the `alterSecurity` method of the `CclTerminal` class.
- COM programs:  
Use the `AlterSecurity` method of the `Terminal` COM class. This can only be used for sign-on incapable created terminals.

---

## Password expiry management

For CICS clients, the management of expired passwords can be handled by the ESI functions `CICS_ChangePassword` and `CICS_VerifyPassword`. Also, security windows will prompt specifically for any unknown user ID, incorrect password, or expired password, after the user has initially entered a user ID and password through a security window.

The ESI functions can be used only with CICS servers that support password expiry management (PEM). See "Supported software" on page 3 for information on supported servers. Refer to the documentation for your CICS server for information on PEM support.

To use PEM, the Client daemon must be connected to the CICS server over SNA. An External Security Manager such as Resource Access Control Facility (RACF®), must also be available to the CICS server. ESI calls can be included within your ECI or EPI application. Only CICS servers returned by the `CICS_EciListSystems` and `CICS_EpiListSystems` functions are valid.

---

## Sign-on capable and sign-on incapable terminals

Sign-on capable terminals allow sign-on transactions, either CICS-supplied (CESN) or user-written, to be run, whereas sign-on incapable terminals do not allow these transactions to be run.

If a terminal resource is installed as **sign-on capable**, the application or user is responsible for starting a sign-on transaction; the user ID and password, once entered, are embedded in the 3270 data. If the terminal resource is installed as **sign-on incapable**, the user ID and password are authenticated for each transaction started for the terminal resource.

## Specifying the sign-on capability of a terminal

Prior to Version 3.1.0 of Clients and Gateways, whether a terminal was sign-on capable or not depended upon the server implementation. Client terminals installed on distributed CICS servers were sign-on capable; terminals installed on mainframe CICS and CICS Transaction Server for iSeries servers were sign-on incapable.

In Version 3.1.0, extended EPI function was introduced to allow the sign-on capability of a terminal to be specified by one of the following methods.

- C programs:  
Use **CICS\_EpiAddExTerminal** and set the sign-on capability parameter in the **CICS\_EpiAttributes\_t** structure.
- C++ programs:  
Set the sign-on capability parameter when constructing a **CclTerminal** class object.
- COM programs:  
Use the **SetTermDefns** method of the **Terminal** COM class.

The sign-on capability of the installed terminal is returned in the terminal attributes. This will be set to **SIGNON\_UNKNOWN** if the server does not return a sign-on capability parameter in the terminal install (CTIN) response.

To use any of the extended EPI functionality, ensure that you have applied the relevant server APAR; see “CICS server PTF requirements” on page 5.

### Mainframe CICS servers

These servers support both sign-on capable and incapable terminals, provided that they are at the prerequisite maintenance level. A terminal install request that does not specify any sign-on capability, for example from **CICS\_EpiAddTerminal**, results in a sign-on incapable terminal being installed.

#### For sign-on capable terminals:

- Use the **CICS\_EpiAddExTerminal** call specifying a **SignonCapability** of **CICS\_EPI\_SIGNON\_CAPABLE**.
- You do not need to set the userid and password fields on the **CICS\_EpiAddExTerminal** call or use **CICS\_EpiSetSecurity**, provided that you specify **UseDfltUser = Yes** in the CICS connection definition on the server.
- A userid and password entered through a sign-on transaction are flowed to the server as part of the 3270 data stream and they will therefore appear in a client trace.

Specify **UseDfltUser = Yes** in the CICS CONNECTION definition, or ensure that the system administrator sets a default connection userid and password for the client. Otherwise, the add terminal request might fail with an **EPI\_ERR\_SECURITY** return code. The default user ID must have sufficient privileges to allow the CTIN transaction to run.

- Before the user has signed on, transactions run under the default userid for the CICS server. After sign-on, transactions run under the signed-on userid.

#### For sign-on incapable terminals without terminal security:

- Use the **CICS\_EpiAddTerminal** call
- A connection userid and password are required regardless of the setting of the **UseDfltUser** in the CICS connection definition on the server.



- Transactions run under the userid specified in the corresponding FMH attach request.

**For sign-on incapable terminals with terminal security:**

- Use the **EpiAddExTerminal** call specifying a **SignonCapability** of **CICS\_EPI\_SIGNON\_INCAPABLE**.
- Set the userid and password fields on the **CICS\_EpiAddExTerminal** call.
- Specify **UseDfltUser = No** in the CICS connection definition on the server to enforce security.
- Use **CICS\_EpiSetSecurity** in conjunction with **CICS\_VerifyPassword** and **CICS\_ChangePassword** to change the security settings for an existing terminal.
- The userid and password are flowed to the server in the FMH of the attach request and will not appear in a client trace.
- Transactions will run under the userid specified in the corresponding FMH attach request.

To use one of the APIs that does not support the extended EPI functionality, use CRTE through a middle tier system to get sign-on capable terminal-like functionality.

**CICS Transaction Server for iSeries servers**

These servers do not support the sign-on capability parameter in a terminal install (CTIN) request. A terminal install request always results in a sign-on incapable terminal being installed.



---

## Chapter 7. Performance

This information helps you to:

- Understand the factors that affect CICS Universal Client performance
- Achieve the best performance from your system

---

### System considerations

#### CICS server transactions

The design of your CICS server transactions affects the performance of your system. The response time through the CICS Universal Client might increase if your transactions:

- Need to wait for shared resources, for example data sets or applications, to become available
- Make remote links to other CICS systems
- Are unnecessarily complex

Refer to the performance and tuning documentation for your CICS server system for information on how to get the best performance.

#### Extended logical units of work

Take care when extending a logical unit of work across multiple program link calls that might span a long time period (for example, user thinking time). The logical unit of work holds various locks, and other CICS resources, on the server. This might cause delays to other users who are waiting for the same locks and resources.

Also, each logical unit of work occupies one CICS non-facility task for the duration of its execution. This means that you must define enough free tasks in the CICS server to service the maximum expected number of concurrent calls.

Refer to *CICS Transaction Gateway: Programming Guide* for more information.

---

### Tracing and performance

Tracing the Client reduces performance significantly. Where possible, try to measure response times, without using tracing, through the different parts of your system, to find where delays are happening. For example, you could measure response times at the user application, or through the facilities provided by CICS and WebSphere Application Server.

If you need to trace the Client, take the following steps to lessen the impact on performance:

- Use memory mapped trace whenever possible; see “Memory mapped tracing” on page 94. This should be suitable in most cases, unless it was not possible to flush the buffers, for example.
- Start by specifying the API.2, CCL and DRV.1 components. If this does not isolate the problem, include extra components as necessary.

IBM does not recommend the use of the full CICS Universal Client trace to monitor performance in a production environment.

---

## Performance monitoring tools

### **Performance Monitor (perfmon)**

This utility is available on Windows. Refer to the documentation for your operating system for more information.

### **netstat**

Shows network status.

Refer also to the performance and tuning documentation for SNA, TCP/IP, CICS Transaction Server for z/OS, and TXSeries, and the documentation supplied with your operating system.

---

## Chapter 8. Operating the Client daemon

This information describes how to operate the Client daemon. The Client daemon always runs as a user process for CICS Universal Client. The process is started and stopped from a command prompt using the cicscli command. Running the Client daemon as a service for CICS Universal Client is not supported.

---

### The cicscli command

The cicscli command is used to start and shut down the Client daemon, check the availability of servers, and set other options.

The Client daemon starts automatically when you invoke any of the client functions such as EPI, ECI, or 3270 terminal emulation; you do not need to explicitly start the Client daemon, but you must use the cicscli command to shut it down.

The following table shows the functions that you can perform with the cicscli command, and the options associated with each function:

| Function   | Options        |
|--|----------------|
| Start the Client daemon, and start communication with CICS servers         | -s             |
| Shut down the Client daemon  | -i or -x       |
| Restart the Client daemon  | -j or -y       |
| Create autostart parameters for the Client daemon                          | -r             |
| Start client tracing   | -d             |
| Use memory mapped tracing  | -b             |
| Stop client tracing  | -o             |
| Specify the client components to be traced                                 | -m             |
| Set up security  | -c, -u, and -p |
| List connected CICS servers  | -l             |
| Enable the display of pop-up messages                                      | -e             |
| Disable the display of pop-up messages                                     | -n             |
| Disable all output messages  | -q             |
| Wait for confirmation before completion                                    | -w             |
| Display information about the version and build level of the Client daemon | -v             |

The following sections provide examples of using the cicscli command. Full details of the command syntax are in “cicscli command reference” on page 69.

### Starting the Client daemon

To start the Client daemon, enter:

```
cicscli -s
```

or use the **Start Client** shortcut on the Start menu.

To start the Client daemon and start communication with a CICS server, enter:

```
cicscli -s=servername
```

where *servername* is the name of a CICS server.

## Starting connections with additional servers

To start a connection to a CICS server when the Client daemon is already running, enter:

```
cicscli -s=servername
```

where *servername* is the name of a CICS server.

**Note:** If you change and reinstall the CICS connection definition, you must stop and restart the connection.

## Shutting down the Client daemon normally

To shut down the Client daemon for all connected servers, after all outstanding units of work have completed, enter:

```
cicscli -x
```

or use the **Stop Client** shortcut on the Start menu.

To shut down the session with a particular server, enter:

```
cicscli -x=servername
```

where *servername* is the name of a CICS server. This stops only the session with the named server; it does not shut down the Client daemon or connections to other servers.

## Shutting down the Client daemon immediately

To shut down the Client daemon for all connected servers, without completing outstanding units of work, enter:

```
cicscli -i
```

To shut down the session with a particular server, enter:

```
cicscli -i=servername
```

where *servername* is the name of a CICS server. This stops only the session with the named server; it does not shut down the Client daemon or connections to other servers.

## Restarting the Client daemon normally

To shut down the Client daemon for all connected servers, after all outstanding units of work have completed, and then start it again, enter:

```
cicscli -y
```

`cicscli -y` is equivalent to `cicscli -x` followed by `cicscli -s`. This does not re-establish server connections or trace settings.

## Restarting the Client daemon immediately

To shut down the Client daemon for all connected servers, without completing outstanding units of work, and then start it again, enter:

```
cicscli -j
```

`cicscli -j` is equivalent to `cicscli -i` followed by `cicscli -s`. This does not re-establish server connections or trace settings.

## Starting client tracing

To start tracing the Client daemon, enter:

```
cicscli -d
```

To trace the Client daemon from the startup sequence, enter the `-s` and `-d` options together:

```
cicscli -d -s
```

The Client daemon writes trace entries to the `cicscli.bin` file in the `<install_path>\bin` subdirectory. New trace entries overwrite any existing entries in the trace file. If required, make a backup copy of the old trace file before you start tracing.

Performance while tracing is on can be improved by using *memory mapped tracing*. With memory mapped tracing, data is stored initially in memory, and flushed to disk by the operating system's paging mechanism. For more information, see "Memory mapped tracing" on page 94.

To use memory mapped tracing, do the following:

1. Turn on wrapping trace by setting the **Client trace file wrap size (KB)** field in the Configuration Tool to a value greater than 0; see "Client trace file wrap size (KB)" on page 46 for details of the field setting.
2. When you turn on tracing, specify the `-b` option as well as the other options, for example:

```
cicscli -d -b
```

or

```
cicscli -d -m=component_list -b
```

Use the `cicsftrc` utility to format the trace file; see "Formatting the binary trace file" on page 94.

## Specifying the trace components

To specify which client components to trace, enter, for example:

```
cicscli -m=TRN,API.2
```

For information on which components you can trace, see "cicscli command reference" on page 69.

## Stopping client tracing

To stop tracing the Client daemon, enter:

```
cicscli -o
```

Trace stops automatically if you enter the `cicscli -x` command.

## Setting up security for the Client daemon

You can use the following commands after first starting the Client daemon.

To set a user ID to use when accessing server *servername*, enter:

```
cicscli -c=servername -u=userid
```

where *userid* is the user ID and *servername* is the server name.

To set a password to use when accessing server *servername*, enter:

```
cicscli -c=servername -p=password
```

where *servername* is the name of the server and *password* is the password.

You can enter the -u and -p options together.

You can also specify the security parameters when you start the Client daemon or make a connection to a server:

```
cicscli -s=servername -u=userid -p=password
```

## Displaying information about the version of the Client daemon

To display information about the version and build level of your Client daemon, enter the command

```
cicscli -v
```

## Listing the connected servers

To list all the servers being used by the Client daemon, and their status, enter:

```
cicscli -l
```

The status of connected servers is updated as a result of requests being flowed and protocol specific events. The status returned is the last known state of connected servers, which might not be the same as the current state.

## Disabling the display of messages from the Client daemon

To disable the display of all messages produced by the command, enter, for example:

```
cicscli -s -q
```

## Enabling and disabling the display of pop-up messages from the Client daemon

To disable the display of pop-up messages, enter:

```
cicscli -n
```

To enable the display of pop-up messages, enter:

```
cicscli -e
```

You can specify the -n option together with the -s option.

The display of pop-up messages is enabled by default.



## Displaying command options for the Client daemon

To display the options of the cicscli command, enter:

```
cicscli -?
```

## Alternative to cicscli.exe

cicscliw.exe performs the same functions as cicscli. However, it is a Windows program that issues all of its messages into a dialog box, rather than the command prompt. Use it if you want the Client daemon to behave in the same way as the CICS Client for Windows 3.11 v2.

---

## cicscli command reference

This section provides a reference guide for the cicscli command.

The dash (-) may be replaced with the forward slash (/) character. The commands and options are not case-sensitive.

All options of the form *-x=variable* may contain spaces in the variable part, if it is enclosed in double quotes. Double quotes within variables must be entered as `\"`, that is with a backslash preceding the double quote.

```
cicscli [[-s[=servername]]|[-x[=servername]]|[-i[=servername]]|[-j]|[-y] ]
[-l]
[[-d[=nnn] [-b] [-m[=components]]]|-o]
[-n|-e]
[-c=servername [-u[=userid]] [-p[=password]]]
[-r [-a<parameter1> [-a<parameter2>...]] [-w|-q]
[-v]
[-y|-j]
```

The options are:

**-b** Uses memory mapped trace. This improves performance significantly compared with standard file I/O. This option is valid only if specified when tracing is switched on, and requires wrapping trace to be enabled. See “Starting client tracing” on page 67 for more details.

**-c=servername**

Identifies the name of the server to which security information in the form of a user ID and password is to be associated. Some CICS servers require the user to provide security information to the server before interacting with the server. The Client daemon prompts the user at the workstation for a user ID and password, unless you provide them by using the `-u` and `-p` options.

**-d=[nnn]**

Starts debug tracing for the Client daemon. If tracing is required while the Client daemon is starting up, this option may be specified along with the `-s` option.

*nnn* is the maximum size of data areas to be traced in bytes. The range is 1 through 32 767 bytes, and the default value is 512 bytes. If you are producing a trace for your support organization, set `-d` to at least 1000 to ensure that all relevant data is included.

The Client daemon writes trace entries to the `cicscli.bin` file in the `<install_path>\bin` subdirectory. New trace entries overwrite any existing entries in the trace file. If required, make a backup copy of the old trace file before you start tracing.

Use the `cicsftrc` utility to format the trace file. The resulting file, `cicscli.trc`, is an ASCII file that you can read with a text editor. For more information see “Formatting the binary trace file” on page 94.

- e** Enables the display of Client daemon error and security messages in pop-up windows.
- i** Shuts down the Client daemon immediately. The Client daemon does not wait for outstanding units of work to complete. Stopping the Client daemon in this way can result in a loss of data at connected servers. To stop the Client daemon normally, use the `-x` option.
- j** Shuts down the Client daemon immediately and then restarts it.

A restart involves shutting down the Client daemon, waiting for it to shut down, and then starting it again. `cicscli -j` is equivalent to `cicscli -i` followed by `cicscli -s`. Server connections are not re-established when the Client daemon is restarted.

The Client daemon does not wait for units of work to complete. This might result in loss of data. To restart the Client daemon normally, use the `-y` option.
- l** Displays a list of all connected servers. For each server, the netname of the server as it is known to the Client daemon is also displayed, as well as the state of the connection to the server and the connection protocol.
- m=[components]**

Specifies a comma-separated list of identifiers for components that will be traced when tracing starts. You can specify any of the following components:

  - ALL** All components. Use it if performance allows, and consider using the binary formatting tool to filter information. See “Formatting the binary trace file” on page 94 for details.
  - API.1** The client API layer (level 1). This traces the boundary between the Client application and the Client daemon.
  - API.2** The client API layer (level 1 and 2). This gives level 1 plus additional parameter tracing.
  - API** Synonymous with **API.1**.
  - CCL** The Client daemon.
  - CPP** The C++ class libraries.
  - CLI** The `cicscli` command interface.
  - DEF** The default components, that is the **API**, **CCL**, and **DRV.1** components.
  - DRV** Synonymous with **DRV.1**.
  - DRV.1** Protocol driver tracing level 1. This traces data sent and received and provides supplementary information about failures.
  - DRV.2** Protocol driver tracing level 2. This traces internal flows through the protocol drivers and interactions with other software components. It is currently supported only by the **CCLTCP62** protocol driver.
  - EMU** `cicsterm` and `cicsprnt` emulators.
  - LMG** The Workload Manager.

**SER** When SER is included in the trace component list for CICS Universal Client the SER trace component will not be activated, it will be ignored and treated as an invalid component.

**TRN** The TRN component traces the internal interprocess transport between Client processes. Use it if entries in the Client log refer to functions such as FaarqGetMsg, FaarqPutMsg, or FaarqStart. TRN is the most verbose tracing component.

- If you are not sure whether a problem is inside the Client daemon, and you want to minimize the impact on performance, specify the DRV.1 and API components. You can also specify these components to help to determine which product is causing the system to lock up.
- Specify the API and CCL components if you believe that the problem is within the Client daemon.
- If you want to diagnose an application error, and are not interested in the Client daemon, specify only the API.2 and CPP tracepoints. The trace contains less information, and is easier to understand.

The **-m** option does not start tracing in the Client daemon; it simply specifies the components to trace. You cannot use **-m** while the Client daemon is not running, so in this case you must specify the **-s** option as well. Consider using wrapping trace (**-b**) for improved performance:

```
cicscli -m=component_list -b
```

If you specify **-m** with no parameters, a list of the possible component identifiers is displayed, with an 'x' beside each component that it is currently enabled for tracing.

You can also specify settings for trace components using the Configuration Tool (see "Trace settings" on page 45 in the Configuration chapter for details). Any component tracing specified using **cicscli** overrides that specified using the Configuration Tool. If component tracing is not specified either by the **cicscli** command or by using the Configuration Tool, a default set of components is traced, namely: DRV.1, CCL, and API. Any component tracing specified using the Configuration Tool overrides the default set of components.

Note that the **cicscli -d=nnn** command is used to set the maximum size of the data areas to be traced. The trace data might be truncated if you set *nnn* lower than the size of data expected.

**-n** Disables the display of Client daemon error and security messages in pop-up windows.

Any messages that would have been logged are still logged.

**-o** Stops tracing if it is already active.

**-p=password**

Sets the current password to be used when accessing the server specified by the **-c** option. (Or by the **-s** option.) This password is used if the server requires a password (and user ID) before running transactions on the client's behalf.

For ECI applications, any user ID and password specified in the ECI parameter block override values set by the **cicscli** command.

Specifying **-p** or **-p=** (that is, no password is specified) resets the associated password to a null value.

**-q** Disables the display of all messages produced by the **cicscli** command.

- s Starts the Client daemon. No attempt is made to initiate communication with a server unless *-s=servername* is specified. In this case, the Client daemon also connects to the server using information specified in the configuration file. The *servername* must correspond to an entry in the configuration file.
  
- u=*userid*  
 Sets the current user ID to be used when accessing the server specified by the *-c* option. (Or by the *-s* option.) This user ID is used if the server requires a user ID (and password) before running transactions for the Client daemon.  
  
 For ECI applications, any user ID and password specified in the ECI parameter block override values set by the *cicscli* command.  
  
 Specifying *-u* or *-u=* (that is, no user ID is specified) resets the associated user ID to a null value.
  
- v Displays information about the version and build level of the Client daemon.
  
- w Prompts the user, before the command completes, to press the Enter key, to confirm that information and error messages output to the screen have been read.
  
- x Shuts down the Client daemon normally. If *-x=servername* is specified, the connection to the server is terminated when all outstanding units of work on the specified server have completed. If other server connections are active, these remain unchanged.  
  
 If *-x* is specified without a server name, the Client daemon waits for all outstanding units of work to complete, terminates all connections to servers, and ends the control process. Using *-x* or *-x=servername* is the preferred way of stopping the Client daemon.
  
- y Restarts the Client daemon normally.  
  
 A restart involves shutting down the Client daemon, waiting for it to shut down, and then starting it up again. *cicscli -y* is equivalent to *cicscli -x* followed by *cicscli -s*. Server connections are not reestablished when the Client daemon is restarted.  
  
 Using *-y* is the preferred way of restarting the Client daemon.
  
- ? Causes the command syntax to be displayed.

---

## Changing the system time

| You can change the system time while the CICS Universal Client is running. If you  
 | change the system time, an active process responds to the changed time and not to  
 | the elapsed time.

| When setting clocks forward or back, the behavior of timeout settings will change.  
 | When the clock is set back the elapsed time for a timeout may be increased. When  
 | the clock is set forward a timeout may expire earlier. The maximum elapsed time  
 | for a timeout will be the original timeout value plus the value of the change in  
 | time. For example, if the current time is 19:00, and a timeout is set to expire 5  
 | minutes from now; the effect of setting the clock back by 1 hour is to increase the  
 | value of the timeout by 1 hour. The total elapsed time for the timeout is 1 hour  
 | and 5 minutes.

| The following time-outs are effected by this change:

- | • ECI time-outs
- | • EPI install timeout
- | • EPI read timeout
- | • Client daemon connection timeout.
- | • Client daemon load manager region timeout
- | • Client daemon server retry interval
- | • Gateway daemon idle timeout
- | • Gateway daemon ping timeout
- | • Gateway daemon close timeout
- | • Server idle time-outs
- | • Worker thread available thread timeout
- | • EXCI timeout



---

## Chapter 9. Terminal Emulation

This information describes how to use the cicsterm and cicsprnt programs.

---

### Summary of Terminal Emulation commands

#### cicsterm

This command starts a terminal emulation session with particular options.

#### cicsprnt

This command starts a printer terminal session with particular options.

---

### The cicsterm command

The cicsterm command controls 3270 terminal emulation. You can start emulator sessions, specify terminal emulator characteristics, and the names of the keyboard mapping and color mapping files.

You can have multiple terminal emulation sessions running simultaneously.

The cicsterm command detects whether the hardware on which the Client daemon is running is enabled for double-byte character set (DBCS) display. If it is, the emulator can display DBCS characters. Some uses of servers and protocols require a Model terminal definition for the emulator that explicitly specifies that the Client daemon wants to display DBCS.

For cicsterm emulators, the maximum screen size is 27 rows by 132 columns. This is because the Client daemon supports the ASCII-7 subset of the 3270 data stream architecture, which supports only 12 bit addressing. For more information, see *CICS Transaction Gateway: Programming Guide*.

The CICS Transaction Server interprets cicsterm as a remote terminal. The execution diagnostic facilities CEDF and CEDX have some restrictions on remote terminals. Refer to your CICS Transaction Server documentation for details.

### Using cicsterm

The following table shows the functions that you can perform with the cicsterm command, and the parameters associated with each function:

| Function  | Parameters |
|---|------------|
| Start a 3270 terminal emulator                        | -s and -r  |
| Specify the initial transaction                       | -t         |
| Specify the name of the keyboard mapping file         | -k         |
| Specify the name of the color mapping file            | -c         |
| Define the 3270 terminal emulator characteristics     | -n and -m  |
| Specify a terminal emulator that is sign-on incapable | -a         |
| Determine the print file processing                   | -p         |
| Specify a file to which print files are appended      | -f         |
| Wait for confirmation before completing               | -w         |

| Function                    | Parameters |
|-----------------------------|------------|
| Inhibit all output messages | -q         |

Issue a single `cicsterm` command, with all the parameters you require, as shown in the following example:

```
cicsterm -s=CICSTSW -t=CESN -k=mykeys.ini -c=mycols.ini
        -n=cicsv123 -f=clprint.txt -q
```

In this example:

**-s=CICSTSW**

A 3270 terminal emulator is started for the server `CICSTSW`.

**-t=CESN**

The initial transaction is `CESN`.

**-k=mykeys.ini**

The keyboard mapping file is `mykeys.ini`.

**-c=mycols.ini**

The color mapping file is `mycols.ini`.

**-n=cicsv123**

The 3270 terminal emulator characteristics are defined by the terminal definition `cicsv123`.

**-f=clprint.txt**

The print file will be appended to the file `clprint.txt`.

**-q** The display of messages output by the command is disabled.

All `cicsterm` parameters are optional. If you enter the `cicsterm` command without any parameters, defaults are taken from the configuration file. This is equivalent to using the CICS Terminal Start menu shortcut. Full details of the parameters are given in “`cicsterm` command reference” on page 77.

## Stopping a terminal emulator

To stop a terminal emulator, enter the string specified by the Terminal exit configuration setting from an empty terminal screen, and then press Enter. The default string is `EXIT`

## cicsterm and user exits

You can use `cicsterm` to drive EPI user exits.

The EPI user exits, and how `cicsterm` can use them, are described in *CICS Transaction Gateway: Programming Guide*.

## cicsterm and RETURN TRANSID IMMEDIATE

When an application running from a `cicsterm` session issues either of the commands:

```
EXEC CICS RETURN TRANSID(name) IMMEDIATE
EXEC CICS RETURN TRANSID(name) IMMEDIATE INPUTMESSAGE(data-area)
```



the transaction named in the TRANSID option starts immediately without any user input. When the INPUTMESSAGE option is specified, the contents of the *data-area* are passed to the new transaction, and the screen is not updated with the *data-area* contents.

Issuing these EXEC CICS commands from cicsterm does not result in the StartTranExit or ReplyExit user exits being driven. See *CICS Transaction Gateway: Programming Guide* for more information.

---

## cicsterm command reference

The dash (-) may be replaced with the forward slash (/) character.

```
cicsterm [-s[=servername] | -r[=servername]]
[-t=[initialtransid]]
[-k=keyfile]
[-c=[colorfile]]
[-m=[modelname]]
[-a]
[-n=netname]
[-p=printcmd | -f=printfile]
[-q | -w]
[-?]
```

The options are:

**-a** Specifies that the terminal emulator is *not* sign-on capable. By default, cicsterm creates terminal emulators that are sign-on capable.

For more information on sign-on capability, see *CICS Transaction Gateway: Programming Guide*.

**-c=colorfile**

Identifies the name of a color mapping file to be used with the emulator; see “Customizing the screen colors for cicsterm” on page 53 for more details. If you omit this parameter, the environment variable CICSCOL is assumed to identify the color mapping file. If CICSCOL is not defined, a file name of cicscol.ini in the <install\_path>\bin subdirectory is assumed.

If the parameter is specified as -c=, that is, the color mapping file name is omitted, the emulator runs without any color definitions.

**-f=printfile**

Specifies the name of a file to which the output of print requests is appended. If you do not specify a full path, *printfile* is created in the <install\_path>\bin directory. If the name of the file contains embedded blanks, it must be surrounded by double quotes (“”). Any double quotes within the name of the file must be entered as backslash double quote (\”).

If neither the -f or -p parameters is specified, the **Print command** or **Print file** configuration settings define the command, file, or default action to take with print requests.

**-k=keyfile**

Identifies the name of a keyboard mapping file to be used with the emulator; see “Keyboard mapping for cicsterm” on page 51 for more details. If this parameter is omitted, the environment variable CICSKEY is assumed to identify the key mapping file. If CICSKEY is not defined, a file name of cicskey.ini in the <install\_path>\bin subdirectory is assumed.

**-m=modelname**

Specifies the name of a Model terminal definition, as known at the server

to which the emulator is to connect, to be used to define the terminal characteristics. If neither this parameter nor `-n=netname` is specified, any Model terminal definition value from the configuration file is used. If no Model terminal definition value has been specified in the configuration file, the server's default terminal definition is assumed.

If the parameter is specified as `-m=` (that is, the modelname is omitted), any Model terminal definition value specified in the configuration file is ignored, and the server's default terminal definition is assumed.

This option is case-sensitive.

**`-n=netname`**

Specifies the name of a particular terminal definition at the server that this emulator is to be installed as. The precise interpretation of netname varies between servers.

This option is case-sensitive.

**`-p=printcmd`**

Specifies an operating system command used to process the temporary print file generated when print requests are received by the terminal emulator. If the command contains embedded blanks, enclose it in double quotes ("). Any double quotes within the command must be entered as backslash double quote (\").

The temporary print file is post-processed by appending the file name to the command, and executing the resultant command. Thus print output may simply be copied to a local printer, copied into a permanent file, processed further for inclusion into a document, and so on. If the temporary file is to be processed by a print command, the command is responsible for deleting the temporary file.

If neither the `-f` or `-p` parameters is specified, the **Print command** or **Print file** configuration settings define the command, file, or default action to take with print requests.

**`-q`** Disables the display of all messages output by the command.

**`-s=servername` or `-r=servername`**

Specifies the name of the server that the terminal emulator is to be connected to. This server name must correspond to an entry in the configuration file.

You can specify `-s`, or `-r`, but not both. If neither parameter is specified, the first server entry in the configuration file is used.

If the parameter is specified as `-s` or `-r` (that is, no server name is provided), and the configuration file identifies more than one potential server to which the Client daemon can connect, the user is prompted to select from a list of available servers. These prompts are generated even if messages have been disabled (the `-q` parameter is specified).

If there is only one potential server identified in the configuration file, that server is used and the user is not prompted.

**`-t=initialtransid`**

Identifies the initial transaction to be invoked for this terminal. If this option is omitted, any initial transaction specified in the configuration file is run. The string can be up to 128 characters long, specifying both a transaction name, and parameters to be passed to the transaction. The

transaction name is the first four characters or the characters up to the first blank in the string. The rest of the string is the parameter data.

If the parameter is specified as `-t=` (that is, the initialtransid is omitted), any initial transaction specified in the configuration file is ignored.

This option is case-sensitive.

Ensure that transaction that you specify here does not require terminal input to complete.

- w** Prompts the user to press the Enter key, to confirm that messages output to the screen (both informational and error) have been read, before the command completes.
- ?** Causes the parameter syntax to be listed; any other options specified are ignored.

---

## Terminal emulator preferences

The terminal emulator allows you to choose a font, by clicking **Settings → Font**. If the **Settings → Save on exit** menu option is selected, your choices are stored in CICSTERM.INI, for use in future sessions. The Windows variable APPDATA defines the path for the CICSTERM.INI file. A copy of CICSTERM.INI is created for each Windows user account as follows:

```
c:\Documents and Settings\username\Application Data\IBM\CTG\CICSTERM.INI
```

where *username* represents your Windows logon name.

On Windows® Vista systems the value of APPDATA is:

If you share a computer with others, or are a user of multiple computers on a network, your preferences will be used whenever and wherever you launch terminal emulator. This functionality is provided by means of Windows roaming user support.

The CICSTERM.INI file is not erased when you uninstall CICS Universal Client. Therefore, when you re-install CICS Universal Client, the emulator uses the settings from the old CICSTERM.INI files.

The terminal emulator has a menu bar with **File** and **Settings** menus.

The commands on the **File** menu are:

- Print** Prints the emulator screen. This has the same effect as pressing the Print Screen key.
- Exit** Stops the terminal emulator.

The commands on the **Settings** menu are:

- Font** Opens a standard Windows dialog box that allows you to select any of the fixed-pitch fonts installed on your system. Select a font, font style, and size, and then select **OK**. The terminal window is then resized according to your font selection.

### **Autosize**

Specifies that the size of TrueType fonts is adjusted according to the size of the terminal window. That is, when you maximize, minimize, or drag the

borders to resize the window, the font is resized to match the new window size. This command has no effect if the current font is not a TrueType font.

#### Save on Exit

Specifies that the current font, terminal window size and terminal position will be saved when you close the terminal window. The settings are saved in the CICSTERM.INI file, as explained at the start of this section.

---

## The cicsprnt command

The cicsprnt command controls 3270 printer terminal emulation.

An application running on a server can direct output to a printer in one of the following ways:

- An application running from a terminal can initiate printing by sending a map or data with the PRINT indicator set.
- A user can start a 3270 Print Terminal Emulator, at a client, using the cicsprnt command. A 3270 Print Terminal Emulator must be started for a netname or model terminal definition predefined in the server's terminal tables. Output is directed to such a device by starting a transaction against the printer device.
- At client workstations you can use the PrintScreen key, as defined by the keyboard mapping file. However, any lines that contain only null characters are not printed. For a 'blank' line to be printed, it must contain at least one space character.

For cicsprnt emulators, the maximum screen size is 27 rows by 132 columns. This is because the Client daemon supports the ASCII-7 subset of the 3270 data stream architecture, which supports only 12 bit addressing. For more information, see *CICS Transaction Gateway: Programming Guide*.

## Using cicsprnt

The following table shows the functions that you can perform with the cicsprnt command, and the parameters associated with each function:

| Function  | Parameters |
|---|------------|
| Start a 3270 print terminal emulator.   | -s and -r  |
| Specify the initial transaction.  | -t         |
| Define the 3270 printer terminal emulator characteristics.                                    | -n and -m  |
| Determine the print file processing.  | -p         |
| Specify a file to which print files are appended. The default location is <install_path>\bin. | -f         |
| Wait for confirmation before completing.  | -w         |
| Inhibit all output messages.  | -q         |
| Issue one print job per transaction.  | -j         |
| Display help  | -?         |

Issue the cicsprnt command once with all the parameters you require, as shown in this example:

```
cicsprnt -s=CICSTSW -n=P123 -t=XPRT -f=clprint.txt -q
```

In this example:

**-s=CICSTSW**

A 3270 print terminal emulator is started for the server CICSTSW.

**-n=P123**

The 3270 print terminal emulator characteristics are defined by the terminal definition P123

**-t=XPRT**

The initial transaction is XPRT.

**-f=clprint.txt**

The print file to which print requests are appended is clprint.txt, in the default location (<install\_path>\bin).

**-q** The display of messages output by the command is disabled.

You must specify at least one of these parameters:

**-n=netname**

**-m=modelname**

All other parameters are optional, and defaults are taken from the configuration file. Full details of the parameters are given in “cicsprnt command reference.”

If the system running the Client daemon supports DBCS, it is assumed that the printer attached to the processor also supports DBCS. Conversely, if the system does not support DBCS, the Client daemon will not send DBCS data to the printer.

The cicsprnt process runs as a minimized window, which can be enlarged to view the printer status. Use the pulldown menu to terminate the print function.

## cicsprnt and user exits

You can use cicsprnt to drive EPI user exits.

The EPI user exits, and how cicsprnt can use them, are described in *CICS Transaction Gateway: Programming Guide*.

## cicsprnt and RETURN TRANSID IMMEDIATE

Unlike cicsterm, cicsprnt does not support these commands:

EXEC CICS RETURN TRANSID(*name*) IMMEDIATE

EXEC CICS RETURN TRANSID(*name*) IMMEDIATE INPUTMESSAGE(*data-area*)

For more information, refer to “cicsterm and RETURN TRANSID IMMEDIATE” on page 76.

---

## cicsprnt command reference

The dash (-) may be replaced with the forward slash (/) character.

```
cicsprnt -m=modelname|-n=netname  
[-s[=servername]|-r[=servername]]  
[-t=[initialtransid]]  
[-p=printcmd|-f=printfile]  
[-q|-w]  
[-j]  
[-?]
```

The options are:

**-f=printfile**

Specifies the name of a file to which the output of print requests is appended. If you do not specify a full path, *printfile* is created in the <install\_path>\bin directory. If the name of the file contains embedded blanks, it must be surrounded by double quotes (""). Any double quotes within the name of the file must be entered as backslash double quote (\").

If neither of the -f or -p parameters is provided, the **Print command** or **Print file** setting in the configuration file defines the command, file, or default action to take with print requests.

- j** Specifies that cicsprnt should concatenate all EXEC CICS SEND PRINT commands issued on a server transaction into a single print job. This print job is issued when the transaction terminates. Otherwise cicsprnt will generate a separate print job for every EXEC CICS SEND PRINT command issued for a server transaction.

**-m=modelname**

Specifies the name of a model terminal definition, as known at the server to which the 3270 Print Terminal emulator is to connect, to be used to define the terminal characteristics. If this parameter is not specified, any Model terminal definition value from the configuration file is used. If no Model terminal definition value has been specified in the configuration file, the server's default terminal definition is assumed.

You must specify either the -m or the -n option, or both.

This option is case-sensitive

**-n=netname**

Specifies the name of a particular terminal definition at the server that this 3270 Print Terminal emulator is to be installed as. The precise interpretation of netname varies between servers. For example, on TXSeries for AIX it is a netname.

You must specify either the -m or the -n option, or both.

This option is case-sensitive.

**-p=printcmd**

Specifies a command used to process the temporary print file generated when print requests are received by the terminal emulator. Enter the full path to the command, even if it is in a directory that appears in the search path.

If the command contains embedded blanks, the command must be surrounded by double quotes (""). Any double quotes within the command must be entered as backslash double quote (\").

If neither of the -f or -p parameters is specified, the **Print command** or **Print file** setting in the configuration file defines the command, file, or default action to take with print requests.

The temporary print file is post-processed by appending the file name to the command, and executing the resultant command. Thus print output may simply be copied to a local printer, copied into a permanent file, processed further for inclusion into a document, and so on. If the temporary file is to be processed by a print command, the command is responsible for deleting the temporary file.

- q** Disables the display of all messages output by the command.

**-s=servername or -r=servername**

Specifies the name of the server that the printer is to be connected to. This servername must correspond to an entry in the configuration file. You can specify -s, or -r, but not both.

If neither parameter is specified, the first server entry in the configuration file is used.

If the parameter is specified as -s or -r (that is, no servername is provided) then, if the configuration file identifies more than one potential server to which the Client daemon can connect, the user is prompted to select from a list of available servers. These prompts are generated even if the -q parameter is specified.

If there is only one potential server identified in the configuration file that server is used and the user is not prompted.

**-t=initialtransid**

Identifies the initial transaction to be invoked for this printer. If this option is omitted, any initial transaction specified in the configuration file is run. The string may be up to 128 characters long, specifying both a transaction name, and parameters to be passed to the transaction. The transaction name is the first four characters or the characters up to the first blank in the string. The rest of the string is the parameter data.

If the parameter is specified as -t= (that is, the initialtransid is omitted), any initial transaction specified in the configuration file is ignored.

**Note:** Be careful that transactions that you specify either here or in the configuration file do not require terminal input to complete.

This option is case-sensitive.

**-w** Prompts the user, before the command completes, to press the Enter key, to confirm that messages output to the screen (both informational and error) have been read.

**-?** Causes the parameter syntax to be listed; any other options specified are ignored.





---

## Chapter 10. Using the Workload Manager

This information discusses how to use the Workload Manager to balance the workload in your system effectively. For details of how to configure the Workload Manager see “Configuring the Workload Manager” on page 41.

---

### Workload Manager overview

The Workload Manager is designed to handle various problems when the Client daemon is used to connect with one or more CICS servers (CICS regions):

- How to get round the restriction on the number of clients that a single CICS server can accommodate on a particular port.
- How to distribute work across available, equivalent CICS regions.
- How to favor one region over another (*biasing*).
- How to handle requests that fail to reach a target CICS region.

The Workload Manager resolves these problems and others by dynamically selecting target regions and ports based upon criteria that you configure. It ensures that all calls in an extended Logical Unit of Work (LUW) are routed to the same CICS server.

### Key concepts

It is essential to understand the following concepts:

#### Regions

A region is an instance of a CICS server. This includes all the listeners configured for that region.

#### Programs

CICS programs are executable units that can be started within a CICS region. A particular CICS program might be available on multiple CICS regions. The Workload Manager has a list of CICS regions on which the program is defined (*program affinity*).

#### TCP/IP address

An address that uniquely identifies a machine on a particular network. Each machine may have many threads of execution running simultaneously; a TCP/IP port uniquely identifies a particular thread of execution.

#### TCP/IP port

A numeric TCP/IP end-point in the range of 0-65535. This port number is defined in the configuration file (ctg.ini) file for each instance of a server definition.

The number of client requests that can be handled on a particular port varies with the CICS server platform. For example, a TXSeries for AIX or TXSeries for Windows may handle client requests via a number of ports, but only about 250 client requests can be handled per port. You might need to define multiple server instances.

#### Server instance

An entry in ctg.ini that corresponds to an instance of a CICS server. For a particular CICS region there may be multiple instances of CICS server definitions, each with different port numbers. The names provided by the

**Server name** configuration setting (Server=*servername* in the configuration file) are used in the actual ECI requests. In the Workload Manager section of the Configuration Tool, the server instances are gathered together in Server Groups.

In CICS Universal Client Version 3.0 this was known as a *Listener*.

### Server Group

The Configuration Tool uses Server Groups to group together server instances. A Server Group can correspond to one CICS region on a server, or to several physical servers.

The first time an instance of the Client daemon makes a request, it selects a server instance from the group at random. For the duration of the life of that Client daemon instance, all subsequent requests to that Server Group are sent to the same server instance.

An ECI program can be associated with a Server Group. The Workload Manager assumes that the program exists on all server instances in the Server Group.

### Workload management

The ability of the Workload Manager to select a suitable CICS server as a target for a client request. The load balancing algorithms try to spread the workload over various server instances on a particular region (via random selection) and they allow the user to effectively specify a bias for the selection of a particular region. Known inactive regions are not considered for selection.

**Note:** Apart from TCP/IP, other supported protocols can be used to communicate with CICS servers. For example, SNA can be used, and in this case the server instances can be identified by Logical Units (LU), rather than by TCP/IP ports.

---

## What the Workload Manager needs to know

This section discusses how CICS server instances relate to the CICS regions, and the information required by the Workload Manager to perform its load management.

The following table illustrates knowledge that the Workload Manager must have. Specifically, the Client daemon must be able to correlate server instances against the regions to which they belong.

| CICS Region | Server instance   |
|-------------|---|
| REGION1     | <ul style="list-style-type: none"><li>• CICS1</li><li>• CICS2</li><li>• CICS3</li></ul> |
| REGION2     | <ul style="list-style-type: none"><li>• CICS4</li><li>• CICS5</li></ul>                 |
| REGION3     | <ul style="list-style-type: none"><li>• CICS6</li></ul>                                 |

The Client daemon can connect to a specific region through only one server instance. So, in the example, a Client daemon can connect to a region using one of the following groups of servers:

- CICS1, CICS2, CICS3
- CICS4, CICS5
- CICS6

For example, connections from a specific client to CICS2, CICS4, and CICS6 would be valid but connections to CICS1, CICS3, and CICS5 would not be valid because CICS1 and CICS3 belong to the same region.

As mentioned previously, if a TCP/IP CICS region needs to service a large number of clients, it might need to define multiple server instances, each with its own port number. From a client perspective, each server definition represents a uniquely targetable CICS region instance.

For example, if a port can handle 200 concurrent clients and there are 8000 clients, 40 ports are needed to support all clients. If the clients can distribute their connections across these ports, this would optimally result in 200 clients per port. Using a random distribution model, it is statistically possible for the distribution to be 210 clients on one port and only 190 on another (assuming 200 on the remainder). This would result in a set of client failures. The solution is to increase the number of ports available. For example, increasing the number of ports to 50 would result in a randomly even distribution of 160 clients/ports. The random selection algorithm would now have to deviate by 25% to exceed 200 clients on one port.

As a port can handle only a relatively small number of concurrent client connections, balancing the distribution of server instances across all the clients is vital. In the example, if all clients selected CICS2 as the connection to REGION1, it is likely that the port for CICS2 would quickly be overloaded, resulting in failures. If all clients need to access REGION2, 50% should use CICS4, and 50% should use CICS5.

Not all CICS programs need be available on all possible CICS regions. The Workload Manager knows the name of the program that the client request is for, and can select, from a subset of all regions, those regions on which a particular program is defined. The Workload Manager also has knowledge of a set of regions to which undefined programs may be routed.

For example:

| Program | Region  | Average Elapsed Time   |
|---------|---|--|
| PROG1   | <ul style="list-style-type: none"> <li>• REGION1</li> <li>• REGION2</li> <li>• REGION3</li> </ul> | <ul style="list-style-type: none"> <li>• 10</li> <li>• 20</li> <li>• 15</li> </ul> |
| PROG2   | <ul style="list-style-type: none"> <li>• REGION1</li> <li>• REGION3</li> </ul>                    | <ul style="list-style-type: none"> <li>• 20</li> <li>• 10</li> </ul>               |
| PROG3   | <ul style="list-style-type: none"> <li>• REGION2</li> </ul>                                       | <ul style="list-style-type: none"> <li>• 5</li> </ul>                              |

This data can be used both to monitor application execution, and to provide input to workload management algorithms.

To sum up, the Workload Manager must know:

- The regions to which the Client daemon can connect

- The server instances that belong to each region
- The programs that can run in each region

You supply this information using the Configuration Tool which produces the appropriate entries in the configuration file; see “Configuring the Workload Manager” on page 41.

---

## Load balancing algorithms

You can select a *round-robin* algorithm or a *biasing* algorithm for load balancing. You select an algorithm using the Configuration Tool; see “Configuring the Workload Manager” on page 41.

### The round-robin algorithm

The round-robin algorithm assumes that all CICS regions are equally valid for selection. In the round-robin algorithm, when the Client daemon is initially started, it reads from the configuration file a list of all possible CICS regions to which any ECI or EPI request can be sent.

The Workload Manager also records the last region selected. When a new ECI or EPI request is made, the next region in the list is selected as the target. When it reaches the last region it loops around to the first one.

### The biasing algorithm

The biasing algorithm provides a way of balancing workload by specifying that workload distribution should favor particular regions. For example, if there are two regions with a bias of 75 and 25, program requests are sent in a ratio of 3:1 to the first region.

If a region fails, the internal biasing calculation changes. If two regions are available, one with a bias of 100 and the other with a bias of 0, all requests are sent to the first region. If the first region becomes unavailable, all requests are directed to the second region. A bias value of 0 is a special case, meaning *use only if no other region is available*.

The biasing algorithm works only for ECI calls. If you try to run an EPI application whilst the biasing algorithm is selected, the round-robin algorithm is used instead.

---

## Workload Manager failure recovery

If a request to route an ECI call to a particular region fails, indicating that the region is no longer available, the region is removed from the list of available regions.

If a request fails to reach the target CICS region the Workload Manager tries again, this time sending it to a different region that it knows is available. The region that failed is removed from the list of active regions. It is added back after a period of time which you specify in the **Region timeout (s)** field in the Configuration Tool. If the region fails again, the process is repeated.

---

## Workload Manager implementation

The Workload Manager is invoked during ECI and EPI calls from the Client daemon, and implements ECI and EPI user exit functions. These ECI and EPI exit functions are accessed during processing at a number of points during the execution of a request. They are described in *CICS Transaction Gateway: Programming Guide*.

The exit is implemented as a re-entrant multi-threaded Dynamic Load Library (DLL). This exit (code) is dynamically loaded by each client application that executes. The DLL executes in the process address space of the ECI-calling application rather than the Client daemon.

Instead of using the supplied Workload Manager you can write your own user exits that implement the ECI and EPI functions, and these exits can be driven by the `cicsterm` and `cicsprnt` commands. Information on producing such exits is given in the *CICS Transaction Gateway: Programming Guide* book.

When the Workload Manager is activated for a `cicsterm` or `cicsprnt` command, it determines which server the Client daemon should connect to. The Workload Manager server selection overrides any server specified with the `cicsterm` or `cicsprnt` command.

### ECI implementation

The Workload Manager is implemented as a Windows DLL called **cclmecix.dll**. This DLL contains implementations for the following functions:

#### **CICS\_EciInitializeExit**

Initialize the exit. Called once per process at the first ECI call. This function builds the list of available regions and other attributes.

#### **CICS\_EciExternalCallExit1**

Called at the start of an ECI call. This function is passed a reference to the ECI parameter block and may change the value of the `eci_system_name` field to select an alternate CICS server. The value of this field may be a Server name. This function selects the correct target CICS server for each ECI client request. This function involves workload management algorithms.

#### **CICS\_EciSystemIdExit**

If on return from the **CICS\_EciExternalCallExit1**, the ECI request fails to reach the target CICS server, either because of communication failure or a CICS server failure, **CICS\_EciSystemIdExit** is called to select an alternate CICS server target. The function flags that a CICS server is no longer available and should be removed from the list of selectable CICS servers. The workload management algorithm is then re-executed to select the next CICS server to be targeted by the Client daemon.

### EPI implementation

The Workload Manager is implemented as a Windows DLL called **cclmepix.dll**. This DLL contains implementations for the following functions:

#### **CICS\_EpiInitializeExit**

Initialize the exit. Called once per process at the first EPI call. This function builds the list of available regions and other attributes.

### **CICS\_AddTerminalExit**

Selects a CICS server.

### **CICS\_EpiSystemIdExit**

**CICS\_EpiSystemIdExit** is called to select an alternate CICS server target. The function flags that a CICS server is no longer available and should be removed from the list of selectable CICS servers. The workload management algorithm is then re-executed to select the next CICS server to be targeted by the Client daemon.

---

## **Workload Manager installation**

When you install CICS Universal Client, the ECI Exit DLL (cclmecix.dll) and the EPI Exit DLL (cclmepix.dll) are installed into the <install\_path>\bin subdirectory.

Once installed, the exit is used by succeeding ECI client calls without modification to any currently existing ECI program.

The supplied load management DLLs can coexist with any user-written DLLs. With the exception of **CICS\_EciSetProgramAliasExit**, user-written DLLs are called after the load management DLLs.

---

## **Tracing the Workload Manager**

You can enable tracing for the Workload Manager in two ways:

1. By selecting Workload Manager in the **Trace** section of the Configuration Tool.
2. By specifying **LMG** on the cicscli -m command.

This command overrides the configuration setting.

By default, tracing of the Workload Manager is not enabled.

---

## Chapter 11. Problem determination and problem solving

Most problems in a CICS Universal Client system are caused by one of the following:

- User errors
- Programming errors
- Configuration errors

---

### Problem determination: preliminary checks

Before investigating a problem, check whether there is an obvious cause:

- Has the system run successfully before now?
- Have you made any changes to the configuration of the system or added new features or programs?
- Is the environment configured correctly?
- Can the Client daemon connect to the CICS server?

Use the command:

```
cicscli -s=servername
```

followed by the command:

```
cicscli -l
```

If the connection is good, this command returns the name of the server that you specified in *servername*.

- Are there any messages explaining the failure?
- Can you re-create the failure?
- Do any of the available statistics help to explain the failure?

### What to do next

If you think the problem is with the CICS Universal Client, see “Diagnosing common problems” on page 98. Here you will find information on diagnosing common configuration and other errors, as well as advice on the documentation you need to collect in specific situations.

See “Program support” on page 106 for information on how to contact IBM. See “Documenting problems” on page 107 for the information that you will be asked to provide.

If you think the problem is in another product, follow the problem determination procedures provided with that product. For CICS servers, see the *CICS Problem Determination Guide*.

---

### Problems installing the product

This information describes problems that you might meet when installing or uninstalling the CICS Universal Client.

## A message indicates that the CICS Universal Client is running

You might see this message when migrating from an earlier version, or when installing the product. Check the following components, and stop them as necessary:

### Client daemon

This can be seen in the process list as `cc1clnt`. See “The `cicscli` command” on page 65 for information on stopping the Client daemon.

### IBM CICS Universal Client service

This can be seen in the process list as `cc1serv`. See .

### Configuration Tool

Close the Configuration Tool.

---

## Problems with the Client daemon

### Messages

There are two types of message in the Client daemon:

1. Messages displayed to the user
2. Errors written to the Client daemon error log and trace file

The *CICS Transaction Gateway: Messages* book explains all error and warning messages.

### Error log messages

Any errors on the client workstation that are not caused by incorrect use of the API are written to the Client daemon error log.

The log file is named in the configuration file. The default name is `cicscli.log`. The log file is written to the `<install_path>\bin` directory.

Help information for all messages is provided in two ASCII text files in the `<install_path>\bin` subdirectory. You can view these using any standard text editor:

#### **`cc1msg.hlp`**

Help for the end user messages, in the language you chose at installation time.

#### **`cc1log.hlp`**

Help for the trace and log messages. This is provided in English only.

Errors resulting from incorrect use of the APIs simply result in error return codes to the application. It is the responsibility of the application to notify the end user of the error and provide guidance on corrective actions.

### Pop-up messages

Errors generated from within the Client daemon are displayed in a pop-up window. You must click on **OK** in the pop-up window before the Client daemon can continue processing. There may be times when you do not want messages to appear in pop-up windows, for example, if you leave the Client daemon running unattended overnight. To disable the display of pop-up messages, enter the following command:

```
cicscli -n
```



When the display of pop-up messages is disabled, the messages are still written to the Client daemon error log. To re-enable the display of pop-up messages, enter the following command:

```
cicscli -e
```

You can specify the `-n` parameter together with the `-s` parameter. The display of pop-up messages is enabled by default.

## Tracing

Client daemon tracing is a useful problem determination tool for communication problems. You can use the trace functions to collect detailed information on the execution of a certain function or transaction. A trace can show how the execution of a particular activity is affected by, for example, the execution of other tasks in a CICS system. Each trace entry has a time stamp, which provides information on the time taken to perform certain activities.

To learn how to turn tracing on, see “Starting client tracing” on page 67.

For information on specifying the components of the Client daemon to be traced, see the `cicscli -m` command.

The output from the trace function is a binary trace file called, by default, `cicscli.bin` in the `<install_path>\bin` subdirectory. You can specify a different name for this file, using the Configuration Tool. However, you cannot change the `.BIN` extension. Using the **Client trace file wrap size (KB)** configuration setting, you can specify that the binary trace file should wrap into a second trace file, and you can also specify the maximum size of these files.

To read the trace, run the `cicsftrc` utility to convert the binary file or files into a text file. This text file is called `cicscli.trc` by default. The default trace files are:

### **cicscli.bin**

The binary trace file produced by running the Client daemon trace.

### **cicscli.wrp**

The second binary trace file if wrapping of client trace is enabled.

### **cicscli.trc**

The name of the text trace file produced when the binary trace file is converted to a text file using the `cicsftrc` utility.

### **cicscli.bak**

The backup file of the binary trace file. A backup file is produced from any existing `.BIN` file when you turn tracing on.

### **cicscli.bbk**

The backup of the first binary trace file if memory mapped tracing is enabled.

### **cicscli.wbk $n$**

The backup of subsequent binary trace files, if memory mapped tracing is enabled, where  $n$  is the number of the original `.WRP` file.

See “Formatting the binary trace file” on page 94 for information on the trace conversion utility.

## Wrapping the Client daemon trace

You can control the size of the binary trace file by specifying that it wraps into a second trace file. Use the **Client trace file wrap size (KB)** configuration setting to turn on wrapping trace; specify the maximum size of the wrapping trace (in kilobytes). If this value is 0 (the default), wrapping trace is not turned on.

When wrapping trace is turned on with standard I/O tracing, two files (called `cicscli.bin` and `cicscli.wrp`) are used. Each file can be up to half the size of the **Client trace file wrap size (KB)** value.

## Memory mapped tracing

If you enable wrapping trace, you can use the `-b` switch when you issue the `cicscli` command to turn tracing on. This specifies that memory mapped trace files should be used.

With memory mapped tracing, the operating system's paging mechanism is used to swap data between memory and the trace file. This improves performance significantly when compared to standard file I/O, because the trace file is opened and written to less frequently. Because the operating system is responsible for flushing data to disk, data is not normally lost if an application terminates unexpectedly. However, if the operating system itself fails, data can be lost, and the trace file can be corrupted. If you are diagnosing problems where the server fails and needs to be restarted, use standard I/O tracing instead of memory mapped tracing.

If you use memory mapped tracing, the size of the trace files is limited to 10 MB, and in addition to `cicscli.bin` and `cicscli.wrp`, you might see a series of files of the form `cicscli.wrp1`, `cicscli.wrp2`...`cicscli.wrpn`, where *n* is the number of files needed to hold the total amount of trace data specified in the Client trace file wrap size (KB) field of the Configuration Tool; see "Client trace file wrap size (KB)" on page 46 for the maximum amount of data that can be specified. The trace formatter finds all files in the sequence when you format the binary files. Memory mapped tracing uses up to 10 MB of virtual storage.

See "Starting client tracing" on page 67 for details of how to issue the command.

## Formatting the binary trace file

If you are using memory mapped tracing, note that data is not always written to disk immediately. As a consequence, turn tracing off before you format the binary trace file, to ensure that all data is flushed to disk.

You use the Binary Trace Formatter utility `cicsftrc` to convert the binary trace file `cicscli.bin` to ASCII text. The utility has the following parameters:

**-m**=*list of components*

Specifies that only trace points from the listed components are written to the text file. The components you can specify are the same as for `cicscli -m`; see the `cicscli -m` command. If `-m` is not specified, all trace points in the binary trace are written to the text file.

**-w**[=*filename*]

Indicates that there are two or more binary trace files to format and then concatenate (that is, the binary files were created with a wrapping trace). If no file name is specified with the `-w` parameter, `cicsftrc` assumes that the name of the second trace file is `cicscli.wrp`.

- n Indents entry and exit points in the test trace file to make it more readable. By default, indentation is turned off.
- d Specifies detailed trace formatting. If you are using EPI calls, cicsterm or CICS PRINT, an approximation of the screen layout will be included in the trace.
- i=filename  
Specifies the name of the input (binary) trace file, which is cicsccli.bin by default.
- o=filename  
Specifies the name of the output (text) trace file. If no -o parameter is specified, the name of the text trace file is assumed to be cicsccli.trc.
- f Overwrite any existing files.
- s Do summary trace formatting. Summary trace formatting is controlled by a template file (cclsumtr.txt), which is read in at initialization time. It formats key trace points, and shows for example the flow of user API calls, the progress of calls through the Client daemon, and network flows to the server. For the most detailed results, specify the API.2 component when you define the components to be traced. Summary tracing provides an overview; use it as requested by your IBM support organization.

**Note:** Versions of the CICS Universal Client earlier than 5.0.1 cannot format binary trace files produced by this version.

Figure 7 shows an example summary trace.

```
-->Sample of API summary trace taken with API.2 and DRV options.

[Process ,Thread ]      Time      API Summary      CCLCLNT Summary      Comms Summary
=====
...
...
[000000bf,0000017c] 12:08:32.190 --->[7315] CCL3310 ECI Call type ECI_SYNC, UOW=0
[00000089,000000a4] 12:08:32.290 -S->[4410] CCL4411 TCP/IP (to STEMLAR) send data: Length=89
[00000089,00000063] 12:08:32.400 <-R-[4418] CCL4412 TCP/IP (to STEMLAR) receive data: Length=12
[00000089,0000010b] 12:08:32.511 <-R-[4418] CCL4412 TCP/IP (to STEMLAR) receive data: Length=29
[00000089,000000a4] 12:08:32.521 -S->[4410] CCL4411 TCP/IP (to STEMLAR) send data: Length=94
[00000089,000000a4] 12:08:32.531 -S->[4410] CCL4411 TCP/IP (to STEMLAR) send data: Length=94
[00000089,000000a4] 12:08:32.541 -S->[4410] CCL4411 TCP/IP (to STEMLAR) send data: Length=94
[00000089,000000a4] 12:08:32.541 -S->[4410] CCL4411 TCP/IP (to STEMLAR) send data: Length=94
[00000089,000000a4] 12:08:32.551 -S->[4410] CCL4411 TCP/IP (to STEMLAR) send data: Length=94
[00000089,00000168] 12:08:32.581 <-R-[4418] CCL4412 TCP/IP (to STEMLAR) receive data: Length=12
[00000089,0000017e] 12:08:32.601 <-R-[4418] CCL4412 TCP/IP (to STEMLAR) receive data: Length=31
[000000bf,0000018e] 12:08:32.621 [7364] CCL3350 Event Service Thread got a request REQUEST_TYPE_ECI_1
[000000bf,0000008a] 12:08:32.671 <---[7316] CCL3311 ECI Call type ECI_SYNC, UOW=0 got rc=ECI_NO_ERROR (Time in API = 0.821 seconds)
```

Figure 7. Sample of API summary trace taken with API.2 and DRV options

#### Points to note:

1. {Time in API} shows the amount of time that the client API call took to complete. This can help when investigating performance problems; see Chapter 7, "Performance," on page 63 for more information.
2. The API Summary column refers to client API code inside the user application process. It tracks when user requests enter and leave the client API code. ---> and <--- show the program entering and leaving the Client daemon API.
3. CCLCLNT is the background Client daemon process. You get entries here only if you specify the CCL component.
4. The Comms Summary tracks when Client daemon calls enter and leave the network. -S-> shows a request being sent to the network; <-R- shows a reply being received.

If a user application is making EPI calls, or using cicsterm or cicsprnt, the trace formatter puts an approximation of the screen into the trace. Figure 8 shows a 3270 screen capture from a formatted trace file, taken from the CECI transaction. It is an aid to problem determination, not a completely accurate representation of the screen. See “Formatting the binary trace file” on page 94 for details of how to format the trace file.

```
Command = Erase/Write, so clearing main screen
Command2 = Read Modified
WCC = 0x32 ( Free Kbd,80 char)
Set Buffer Address to (1,2)
Insert Cursor @ (1,2)
Set Buffer Address to (1,1)
Start Field Extended (Unprotected,Alphanumeric,Display,not-pen-detectable,Foreground Colour Green)
Data : ' '
Insert Cursor @ (1,3)
Set Buffer Address to (2,1)
Data : 'User'
.....
.....
.....
.....
Set Buffer Address to (24,49)
Start Field Extended (Autoskip (Prot+Num),Display,not-pen-detectable,Foreground Colour Turquoise)
Data : '9'
Set Buffer Address to (24,51)
Start Field Extended (Unprotected,Alphanumeric,Intense,pen-detectable,Foreground Colour Red)
Data : 'Messages'
      1      2      3      4      5      6      7      8
123456789012345678901234567890123456789012345678901234567890
+-----+
01 | -
02 | STATUS. . : Enter one of the following:
03 |
04 | ABend      EXtract      READPrev    WAit
05 | Address    FEpi        READQ        WRITE
06 | ALlocate   Formattime  RECeive     WRITeQ
07 | ASKtime    FREE        RElease     Xct1
08 | ASSign     FREEMain    RESetbr
09 | Bif        Getmain     RETRieve
10 | CAnce1     Handle      RETUrN
11 | CHange     Ignore      REWrite
12 | CONNect    INquire     SENd
13 | CONVerse   ISsue       SET
14 | DELAy     LInk        SIGNOff
15 | DELETE    LLoad       SIGNON
16 | DELETEQ   PErform     START
17 | DEQ       POP         STARTBr
18 | DUmp      POST        SUSpend
19 | ENDbR     PUsH        SYncpoint
20 | ENQ       READ        Unlock
21 | ENTer     READNext    Verify
22 |
23 | PF1-He1p    2-HEX      3-End      4-EIB      5-Variables
24 | 6-User      9-Messages
+-----+
| 1BpC000      STEMLAR
+-----+
123456789012345678901234567890123456789012345678901234567890
      1      2      3      4      5      6      7      8
```

Figure 8. Screen capture from a formatted trace file

The formatter lists the commands which built the screen, and shows an approximation of the screen.

**Format of trace entries**

The entries in the Client daemon trace file have the following format:

*time* [*process id,thread id*] [*number*] *component trace message*  
*data*

where:

*time*

The time the entry was written, to millisecond accuracy.

[*process id, thread id*]

Process id is a unique number that the operating system uses to identify a process. Thread id is a unique number that the operating system uses to identify a thread within a particular process.

[*number*]

A number that uniquely identifies the particular trace entry. This helps your support organization in the diagnosis of serious problems.

[*component*]

The component of the product to which this entry applies.

*trace message*

The trace message number and text.

*data*

Some trace entries include a dump of key data blocks in addition to the trace message.

**Sample Client daemon trace:** Figure 9 shows the trace information recorded during the successful connection of a Client daemon to a CICS server using the TCP/IP protocol. The trace was generated using the commands:

```
cicscli -s=cicstcp -dcicscli
-o
```

```
17:03:57.580 [0000080c,00000908] [1007] TRC:CCL1042 *** CICS Client for Windows v7 Service Level 00 - service trace started ***
17:03:57.590 [0000080c,00000908] [2183] CCL:CCL2048 Maximum trace data size set to 512
17:03:57.600 [0000080c,00000908] [2114] CCL:CCL2142 GetNextTimeout timeout is 0 seconds
17:03:58.612 [0000080c,00000908] [2030] CCL:CCL2106 Comms Event : LINK-UP
17:03:58.622 [0000080c,00000908] [2019] DRV:CCL2055 Connection with server established (linkID=1)
17:03:58.622 [0000080c,00000908] [2035] CCL:CCL2109 Send server TCS data
17:03:58.632 [0000080c,00000908] [3214] CCL:CCL3251 Comms Allocate request (LinkId=1, Tran='CCIN')
17:03:58.632 [0000080c,00000908] [3217] CCL:CCL3238 Comms Allocate completed (LinkId=1, ConvId=1, Rc=0)
17:03:58.632 [0000080c,00000908] [2127] CCL:CCL2143 CommsBegin - OK
17:03:58.632 [0000080c,00000908] [3100] CCL:CCL3113 CCIN install request: ApplId='*      ', Code page=819
...
...
17:04:00.625 [0000080c,00000908] [3102] CCL:CCL3114 CCIN install response: ApplId='@Z8AAAA', Code page=8859-1, Rc=0
17:04:00.625 [0000080c,00000908] [3241] CCL:CCL3255 Comms Complete request (ConvId=1)
17:04:00.635 [0000080c,00000908] [3244] CCL:CCL3246 Comms Complete completed (ConvId=1, Rc=0)
17:04:00.635 [0000080c,00000908] [3218] CCL:CCL3252 Comms Deallocate request (ConvId=1)
17:04:00.645 [0000080c,00000908] [3221] CCL:CCL3239 Comms Deallocate completed (ConvId=1, Reason=0, Rc=0)
17:04:00.645 [0000080c,00000908] [2042] CCL:CCL2114 Processed TCS Reply - Server connected
17:04:00.645 [0000080c,00000908] [2114] CCL:CCL2142 GetNextTimeout timeout is 0 seconds
17:04:00.655 [0000080c,00000908] [2114] CCL:CCL2142 GetNextTimeout timeout is 0 seconds
17:04:00.664 [0000080c,00000908] [1004] TRC:CCL1043 *** Service trace ended ***
```

Figure 9. Sample Client daemon trace

| Message ID | Explanation |
|------------|-------------|
|------------|-------------|

|                |   |
|----------------|---|
| <b>CCL1042</b> | Start of trace message. Each time a trace is started, a backup of the old trace file is created, and the trace file is overwritten. You can delete the file when required. Check the time stamp to ensure that you are reading the correct trace. |
|----------------|---|

|                |   |
|----------------|---|
| <b>CCL2048</b> | Maximum trace data size is at the default size of 512 bytes. You can modify this size by specifying the size value in the start command for the client trace; see the cicscli -d command. |
|----------------|---|

|                |   |
|----------------|---|
| <b>CCL3251</b> | The client sends a CCIN transaction to the server to install its connection definition on the server. |
|----------------|---|

### CCL3238

A conversation ID has been successfully allocated. If more than one conversation is active, use the conversation ID to distinguish between them.

### CCL3113

The client sends a CCIN transaction to the server with Appl ID set to \* to install its application. The Appl ID is specified in the configuration file as Client=\*. This requests the server to dynamically generate an Appl ID that is unique within the CICS server system.

### CCL3114

This shows the dynamically generated Appl ID.

### CCL1043

End of trace message.

Figure 10 shows trace information recorded when we tried to connect to a CICS server over TCP/IP using an invalid port number. The port number specified in the configuration file was not defined in the services file of the server. Hence, the connection could not be established.

```
16:16:41.562 [0000093c,000008ec] [1007] TRC:CCL1042 *** CICS Client for Windows v6 Service Level 00 - service trace started ***
16:16:41.572 [0000093c,000008ec] [2183] CCL:CCL2048 Maximum trace data size set to 512
16:16:41.582 [0000093c,000008ec] [2114] CCL:CCL2142 GetNextTimeout timeout is 0 seconds
16:16:41.612 [0000093c,000008ec] [2114] CCL:CCL2142 GetNextTimeout timeout is -1 seconds
16:16:41.622 [0000093c,000008ec] [3207] CCL:CCL3249 Comms Open request (Server=CICSTCP, Driver=CCLIBMIP)
16:16:41.622 [0000093c,000008ec] [4408] DRV:CCL4413 CCL4413 TCP/IP (to CICSTCP) address=192.113.36.200, port=1089, socket=3
16:16:41.622 [0000093c,000008ec] [3210] CCL:CCL3236 Comms Open completed (Server=CICSTCP, LinkId=1, Rc=0)
16:16:41.633 [0000093c,000008ec] [2114] CCL:CCL2142 GetNextTimeout timeout is 3660 seconds
16:16:41.633 [0000093c,000008ec] [1004] TRC:CCL1043 ***Service trace ended ***
```

Figure 10. Client daemon trace: using an invalid port number

### Message ID

#### Explanation

### CCL4413

Shows the port number used for this connection request.

You must check your definitions in the SIT on the server, the configuration file on the workstation, and the services file for the port number specified.

You must provide a valid port number or use the default value.

## Diagnosing common problems

This section provides information to help you solve some common problems with the Client daemon. The problems are discussed under the following headings:

- “Starting clients and terminals” on page 99
- “TCP/IP communication problems” on page 99
- “APPC communication problems” on page 100.
- “Traps” on page 101
- “The Client daemon stops responding” on page 102
- “CICS server problem determination” on page 103
- “Communication problem determination” on page 103

For information on error messages, refer to *CICS Transaction Gateway: Messages*.

## Starting clients and terminals

The following are solutions to problems that can occur when starting clients and terminals:

### Users without administrator privileges cannot communicate with the Client daemon on Windows 2000 Service pack 4

When users issue a cicscli command they receive error message CCL8024E. Service pack 4 introduced a new user right "Impersonate a client after authentication". To allow users to issue cicscli commands they must be granted this user right. To give users the right, do the following:

1. Click **Start -> Programs -> Administrative Tools -> Local Security Policy**
2. In the Local Security Policy tool, expand **Local Policies** and then select User Rights Assignment
3. In the right pane, double click **Impersonate a client after authentication**
4. Click **Add**, and then select the users who need to use the CICS Universal Client
5. Click **OK** twice to return to the main Local Security Policy window.
6. Close the Local Security Policy application.

### A cicsterm request has gone to the wrong server

If you do not specify the `-s=servername` option on the cicsterm command, the Client daemon sends a cicsterm request to either of:

- the default server
- the first server listed in the configuration file, even if it is not yet activated.

The *servername* should be as specified in the configuration file.

### Problems loading protocol drivers

The message "Cannot load protocol driver" in the cicscli.log file means that you are trying to use a protocol driver that does not exist. Check your configuration file to make sure that the driver name is correct, and is supported in this release.

### The Client daemon can connect to the server, but cicsterm cannot

In other words, cicscli `-s=servername` connects successfully, but cicsterm `-s=servername` does not. Check the following:

- Is the CTIN transaction defined on the server?
- Does cicsterm-a successfully install a terminal that is not sign-on capable? cicsterm attempts to install a sign-on capable terminal by default. If the `-a` option works, the server probably does not support sign-on capable terminals.

CICS servers require APAR fixes to support terminal sign-on capability; see "Supported software" on page 3. Refer to the CICS Universal Client README file for the latest details and check the PTFs for the CICS servers.

See "APARs and fixes" on page 109 for general information about APARs.

## TCP/IP communication problems

The following are solutions to problems that can occur when communicating over TCP/IP:



### **A Client daemon running on Windows cannot load the TCP/IP protocol driver**

You have probably received message CCL3229E in a pop-up window and message CCL3247 in the cicscli.log error log file. These messages indicate you have probably specified the wrong device driver in the configuration file. For all TCP/IP communication, the Client daemon on Windows should use the CCLWNTIP driver. Any vendor offering a WINSOCK interface can use this TCP/IP driver.

### **Message CCL4404 TCP/IP (to 'CICSTCP') unable to resolve name: RC=2**

The CICS server, in this example CICSTCP, could not be resolved by the TCP/IP protocol driver. Ensure that your domain name server and router address information is correct, and that any names and IP addresses in the TCP/IP etc\hosts file are correct.

Use the TCP/IP ping or nslookup commands to see if TCP/IP can resolve the hostname.

### **CCIN not recognized, CTIN not recognized**

The CCIN transaction installs your Client daemon definition on the CICS server. The CTIN transaction installs your client terminal definition on the CICS server. These transactions must be available on the CICS server if it supports the EPI, because the EPI implies CICS 3270 terminal emulation and CICS 3270 printer emulation. For information on which CICS servers support EPI and hence CICS 3270 emulation, see Table 1 on page 7. You can ignore these messages if your CICS server does not support the EPI.

### **A cicsterm command for a mainframe CICS server failed**

cicsterm and cicsprnt use CICS 3270 emulation. Some mainframe CICS servers do not support CICS 3270 emulation. For information on which CICS servers support CICS 3270 emulation, see Table 1 on page 7.

### **APPC communication problems**

The following are solutions to problems that can occur when communicating over APPC:

#### **Automatic transaction initiation against a Client daemon terminal does not work**

Different products provide different APPC implementations for handling inbound attaches. Therefore for the Client daemon using IBM Communications Server, Microsoft Host Integration Server, and IBM Personal Communications, you must predefine the CRSR attach program to relay the information to the Client daemon. This is necessary to enable the CICS server to perform automatic transaction initiation (ATI) against the Client daemon terminals.

For the Client daemon therefore, you must define the inbound attach transaction CRSR as follows:

#### **A Client daemon running on Windows and using IBM Communications Server**

Define CRSR to use program CCLCLNT.EXE. See "SNA using IBM Communications Server" on page 18.



## **A Client daemon running on Windows and using IBM Personal Communications**

Define CRSR to use program CCLCLNT.EXE. See “Configuring IBM Personal Communications” on page 20.

**SNA error log:** The SNA error log can help your support organization to diagnose problems. In a default installation, the log is located as follows:

### **Product**

#### **Location**

#### **IBM Communications Server API client**

C:\IBMCS\w32cli\sna.err

#### **IBM Communications Server**

C:\IBMCS\PCWMSG.MLG

#### **Microsoft Host Integration Server 2004**

Launch Windows Event Viewer and view the Application log.

#### **Microsoft Host Integration Server 2004 Client**

Launch Windows Event Viewer and view the Application log.

Consult the documentation supplied with your operating system for details of how to launch Windows Event Viewer.

## **Traps**

### **Dr. Watson**

On Windows systems, the Dr. Watson tool can supply useful information in the event of an operating system trap. It attempts to produce a stack of trace exceptions. Dr. Watson is the program error debugger supplied with Windows. Refer to the product documentation for full instructions on how to install and use it. What follows is an example of how to run Dr. Watson and use the information supplied.

1. Run file %windir%\system32\drwtsn32.exe. This opens a window that allows you to configure Dr. Watson.
  - The log file path defaults to %windir%.
  - A crash dump is a binary system dump, and can be large. Clear the **Create Crash Dump File** check box if you do not want a binary system dump.
2. Leave Dr. Watson running, and recreate the trap scenario.
3. When a window appears saying that a trap has occurred, press cancel to debug the application.
4. Click OK when prompted, to create the log file.
5. You can now open the log file (drwtsn32.log) to determine which process trapped.
6. Near the top of the log are entries that give the process id (pid) of the trapping process:

```
*----> System Information <----*
Application exception occurred:
App: (pid=253)
When: 11/4/2000 @ 15:16:40.618
Exception number: c0000005 (access violation)
```

If the file that trapped contains debug symbols, the application exception occurred section also contains the process name. If not, then

you can cross-reference the pid given to the processes in the task list section to find the name of the process. In the example above the task list contains the following entries:

```
*----> Task List <----*
0 Idle.exe
2 System.exe
.....
.....
251 CICSCLI.exe
253 CCLCLNT.exe
241 CCLSERV.exe
146 DRWTSN32.exe
0 _Total.exe
```

In this example pid 253 is CCLCLNT, the Client daemon process.

7. A trap in CCLCLNT, CICSCLI or cicsterm may indicate a problem with the Client daemon, or with an API that the Client daemon uses. For example, a trap can occur in a Windows API call, or a SNA API call that the Client daemon references.
8. If the trap is in a user application process it may be a user error. It is only a Client daemon problem if the trap occurred in the Client daemon .DLL address space. The Client daemon dynamic link libraries are cclapi32.dll and cclipc.dll. If the problem occurred in the user application's .EXE address space it is a problem with the user application.
9. If a trap is a Client daemon problem, the IBM service groups need a Dr. Watson log of the failure.
10. The task list shows which tasks were running at the time the trap occurred, and shows which address of memory they were loaded into. You can cross-reference this with the fault address to work out which file the trap occurred in.

## The Client daemon stops responding

This section discusses what to do if you think the Client daemon has stopped responding, for example because:

- API, ECI and EPI calls do not complete, or
- cicsterm hangs

Check that your CICS Transaction Server is working correctly, for example by looking at the CICS log. Insufficient storage on the CICS region may cause CICS Universal Client to hang.

To test whether CICS Universal Client has stopped responding, issue cicscli -l from the command line. If the call hangs then CICS Universal Client is not responding.

Try to reproduce the problem with tracing turned on. Take a client trace with as many components as possible active. As a minimum you need the API, DRV and CCL tracepoints; add TRN if possible. (Use wrapping trace if you do not want the trace file to get too large.) The summary trace shows whether the client or user application has stopped responding, and gives an indication as to whether the problem is in the client or server.

If you can reproduce the problem, have details of how to reproduce it available for your support organization. If you cannot reproduce the problem, have available details of the circumstances that led up to the hang, for example:

- Does it hang only when the system is under heavy load?

- Does it hang only when there are many concurrent users?
- Does it hang only under a particular configuration, or after a known sequence of events?

### **CICS server problem determination**

The most important facilities for problem determination on CICS servers are:

- Traces
  - auxiliary
  - internal
- Dumps
- CICS message logs
- Statistics information
- Monitoring information
- Execution diagnostic facility (EDF)
- CICS-supplied transactions, CEBR and CECI
- Independent software vendor (ISV) tools

Information about these facilities is given in the *Problem Determination* books for the individual products (see “CICS Transaction Server publications” on page 128). You may need to contact the server system administrator for more information, for example, about a CICS server error log.

The following shows the error message prefixes for CICS products:

**CCL** CICS Universal Client  
**CTG** CICS Transaction Gateway  
**DFH** CICS on CICS on System/390® and z/OS  
**ERZ** CICS Transaction Server for Windows, and TXSeries  
**AEG** CICS Transaction Server for iSeries.

**CPMI tasks lock in CICS Transaction Server for z/OS:** If a CPMI (or equivalent mirror transaction) task locks in your CICS region, it is possibly because you have reached the MAXTASKS limit of your CICS region. This prevents the mirror program from sending data back to the Client daemon, which appears to hang. The problem typically occurs when CICS has a high number of concurrent transactions. A solution is to put the mirror transaction in a TranClass that has a MAXACTIVE lower than the MAXTASKS of your CICS region. All new requests to the CICS region are queued, and CICS can continue to process current requests. The value you specify for MAXACTIVE depends on your installation, and other tasks running in the region.

### **Communication problem determination**

Even a small telecommunications network is a very complex system in which all components depend on one another. If one component fails and presents incorrect information to the other components, the latter may fail even more severely than the former. Sometimes the failure may be considerably delayed, and the error indicator may be lost before the error is detected. Thus, it is sometimes difficult to analyze a problem in the communication part of a system.

The Client daemon generates various messages associated with the use of the supported communication protocols and the associated products. Refer to *CICS Transaction Gateway: Messages* for a list of these messages and their explanations.

The communication products themselves generate error messages. For details of these, and information on troubleshooting, you should refer to the documentation for the communication product. The following sections summarize useful commands and utilities for problem determination.

**TCP/IP-providing products:** TCP/IP provides the following diagnostic tools:

**arp** Displays and modifies the IP-to-Ethernet or token ring physical address translation tables used by address resolution protocol (ARP).

**hostname**

Displays the host name of your workstation.

**ipconfig**

Displays all current TCP/IP network configuration values. This is helpful if you have to find out if an IP interface is active.

**netstat**

Displays protocol statistics and current TCP/IP network connections. This helps you obtain information about your own IP interfaces, for example, to list IP addresses and TCP/IP routing tables in use at your workstation.

**nslookup**

Displays information from Domain Name System (DNS) name servers.

**ping** Verifies connections to a remote computer or computers.

**tracert** Traces the TCP/IP path to a requested destination. It is useful for determining whether there is a problem with one of the intermediate nodes.

For more information on these utilities, refer to the online help for TCP/IP.

**APPC-providing products:** This section describes problem determination in products involved in APPC communication.

*VTAM Buffer Trace:* You can use VTAM buffer tracing to record the flow of data between logical units in the CICS environment. The trace entries include the netname of the terminal (logical unit) to which they relate. For details on VTAM buffer tracing and other VTAM problem determination functions, see the appropriate book in the VTAM library.

*The APING utility:* In an APPC environment, you can use the APING utility to test a connection. APING exchanges data packets with a partner computer over APPC and times how long the data transfer takes. It can be used to get a first estimate of the session setup time between two computers and the throughput and turnaround time on that APPC session. You can use APING to determine whether a session can be set up between two computers and to display extensive error information if session allocation fails. APING consists of two transaction programs: APING, which runs on the client side, and APINGD, which runs on the server side.

*Checking client and host configuration:* If the SNA product on the Client daemon machine, and the host are both correctly configured, you should be able to activate the connection between them. Follow the steps below to activate the connection; you do not need to start the client first.

1. Start the node on the SNA product on the Client daemon machine.
2. Use the CEMT transaction to acquire the connection. Type CEMT I CON. The screen will look similar to this:

```

I CON
STATUS: RESULTS - OVERTYPE TO MODIFY
Con(SIMD) Net(PYKS88BA)      Ins Rel Vta Appc
Con(SYSB) Net(IYCKZCCV)      Ins Rel Vta Appc

                                SYSID=SYSA APPLID=IYCKZCCU
RESPONSE: NORMAL                TIME: 12.25.04 DATE: 03.01.01
PF 1 HELP          3 END          5 VAR          7 SBH 8 SFH 9 MSG 10 SB 11 SF

```

### 3. Overtyping Rel with ACQ, to acquire the connection.

If you cannot acquire the connection, SNA is wrongly configured on the product or the host.

**IBM Communications Server for Windows:** IBM Communications Server writes a log file called `pcwmsg.mlg`, which can help to diagnose communications errors. Because it is a text file, you can view it in any text editor, or you can use the supplied *Communications Server Log Viewer* utility. The viewer includes online help.

Use the supplied *Getsense* utility to understand error messages that contain sense codes.

Your IBM support organization will need the log file if you have SNA errors that you cannot resolve. They may also ask you for a trace. To turn trace on, select the *Communications Server Trace Facility*. The trace facility has options to start and stop the trace, save it, and format it to a text file. IBM support will probably ask you to trace these components:

| Function      | Component           | Trace options              |
|---------------|---------------------|----------------------------|
| APPN and APPC | Nof API             | Verb trace up to 128 bytes |
|               | APPC API            | Verb trace up to 128 bytes |
| Connectivity  | (Your network type) | Verb trace up to 128 bytes |

For more details, see your IBM Communications Server documentation.

### Mirror transaction does not time out

The default ECI mirror transaction (CPMI or CSMI) uses a PROFILE of DFHCICSA. This profile has an RTIMOUT value of NO. This means that if an ECI request is suspended in CICS during an extended unit of work, the mirror transaction never times out. To enable timeout in these situations:

1. Define a new mirror transaction with SPURGE=YES, and which specifies a PROFILE containing an RTIMOUT value other than NO.
2. Specify this new mirror transaction as the Transid in the ECIREquest using a call type of ECI\_SYNC\_TPN.

In these situations, if no response is received from the client after the timeout period has elapsed, CICS purges the mirror transaction and rolls back the associated unit of work.

## Telnet clients

If you run the CICS Universal Client **cicsterm** command from a Telnet prompt, certain Telnet clients can cause problems with the display. For example, your Telnet session might truncate message lines over a certain length. This is usually a

problem with the Telnet client that you are using, or the terminal type that you are emulating. Currently there is no solution to this problem.

---

## Program support

If you need to contact your IBM support organization, first refer to the Service and Support card supplied with the product for details of the support available to you, or visit our Web site at: [www.ibm.com/software/cics/cuc](http://www.ibm.com/software/cics/cuc) and follow the **Support** link.

This section provides guidance on reporting problems, detailing the information you should collect to assist your support organization. It also explains how the problem is handled through to resolution and the provision of a fix.

## Reporting problems

Before reporting your problem to the support organization try to ensure that the error is actually occurring within your CICS Universal Client system, even if you are unsure whether the problem is due to the CICS Universal Client itself.

In practice, many errors reported to support organizations turn out to be user errors, or they cannot be reproduced, indicating just how difficult it can be to determine the precise cause of a problem. User errors are mainly caused by faults in application programs or by errors in setting up systems.

The ability of the support organization to resolve your problem quickly depends on the quality of the information you provide to them. For this reason it is good practice to collect and organize problem data before making the initial contact.

Summarize your problem and the documentation/information you collect on a problem reporting sheet. This sheet provides a valuable summary to the support organization, and a copy will be useful for your own records.

### Level-1 support

If this is your first contact regarding this problem a unique incident number will be assigned. A Problem Management Record (PMR) is opened on the RETAIN<sup>®</sup> database system, where all activity associated with your problem is recorded. The PMR remains “open” until it is solved.

Make a note of the incident number on your copy of the problem reporting sheet. You will be expected to quote the incident number in all future correspondence relating to this problem.

Your initial communication with the support organization is through a Level-1 representative, who uses the keywords that you have provided to search the RETAIN database for problems with similar symptoms. If your problem is found to be one already known to the support organization, and a fix has been devised for it, you will be advised of the availability of corrective service software that you can install to overcome the problem, as described in “Obtaining the fix” on page 109. If the RETAIN search is unsuccessful, the problem is passed on to a Level-2 representative who will contact you for more information about your problem, to start a more detailed investigation of the cause.

### Level-2 support

Let the Level-2 representative know if any of the following events occurred before the problem appeared:

1. Changes in level of the CICS Universal Client, compiler or associated licensed programs
2. Corrective service software and fixes applied to workstation software
3. Problem Tracking Fixes (PTFs) applied to other associated products
4. Additional features used
5. Application programs changed
6. Unusual operator action.

At this stage you may be asked to supply more details or documentation. If this happens, the PMR is updated to show any documentation you have submitted.

Based on the information you supply, the investigation then carried out can determine whether the cause of your problem is new to the support organization, or is already known.

If the problem is a valid new one, an APAR may be raised, to be dealt with by the CICS service team, as described in “APARs and fixes” on page 109. If, however, the problem is already known, and a fix has been developed, you can obtain it as described in “Obtaining the fix” on page 109.

## Documenting problems

In a communication environment, where many clients may be connected to several servers, you must obtain information from both the client and the server sides.

To facilitate problem determination, try to reduce your environment to only one client workstation and one server to narrow down the range of possibilities that may cause the error.

Listed below are the types of information most likely to be needed by the support organization. The list is not exhaustive; it covers the most commonly requested information.

- The version of the CICS Universal Client, including details of any service releases applied.
- The utility or programming language that gives the problem, for example:
  - ECI, EPI, ESI
  - C, C++

For languages, include the version.

- The network protocols being used.
- The end-to-end configuration, and product stacks at each step of the way, for example, WebSphere Application Server async ECIRRequest class over SSL to the Gateway daemon on Solaris using TCP/IP to CICS Transaction Server 2.3.
- The operating system on which the problem occurs. If the Client application and CICS Universal Client are on different operating systems, provide details of both. Details of the CICS server are also useful.
- A minimum recreate scenario, if possible.
- Details of any log messages at the time the problem occurred.
- A short description of the problem in terms of CICS Universal Client calls, including why you think it is a problem with the CICS Universal Client. For example, a specific API call hangs and never returns, or an unexpected return code on a specific API call.



## Locating and compiling information

The advice listed below will help you compile the information required. If you are in any doubt about how to gather any of the items listed above, wait until you can seek advice from your support organization.

- Try to establish which program in your system seems to be the cause of the problem. As you are reading this book, it is likely that you already believe the CICS Universal Client to be the problem source.

You also need to provide the version and release number of the product, for example Version 7.1, together with the number of any PTF or other fix applied, for example UNnnnnn (where *nnnnn* is a valid PTF number).

- Obtain Windows operating system details by using the WINVER.EXE command at a command prompt.

If you are using SNA Server, you can find its version number by entering the SNAVER.EXE command.

- You should find details of your compiler level on the product media labels or the associated documentation. Alternatively, check the panel displayed on the screen at compile time.
- Give the problem a severity level. Severity levels have the following meanings:
  - Severity level 1 indicates that you are unable to use a program, resulting in a critical condition that needs immediate attention.
  - Severity level 2 indicates that you are able to use the program, but that operation is severely restricted.
  - Severity level 3 indicates that you are able to use the program, with limited functions, but the problem is not critical to your overall operation.
  - Severity level 4 indicates that you are able to use the program with the problem causing negligible hindrance.
- Also, try to classify the error and give a brief description of the problem. Include keywords associated with the problem, such as ABEND, WAIT, LOOP, PERFORMANCE, INCORROUT, and MESSAGE, corresponding to the problem classification types used in the RETAIN database. Strings containing other keywords are also useful. These are not predefined, and might include such items as a message or message number, an abend code, any parameters known to be associated with the problem, or, for example, STARTUP, INITIALIZATION, or TRANSIENT DATA.
- Finally, you should include your address, relevant contact names, and details of the other products at your installation.

Keep a copy of the problem reporting sheet which summarizes all the information relevant to the problem, together with any available documentation such as dumps, traces and output from programs, translators, and compilers.

## Submitting the documentation

If you are asked to provide documentation, it will help the support organization during their investigation if you adhere to the following rules when preparing it:

- Provide as much information as possible in softcopy format.
- Write any notes and documents in English.
- If you are asked to supply any additional trace output, provide an unformatted binary version, rather than the viewable output from the formatter.
- If you upload files to a mainframe system, do so in binary rather than ASCII format.



## APARs and fixes

After a reported problem is confirmed as being both new and valid, an *authorized program analysis report* (APAR) is raised from the Problem Management Record (PMR) and becomes a permanent record describing your error, and its solution. An APAR is the means of reporting to the appropriate product service team any problems you find with an IBM program.

### The APAR process

The first step in the APAR process is that a Level-2 representative from the support organization enters an APAR containing a description of your problem into the RETAIN system. If you have a means of getting round the problem, details of this are entered as well. Your name is also entered, so that your support organization knows who to contact if the service team need to ask anything further about the APAR documentation.

At this stage, you are given an APAR number. This number is always associated with the APAR and its resolution and, if a code change is required, is associated with the fix as well.

The service team may ask for additional backup documentation, normally via the Level-2 representative. The specific documentation required will vary from problem to problem, and depends on what information has already been supplied during the PMR stage.

During the investigation, you can ask your support organization at any time about how your APAR is progressing, particularly if it is a problem of high severity.

### Obtaining the fix

When the service team has found a fix for your problem, you may be asked to test it on your system. If so, you may be sent a Program Temporary Fix (PTF) in the form of individual replacement modules. This is normally done through the Level-2 organization and feedback from your testing will be requested.

Each PTF may contain several APAR fixes. If an individual APAR fix within a PTF is found to be in error, it may still be advisable to apply the PTF, to obtain the other APAR fixes.

In time, formal corrective service software is made available, which you can order through your support organization. Traditionally, corrective service software has been supplied on Corrective Service Diskettes (CSD) ordered by CSD number. It may now be supplied on CD-ROM or via the Internet.

Fixes for CICS Universal Client are available from the CICS Support web page at:  
[www.ibm.com/software/ts/cics/support/](http://www.ibm.com/software/ts/cics/support/)



---

## Chapter 12. Migration

This information deals with issues that can arise when you move from an earlier version of the CICS Universal Client, or a product related to the CICS Universal Client.

See also “Preparing to install CICS Universal Client” on page 9.

---

### Migrating to Version 7.1

This information details any special action you need to take if migrating from an earlier version of the product.

#### Installation location

If you are upgrading from Version 5, Version 6 or Version 7, the product is installed into your existing directory structure, replacing the older version.

#### Removal of TCP62 support

The announcement of CICS Transaction Gateway for z/OS V6.1 indicated that the releases of CICS Transaction Gateway V7.0 and CICS Universal Client V7.0, would be the last releases that would contain TCP62 support for the AnyNet protocol communicating with remote CICS systems using SNA over TCP/IP protocol encapsulation. Accordingly, this capability has been removed from the V7.1 level of the products. For continued use of SNA over TCP/IP, it is necessary to migrate TCP62 server definitions to SNA and implement another IBM Communications Server TCP/IP protocol encapsulation solution, such as Enterprise Extender or Remote API client support.

For information on migrating from TCP62 to Enterprise Extender support refer to the IBM publication *Migrating an SNA connection from TCP62 to Enterprise Extender* - GC34-6889-00.

For information on the removal of AnyNet support from z/OS Communications Server, refer to the z/OS and z/OS.e statements of direction announcement, Software Announcement 203-266, dated October 7, 2003, and the z/OS V1.7 preview announcement, Software Announcement 205-034, dated February 15, 2005.

#### Removal of SNA Server configuration setting LUALIASNAMES

On Windows operating systems LUALIASNAMES has been replaced by LOCALLUALIAS and PARTNERLUALIAS.

On Unix and Linux operating systems LUALIASNAMES has been replaced by PARTNERLUALIAS.

After migration if LUALIASNAMES is found in the configuration file the Client daemon will attempt to start the SNA Server connection and will generate a warning in the Client daemon log file saying that the deprecated entry LUALIASNAMES exists.

## Named pipes

Use of the named pipes protocol is deprecated for removal from other Windows® platforms in a future release.

## Client daemon runs as a user process

The Client daemon now runs as a Windows user process. Running the Client daemon as a Windows service is no longer supported. The cicscli command controls the process.

## MAXSERVERS parameter

The MAXSERVERS parameter, a setting in the CLIENT section of the configuration file for SNA and TCP/IP protocols is deprecated, and might be removed in a future release.

## Support for mixed case passwords

CICS Transaction Server for z/OS version 2.2 and higher supports mixed-case passwords. To use mixed-case passwords, ensure that the “Use uppercase security” on page 39 field in the Configuration Tool is cleared.

## Information log

Some Client information messages are now logged. You can configure a separate log for information messages; see “Changing settings for Client daemon logging” on page 36.

---

## Migration considerations at Version 6

This information applies if you are migrating from Version 5 to Version 7.1.

### Supported ECI and EPI versions

Applications can be built only with the following ECI and EPI versions:

ECI\_VERSION\_1A

CICS\_EPI\_VERSION\_200

Existing applications built with the following versions are still supported at run time:

CICS\_EPI\_VERSION\_100

CICS\_EPI\_VERSION\_101

ECI\_VERSION\_1

Recompiling these applications will give a compiler error.

### Change to maxrequests configuration setting

The maximum value permitted for this setting is now 32. If the configuration file specifies a value greater than this an error is logged, and the maximum value is used. See “Maximum requests” on page 32 for details of the configuration setting.

### Out-of-process libraries

Versions of the CICS Universal Client earlier than version 6 allowed COM libraries to be registered as in-process (DLL files) or out-of-process (EXE files). From version

6, only in-process libraries are supported. If you registered COM libraries as out-of-process with a version of the CICS Universal Client earlier than version 5, unregister them before installing the product. Issue the following commands from a command prompt:

```
ccloepi /unregister  
ccloeci /unregister
```



---

## Appendix. Data conversion

Data conversion between the Client daemon and a CICS server

The ECI and EPI allow non-CICS applications running in a client system to gain access to CICS facilities and data managed by a CICS server system.

Character data may have to be converted as it is passed between client and server; for example data is encoded in ASCII on a client system and in EBCDIC on a CICS mainframe server system. Data conversion is performed by the server system.

The possible ASCII and EBCDIC encoding schemes are described in detail in SC09-2190, the Character Data Representation Architecture Reference and Registry (CRDA). In summary, each encoding scheme is identified by a Coded Character Set Identifier (CCSID) which defines a set of graphic characters and the Code Page Global Identifier (CPGID) which specifies the code points used to represent the graphic characters.

The data managed by the server system may be accessed from several client systems each of which uses a different ASCII encoding scheme. To support such access, each client system must be able to supply a CCSID 'tag' in order that the data is converted correctly.

---

### Data conversion on Windows

The ASCII CCSID is determined dynamically. By default the GetOEMCP function is used to obtain the current OEM code page identifier, for example CCSID 850, for the system. If the **Use OEM code page** configuration setting is specified, the GetACP function is used to obtain the current ANSI code page identifier, for example CCSID 1252, for the system.

The identifier may not be unique. For example, there are differences between IBM CCSID 932 and Microsoft CCSID 932 - the Client daemon maps the Microsoft one to CCSID 943 which is the equivalent one defined in the CRDA Registry. The Microsoft CCSID 1252 may be the pre-euro or post-euro version - the post-euro is mapped to CCSID 5348.

---

### Supported conversions

The method used to perform data conversion depends on the server platform. The range of data conversions supported also depends on the platform. The following information is taken from *Communicating from CICS on System/390*, and is provided as a guide; check the current copy of the book for full information. ASCII and EBCDIC CCSIDs are assigned to geographic or linguistic groups.

Data conversion is supported between ASCII and EBCDIC where both CCSIDs belong to the same group. The groups are:

**Arabic**

**Baltic Rim**

Latvia, Lithuania

**Cyrillic**

Eastern Europe: Bulgaria, Russia, Yugoslavia

**Estonian**

Estonia

**Greek**

Greece

**Hebrew**

Israel

**Japanese**

Japan

**Korean**

Korea

**Latin-1 and Latin-9**

USA, Western Europe, and many other countries

**Latin-2**

Eastern Europe: Albania, Czech Republic, Hungary, Poland, Romania, Slovakia, Yugoslavia, Former Yugoslavia

**Latin-5**

Turkey

**Simplified Chinese**

People's Republic of China

**Traditional Chinese**

Taiwan

**Vietnamese**

Vietnam

The following tables list the CCSIDs supported for each group. For each CCSID, they show:

- The value to be specified for the CLINTCP or SRVERCP keyword.
- The code page identifier or identifiers (CPGIDs).
- The current CICS on System/390 products that support the CCSID. Three levels of support are defined—"Base", "T01", and "T02".

**Base**

- CICS Transaction Server for z/OS
- CICS Transaction Server for OS/390® (all releases)
- CICS/ESA® Version 4 Release 1
- CICS/VSE
- CICS/VSE Version 2 Release 3

**T01**

- CICS Transaction Server for z/OS
- CICS Transaction Server for OS/390 Release 3
- CICS Transaction Server for OS/390 Release 1 or Release 2 plus APAR PQ19018
- CICS/ESA Version 4 Release 1 plus APAR PQ18896
- CICS/VSE
- CICS/VSE Version 2 Release 3 plus APAR PQ19019



## T02

– CICS Transaction Server for z/OS

### Arabic

Table 12. Arabic, Client CCSIDs

| CLINTCP        | in   | CCSID | CPGID | Comments                                |
|----------------|------|-------|-------|---|
| 864            | Base | 00864 | 00864 | PC data: Arabic                         |
| 1089<br>8859-6 | Base | 01089 | 01089 | ISO 8859-6: Arabic                      |
| 1256           | T01  | 01256 | 01256 | MS Windows: Arabic                      |
| 5352           | T02  | 05352 | 05352 | MS Windows: Arabic, version 2 with euro |
| 17248          | T02  | 17248 | 00864 | PC Data: Arabic with euro               |

Table 13. Arabic, Server CCSIDs

| SRVERCP | in   | CCSID | CPGID | Comments               |
|---------|------|-------|-------|------------------------|
| 420     | Base | 00420 | 00420 | Host: Arabic           |
| 16804   | T02  | 16804 | 00420 | Host: Arabic with euro |

**Note:** Data conversion does not change the direction of Arabic data.

### Baltic Rim

Table 14. Baltic Rim, Client CCSIDs

| CLINTCP | in  | CCSID | CPGID | Comments                                    |
|---------|-----|-------|-------|---|
| 901     | T02 | 00901 | 00901 | PC data: Latvia, Lithuania; with euro       |
| 921     | T01 | 00921 | 00921 | PC data: Latvia, Lithuania                  |
| 1257    | T01 | 01257 | 01257 | MS Windows: Baltic Rim                      |
| 5353    | T02 | 05353 | 05353 | MS Windows: Baltic Rim, version 2 with euro |

Table 15. Baltic Rim, Server CCSIDs

| SRVERCP | in  | CCSID | CPGID | Comments                           |
|---------|-----|-------|-------|------------------------------------|
| 1112    | T01 | 01112 | 01112 | Host: Latvia, Lithuania            |
| 1156    | T02 | 01156 | 01156 | Host: Latvia, Lithuania; with euro |

### Cyrillic

Table 16. Cyrillic, Client CCSIDs

| CLINTCP | in   | CCSID | CPGID | Comments                              |
|---------|------|-------|-------|---------------------------------------|
| 808     | T02  | 00808 | 00808 | PC data: Cyrillic, Russia; with euro  |
| 848     | T02  | 00848 | 00848 | PC data: Cyrillic, Ukraine; with euro |
| 849     | T02  | 00849 | 00849 | PC data: Cyrillic, Belarus; with euro |
| 855     | Base | 01235 | 00855 | PC data: Cyrillic                     |
| 866     | Base | 00866 | 00866 | PC data: Cyrillic, Russia             |

Table 16. Cyrillic, Client CCSIDs (continued)

| CLINTCP       | in   | CCSID | CPGID | Comments                                  |
|---------------|------|-------|-------|---|
| 872           | T02  | 00872 | 00872 | PC data: Cyrillic with euro               |
| 915<br>8859-5 | Base | 00915 | 00915 | ISO 8859-5: Cyrillic                      |
| 1124          | T02  | 01124 | 01124 | 8-bit: Cyrillic, Belarus                  |
| 1125          | T02  | 01125 | 01125 | PC Data: Cyrillic, Ukraine                |
| 1131          | T02  | 01131 | 01131 | PC Data: Cyrillic, Belarus                |
| 1251          | T01  | 01251 | 01251 | MS Windows: Cyrillic                      |
| 5347          | T02  | 05347 | 05347 | MS Windows: Cyrillic, version 2 with euro |

Table 17. Cyrillic, Server CCSIDs

| SRVERCP | in   | CCSID | CPGID | Comments                               |
|---------|------|-------|-------|--|
| 1025    | Base | 01025 | 01025 | Host: Cyrillic multilingual            |
| 1123    | T02  | 01123 | 01123 | Host: Cyrillic Ukraine                 |
| 1154    | T02  | 01154 | 01154 | Host: Cyrillic multilingual; with euro |
| 1158    | T02  | 01158 | 01158 | Host: Cyrillic Ukraine; with euro      |

## Estonian

Table 18. Estonian, Client CCSIDs

| CLINTCP | in  | CCSID | CPGID | Comments                                   |
|---------|-----|-------|-------|--|
| 902     | T02 | 00902 | 00902 | PC data: Estonia with euro                 |
| 922     | T01 | 00922 | 00922 | PC data: Estonia                           |
| 1257    | T01 | 01257 | 01257 | MS Windows: Baltic Rim                     |
| 5353    | T02 | 05353 | 05353 | MS Windows: Baltic Rim, version2 with euro |

Table 19. Estonian, Server CCSIDs

| SRVERCP | in  | CCSID | CPGID | Comments                |
|---------|-----|-------|-------|-------------------------|
| 1122    | T01 | 01122 | 01122 | Host: Estonia           |
| 1157    | T01 | 01157 | 01157 | Host: Estonia with euro |

## Greek

Table 20. Greek, Client CCSIDs

| CLINTCP       | in   | CCSID | CPGID | Comments                                |
|---------------|------|-------|-------|---|
| 813<br>8859-7 | Base | 00813 | 00813 | ISO 8859-7: Greece                      |
| 869           | Base | 00869 | 00869 | PC data: Greece                         |
| 1253          | T01  | 01253 | 01253 | MS Windows: Greece                      |
| 4909          | T02  | 04909 | 00813 | ISO 8859-7: Greece with euro            |
| 5349          | T02  | 05349 | 01253 | MS Windows: Greece, version 2 with euro |

Table 20. Greek, Client CCSIDs (continued)

| CLINTCP | in  | CCSID | CPGID | Comments                  |
|---------|-----|-------|-------|---------------------------|
| 9061    | T02 | 09061 | 00869 | PC Data: Greece with euro |

Table 21. Greek, Server CCSIDs

| SRVERCP | in   | CCSID | CPGID | Comments               |
|---------|------|-------|-------|------------------------|
| 875     | Base | 00875 | 00875 | Host: Greece           |
| 4971    | T02  | 04971 | 00875 | Host: Greece with euro |

## Hebrew

Table 22. Hebrew, Client CCSIDs

| CLINTCP       | in   | CCSID | CPGID | Comments                                |
|---------------|------|-------|-------|---|
| 856           | Base | 00856 | 00856 | PC data: Hebrew                         |
| 862           | T02  | 00862 | 00862 | PC data: Hebrew (migration)             |
| 867           | T02  | 00867 | 00867 | PC Data: Hebrew with euro               |
| 916<br>8859-8 | Base | 00916 | 00916 | ISO 8859-8: Hebrew                      |
| 1255          | T01  | 01255 | 01255 | MS Windows: Hebrew                      |
| 5351          | T02  | 05351 | 05351 | MS Windows: Hebrew, version 2 with euro |

Table 23. Hebrew, Server CCSIDs

| SRVERCP | in   | CCSID | CPGID | Comments                                 |
|---------|------|-------|-------|--|
| 424     | Base | 00424 | 00424 | Host: Hebrew                             |
| 803     | T02  | 00803 | 00803 | Host: Hebrew (Character Set A)           |
| 4899    | T02  | 04899 | 00803 | Host: Hebrew (Character Set A) with euro |
| 12712   | T02  | 12712 | 00424 | Host: Hebrew with euro and new sheqel    |

**Note:** Data conversion does not change the direction of Hebrew data.

## Japanese

Table 24. Japanese, ASCII

| CLINTCP | in   | CCSID | CPGID                | Comments   |
|---------|------|-------|----------------------|--|
| 932     | Base | 00932 | 1. 00897<br>2. 00301 | 1. PC data: SBCS<br>2. PC data: DBCS including 1880 user-defined characters                          |
| 942     | Base | 00942 | 1. 01041<br>2. 00301 | 1. PC data: Extended SBCS<br>2. PC data: DBCS including 1880 user-defined characters                 |
| 943     | T01  | 00943 | 1. 00897<br>2. 00941 | 1. PC data: SBCS<br>2. PC data: DBCS for Open environment including 1880 IBM user-defined characters |

Table 24. Japanese, ASCII (continued)

| CLINTCP      | in   | CCSID | CPGID  | Comments   |
|--------------|------|-------|--|--|
| 954<br>EUCJP | Base | 00954 | 1. 00895<br>2. 00952<br>3. 00896<br>4. 00953 | 1. G0: JIS X201 Roman<br>2. G1: JIS X208-1990<br>3. G1: JIS X201 Katakana<br>4. G1: JIS X212 |
| 5050         | T02  | 05050 | 1. 00895<br>2. 00952<br>3. 00896<br>4. 00953 | 1. G0: JIS X201 Roman<br>2. G1: JIS X208-1990<br>3. G1: JIS X201 Katakana<br>4. G1: JIS X212 |

Table 25. Japanese, EBCDIC

| SRVERCP |      | CCSID | CPGID  | Comments   |
|---------|------|-------|--|--|
| 930     | Base | 00930 | 1. 00290<br>2. 00300<br>3. 00290<br>4. 00300 | 1. Katakana Host: extended SBCS<br>2. Kanji Host: DBCS including 4370 user-defined characters<br>3. Katakana Host: extended SBCS<br>4. Kanji Host: DBCS including 1880 user-defined characters |
| 931     | Base | 00931 | 1. 00037<br>2. 00300                         | 1. Latin Host: SBCS<br>2. Kanji Host: DBCS including 4370 user-defined characters  |
| 939     | Base | 00939 | 1. 01027<br>2. 00300<br>3. 01027<br>4. 00300 | 1. Latin Host: extended SBCS<br>2. Kanji Host: DBCS including 4370 user-defined characters<br>3. Latin Host: extended SBCS<br>4. Kanji Host: DBCS including 1880 user-defined characters       |
| 1390    | T02  | 01390 | 1. 00290<br>2. 00300                         | 1. Katakana Host: extended SBCS; with euro<br>2. Kanji Host: DBCS including 6205 user-defined characters   |
| 1399    | T02  | 01399 | 1. 01027<br>2. 00300                         | 1. Latin Host: extended SBCS; with euro<br>2. Kanji Host: DBCS including 4370 user-defined characters; with euro   |

## Korean

Table 26. Korean, ASCII

| CLINTCP      | in   | CCSID | CPGID                | Comments  |
|--------------|------|-------|----------------------|---|
| 934          | Base | 00934 | 1. 00891<br>2. 00926 | 1. PC data: SBCS<br>2. PC data: DBCS including 1880 user-defined characters                             |
| 944          | Base | 00944 | 1. 01040<br>2. 00926 | 1. PC data: Extended SBCS<br>2. PC data: DBCS including 1880 user-defined characters                    |
| 949          | Base | 00949 | 1. 01088<br>2. 00951 | 1. IBM KS Code - PC data: SBCS<br>2. IBM KS code - PC data: DBCS including 1880 user-defined characters |
| 970<br>EUCKR | Base | 00970 | 1. 00367<br>2. 00971 | 1. G0: ASCII<br>2. G1: KSC X5601-1989 including 1880 user-defined characters                            |

Table 26. Korean, ASCII (continued)

| CLINTCP | in  | CCSID | CPGID                | Comments   |
|---------|-----|-------|----------------------|--|
| 1363    | T01 | 01363 | 1. 01126<br>2. 01362 | 1. PC data: MS Windows Korean SBCS<br>2. PC data: MS Windows Korean DBCS including 11172 full Hangul |

Table 27. Korean, EBCDIC

| SRVERCP | in   | CCSID | CPGID                | Comments  |
|---------|------|-------|----------------------|---|
| 933     | Base | 00933 | 1. 00833<br>2. 00834 | 1. Host: Extended SBCS<br>2. Host: DBCS including 1880 user-defined characters and 11172 full Hangul characters |
| 1364    | T02  | 01364 | 1. 00833<br>2. 00834 | 1. Host: Extended SBCS<br>2. Host: DBCS including 1880 user-defined characters and 11172 full Hangul characters |

## Latin-1 and Latin-9

Table 28. Latin-1, Client CCSIDs

| CLINTCP       | in   | CCSID | CPGID | Comments   |
|---------------|------|-------|-------|--|
| 437           | Base | 00437 | 00437 | PC data: PC Base; USA, many other countries        |
| 819<br>8859-1 | Base | 00819 | 00819 | ISO 8859-1: Latin-1 countries                      |
| 850           | Base | 00850 | 00850 | PC data: Latin-1 countries                         |
| 858           | T01  | 00858 | 00858 | PC data: Latin-1 countries; with euro              |
| 923           | T01  | 00923 | 00923 | ISO 8859-15: Latin-9                               |
| 924           | T02  | 00924 | 00924 | ISO 8859-15: Latin-9                               |
| 1047          | T02  | 01047 | 01047 | Host: Open Edition Latin-1                         |
| 1252          | T01  | 01252 | 01252 | MS Windows: Latin-1 countries                      |
| 5348          | T01  | 05348 | 01252 | MS Windows: Latin-1 countries, version 2 with euro |

Table 29. Latin-1 and Latin-9, Server CCSIDs

| SRVERCP | in   | CCSID | CPGID | Comments   |
|---------|------|-------|-------|--|
| 037     | Base | 00037 | 00037 | Host: USA, Canada (ESA), Netherlands, Portugal, Brazil, Australia, New Zealand |
| 273     | Base | 00273 | 00273 | Host: Austria, Germany   |
| 277     | Base | 00277 | 00277 | Host: Denmark, Norway  |
| 278     | Base | 00278 | 00278 | Host: Finland, Sweden  |
| 280     | Base | 00280 | 00280 | Host: Italy  |
| 284     | Base | 00284 | 00284 | Host: Spain, Latin America (Spanish)   |
| 285     | Base | 00285 | 00285 | Host: United Kingdom   |
| 297     | Base | 00297 | 00297 | Host: France   |
| 500     | Base | 00500 | 00500 | Host: Belgium, Canada (AS/400®), Switzerland, International Latin-1            |
| 871     | Base | 00871 | 00871 | Host: Iceland  |
| 924     | T01  | 00924 | 00924 | Host: Latin-9  |

Table 29. Latin-1 and Latin-9, Server CCSIDs (continued)

| SRVERCP | in  | CCSID | CPGID | Comments  |
|---------|-----|-------|-------|---|
| 1047    | T01 | 01047 | 01047 | Host: Open Edition Latin-1  |
| 1140    | T01 | 01140 | 01140 | Host: USA, Canada (ESA), Netherlands, Portugal, Brazil, Australia, New Zealand; with euro |
| 1141    | T01 | 01141 | 01141 | Host: Austria, Germany; with euro   |
| 1142    | T01 | 01142 | 01142 | Host: Denmark, Norway; with euro  |
| 1143    | T01 | 01143 | 01143 | Host: Finland, Sweden; with euro  |
| 1144    | T01 | 01144 | 01144 | Host: Italy; with euro  |
| 1145    | T01 | 01145 | 01145 | Host: Spain, Latin America (Spanish); with euro   |
| 1146    | T01 | 01146 | 01146 | Host: United Kingdom; with euro   |
| 1147    | T01 | 01147 | 01147 | Host: France; with euro   |
| 1148    | T01 | 01148 | 01148 | Host: Belgium, Canada (AS/400), Switzerland, International Latin-1; with euro             |
| 1149    | T01 | 01149 | 01149 | Host: Iceland; with euro  |

**Note:** Conversions are supported between non euro-supported CCSIDs and euro-supported CCSIDs. These should be used with care because:

- The international currency symbol in each non euro-supported EBCDIC CCSID (for example, 00500) has been replaced by the euro symbol in the equivalent euro-supported EBCDIC CCSID (for example, 01148).
- The dotless *i* in non euro-supported ASCII CCSID 00850 has been replaced by the euro symbol in the equivalent euro-supported ASCII CCSID 00858.

## Latin-2

Table 30. Latin-2, ASCII

| CLINTCP       | in   | CCSID | CPGID | Comments                                 |
|---------------|------|-------|-------|--|
| 852           | Base | 00852 | 00852 | PC data: Latin-2 multilingual            |
| 912<br>8859-2 | Base | 00912 | 00912 | ISO 8859-2: Latin-2 multilingual         |
| 1250          | T01  | 01250 | 01250 | MS Windows: Latin-2                      |
| 5346          | T02  | 05346 | 01250 | MS Windows: Latin-2, version 2 with euro |
| 9044          | T02  | 09044 | 00852 | PC data: Latin-2 multilingual with euro  |

Table 31. Latin-2, Server CCSIDs

| SRVERCP | in   | CCSID | CPGID | Comments                              |
|---------|------|-------|-------|---------------------------------------|
| 500     | T02  | 00500 | 00500 | Host: International Latin-1           |
| 870     | Base | 00870 | 00870 | Host: Latin-2 multilingual            |
| 1148    | T02  | 01148 | 01148 | Host: International Latin-1 with euro |
| 1153    | T02  | 01153 | 01153 | Host: Latin-2 multilingual with euro  |

**Note:** Conversions are supported for some combinations of Latin-2 ASCII CCSIDs and Latin-1 EBCDIC CCSIDs.

## Latin-5

Table 32. Latin-5, Client CCSIDs

| CLINTCP       | in   | CCSID | CPGID | Comments                                       |
|---------------|------|-------|-------|--|
| 857           | Base | 00857 | 00857 | PC data: Latin-5 (Turkey)                      |
| 920<br>8859-9 | Base | 00920 | 00920 | ISO 8859-9: Latin-5 (ECMA-128, Turkey TS-5881) |
| 1254          | T01  | 01254 | 01254 | MS Windows: Turkey                             |
| 5350          | T02  | 05350 | 01254 | MS Windows: Turkey, version 2 with euro        |
| 9049          | T02  | 09049 | 00857 | PC data: Latin-5 (Turkey) with euro            |

Table 33. Latin-5, Server CCSIDs

| SRVERCP | in   | CCSID | CPGID | Comments                         |
|---------|------|-------|-------|----------------------------------|
| 1026    | Base | 01026 | 01026 | Host: Latin-5 (Turkey)           |
| 1155    | T02  | 01155 | 01155 | Host: Latin-5 (Turkey) with euro |

## Simplified Chinese

Table 34. Simplified Chinese, ASCII

| CLINTCP       | in   | CCSID | CPGID                | Comments  |
|---------------|------|-------|----------------------|---|
| 946           | Base | 00946 | 1. 01042<br>2. 00928 | 1. PC data: Extended SBCS<br>2. PC data: DBCS including 1880 user-defined characters                                    |
| 1381          | Base | 01381 | 1. 01115<br>2. 01380 | 1. PC data: Extended SBCS (IBM GB)<br>2. PC data: DBCS (IBM GB) including 31 IBM-selected, 1880 user-defined characters |
| 1383<br>EUCCN | T01  | 01383 | 1. 00367<br>2. 01382 | 1. G0: ASCII<br>2. G1: GB 2312-80 set   |
| 1386          | T01  | 01386 | 1. 01114<br>2. 01385 | 1. PC data: S-Chinese GBK and T-Chinese IBM BIG-5<br>2. PC data: S-Chinese GBK  |

Table 35. Simplified Chinese, EBCDIC

| SRVERCP | in   | CCSID | CPGID                | Comments   |
|---------|------|-------|----------------------|--|
| 935     | Base | 00935 | 1. 00836<br>2. 00837 | 1. Host: Extended SBCS<br>2. Host: DBCS including 1880 user-defined characters |
| 1388    | T02  | 01388 | 1. 00836<br>2. 00837 | 1. Host: Extended SBCS<br>2. Host: DBCS including 1880 user-defined characters |
| 9127    | T02  | 09127 | 1. 00836<br>2. 00837 | 1. Host: Extended SBCS<br>2. Host: DBCS including 1880 user-defined characters |

## Traditional Chinese

Table 36. Traditional Chinese, ASCII

| CLINTCP      | in   | CCSID | CPGID                            | Comments  |
|--------------|------|-------|----------------------------------|---|
| 938          | Base | 00938 | 1. 00904<br>2. 00927             | 1. PC data: SBCS<br>2. PC data: DBCS including 6204 user-defined characters   |
| 948          | Base | 00948 | 1. 01043<br>2. 00927             | 1. PC data: Extended SBCS<br>2. PC data: DBCS including 6204 user-defined characters                                |
| 950<br>BIG5  | Base | 00950 | 1. 01114<br>2. 00947             | 1. PC data: SBCS (IBM BIG5)<br>2. PC data: DBCS including 13493 CNS, 566 IBM selected, 6204 user-defined characters |
| 964<br>EUCTW | Base | 00964 | 1. 00367<br>2. 00960<br>3. 00961 | 1. G0: ASCII<br>2. G1: CNS 11643 plane 1<br>3. G1: CNS 11643 plane 2  |
| 1370         | T02  | 01370 | 1. 01114<br>2. 00947             | 1. PC data: Extended SBCS; with euro<br>2. PC data: DBCS including 6204 user-defined characters; with euro          |

Table 37. Traditional Chinese, EBCDIC

| SRVERCP | in   | CCSID | CPGID                | Comments   |
|---------|------|-------|----------------------|--|
| 937     | Base | 00937 | 1. 00037<br>2. 00835 | 1. Host: Extended SBCS<br>2. Host: DBCS including 6204 user-defined characters                       |
| 1371    | T02  | 01371 | 1. 01159<br>2. 00835 | 1. Host: Extended SBCS; with euro<br>2. Host: DBCS including 6204 user-defined characters; with euro |

## Vietnamese

Table 38. Vietnamese, Client CCSIDs

| CLINTCP | in  | CCSID | CPGID | Comments                                    |
|---------|-----|-------|-------|---|
| 1129    | T02 | 01129 | 01129 | ISO-8: Vietnamese                           |
| 1163    | T02 | 01163 | 01163 | ISO-8: Vietnamese with euro                 |
| 1258    | T02 | 01258 | 01258 | MS Windows: Vietnamese                      |
| 5354    | T02 | 05354 | 01258 | MS Windows: Vietnamese, version 2 with euro |

Table 39. Vietnamese, Server CCSIDs

| SRVERCP | in  | CCSID | CPGID | Comments                   |
|---------|-----|-------|-------|----------------------------|
| 1130    | T02 | 01130 | 01130 | Host: Vietnamese           |
| 1164    | T02 | 01164 | 01164 | Host: Vietnamese with euro |

## Unicode data

CICS on System/390 provides limited support for Unicode-encoded character data. The support allows workstations to share UCS-2 or UTF-8 encoded data with the System/390 provided, that no conversion is required.



Table 40. Unicode

| CLINTCP<br>SRVERCP | in  | CCSID | CPGID | Comments   |
|--------------------|-----|-------|-------|--|
| 1200 UCS-2         | T01 | 01200 | 01400 | UCS-2 level 3, maximal (growing) character set                 |
| 1208 UTF-8         | T01 | 01200 | 01400 | UTF-8 based on UCS-2 level 3, maximal (growing) character set  |
| 13488              | T01 | 13488 | 01400 | UCS-2 level 1 (level 3 tolerant), subset (fixed) character set |



---

## The product library and related literature

This information lists books on the CICS Universal Client, and related topics.

---

### CICS Universal Client books

- *CICS Universal Client: Windows Administration*, SC34-6963-00  
This book describes the administration of the CICS Universal Client for Windows.
- *CICS Transaction Gateway: Messages*, SC34-6964-00  
This online book lists and explains the error messages that can be generated by the CICS Transaction Gateway or the CICS Universal Client.
- *CICS Transaction Gateway: Programming Reference*, SC34-6966-00  
This book provides information on the APIs of the programming languages supported by the CICS Transaction Gateway and the CICS Universal Client.
- *CICS Transaction Gateway: Programming Guide*, SC34-6965-00  
This introduction to programming for the CICS Transaction Gateway and the CICS Universal Client provides the information that you need to allow user applications to use CICS facilities in a client/server environment.

---

### Sample configuration documents

Several sample configuration documents are available in portable document format (PDF). These documents give step-by-step guidance for configuring CICS Transaction Gateway for communication with CICS servers, using various protocols. They provide detailed instructions that extend the information in the CICS Transaction Gateway library. Although written for the CICS Transaction Gateway, they also contain information relevant to the CICS Universal Client.

Visit the following Web site:

[www.ibm.com/software/cics/cuc](http://www.ibm.com/software/cics/cuc)

and follow the **Library** link.

---

### Redbooks

The following International Technical Support Organization (ITSO) Redbook publication contains many examples of client/server configurations. Although these were written for the CICS Transaction Gateway they also contain information applicable to the CICS Universal Client.

- *CICS Transaction Gateway V5 - The WebSphere Connector for CICS*, SG24-6133
- *Revealed! Architecting Web Access to CICS*, SG24-5466
- *Enterprise JavaBeans for z/OS and OS/390 CICS Transaction Server V2.2*, SG24-6284
- *Java Connectors for CICS: Featuring the J2EE Connector Architecture*, SG24-6401.  
This book provides information on developing J2EE applications.
- *Systems Programmer's Guide to Resource Recovery Services (RRS)*, SG24-6980-00.  
This book provides information on using RRS in various scenarios.

- *Communications Server for z/OS V1R2 TCP/IP Implementation Guide, SG24-6517-00.* This book provides information on using Communications Server for z/OS V1R2, including load balancing.
- *Redpaper: Transactions in J2EE, REDP-3659-00.* This redpaper provides a discussion of transactions in the J2EE environment, including one- and XA transactions.

You can obtain ITSO Redbooks® from a number of sources. For the latest information, see:

[www.ibm.com/redbooks/](http://www.ibm.com/redbooks/)

---

## Other Useful Books

### CICS Transaction Server publications

*CICS Transaction Server for z/OS RACF Security Guide, SC34-6249*

#### CICS interproduct communication

The following books describe the intercommunication facilities of the CICS server products:

- *CICS Family: Interproduct Communication, SC34-6267*
- *CICS Transaction Server for Windows V5.0 Intercommunication, SC34-6209*
- *CICS Transaction Server for z/OS CICS External Interfaces Guide, SC34-6449*
- *CICS Transaction Server for z/OS: Intercommunication Guide, SC34-6448*
- *CICS/VSE 2.3: Intercommunication Guide, SC33-0701*
- *CICS Transaction Server for iSeries V5R2: Intercommunication, SC41-5456*
- *TXSeries 5.1: CICS Intercommunication Guide, SC09-4462*

The first book above is a CICS family book containing a platform-independent overview of CICS interproduct communication.

#### CICS problem determination books

The following books describe the problem determination facilities of the CICS server products:

- *Transaction Server for Windows V5.0: Problem Determination, GC34-6210*
- *CICS Transaction Server for z/OS V3.1 CICS Problem Determination Guide, SC34-6441*
- *CICS/VSE 2.3 Problem Determination Guide, SC33-0716*
- *CICS Transaction Server for iSeries V5R2: Problem Determination, SC41-5453*
- *TXSeries V5.1: CICS Problem Determination Guide, SC09-4465*

You can find information on CICS products at the following Web site:

[www.ibm.com/software/cics/cuc](http://www.ibm.com/software/cics/cuc)

### Microsoft Windows publications

See this Web site:

[www.microsoft.com/windows](http://www.microsoft.com/windows)

## APPC-related publications

### IBM products

#### IBM Communications Server

See this Web page:

[www.ibm.com/software/network/commserver/library](http://www.ibm.com/software/network/commserver/library)

#### IBM Personal Communications

See this Web page:

[www.ibm.com/software/network/pcomm/library](http://www.ibm.com/software/network/pcomm/library)

### Microsoft products

See this page Web:

<http://www.microsoft.com/hiserver/techinfo/productdoc/default.msp>

### Systems Network Architecture (SNA)

- *SNA Formats*, GA27-3136
- *Systems Network Architecture Technical Overview*, GC30-3073
- *Guide to SNA over TCP/IP*, SC31-6527

---

## Obtaining books from IBM

For information on books you can download, visit our Web site at:

[www.ibm.com/software/cics/cuc](http://www.ibm.com/software/cics/cuc)

and follow the **Library** link.



---

## Accessibility features for CICS Universal Client

Accessibility features help users who have a physical disability, such as restricted mobility or limited vision, to use information technology products successfully. The CICS Universal Client supports keyboard-only operation. Topics on the following pages give details of accessibility features.

Visit the IBM Accessibility Center for more information about IBM's commitment to accessibility.

---

### Installation

The InstallShield wizard is not fully accessible to screen readers. An alternative is to use the -console option; see "Installing from the command line" on page 11.

---

### Documentation

See the Eclipse information center for an HTML version of the documentation.

---

### Configuration Tool accessibility

See "Editing the configuration file" on page 47 for information on how to configure the CICS Universal Client by editing the configuration file. This is the recommended way if you use a screen reader. f

The configuration file uses the number sign (#) character to denote a comment; consider configuring your screen reader accordingly.

### Components

Each component in the Configuration Tool has a name and description for screen readers.

### Using help

Screen readers read the entire page in the help window, rather than the area required by a user who has pressed F1. In addition, you cannot use the keyboard to navigate the help window. For example, pressing **Tab** while the help page is displayed prevents navigation of the page using the arrow keys. Use **Alt+F4** to close the page, and then open the help files, which are html files, in a browser outside the Configuration Tool. The help file index is cclhlp15.htm in directory:

<install\_path>\bin\resource\<html\_dir>

where <html\_dir> represents the directory containing the help files in these languages:

| Language | <html_dir> |
|----------|------------|
| English  | html       |
| German   | html_de    |
| Spanish  | html_es    |
| French   | html_fr    |
| Italian  | html_it    |

| Language           | <htmldir> |
|--------------------|-----------|
| Japanese           | html_ja   |
| Korean             | html_ko   |
| Turkish            | html_tr   |
| Simplified Chinese | html_zh   |

## Keys

You can use the following keys to operate the Configuration Tool:

### Alt, Space

Press and release the **Alt** key, then press **Space**, to open the window menu.

This allows you to move, size, maximize or minimize the window.

### Ctrl+key

Certain actions have shortcuts assigned to them. Hold down the Ctrl key and type the letter to do the action.

| Action   | Ctrl+key   |
|--|--|
| Activate a link.   | Spacebar   |
| Copy the selected value  | C except in the following locales:<br><b>Locale</b> <b>Key</b><br><b>German</b><br>K<br><b>Turkish</b><br>P  |
| Create a new configuration   | N  |
| Create a new server definition   | W except in the following locales:<br><b>Locale</b> <b>Key</b><br><b>German</b><br>N<br><b>Italian</b> V<br><b>Spanish</b><br>V<br><b>Turkish</b><br>S |
| Cut the selected value   | U except in the following locales:<br><b>Locale</b> <b>Key</b><br><b>Italian</b> G<br><b>Spanish</b><br>O<br><b>Turkish</b><br>E                       |
| Cycle between the navigation panel, objects on the settings panel, and the buttons | Use this key combination on panels that contain a table. Otherwise use <b>Tab</b> .  |
| Next link or other focusable object  | T  |



| Action                                  | Ctrl+key  |
|---|---|
| Open an existing configuration          | O except in the following locales:<br><b>Locale</b> <b>Key</b><br><b>German</b> F<br><b>Italian</b> A<br><b>Spanish</b> B<br><b>Turkish</b> A |
| Paste                                   | P except in the following locales:<br><b>Locale</b> <b>Key</b><br><b>French</b> L<br><b>German</b> F<br><b>Italian</b> I<br><b>Turkish</b> P  |
| Previous link or other focusable object | Shift+T   |
| Save the current configuration          | S except in the following locales:<br><b>Locale</b> <b>Key</b><br><b>Spanish</b> G<br><b>Italian</b> L  |
| Scroll left                             | Page Up   |
| Scroll right                            | Page Down   |

#### Arrows (left and right)

1. (Applies if the menus are active.) Move to a different menu.
2. (Applies if the buttons are active.) Cycle through the buttons.
3. (Applies if the navigation panel is active.) If a node contains subnodes, the left arrow collapses the node, the right arrow expands it. If a node cannot be expanded further, pressing the right arrow moves down to the next node. If a subnode is selected, pressing the left arrow moves to the parent node.

#### Arrows (up and down)

1. (Applies if the navigation panel is active.) Move up and down through the navigation panel.
2. (Applies if the buttons are active.) Cycle through the buttons.

#### Escape

Closes the menu.

**F2** Select and change an editable number field in a table, for example the **Bias value** field on the **Program definition for managing workload** panel.

**F6** (Applies if the navigation panel or the settings panel is active.) Toggles between the navigation panel and the settings panel.

**F8** (Applies if the navigation panel or the settings panel is active.) Allows you to gain control of the split between the navigation panel and settings panel areas. After pressing F8, use the arrow keys to move the split:

- Press the left arrow key to move the split left (decrease the width of the navigation panel, increase the width of the settings panel).
- Press the right arrow key to move the split right (increase the width of the navigation panel, decrease the width of the settings panel).

**F10**

Opens the file menu.

**Page Up**

Scroll up.

**Page Down**

Scroll down.

**Scroll bars**

You cannot use the keyboard to control scroll bars in the navigation panel. Use the up and down arrow keys to navigate the tree; settings for the selected item are shown in the settings panel.

**Shift+Tab**

If the cursor is on a field in the settings panel other than the first field, moves backwards through the fields. Otherwise, toggles between the navigation panel and the settings panel.

**Space**

1. Activates a button.
2. Selects a check box.
3. Selects a node in the tree.

**Tab**

Cycles through the tree, fields in the settings panel, and the buttons.

## Customizing colors and fonts

Use the **Settings** option on the menu to change colors and fonts.

Fields that contain errors are displayed by default in the font warning color, preceded by an asterisk. Use the **Settings->Font** option on the menu to change the warning color.

## Screen readers and pop-up windows

If you try to delete a server, a server group, or a program definition, a window with the title **Choose an option** opens. This window has a drop-down list of options, and **Cancel** and **OK** buttons. The window does not fully support screen readers. When the window opens, use the up and down arrow keys to select the required option, then tab once to **OK** to delete the item. Tab again to **Cancel** to cancel the operation.

---

## cicsterm

Although cicsterm is accessible, it relies on the application that is being processed to define an accessible 3270 screen.

The bottom row of cicsterm contains status information. The following list shows this information, as it appears from left to right:

**Status** For example, **1B** is displayed while cicsterm is connecting to a server. Displayed at columns 1 – 3.

**Terminal name**

Also referred to as *LU Name*. Columns 4 – 7.

**Action**

For example, **X-System**, indicating that you cannot enter text in the terminal window because cicsterm is waiting for a response from the server. Columns 9 – 16.

**Error number**

Errors in the form CCLNNNN, relating to the CICS Universal Client. Columns 17 – 24.

**Server name**

The server to which cicsterm is connected. Columns 27 – 35.

**Upper case**

An up arrow is displayed when the Shift key is pressed. Column 42.

**Caps Lock**

A capital A is displayed when Caps Lock is on. Column 43.

**Insert on**

The caret symbol (^) is displayed if text will be inserted, rather than overwriting existing text. If you have difficulty seeing the caret, change the font face and size, or use a screen magnifier to increase the size of the status line. Column 52.

**Cursor position**

The cursor position, in the form ROW/COLUMN, where ROW is a two-digit number, and COLUMN a three-digit number. The top left of the screen is 01/001. Column 75–80.

**Note:** You might need to change the default behavior of your screen reader if it reads only the last digit of the cursor position. Customize your screen reader to specify that columns 75–80 of the status row are to be treated as one field. This will cause the full area to be read when any digit changes.

## The cicsterm -? command

After issuing the cicsterm -? command, use the up arrow key to move from the **OK** button to the list of messages. Use the up and down arrow keys to move through the messages. Press **Tab** and then **Enter** when done.



---

## Glossary

This glossary defines special terms used in the CICS Universal Client library.

### **3270 emulation**

The use of software that enables a client to emulate an IBM 3270 display station or printer, and to use the functions of an IBM host system.

### **abnormal end of task (abend)**

The termination of a task, job, or subsystem because of an error condition that recovery facilities cannot resolve.

### **Advanced program-to-program communication (APPC)**

An implementation of the SNA/SDLC LU 6.2 protocol that allows interconnected systems to communicate and share the processing of programs. The Client daemon uses APPC to communicate with CICS server systems.

**APAR** See *Authorized program analysis report*.

**API** Application programming interface.

**applet** A small application program that performs a specific task and is usually portable between operating systems. Often written in Java, applets can be downloaded from the Internet and run in a Web browser.

### **application identifier**

The name by which a CICS system is known in a network of interconnected CICS systems. CICS Transaction Gateway application identifiers do not need to be defined in SYS1.VTAMLST. The CICS APPLID is specified in the APPLID system initialization parameter.

### **application programming interface (API)**

A functional interface that allows an application program that is written in a high-level language to use specific data or functions of the operating system or another program.

### **APPLID**

See *application identifier*.

**ARM** See *automatic restart management*.

### **Authorized program analysis report (APAR)**

A request for correction of a defect in a current release of an IBM-supplied program.

**ATI** See *automatic transaction initiation*.

**attach** In SNA, the request unit that flows on a session to initiate a conversation.

### **Attach Manager**

The component of APPC that matches attaches received from remote computers to accepts issued by local programs.

### **autoinstall**

A method of creating and installing resources dynamically as terminals log on, and deleting them at logoff.

**automatic restart manager**

A z/OS recovery function that can improve the availability of specific batch jobs or started tasks, and therefore result in faster resumption of productive work. Acronym: ARM.

**automatic transaction initiation (ATI)**

The initiation of a CICS transaction by an internally generated request, for example, the issue of an EXEC CICS START command or the reaching of a transient data trigger level. CICS resource definition can associate a trigger level and a transaction with a transient data destination. When the number of records written to the destination reaches the trigger level, the specified transaction is automatically initiated.

**bean** A definition or instance of a JavaBeans™ component. See also *JavaBeans*.

**BIND command**

In SNA, a request to activate a session between two logical units (LUs).

**business logic**

The part of a distributed application that is concerned with the application logic rather than the user interface of the application. Compare with *presentation logic*.

**CA** See *certificate authority*.

**callback**

A way for one thread to notify another application thread that an event has happened.

**certificate authority**

In computer security, an organization that issues certificates. The certificate authority authenticates the certificate owner's identity and the services that the owner is authorized to use. It issues new certificates and revokes certificates from users who are no longer authorized to use them.

**change-number-of-sessions (CNOS)**

An internal transaction program that regulates the number of parallel sessions between the partner LUs with specific characteristics.

**CICS connectivity components**

A generic reference to the Client daemon, EXCI, and the IPIC protocol.

**CICS on System/390**

A generic reference to the products CICS Transaction Server for z/OS, CICS for MVS/ESA™, CICS Transaction Server for VSE/ESA, and CICS/VSE.

**CICS TS**

Abbreviation of CICS Transaction Server.

**class** In object-oriented programming, a model or template that can be instantiated to create objects with a common definition and therefore, common properties, operations, and behavior. An object is an instance of a class.

**classpath**

In the execution environment, an environment variable keyword that specifies the directories in which to look for class and resource files.

**Client API**

The Client API is the interface used by Client applications to invoke services in CICS using the Client daemon. See External Call Interface, External Presentation Interface, and External Security Interface.

**Client application**

The client application is a user application written in a supported programming language, other than Java, that uses the Client API.

**Client daemon**

The Client daemon, process cclclnt, exists only on UNIX, Windows, and Linux. It manages network connections to CICS servers. It processes ECI, EPI, and ESI requests, sending and receiving the appropriate flows from the CICS server to satisfy the application requests. It uses the CLIENT section of ctg.ini for its configuration.

**client/server**

Pertaining to the model of interaction in distributed data processing in which a program on one computer sends a request to a program on another computer and awaits a response. The requesting program is called a client; the answering program is called a server.

**CNOS** See *Change-Number-of-Sessions*.

**code page**

An assignment of hexadecimal identifiers (code points) to graphic characters. Within a given code page, a code point can have only one meaning.

**color mapping file**

A file that is used to customize the 3270 screen color attributes on client workstations.

**communication area (COMMAREA)**

A communication area that is used for passing data both between programs within a transaction and between transactions.

**configuration file**

A file that specifies the characteristics of a program, system device, server or network.

**connection**

In data communication, an association established between functional units for conveying information.

In Open Systems Interconnection architecture, an association established by a given layer between two or more entities of the next higher layer for the purpose of data transfer.

In TCP/IP, the path between two protocol application that provides reliable data stream delivery service.

In Internet, a connection extends from a TCP application on one system to a TCP application on another system.

**control table**

In CICS, a storage area used to describe or define the configuration or operation of the system.

**conversation**

A connection between two programs over a session that allows them to communicate with each other while processing a transaction.

**conversation security**

In APPC, a process that allows validation of a user ID or group ID and password before establishing a connection.

**daemon**

A program that runs unattended to perform continuous or periodic systemwide functions, such as network control. A daemon may be launched automatically, such as when the operating system is started, or manually.

**data link control (DLC)**

A set of rules used by nodes on a data link (such as an SDLC link or a token ring) to accomplish an orderly exchange of information.

**DBCS** See *double-byte character set*.

**dependent logical unit**

A logical unit that requires assistance from a system services control point (SSCP) to instantiate an LU-to-LU session.

**deprecated**

Pertaining to an entity, such as a programming element or feature, that is supported but no longer recommended, and that might become obsolete.

**digital certificate**

An electronic document used to identify an individual, server, company, or some other entity, and to associate a public key with the entity. A digital certificate is issued by a certificate authority and is digitally signed by that authority.

**digital signature**

Information that is encrypted with an entity's private key and is appended to a message to assure the recipient of the authenticity and integrity of the message. The digital signature proves that the message was signed by the entity that owns, or has access to, the private key or shared secret symmetric key.

**distributed application**

An application for which the component application programs are distributed between two or more interconnected processors.

**distributed processing**

The processing of different parts of the same application in different systems, on one or more processors.

**distributed program link (DPL)**

A link that enables an application program running on one CICS system to link to another application program running in another CICS system.

**domain**

In the Internet, a part of a naming hierarchy in which the domain name consists of a sequence of names (labels) separated by periods (dots).

**domain name**

In TCP/IP, a name of a host system in a network.

**domain name server**

In TCP/IP, a server program that supplies name-to-address translation by mapping domain names to internet addresses. Synonymous with name server.

**dotted decimal notation**

The syntactical representation for a 32-bit integer that consists of four 8-bit numbers written in base 10 with periods (dots) separating them. It is used to represent IP addresses.



**double-byte character set (DBCS)**

A set of characters in which each character is represented by 2 bytes. Languages such as Japanese, Chinese and Korean, which contain more symbols than can be represented by 256 code points, require double-byte character sets. Because each character requires 2 bytes, the typing, display, and printing of DBCS characters requires hardware and programs that support DBCS. Contrast with *single-byte character set*.

**DPL** See *distributed program link*.

**EBCDIC**

See *Extended binary-coded decimal interchange code*.

**ECI** See *external call interface*.

**EJB** See *Enterprise JavaBeans*.

**emulation program**

A program that allows a host system to communicate with a workstation in the same way as it would with the emulated terminal.

**emulator**

A program that causes a computer to act as a workstation attached to another system.

**encryption**

The process of transforming data into an unintelligible form in such a way that the original data can be obtained only by using a decryption process.

**enterprise bean**

A Java component that can be combined with other resources to create J2EE applications. There are three types of enterprise beans: entity beans, session beans, and message-driven beans.

**Enterprise JavaBeans**

A component architecture defined by Sun Microsystems for the development and deployment of object-oriented, distributed, enterprise-level applications (J2EE).

**environment variable**

A variable that specifies the operating environment for a process. For example, environment variables can describe the home directory, the command search path, the terminal in use, and the current time zone.

**EPI** See *external presentation interface*.

**ESI** See *external security interface*.

**Ethernet**

A local area network that allows multiple stations to access the transmission medium at will without prior coordination, avoids contention by using carrier sense and deference, and resolves contention by using collision detection and transmission. Ethernet uses carrier sense multiple access with collision detection (CSMA/CD).

**EXCI** See *External CICS Interface*.

**external call interface (ECI)**

A facility that allows a non-CICS program to run a CICS program. Data is exchanged in a COMMAREA as for normal CICS interprogram communication.

**Extended binary-coded decimal interchange code (EBCDIC)**

A coded character set of 256 8-bit characters developed for the representation of textual data.

**extended logical unit of work (extended LUW)**

A logical unit of work that is extended across successive ECI requests to the same CICS server.

**External CICS Interface (EXCI)**

The EXCI is an MVS™ application programming interface provided by CICS Transaction Server for z/OS that enables a non-CICS program to call a CICS program and to pass and receive data using a COMMAREA or container. The CICS application program is invoked as if linked-to by another CICS application program.

**external presentation interface (EPI)**

A facility that allows a non-CICS program to appear to CICS as one or more standard 3270 terminals. 3270 data can be presented to the user by emulating a 3270 terminal or by using a graphical user interface.

**external security interface (ESI)**

A facility that enables client applications to verify and change passwords for user IDs on CICS servers.

**firewall**

A configuration of software that prevents unauthorized traffic between a trusted network and an untrusted network.

**gateway**

A device or program used to connect two systems or networks.

**host** A computer that is connected to a network (such as the Internet or an SNA network) and provides an access point to that network. The host can be any system; it does not have to be a mainframe.

**host address**

An IP address that is used to identify a host on a network.

**host ID**

In TCP/IP, that part of the Internet address that defines the host on the network. The length of the host ID depends on the type of network or network class (A, B, or C).

**host name**

In the Internet suite of protocols, the name given to a computer. Sometimes, host name is used to mean the fully qualified domain name; other times, it is used to mean the most specific subname of a fully qualified domain name. For example, if mycomputer.city.company.com is the fully qualified domain name, either of the following may be considered the host name: mycomputer.city.company.com, mycomputer.

**hover help**

Information that can be viewed by holding a mouse over an item such as an icon in the user interface.

**HTTP** See *Hypertext Transfer Protocol*.

**HTTPS**

See *Hypertext Transfer Protocol Secure*.

**Hypertext Transfer Protocol**

In the Internet suite of protocols, the protocol that is used to transfer and display hypertext and XML documents.

**Hypertext Transfer Protocol Secure**

A TCP/IP protocol that is used by World Wide Web servers and Web browsers to transfer and display hypermedia documents securely across the Internet.

**iKeyman**

A tool for maintaining digital certificates for JSSE.

**independent logical unit**

A logical unit (LU) that can both send and receive a BIND, and which supports single, parallel, and multiple sessions. See *BIND*.

**Internet Architecture Board**

The technical body that oversees the development of the internet suite of protocols known as TCP/IP.

**Internet Protocol (IP)**

In TCP/IP, a protocol that routes data from its source to its destination in an Internet environment.

**interoperability**

The capability to communicate, execute programs, or transfer data among various functional units in a way that requires the user to have little or no knowledge of the unique characteristics of those units.

**IP** Internet Protocol.

**IP address**

A unique address for a device or logical unit on a network that uses the IP standard.

**J2EE** See *Java 2 Platform Enterprise Edition*

**J2EE Connector architecture (JCA)**

A standard architecture for connecting the J2EE platform to heterogeneous enterprise information systems (EIS).

**Java** An object-oriented programming language for portable interpretive code that supports interaction among remote objects.

**Java 2 Platform Enterprise Edition (J2EE)**

An environment for developing and deploying enterprise applications, defined by Sun Microsystems Inc. The J2EE platform consists of a set of services, application programming interfaces (APIs), and protocols that allow multitiered, Web-based applications to be developed.

**JavaBeans**

As defined for Java by Sun Microsystems, a portable, platform-independent, reusable component model.

**Java Client application**

The Java client application is a user application written in Java, including servlets and enterprise beans, that uses the Gateway classes.

**Java Development Kit (JDK)**

The name of the software development kit that Sun Microsystems provided for the Java platform, up to and including v 1.1.x. Sometimes used erroneously to mean the Java platform or as a generic term for any software developer kits for Java.

**Java Native Interface (JNI)**

A programming interface that allows Java code running in a Java virtual machine to work with functions that are written in other programming languages.

**Java Runtime Environment (JRE)**

A subset of the Java Software Development Kit (SDK) that supports the execution, but not the development, of Java applications. The JRE comprises the Java Virtual Machine (JVM), the core classes, and supporting files.

**Java Secure Socket Extension (JSSE)**

A Java package that enables secure Internet communications. It implements a Java version of the Secure Sockets Layer (SSL) and Transport Layer Security (TLS) protocols and supports data encryption, server authentication, message integrity, and optionally client authentication.

**Java virtual machine (JVM)**

A software implementation of a processor that runs compiled Java code (applets and applications).

**JDK** See *Java development kit (JDK)*.

**JCA** See *J2EE Connector Architecture (JCA)*.

**JNI** See *Java Native Interface (JNI)*.

**JRE** See *Java Runtime Environment*

**JSSE** See *Java Secure Socket Extension (JSSE)*.

**JVM** See *Java Virtual Machine (JVM)*.

**keyboard mapping**

A list that establishes a correspondence between keys on the keyboard and characters displayed on a display screen, or action taken by a program, when that key is pressed.

**key ring**

In the JSSE protocol, a file that contains public keys, private keys, trusted roots, and certificates.

**logical unit (LU)**

In SNA, a port through which an end user accesses the SNA network in order to communicate with another end user and through which the end user accesses the functions provided by system services control points (SSCP). An LU can support at least two sessions, one with an SSCP and one with another LU, and may be capable of supporting many sessions with other logical units. See *network addressable unit*, *primary logical unit*, *secondary logical unit*.

**logical unit 6.2 (LU 6.2)**

A type of logical unit that supports general communications between programs in a distributed processing environment.

The LU type that supports sessions between two applications using APPC.

**logical unit of work (LUW)**

A recoverable unit of work performed within CICS.

**LU-LU session**

In SNA, a session between two logical units (LUs) in an SNA network. It provides communication between two end users, or between an end user and an LU services component.

**LU-LU session type 6.2**

In SNA, a type of session for communication between peer systems.  
Synonymous with APPC protocol.

**LUW** See *logical unit of work*.

**managed mode**

Describes an environment in which connections are obtained from connection factories that the J2EE server has set up. Such connections are owned by the J2EE server.

**medium access control (MAC) sublayer**

One of two sublayers of the ISO Open Systems Interconnection data link layer proposed for local area networks by the IEEE Project 802 Committee on Local Area Networks and the European Computer Manufacturers Association (ECMA). It provides functions that depend on the topology of the network and uses services of the physical layer to provide services to the logical link control (LLC) sublayer. The OSI data link layer corresponds to the SNA data link control layer.

**method**

In object-oriented programming, an operation that an object can perform. An object can have many methods.

**mode** In SNA, a set of parameters that defines the characteristics of a session between two LUs.

**name server**

In TCP/IP, synonym for Domain Name Server. In Internet communications, a host that translates symbolic names assigned to networks and hosts into Internet addresses.

**network address**

In SNA, an address, consisting of subarea and element fields, that identifies a link, link station, or network addressable unit (NAU). Subarea nodes use network addresses; peripheral nodes use local addresses. The boundary function in the subarea node to which a peripheral node is attached transforms local addresses to network addresses and vice versa. See also *network name*.

**network addressable unit (NAU)**

In SNA, a logical unit, a physical unit, or a system services control point. The NAU is the origin or the destination of information transmitted by the path control network. See also *logical unit*, *network address*, *network name*.

**network name**

In SNA, the symbolic identifier by which end users refer to a network addressable unit (NAU), link station, or link. See also *network address*.

**node type**

In SNA, a designation of a node according to the protocols it supports and the network addressable units (NAUs) it can contain. Four types are defined: 1, 2, 4, and 5. Type 1 and type 2 nodes are peripheral nodes; type 4 and type 5 nodes are subarea nodes.

**nonmanaged mode**

An environment in which the application is responsible for generating and configuring connection factories. The J2EE server does not own or know about these connection factories and therefore provides no Quality of Service facilities.

- object** In object-oriented programming, a concrete realization of a class that consists of data and the operations associated with that data.
- object-oriented (OO)**  
Describing a computer system or programming language that supports objects.
- pacing**  
A technique by which a receiving station controls the rate of transmission of a sending station to prevent overrun.
- parallel session**  
In SNA, two or more concurrently active sessions between the same two LUs using different pairs of network addresses. Each session can have independent session parameters.
- PING** In Internet communications, a program used in TCP/IP networks to test the ability to reach destinations by sending the destinations an Internet Control Message Protocol (ICMP) echo request and waiting for a reply.
- partner logical unit (PLU)**  
In SNA, the remote participant in a session.
- partner transaction program**  
The transaction program engaged in an APPC conversation with a local transaction program.
- PLU** See *primary logical unit* and *partner logical unit*.
- port** An endpoint for communication between devices, generally referring to a logical connection. A 16-bit number identifying a particular Transmission Control Protocol (TCP) or User Datagram Protocol (UDP) resource within a given TCP/IP node.
- presentation logic**  
The part of a distributed application that is concerned with the user interface of the application. Compare with *business logic*.
- primary logical unit (PLU)**  
In SNA, the logical unit that contains the primary half-session for a particular logical unit-to-logical unit (LU-to-LU) session. See also *secondary logical unit*.
- protocol boundary**  
The signals and rules governing interactions between two components within a node.
- Resource Access Control Facility (RACF)**  
An IBM licensed program that provides access control by identifying users to the system; verifying users of the system; authorizing access to protected resources; logging detected unauthorized attempts to enter the system; and logging detected accesses to protected resources.
- region** In workload management on CICS Universal Client for Windows, an instance of a CICS server.
- remote procedure call (RPC)**  
A protocol that allows a program on a client computer to run a program on a server.
- request unit (RU)**  
In SNA, a message unit that contains control information such as a request code, or function management (FM) headers, end-user data, or both.

**request/response unit**

A generic term for a request unit or a response unit. See also *request unit* and *response unit*.

**response file**

A file that contains predefined values that is used instead of someone having to enter those values one at a time. See *CID methodology*.

**response unit (RU)**

A message unit that acknowledges a request unit; it may contain prefix information received in a request unit.

**Resource Recovery Services (RRS)**

A z/OS facility that provides two-phase sync point support across participating resource managers.

**rollback**

An operation in a transaction that reverses all the changes made during the unit of work. After the operation is complete, the unit of work is finished. Also known as a backout.

**RU** Request unit. Response unit.

**RPC** See *remote procedure call*.

**SBCS** See *single-byte character set*.

**secondary logical unit (SLU)**

In SNA, the logical unit (LU) that contains the secondary half-session for a particular LU-LU session. Contrast with primary logical unit. See also *logical unit*.

**Secure Sockets Layer (SSL)**

A security protocol that provides communication privacy. SSL enables client/server applications to communicate in a way that is designed to prevent eavesdropping, tampering, and message forgery. SSL applies only to internet protocols, and is not applicable to SNA.

**servlet**

A Java program that runs on a Web server and extends the server's functionality by generating dynamic content in response to Web client requests. Servlets are commonly used to connect databases to the Web.

**session limit**

In SNA, the maximum number of concurrently active logical unit to logical unit (LU-to-LU) sessions that a particular logical unit (LU) can support.

**single-byte character set (SBCS)**

A character set in which each character is represented by 1 byte. Contrast with double-byte character set.

**sign-on capable terminal**

A sign-on capable terminal allows sign-on transactions, either CICS-supplied (CESN) or user-written, to be run. Contrast with sign-on incapable terminal.

**SIT** See *system initialization table*.

**SNA sense data**

An SNA-defined encoding of error information. In SNA, the data sent with a negative response, indicating the reason for the response.

**SNASVCMG mode name**

The SNA service manager mode name. This is the architecturally-defined



mode name identifying sessions on which CNOS is exchanged. Most APPC-providing products predefine SNASVCMG sessions.

**socket** A network communication concept, typically representing a point of connection between a client and a server. A TCP/IP socket will normally combine a host name or IP address, and a port number.

**SSL** See *Secure Sockets Layer (SSL)*.

**SSLight**

An implementation of SSL, written in Java, and no longer supported by CICS Transaction Gateway.

**system initialization table**

A table containing parameters used to start a CICS control region.

**System Management Interface Tool (SMIT)**

An interface tool of the AIX operating system for installing, maintaining, configuring, and diagnosing tasks.

**standard error**

In many workstation-based operating systems, the output stream to which error messages or diagnostic messages are sent.

**subnet**

An interconnected, but independent segment of a network that is identified by its Internet Protocol (IP) address.

**subnet address**

In Internet communications, an extension to the basic IP addressing scheme where a portion of the host address is interpreted as the local network address.

**sync point**

A logical point in the execution of program where the changes made by the program are consistent and complete, and can be committed. The output, which has been held up to that point, is sent to its destination, the input is removed from the message queues, and updates are made available to other applications. When a program terminates abnormally, CICS recovery and restart facilities do not backout updates prior to the last completed sync point.

**Systems Network Architecture (SNA)**

An architecture that describes the logical structure, formats, protocols, and operational sequences for transmitting information units through the networks and also the operational sequences for controlling the configuration and operation of networks.

**System SSL**

An implementation of SSL, no longer supported by CICS Transaction Gateway on z/OS.

**TCP62** SNA logical unit type 62 (LU62) protocol encapsulated in TCP/IP. This allows APPC applications to communicate over a TCP/IP Network without changes to the applications.

**TCP/IP**

See *Transmission Control Protocol/Internet Protocol*.

**TCP/IP load balancing**

The ability to distribute TCP/IP connections across target servers.



**terminal emulation**

The capability of a microcomputer or personal computer to operate as if it were a particular type of terminal linked to a processing unit and to access data. See also *emulator*, *emulation program*.

**thread** A stream of computer instructions that is in control of a process. In some operating systems, a thread is the smallest unit of operation in a process. Several threads can run concurrently, performing different jobs.

**timeout**

A time interval that is allotted for an event to occur or complete before operation is interrupted.

**TLS** See *Transport Layer Security (TLS)*.

**token-ring network**

A local area network that connects devices in a ring topology and allows unidirectional data transmission between devices by a token-passing procedure. A device must receive a token before it can transmit data.

**trace** A record of the processing of a computer program. It exhibits the sequences in which the instructions were processed.

**transaction program**

A program that uses the Advanced Program-to-Program Communications (APPC) application programming interface (API) to communicate with a partner application program on a remote system.

**Transmission Control Protocol/Internet Protocol (TCP/IP)**

An industry-standard, nonproprietary set of communications protocols that provide reliable end-to-end connections between applications over interconnected networks of different types.

**Transport Layer Security (TLS)**

A security protocol that provides communication privacy. TLS enables client/server applications to communicate in a way that is designed to prevent eavesdropping, tampering, and message forgery. TLS applies only to internet protocols, and is not applicable to SNA. TLS is also known as SSL 3.1.

**type 2.0 node**

A node that attaches to a subarea network as a peripheral node and provides a range of end-user services but no intermediate routing services.

**type 2.1 node**

An SNA node that can be configured as an endpoint or intermediate routing node in a network, or as a peripheral node attached to a subarea network.

**Uniform Resource Locator (URL)**

A sequence of characters that represent information resources on a computer or in a network such as the Internet. This sequence of characters includes (a) the abbreviated name of the protocol used to access the information resource and (b) the information used by the protocol to locate the information resource.

**unit of recovery (UR)**

A defined package of work to be performed by the RRS.

**unit of work (UOW)**

A recoverable sequence of operations performed by an application between

two points of consistency. A unit of work begins when a transaction starts or at a user-requested sync point. It ends either at a user-requested sync point or at the end of a transaction.

**user session**

Any APPC session other than a SNASVCMG session.

**verb** A reserved word that expresses an action to be taken by an application programming interface (API), a compiler, or an object program.

In SNA, the general name for a transaction program's request for communication services.

**Web browser**

A software program that sends requests to a Web server and displays the information that the server returns.

**Web server**

A software program that responds to information requests generated by Web browsers.

**wide area network (WAN)**

A network that provides communication services to a geographic area larger than that served by a local area network or a metropolitan area network, and that may use or provide public communication facilities.

**wrapping trace**

A configuration in which the **Maximum Client wrap size** setting is greater than 0. The total size of Client daemon binary trace files is limited to the value specified in the **Maximum Client wrap size** setting. With standard I/O tracing, two files, called `cicscli.bin` and `cicscli.wrp`, are used; each can be up to half the size of the **Maximum Client wrap size**.

**XA requests**

An XA request is any request sent or received by the CICS Transaction Gateway in support of an XA transaction. These requests include the XA commands commit, complete, end, forget, prepare, recover, rollback, and start.

**XA transaction**

A global transaction that adheres to the X/Open standard for distributed transaction processing (DTP.)

---

## Index

### Special characters

(External Call Interface) 1  
(External Presentation Interface) 1  
(External Security Interface) 1  
<install\_path> vii

### Numerics

3270 data streams 75, 80

## A

accessibility 131  
Acrobat 5  
adding features 13  
Adobe 5  
advanced program-to-program communication (APPC) 17  
Advanced Program-to-Program Communication (APPC) 6  
APAR (authorized program analysis report)  
    authorization 109  
    closing 109  
    documentation needed 107  
    process 109  
    submitting 109  
APPC (advanced program-to-program communication) 17  
APPC (Advanced Program-to-Program Communication) 6  
application development tools 5  
APPLID configuration setting 31  
ATI 100

## B

Biasing configuration setting 43  
binary trace formatter 94  
books 127  
bthdinst 10

## C

CCL8024E 99  
CCLCLNT.EXE 100  
ccllog.hlp 92  
cclmeci.dll 89  
cclmepi.dll 89  
cclmsg.hlp 92  
ccloeci.exe 112  
ccloepi.exe 112  
CICS server PTF requirements 5  
CICS servers 4  
CICS servers, communicating with 15  
cicscli command 65  
CICSCLI environment variable 27  
cicscli.bin 93, 94, 95  
cicscli.log 35, 92  
cicscli.trc 93  
cicscli.wrp 94  
CICSCOL environment variable 53  
cicsftrc utility 94  
CICSKEY environment variable 52

cicsprnt command 80  
cicsterm command 75  
CICSTERM.INI 79  
Citrix 5  
client control 2  
Client daemon 65, 66  
Client daemon, restarting 66  
Client daemon, shutting down 66  
Client daemon, starting 65, 66  
Client daemon, stopping 66  
client security 68  
Client trace file configuration setting 46  
Client trace file wrap size (KB) configuration setting 46  
client tracing 67  
client/server connections 7  
code page identifier override configuration setting 34  
code pages 8  
color mapping file 53, 75  
COM libraries 112  
Communicating with CICS servers 15  
communication  
    cicscli 65  
    cicsprnt 80  
    cicsterm 75  
    problems 103  
communication protocols 4  
    APPC 6  
    TCP/IP 6  
Communications Server 18, 105  
compilers 5  
configuration  
    setting the time 27  
configuration file 27  
    referencing 27  
configuration settings  
    Log file 35  
Configuration settings  
    APPLID 31  
    Biasing 43  
    Client trace file 46  
    Client trace file wrap size (KB) 46  
    code page identifier override 34  
    Connection timeout 40  
    Description 38  
    Enable pop-up windows 34  
    Enable the Workload Manager 42  
    Hostname or IP address 39  
    Information log file 36  
    Initial transaction 38  
    Local LU name 40  
    Log terminal installations and deletions 35  
    Manage workload for this program 45  
    Manage workload for this server group 43  
    Maximum buffer size 32  
    Maximum requests 33  
    Maximum servers 32  
    Mode name 41  
    Model terminal definition 38  
    Named pipe name 41  
    Partner LU name 41  
    Port 40

## Configuration settings *(continued)*

- Print command 33
  - Print file 33
  - Region timeout (s) 43
  - Round robin 42
  - Send TCP/IP KeepAlive packets 40
  - Server idle timeout (mins) 39
  - Server name 38
  - Server retry interval 34
  - Terminal exit 32
  - Trace 45
  - Trace settings 93
  - Use Local LU alias name 41
  - Use OEM code page 35
  - Use Partner LU alias name 41
  - Use the same file for information messages 36
  - Use upper case security 39
- Configuration Tool 27
- Configuration Tool help 131
- connecting to CICS servers 66, 69
- Connection timeout configuration setting 40
- Corrective Service Diskette (CSD) 109
- corrective service software 13
- CPMI 103
- CRSR transaction 18
- CSD (Corrective Service Diskette) 109
- ctgcfg command 27
- ctgjava command 26
- customizing
- keyboard 51
  - screen colors 53

## D

### data conversion

- Arabic conversions 117
  - Baltic Rim conversions 117
  - Cyrillic conversions 117
  - Estonian conversions 118
  - Greek conversions 118
  - Hebrew conversions 119
  - Japanese conversions 119
  - Korean conversions 120
  - Latin-1 conversions 121
  - Latin-2 conversions 122
  - Latin-5 conversions 123
  - Latin-9 conversions 121
  - simplified Chinese conversions 123
  - traditional Chinese conversions 124
  - Vietnamese conversions 124
- Data conversion 24
- default installation location vii
- defining 3270 printer terminal emulator characteristics 80
- defining 3270 terminal emulator characteristics 75
- Description configuration setting 38
- development tools 5
- diagnosing common problems 98
- diagnostic tools
- APING 104
- disability 131
- disabling a pop-up window 55
- disabling the display of messages 68
- disabling the display of pop-up messages 68
- displaying command syntax 69
- DLL 112
- documentation 127
- documenting problems 107

## E

- Enable pop-up windows configuration setting 34
- Enable the Workload Manager configuration setting 42
- enabling a pop-up window 55
- enabling the display of pop-up messages 68
- environment variables
- CICSCLI 27
  - CICSCOL 53
  - CICSKEY 52
  - PATH 12, 13
- error log
- cicscli.log 92
  - client error log 92
  - server error log 103
- Error log
- IBM Communications Server 105
- euro support 34, 35
- EXCI (external CICS interface) 1
- EXEC CICS RETURN TRANSID IMMEDIATE command 76, 81
- External Call Interface (ECI) 1
- external CICS interface (EXCI) 1
- External Presentation Interface (EPI) 1
- External Security Interface (ESI) 1

## F

- font selection on terminal emulators 79
- fonts
- selecting on terminal emulators 79
- free memory 32

## G

- Getsense 105
- glossary of terms and abbreviations 137

## H

- hangs 102
- hardware requirements 3
- help 131
- Host Integration Server 21
- Hostname or IP address configuration setting 39

## I

- IBM Communications Server 105
- Impersonate a client after authentication 12, 13, 99
- Information log file configuration setting 36
- initial transaction 75, 80
- Initial transaction configuration setting 38
- initialization files
- cicscol.inicicscol.ini 53
  - cicskey.inicicskey.ini 52
  - CICSTERM.INI 79
- install\_path vii
- installation 9
- adding features 13
  - complete installation 9
  - custom installation 9
  - default location vii
  - path vii
  - removing features 13
  - silent installation 11

installation (*continued*)  
  types of installation 9  
installation path vii

## J

Java  
  installing 12  
Java virtual machine (JVM) 26  
JRE  
  installing 12  
JVM  
  installing 12  
JVM (Java virtual machine) 26

## K

keyboard 132  
keyboard mapping file 51, 75

## L

listing connected servers 68  
Local LU name configuration setting 40  
Local Named Pipe protocol 7  
Log file configuration setting 35  
Log terminal installations and deletions configuration setting 35  
logical unit (LU) 17, 18  
Logical units of work  
  extending 63  
LU6.2 6

## M

Manage workload for this program configuration setting 45  
Manage workload for this server group configuration setting 43  
MAXACTIVE 103  
Maximum buffer size configuration setting 32  
Maximum requests configuration setting 33  
Maximum servers configuration setting 32  
MAXTASKS 103  
memory mapped tracing 67, 94  
memory requirements 32  
messages 92  
messages, disabling the display of 68  
migration vii  
mode definitions, APPC 17, 18  
Mode name configuration setting 41  
Model terminal definition configuration setting 38

## N

Named pipe name configuration setting 41  
Named Pipes protocol 24  
network drives, problems with 12, 13  
Network Provider Interface 10  
non-existent directories 12, 13  
NPI 10

## O

online help, for end user messages, 92  
online help, for trace and log messages 92  
operating systems 3  
options  
  cicscli command 69  
  cicsprnt command 81  
  cicsterm command 77  
out-of-process libraries 112

## P

Partner LU name configuration setting 41  
password expiry management (PEM) 1, 59  
PATH environment variable 12, 13  
PEM (password expiry management) 1, 59  
performance  
  monitoring 64  
  other system factorssystem considerations 63  
  tracing 63  
planning 3  
PMR (Problem Management Record) 106  
pop-up messages, disabling the display of 68  
pop-up messages, enabling the display of 68  
Port configuration setting 40  
Print command configuration setting 33  
Print file configuration setting 33  
print file, processing 75, 80  
print terminal emulator, starting 80  
printer support 2  
printer terminal emulator characteristics, defining 80  
problem determination 91, 103  
  diagnosing common problems 98  
  messages 92  
  preliminary checks 91  
  tracing 93  
Problem Management Record (PMR) 106  
problem reporting  
  documenting problems 107  
  information needed 108  
  support organization 106  
problems, communication 103  
program support 106  
PTF (Program Temporary Fix) 109  
publications 127

## R

README file 3  
Region timeout (s) configuration setting 43  
removing features 13  
requirements, hardware 3  
restrictions, using CICS servers 7  
RETAIN database 106  
RETAIN problem management system  
  APARs 109  
  Problem Management Record 106  
roaming user support 79  
Round robin configuration setting 42

## S

screen readers 5  
security 39  
  External Security Interface (ESI) 1

- security (*continued*)
  - password expiry management (PEM) 1
- Send TCP/IP KeepAlive packets configuration setting 40
- Sense codes 105
- Server idle timeout (mins) configuration setting 39
- Server name configuration setting 38
- Server retry interval configuration setting 34
- servers
  - CICS 4
- servers, listing 68
- shortcut keys 132
- sign-on capable terminals 5
- silent installation 11
- SNA 4
  - checking configuration 104
  - configuring 17
- SNA (Systems Network Architecture) 6
- sna error log 101
- starting a 3270 print terminal emulator 80
- starting a 3270 terminal emulator 75
- stopping a terminal emulator 76
- support organization
  - program support 106
  - sending documentation to 108
- Systems Network Architecture (SNA) 6

## T

- TCP/IP (Transmission Control Protocol/Internet Protocol) 5, 6, 15
- TCP/IP communication problems 99
- terminal emulation 1
- terminal emulator
  - preferences 79
- terminal emulator characteristics, defining 75
- terminal emulator, starting 75
- terminal emulator, stopping 76
- Terminal exit configuration setting 32
- the system locks up 102
- tools, application development 5
- Trace configuration setting 45
- Trace settings
  - Configuration Tool 93
- trace, wrapping 94
- tracing 93
- tracing, memory mapped 67, 94
- transaction programs (TP), APPC 17, 18
- transmission control protocol/internet protocol (TCP/IP) 6
- Transmission Control Protocol/Internet Protocol (TCP/IP) 6, 15
- traps 101
- troubleshooting
  - hangs 102
  - starting clients and terminals 99
  - traps 101

## U

- uninstalling 14
- updating
  - installed software 13
- Use Local LU alias name configuration setting 41
- Use OEM code page configuration setting 35
- Use Partner LU alias name configuration setting 41
- Use the same file for information messages configuration setting 36

- Use upper case security configuration setting 39
- Use Windows credentials for security 10
- user rights 12, 13, 99

## V

- VTAM
  - buffer trace 104

## W

- Windows secured environment 35
- WINSOCK 100
- Workload management 2
- Workload Manager 28, 41
  - biasing algorithm 88
  - installation 90
  - overview 85
  - port 85
  - programs 85
  - regions 85
  - round-robin algorithm 88
  - server instance 85
  - TCP/IP port 85
  - workload management 85
- wrapping trace 94

---

## Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10504-1785  
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106, Japan

**The following paragraph does not apply in the United Kingdom or any other country where such provisions are inconsistent with local law:**

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the information. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this information at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created

programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact IBM United Kingdom Laboratories, MP151, Hursley Park, Winchester, Hampshire, England, SO21 2JN. Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Programming License Agreement, or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

---

## Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, or other countries, or both:

AIX  
AnyNet  
AS/400  
CICS  
CICS/400  
CICS/ESA  
CICS/VSE  
DB2  
Domino  
Hummingbird  
IBM  
IBM  
IBMLink  
IMS  
iSeries  
MQSeries  
MVS  
MVS/ESA  
Notes  
OS/2  
OS/390  
POWER  
pSeries  
RACF  
Redbooks  
RETAIN  
RMF  
RS/6000  
SAA  
SP2  
System/390  
Tivoli  
TXSeries



VisualAge  
VSE/ESA  
VTAM  
WebSphere  
z/OS  
zSeries

Microsoft, Windows, Windows NT<sup>®</sup>, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Intel, Intel Inside<sup>®</sup> (logos), MMX and Pentium<sup>®</sup> are trademarks of Intel Corporation in the United States, other countries, or both.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Other company, product or service names may be trademarks or service marks of others.



---

## Sending your comments to IBM

If you especially like or dislike anything about this book, use one of the methods listed below to send your comments to IBM.

Feel free to comment on what you regard as specific errors or omissions, and on the accuracy, organization, subject matter, or completeness of this book.

Limit your comments to the information in this book and the way in which the information is presented.

To ask questions, make comments about the functions of IBM products or systems, or to request additional publications, contact your IBM representative or your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate, without incurring any obligation to you.

You can send your comments to IBM in any of the following ways:

- By mail, to this address:  
User Technologies Department (MP095)  
IBM United Kingdom Laboratories  
Hursley Park  
WINCHESTER,  
Hampshire  
SO21 2JN  
United Kingdom
- By fax:
  - +44 1962 842327 (if you are outside the UK)
  - 01962 842327 (if you are in the UK)
- Electronically, use the appropriate network ID:
  - IBM Mail Exchange: GBIBM2Q9 at IBMMAIL
  - IBMLink<sup>™</sup>: HURSLEY(IDRCF)
  - Internet: idrcf@hursley.ibm.com

Whichever you use, ensure that you include:

- The publication title and order number
- The topic to which your comment applies
- Your name and address/telephone number/fax number/network ID.







Program Number: 5724-J09

SC34-6756-02



Spine information:



CICS Universal Client

Windows Client Administration

Version 7.1