

# **Connect:Direct® HP NonStop**

## **User Guide and Reference**

**Version 3.5**

**Connect:Direct HP NonStop User Guide and Reference  
Version 3.5  
First Edition**

(c) Copyright 1998, 2008 Sterling Commerce, Inc. All rights reserved. Additional copyright information is located at the end of the release notes.

**STERLING COMMERCE SOFTWARE**

**\*\*\*TRADE SECRET NOTICE\*\*\***

THE CONNECT:DIRECT SOFTWARE ("STERLING COMMERCE SOFTWARE") IS THE CONFIDENTIAL AND TRADE SECRET PROPERTY OF STERLING COMMERCE, INC., ITS AFFILIATED COMPANIES OR ITS OR THEIR LICENSORS, AND IS PROVIDED UNDER THE TERMS OF A LICENSE AGREEMENT. NO DUPLICATION OR DISCLOSURE WITHOUT PRIOR WRITTEN PERMISSION. RESTRICTED RIGHTS.

This documentation, the Sterling Commerce Software it describes, and the information and know-how they contain constitute the proprietary, confidential and valuable trade secret information of Sterling Commerce, Inc., its affiliated companies or its or their licensors, and may not be used for any unauthorized purpose, or disclosed to others without the prior written permission of the applicable Sterling Commerce entity. This documentation and the Sterling Commerce Software that it describes have been provided pursuant to a license agreement that contains prohibitions against and/or restrictions on their copying, modification and use. Duplication, in whole or in part, if and when permitted, shall bear this notice and the Sterling Commerce, Inc. copyright notice. As and when provided to any governmental entity, government contractor or subcontractor subject to the FARs, this documentation is provided with RESTRICTED RIGHTS under Title 48 52.227-19. Further, as and when provided to any governmental entity, government contractor or subcontractor subject to DFARS, this documentation and the Sterling Commerce Software it describes are provided pursuant to the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation.

These terms of use shall be governed by the laws of the State of Ohio, USA, without regard to its conflict of laws provisions. If you are accessing the Sterling Commerce Software under an executed agreement, then nothing in these terms and conditions supersedes or modifies the executed agreement.

Where any of the Sterling Commerce Software or Third Party Software is used, duplicated or disclosed by or to the United States government or a government contractor or subcontractor, it is provided with RESTRICTED RIGHTS as defined in Title 48 CFR 52.227-19 and is subject to the following: Title 48 CFR 2.101, 52.227-19, 227.7201 through 227.7202-4, FAR 52.227-14, and FAR 52.227-19(c)(1-2) and (6/87), and where applicable, the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation including DFAR 252.227-7013, DFAR 252,227-7014, DFAR 252.227-7015 and DFAR 252.227-7018, all as applicable.

The Sterling Commerce Software and the related documentation are licensed either "AS IS" or with a limited warranty, as described in the Sterling Commerce license agreement. Other than any limited warranties provided, NO OTHER WARRANTY IS EXPRESSED AND NONE SHALL BE IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR USE OR FOR A PARTICULAR PURPOSE. The applicable Sterling Commerce entity reserves the right to revise this publication from time to time and to make changes in the content hereof without the obligation to notify any person or entity of such revisions or changes.

Connect:Direct is a registered trademark of Sterling Commerce. Connect:Enterprise is a registered trademark of Sterling Commerce, U.S. Patent Number 5,734,820. All Third Party Software names are trademarks or registered trademarks of their respective companies. All other brand or product names are trademarks or registered trademarks of their respective companies.

---

Sterling Commerce, Inc.  
4600 Lakehurst Court Dublin, OH 43016-2000 \*  
614/793-7000

---

# Contents

## Preface

Chapter Overview.....	11
-----------------------	----

## Chapter 1 About Connect:Direct HP NonStop

Connect:Direct HP NonStop Components .....	13
Automated Installation and Management System.....	15
Connect:Direct HP NonStop Concepts .....	16
Processes .....	16
Transmission Control Queue.....	16
Network Map.....	16
Defining Domain Nodes to Manage Inbound TCP/IP Connections .....	17
Using Session Redirection for Outbound TCP/IP Connections.....	17
Connect:Direct Secure+ Option .....	19
Sterling Control Center .....	19
Connect:Direct Browser User Interface .....	21
Interfacing with Sterling Control Center or Browser User Interface .....	22
Commands.....	22
User and Administrator Commands.....	23
Environment Commands.....	24
Message Commands .....	25
Flow of Connect:Direct HP NonStop Operations .....	25

## Chapter 2 Using Connect:Direct HP NonStop

Running Connect:Direct HP NonStop.....	27
Changing Ownership of NDMCOM.....	27
Changing the Default Server Process Name .....	28
Changing the Command Prompt.....	28
Issuing Commands through NDMCOM .....	28
Running NDMCOM in Interactive Mode .....	29
Parameters .....	29
Example .....	29
Running NDMCOM in Background Mode.....	30
Parameters .....	30
Example .....	30
Using Connect:Direct HP NonStop Macros.....	30
Macros for Interactive Mode.....	31
Macros for Background Mode .....	31
Implementing Macros .....	31

Connect:Direct HP NonStop Process Statements .....	32
Connect:Direct HP NonStop Operation .....	33
Submitting the Process to the TCQ .....	33
Monitoring the Process Status in the TCQ .....	34
Determining the Outcome of the Process .....	34
Exiting NDMCOM .....	34
Accessing the Message File .....	34
Displaying Messages .....	35
Printing Messages .....	35

### **Chapter 3      Queuing Processes**

Understanding the Transmission Control Queue .....	37
Managing Processes in the TCQ .....	38
Scheduling Connect:Direct HP NonStop Activity .....	38

### **Chapter 4      Controlling the Environment**

Recalling and Reissuing Commands .....	41
Format .....	41
Required Parameters .....	41
Optional Parameters .....	42
Examples .....	42
Invoking the HP NonStop Text Editor (TEDIT) .....	42
Format .....	42
Required Parameters .....	42
Optional Parameters .....	43
Examples .....	43
Exiting NDMCOM .....	43
Format .....	43
Required Parameters .....	43
Optional Parameters .....	44
Examples .....	44
Changing and Reissuing Commands .....	44
Format .....	44
Required Parameters .....	44
Optional Parameters .....	44
Examples .....	45
Accessing the Connect:Direct HP NonStop Help Facility .....	45
Format .....	45
Required Parameters .....	46
Optional Parameters .....	46
Examples .....	46
Displaying Previous Commands .....	47
Format .....	47
Required Parameters .....	47
Optional Parameters .....	47
Examples .....	47

Displaying Edit File Contents .....	48
Format .....	48
Required Parameters .....	48
Optional Parameters .....	48
Examples .....	48
Signing On as Another User within NDMCOM .....	48
Format .....	49
Required Parameters .....	49
Optional Parameters .....	49
Examples .....	49
Executing the Obey Command .....	50
Format .....	50
Required Parameters .....	50
Optional Parameters .....	51
Examples .....	51
Defining the Default Obey Volume .....	52
Format .....	52
Required Parameters .....	52
Optional Parameters .....	52
Examples .....	53
Opening the Server Process .....	53
Format .....	53
Required Parameters .....	53
Optional Parameters .....	53
Examples .....	54
Changing the Output File .....	54
Format .....	54
Required Parameters .....	54
Optional Parameter .....	54
Examples .....	55
Defining Print File Names .....	55
Format .....	55
Required Parameter .....	55
Optional Parameters .....	55
Examples .....	56
Defining the Default Volume For Expansion of Process File Names .....	56
Format .....	56
Required Parameters .....	56
Optional Parameters .....	56
Examples .....	57
Executing Programs without Exiting NDMCOM .....	57
Format .....	57
Required Parameter .....	57
Optional Parameters .....	58
Examples .....	58
Managing Symbols .....	58

Inserting Symbols.....	59
Format .....	59
Required Parameter.....	59
Optional Parameter.....	59
Examples.....	59
Deleting Symbols .....	60
Format .....	60
Required Parameter.....	60
Optional Parameters.....	60
Examples.....	60
Examining Symbols .....	61
Format .....	61
Required Parameters .....	61
Optional Parameters.....	61
Examples.....	62

## Chapter 5 Viewing System Information

Displaying the Status of Connect:Direct HP NonStop Components .....	63
Format .....	63
Required Parameters .....	64
Optional Parameters.....	64
Examples.....	64
Displaying Logging Information.....	66
Format .....	67
Required Parameters .....	67
Optional Parameters.....	67
Examples.....	67
Monitoring Statistics File Information.....	68
Format .....	68
Required Parameters .....	68
Optional Parameters.....	69
Examples.....	69
Displaying Initialization Parameters .....	71
Format .....	71
Required Parameters .....	71
Optional Parameters.....	71
Saving Changes to the Initialization Parameters File .....	71
Examples.....	72
Displaying the Current Connect:Direct HP NonStop Environment.....	73
Format .....	73
Required Parameters .....	73
Optional Parameters.....	73
Examples.....	74
Obtaining the Current System Time.....	75
Format .....	75
Required Parameters .....	75
Optional Parameters.....	75
Example.....	75

Obtaining the Current NDMCOM Version .....	76
Format .....	76
Required Parameters .....	76
Optional Parameters .....	76
Example .....	76
Defining the Current Volume .....	76
Format .....	77
Required Parameters .....	77
Optional Parameter .....	77
Example .....	77

## Chapter 6 Managing Processes

Changing Processes .....	79
Format .....	79
Required Parameters .....	80
Optional Parameters .....	80
Date Formats .....	81
Examples .....	82
Deleting Processes .....	83
Format .....	83
Required Parameters .....	84
Optional Parameters .....	84
Example .....	84
Delete Processes by PNAME .....	84
Delete Processes by SNODE .....	85
Deleting an Executing Process .....	85
Format .....	85
Required Parameters .....	85
Optional Parameter .....	86
Example .....	86
Determining the Number of the Last Submitted Process .....	86
Format .....	86
Required Parameters .....	86
Optional Parameters .....	87
Example .....	87
Resetting the Last Process Number in the TCQ .....	87
Format .....	87
Required Parameters .....	87
Optional Parameters .....	87
Example .....	88
Monitoring Processes .....	88
Format .....	88
Required Parameters .....	88
Optional Parameters .....	89
Example .....	90

Script Source Recovery.....	90
Short Report.....	90
Detailed Report.....	91
Submitting a Process for Execution.....	93
Format.....	93
Required Parameters.....	93
Optional Parameters.....	94
Examples.....	96
Moving an Executing Process to the Hold Queue.....	97
Format.....	97
Required Parameters.....	97
Optional Parameter.....	98
Examples.....	98

## Chapter 7 Viewing System Files

Referencing the Network Map.....	99
Format.....	99
Required Parameters.....	99
Optional Parameters.....	100
Examples.....	101
Examining User Records in the Security File.....	103
Format.....	103
Required Parameters.....	103
Optional Parameters.....	103
Examples.....	104
Examining Statistics Records.....	104
Format.....	105
Required Parameters.....	105
Optional Parameters.....	105
Examples.....	107
PROCESS-SUBMIT Record.....	111
PROCESS-PROCSTART Record.....	111
PROCESS-STEPSTART Record.....	112
PROCESS-STEPEND Record.....	113
PROCESS-STEPSTART Record.....	114
PROCESS-STEPEND Record.....	115
MESSAGE-MSG Record.....	116
PROCESS-PROCEND Record.....	116
Examining Type File Records.....	117
Format.....	117
Required Parameters.....	117
Optional Parameters.....	118
Examples.....	118
Examining Authorization File Records.....	119
Format.....	119
Required Parameters.....	119
Optional Parameters.....	119
Examples.....	120



**Glossary**

**Index**



---

# Preface

The *Connect:Direct HP NonStop User Guide and Reference* is for programmers and network operations staff who use Connect:Direct HP NonStop.

Read the first three chapters in the book to gain the general knowledge required to use Connect:Direct HP NonStop. These chapters introduce basic product components, general concepts, and the tasks you can perform using the command and Process languages. Then, refer to command syntax and parameter descriptions for the particular task you want to perform. The commands are organized alphabetically under the following functions: controlling the environment, viewing system information, managing processes, viewing system files, and transferring multiple files.

This User Guide and Reference assumes knowledge of the HP NonStop operating system, its applications, network, and environment. If you are not familiar with the HP NonStop operating system, refer to the HP NonStop library of manuals.

---

## Chapter Overview

The organization of the *Connect:Direct HP NonStop User Guide and Reference* follows:

- ❖ Chapter 1, *About Connect:Direct HP NonStop*, provides general information about the product and describes how Connect:Direct HP NonStop works.
- ❖ Chapter 2, *Using Connect:Direct HP NonStop*, presents basic information you need to begin working with Connect:Direct HP NonStop.
- ❖ Chapter 3, *Queuing Processes*, describes the Transmission Control Queue and the commands you use to manipulate Processes in the queue.
- ❖ Chapter 4, *Controlling the Environment*, details the Connect:Direct HP NonStop environment commands such as EDIT, LOGON, PRINTER, and RUN.
- ❖ Chapter 5, *Viewing System Information*, describes the commands used to access system information, such as status, time, version, initialization parameters, and volume.
- ❖ Chapter 6, *Managing Processes*, describes the commands used to control Processes.
- ❖ Chapter 7, *Viewing System Files*, describes the commands used to view certain system files, such as the network map, security, and statistics files.
- ❖ *Glossary*, defines Connect:Direct HP NonStop terms used in the manual.



---

# About Connect:Direct HP NonStop


Connect:Direct HP NonStop links technologies and moves all types of information between networked systems and computers. It manages high-performance transfers by providing features such as automation, reliability, efficient use of resources, application integration, and ease of use. Connect:Direct HP NonStop software offers choices in communications protocols, hardware platforms, and operating systems. It provides the flexibility to move information among mainframes, midrange systems, desktop systems, and LAN-based workstations.

---

## Connect:Direct HP NonStop Components

Connect:Direct HP NonStop runs as an application on the HP NonStop operating system. The product components interact to execute the Process statements and commands submitted through the user interface.

The following figure illustrates the basic components of Connect:Direct HP NonStop: Monitor (NDMMON), Server (NDMSRVR), User Interface (NDMCOM), Sterling Control Center and Browser User Interface (NDMAPI), Session Manager (NDMSMGR), I/O Exits (I/O EXIT), Statistics Deletion Program (NDMSTDL), Statistics Utility Program (STUTIL), Application Programming Interface (API) Manager (NDMAPI), and Connect:Direct HP NonStop Spooler Option (NDMSPL). Brief descriptions of each component follow the sample network configuration.



Component	Description
Monitor	The monitor (NDMMON) is a nonstop process that creates and monitors the Connect:Direct HP NonStop server (NDMSRVR) process. For NDMMON startup instructions, refer to the <i>Connect:Direct HP NonStop Installation Guide</i> .
Server	The Connect:Direct HP NonStop server (NDMSRVR) process manages: <ul style="list-style-type: none"> <li>- Command requests</li> <li>- Communication with the session manager</li> <li>- Session establishment requests for TCP/IP</li> </ul> <b>Note:</b> If the NDMSRVR process ends abnormally or the CPU executing the NDMSRVR process fails, NDMMON creates a new NDMSRVR process, retaining the original NDMSRVR process name and parameters.
User Interface	NDMCOM is the user interface with NDMSRVR. Use NDMCOM, the command-line interface, to issue Connect:Direct HP NonStop commands and to change and configure the Connect:Direct HP NonStop environment.

Component	Description
Session Manager	<p>The Connect:Direct HP NonStop session manager (NDMSMGR) module establishes sessions and transfers data between the local and adjacent nodes. The application can be configured to start session managers at initialization, or you can start them manually using the MODIFY command. If you define dynamic LUs for TCP/IP connectivity, NDMSRVR starts session managers as needed. You cannot issue the MODIFY command to start dynamic session managers.</p> <p>The figure on the previous page shows six session managers, two of which are communicating across SNAX sessions, two across TCP/IP, and one across ICE. One session manager is using the PNODE=SNODE facility.</p>
API Manager	<p>The Connect:Direct HP NonStop API Manager (NDMAPI) module provides an interface for browser(s) and Sterling Control Center. To define an API Manager, see the instructions on the INSERT NETMAP AMGR command in the <i>Connect:Direct HP NonStop Administration Guide</i>.</p>
I/O Exits	<p>I/O exit support enables the user-written programs to serve as application interfaces for Connect:Direct HP NonStop data transfers. I/O exits permit manipulation of data formats and database architectures not currently supported by Connect:Direct HP NonStop. For transfers (COPY), Connect:Direct HP NonStop supports direct access only to Enscribe and Spool files. I/O exit support enables user-written programs to access non-supported databases, such as SQL, and manipulate data during a COPY step.</p>
Statistics Deletion Program	<p>The statistics deletion program (NDMSTDL) ensures that sufficient space is available to write statistics records in the statistics files. NDMSTDL deletes records from the Connect:Direct HP NonStop statistics file based on user-specified deletion criteria and maximum percentage of file capacity. For instructions on using NDMSTDL, refer to <i>Optimizing Performance</i> in the <i>Connect:Direct HP NonStop Administration Guide</i>.</p>
Statistics Utility Program	<p>The statistics utility program (STUTIL) analyzes the statistics files to determine how much space is available. Connect:Direct HP NonStop returns this information to the server for determination on when to run NDMSTDL.</p>
Application Program Interface	<p>An Application Program Interface (API) is a user-written application that communicates with NDMCOM. Refer to the <i>Connect:Direct HP NonStop Management Programming Guide</i> for details on creating and using an API.</p>
Connect:Direct HP NonStop Spooler Option	<p>The Connect:Direct HP NonStop Spooler option permits an installation to transfer spooler jobs automatically from an HP NonStop node to a file on an adjacent node.</p> <p>For the information you need to install, configure, and run the Connect:Direct HP NonStop Spooler option, refer to Connect:Direct HP NonStop <i>Spooler Option</i> in the <i>Connect:Direct HP NonStop Administration Guide</i>.</p>

## Automated Installation and Management System

The Automated Installation and Management System (AIMS) is a full-screen, block-mode interface for installing, configuring, and starting Connect:Direct HP NonStop.

AIMS is a menu-driven system that collects information about your node and the nodes you are communicating with and guides you through the installation. Performing the menu options in the displayed numerical order expedites installation. Each user-input screen has a Help feature, which describes the entry fields for the screen. Throughout the AIMS procedure, messages displayed on the bottom line of the screen inform you of the status of the procedure and indicate errors. For more information on AIMS, refer to *Connect:Direct HP NonStop Installation Guide*.

---

## Connect:Direct HP NonStop Concepts

This section introduces certain concepts and definitions important to understanding user operations.

### Processes

The Process language provides instructions for transferring files, running programs, submitting jobs on the adjacent node, and altering the sequence of Process step execution. You can include one or more steps in a Process.

A Process consists of a Process definition statement (PROCESS statement) and one or more additional statements. Parameters further qualify Process instructions. For more information, including sample Processes, see the Processes web site at <http://www.sterlingcommerce.com/documentation/processes/processhome.html>.

### Transmission Control Queue

The Transmission Control Queue (TCQ) controls Process execution as Connect:Direct HP NonStop operates. Connect:Direct HP NonStop stores submitted Processes in the TCQ which is divided into logical queues.

Connect:Direct HP NonStop places the Process in the appropriate queue based on Process statement parameters that affect scheduling. Examples of such parameters are the HOLD, RETAIN, and STARTT parameters.

Connect:Direct HP NonStop selects Processes in a first-in first-out manner for execution in Process class and priority as sessions are available. You can access the queues and manipulate the Processes through Connect:Direct HP NonStop commands.

Refer to *Queuing Processes* in the *Connect:Direct HP NonStop User Guide and Reference* for a discussion of the following topics:

- ❖ Understanding the Transmission Control Queue
- ❖ Managing Processes in the TCQ
- ❖ Scheduling Connect:Direct HP NonStop Activity

### Network Map

The network map file defines the nodes with which Connect:Direct HP NonStop can communicate. The network map includes a local node record and one or more adjacent nodes, logical units (LUs), API managers (AMGRs), and logmode records.

The local node is the logical name for the node on which you installed Connect:Direct HP NonStop. An adjacent node is the node definition for a remote site. LUs provide communication between the HP NonStop system (local node) and adjacent nodes. Logmode records define the session protocol for an SNA HP NonStop LU, and are only used when the local LU is configured as the primary LU (PLU).

In addition to creating explicit adjacent node records for the individual nodes with which you communicate, you can also define domain node adjacent node records for communications with large networks of Connect:Direct nodes, including Connect:Direct/Plex systems, in a TCP domain. These special-purpose adjacent node records simplify your network map and increase efficiency.



## Defining Domain Nodes to Manage Inbound TCP/IP Connections


The domain node feature enables you to manage inbound connection requests to the Connect:Direct HP NonStop node from IP addresses that are not explicitly configured in the network map, for example from multiple Connect:Direct/Server processes under the direction of the Connect:Direct/Plex Manager. Using the domain node feature, you can create an adjacent node entry of the type NDM.DOMAIN for any TCP/IP domain containing one or more Connect:Direct nodes and define a range of IP addresses instead of defining an adjacent node record for each remote connection. When the Connect:Direct HP NonStop server receives a connection request, it first attempts to match the originating IP address with a specific adjacent node entry in the network map. If this search fails, the server searches for adjacent nodes of the type NDM.DOMAIN and then uses the IPMASK parameter as a template to identify a node that best fits the mask's pattern. Without a domain node record, each Connect:Direct/Plex Server or remote node must have an adjacent node record in the Connect:Direct HP NonStop network map to initiate connections.

The DOMAINSERVER and the NETMAPCHECK initialization parameters are associated with this feature. You must set the DOMAINSERVER global initialization parameter to Yes before you can define a domain node.

You can use the NETMAPCHECK initialization parameter and Connect:Direct Secure+ Option to secure the TCP/IP sessions. See *Connect:Direct Secure+ Option* in this chapter for more information about Connect:Direct Secure+ Option and *Planning the Installation* in the *Connect:Direct HP NonStop Installation Guide* for a discussion about how the security options function in your environment.

## Using Session Redirection for Outbound TCP/IP Connections

Connect:Direct HP NonStop supports session redirection for outbound connections to a Connect:Direct/Plex system. As illustrated in the following figure, a Connect:Direct/Plex system is a Connect:Direct for OS/390 (zOS) system consisting of a Connect:Direct/Plex Manager and one or more Connect:Direct/Servers in a TCP/IP environment. Connection requests from the Connect:Direct HP NonStop node to the Connect:Direct/Plex system are routed to the Connect:Direct/Plex Manager, which redirects the connection request to the appropriate, available Connect:Direct/Plex Server process. Redirecting communications sessions across multiple Connect:Direct Server processes simplifies the network map, facilitates load-balancing, and ensures continuous, efficient use of resources.



You can create adjacent node records either through AIMS or with individual network map commands. Use the following table as a guide to the tools and the parameters used to create adjacent node records:

Task	Reference
Planning your network map to use domain nodes and session redirection	<i>Defining Adjacent Node Records for TCP/IP Connections in Planning the Installation in the Connect:Direct HP NonStop Installation Guide</i>
Setting the DOMAINSERVER and NETMAPCHECK initialization parameters	<i>Setting Initialization Parameters in Installing and Configuring Connect:Direct HP NonStop in the Connect:Direct HP NonStop Installation Guide</i>
Assessing your security options	<i>Defining Adjacent Node Records for TCP/IP Connections in Planning the Installation in the Connect:Direct HP NonStop Installation Guide</i>
Creating the worksheets for your adjacent node records in the network map	<i>Preparing to Define the Network Map through AIMS in Planning the Installation in the Connect:Direct HP NonStop Installation Guide</i>
Defining the network map through AIMS	<i>Configuring the Network Map in Installing and Configuring Connect:Direct HP NonStop in the Connect:Direct HP NonStop Installation Guide</i>
Using individual commands, syntax, and parameters to define and maintain the network map	<i>Defining and Maintaining the Network Map in the Connect:Direct HP NonStop Administration Guide</i>


## Connect:Direct Secure+ Option

The client authentication certificates and multiple cipher suites offered by Connect:Direct Secure+ Option provide the confidence that your organization can use public networks knowing that data is being reliably transferred from a known source and can only be read by the intended recipient. To use Connect:Direct Secure+ Option for communications with remote nodes, you must have node records in the Connect:Direct Secure+ Option parameters file (SPNODES) that duplicate the adjacent node records in the Connect:Direct HP NonStop network map. You can populate the Connect:Direct Secure+ Option parameters file from entries defined in an existing network map using the Sync with NetMap function. For more information about populating the Connect:Direct Secure+ Option parameters file (SPNODES) and configuring nodes for Connect:Direct Secure+ Option, refer to the *Connect:Direct Secure+ Option HP NonStop Implementation Guide*. For information about using Connect:Direct Secure+ Option with domain nodes, see *Planning the Installation* in the *Connect:Direct HP NonStop Installation Guide*.

## Sterling Control Center

Sterling Control Center is a centralized management system that provides operations personnel with continuous enterprise-wide business activity monitoring. Control Center lets you monitor these types of servers:

- ❖ Connect:Direct for z/OS
- ❖ Connect:Direct for UNIX
- ❖ Connect:Direct for Windows
- ❖ Connect:Direct HP NonStop
- ❖ Connect:Direct Select
- ❖ Connect:Direct for OS/400 (iSeries)
- ❖ Connect:Enterprise for z/OS
- ❖ Connect:Enterprise for UNIX
- ❖ Gentran Integration Suite (GIS) servers (including GIS clusters)
- ❖ FTP servers that use xferlog format



Sterling Control Center enables you to:

- ❖ Manage Connect:Direct for UNIX, Windows, or z/OS servers. You can manage these types of configuration objects:
  - ◆ Functional authorities
  - ◆ Initialization parameters
  - ◆ Netmap nodes
  - ◆ Netmap modes
  - ◆ Netmap communication paths
  - ◆ Secure+ nodes
  - ◆ Secure+ key certificates
  - ◆ Secure+ trusted certificates
  - ◆ Secure+ cipher suites
  - ◆ User proxies

You can also compare versions of the above configuration objects for a given server, do searches on configuration objects, make templates to simplify the creation of new configuration objects, and do audits of changes to configuration objects. (For more on using Control Center to configure servers, see the *Sterling Control Center Configuration Management Guide*.)

- ❖ Monitor multiple servers
  - ◆ Group individual servers into server groups for a single view of system-wide activity. Group server groups into larger groups, and display a list view of servers and server groups.
  - ◆ View status and statistics on active or completed processing

- ♦ Suspend, release, and handle Connect:Direct Processes on z/OS, Windows, HP NonStop, and UNIX platforms
- ♦ Stop Connect:Direct servers on z/OS, Windows, HP NonStop, OS/400 (iSeries), and UNIX platforms
- ♦ Pause and resume monitoring for a Connect:Direct server
- ❖ Monitor service levels
  - ♦ View information about active and completed Processes across servers within your network
  - ♦ Receive notification of data delivery events that occur or do not occur as scheduled
  - ♦ Define rules based on processing criteria that can generate an alert, send an e-mail notification, generate a Simple Network Management Protocol (SNMP) trap to an Enterprise Systems Manager (ESM), run a system command, or issue a Connect:Direct server command
  - ♦ Monitor for alerts about conditions such as a server failure or a Process that starts late
  - ♦ Create service level criteria (SLCs) that define processing schedules, monitor Processes and file transfers for compliance with the processing schedules, and generate alerts when schedules are not met
- ❖ Analyze key operational metrics through reports to document and analyze processing activity
- ❖ Create customized reports based on criteria you define, and schedule the reports to run and be delivered automatically by e-mail
- ❖ Validate user authenticity for console to engine connections using one or more of four authentication methods, including password validation, host name identification, Windows domain, and TCP/IP address (or three methods in the case of the Web console, which does not support domain authentication)
- ❖ Identify additional Connect:Direct servers (through Node Discovery) that may need to be monitored based on communications with a currently monitored server

Sterling Control Center enhances operational productivity and improves quality of service by:

- ❖ Monitoring and configuring and managing licenses for Connect:Direct servers (for Windows, UNIX, and z/OS) from a central point
- ❖ Ensuring that critical processing windows are met
- ❖ Reducing impact on downstream processing by verifying that expected processing occurs
- ❖ Providing proactive notification for at-risk business processes
- ❖ Consolidating information for throughput analysis, capacity planning, post-processing operational or security audits, and workload analysis
- ❖ Reducing the risk of errors associated with manual system administration, including eliminating individual server logon to view activity and the need to separately configure each server for error and exception notifications

Sterling Control Center is available for purchase as a separate product. Contact your Sterling Commerce representative to learn more about Sterling Control Center.


## Connect:Direct Browser User Interface

Connect:Direct Browser User Interface allows you to build, submit, and monitor Connect:Direct Processes from an Internet browser, such as Microsoft Internet Explorer.

You can also perform Connect:Direct system administration tasks, such as viewing and changing the network map or initialization parameters, from Connect:Direct Browser. The specific administration tasks that you can perform depend on the Connect:Direct platform that your browser is signed on to and your security level.

Connect:Direct Browser is distributed on CD-ROM with Connect:Direct for z/OS, Connect:Direct for Windows, Connect:Direct for UNIX, and Connect:Direct HP NonStop. It can also be downloaded from the Sterling Commerce Web site. Connect:Direct Browser is installed on a Web server and can be accessed by

administrators and users through a URL. The following example shows the page used to graphically build a Process:



To learn more about Connect:Direct Browser, see the documentation on the Connect:Direct Browser CD-ROM or available online from the Sterling Commerce Documentation Library.

## Interfacing with Sterling Control Center or Browser User Interface

Connect:Direct HP NonStop can interface with Sterling Control Center and Connect:Direct Browser User Interface. The TCP/IP API enables users of these other Sterling Commerce applications to configure, control, and operate Connect:Direct HP NonStop from any host on a TCP/IP network. To set up a connection between Connect:Direct HP NonStop and Sterling Control Center or Browser User Interface, you need to define two entities in the network map:

- ❖ An adjacent node with the TYPE parameter defined as NDM.API and the IPADDR parameter defined as the address of the external application client from which connection requests may be received.
- ❖ An API manager (AMGR) to handle communications sessions with the external application. The AMGR record is used to define the local TCP process and port number on which a LISTEN is to be posted to accept incoming connection requests.

After you have defined these components, you must identify the AMGRs you want to use to communicate with an adjacent node by using the RELATE NETMAP command. For more information on both the INSERT and RELATE NETMAP commands, refer to *Defining and Maintaining the Network Map* in the *Connect:Direct HP NonStop Administration Guide*. You can also perform these functions using the Automated Installation & Management System (AIMS) to set up the network map. For more information, refer to *Installing and Configuring Connect:Direct HP NonStop* in the *Connect:Direct HP NonStop Installation Guide*.

## Commands

You use commands to submit Connect:Direct HP NonStop Processes to the TCQ and to manipulate Processes in the queue by flushing, deleting, or suspending them.

The following command submits the Process called ONESTEP to the TCQ with a HOLD status of Yes:

```
SUBMIT FILE ONESTEP HOLD=YES
```

Other commands allow you to select and display statistics or perform administrative functions, such as maintain network maps, user authorities, and default types.

The command language consists of the following types of commands:

- ❖ User
- ❖ Administrator

- ❖ Environment
- ❖ Message

## User and Administrator Commands

Issue user and administrator commands to perform the following tasks:

- ❖ Submit Connect:Direct HP NonStop Processes
- ❖ Monitor and control Process execution
- ❖ Perform administrative functions
- ❖ Examine Connect:Direct HP NonStop node definitions
- ❖ Display and update initialization parameters
- ❖ Stop Connect:Direct HP NonStop

Refer to the *Connect:Direct HP NonStop User Guide and Reference* for command syntax and parameter descriptions for user commands. Command syntax and parameter descriptions for administrator commands are in the *Connect:Direct HP NonStop Administration Guide*.

The following table lists the user and administrator commands and their functions:

Command	Function
CHANGE PROCESS	Modifies a Process in the TCQ.
DELETE PROCESS	Removes a nonexecuting Process from the TCQ.
DELETE NETMAP	Removes a node, LOGMODE, or LU from the network map.
DELETE SECURITY†	Removes a user record from the security file.
DELETE TYPE†	Removes a type record from the type file.
DELETE USER†	Removes a user record from the authorization file.
DISPLAY LICENSE	Displays current license key.
DISPLAY LOGGING	Displays or prints the settings for EMS and STATS, and the name of the collector process.
DISPLAY SESSIONS	Displays active and licensed session counts.
FLUSH PROCESS	Removes an executing Process from the TCQ.
INSERT APIMGR†	Adds an API manager, AMGR, to the network map, which enables connections to Sterling Control Center and the Browser User Interface.
INSERT NETMAP†	Adds an adjacent node to the network map, which lets you add an API manager, LOGMODE, or LU to the network map using the other INSERT NETMAP commands.
INSERT SECURITY†	Adds a security record to the security file.
INSERT TYPE†	Adds a type record to the type file.
INSERT USER†	Adds a user record to the authorization file.
LASTPNUMBER	Determines the number of the last Process submitted in the current NDMCOM session.
MODIFY†	Runs Connect:Direct HP NonStop traces or modifies certain operational functions.
RELATE NETMAP†	Assigns specific LUs or AMGRs to an adjacent node record.

† Administrative commands

Command	Function
SELECT NETMAP	Displays or prints definitions of API Manager, node, LOGMODE, and LU entries in the network map file.
SELECT PROCESS	Displays or prints information about a Process in the TCQ.
SELECT SECURITY	Displays or prints records in the security file.
SELECT STATISTICS	Displays or prints statistics, messages, license information, and /or commands in the statistics log.
SELECT TYPE	Displays or prints type records.
SELECT USER	Displays or prints user records in the authorization file.
STATUS	Displays the status of nodes and LUs, Processes in the CALL and WAIT queues, and TCP listen ports.
STOP ALL <sup>†</sup>	Stops Connect:Direct HP NonStop operation.
SUBMIT	Submits a Process for execution.
SUSPEND PROCESS	Suspends an executing Process.
UPDATE LICENSE	Validates the license key in the LICENSE file and updates the active license.
UPDATE LOGGING <sup>†</sup>	Modifies settings for EMS, STATS, and COLLECTOR.
UPDATE NETMAP <sup>†</sup>	Modifies settings for an API manager, node, LOGMODE, or LU record in the network map.
UPDATE PARM <sup>†</sup>	Alters operating parameters from the NDMINIT file. For more information on this command, see Connect:Direct HP NonStop <i>Installation Guide</i> .
UPDATE SECURITY <sup>†</sup>	Changes a security record in the security file.
UPDATE STATISTICS <sup>†</sup>	Dynamically changes the percentage setting, deletion criteria, and midnight housekeeping flag in the statistics facility (NDMSTDL).
UPDATE TYPE <sup>†</sup>	Changes a type record in the type file.
UPDATE USER <sup>†</sup>	Changes a user record in the authorization file.

<sup>†</sup> Administrative commands

## Environment Commands

Use environment commands to change and define the Connect:Direct HP NonStop environment or to facilitate the use of NDMCOM. The following table lists the environment commands and their functions:

Command <sup>†</sup>	Function
!	Reexecutes a previous command line, without modifications.
DISPLAY PARMS	Displays or prints current settings of the initialization parameters.
DISPLAY STATINFO	Displays percentage setting, deletion criteria, midnight flag setting, last execution of NDMSTDL, and file information for the statistics files (STATFILE, STATSRCH, STATSRC0).
EDIT	Invokes the HP NonStop TEDIT editor.

<sup>†</sup> Refer to the *Controlling the Environment* chapter in the *Connect:Direct HP NonStop User Guide and Reference* for command syntax and parameter descriptions for environment commands.



Command <sup>†</sup>	Function
ENVIRONMENT	Displays the current Connect:Direct HP NonStop environment, including defaults.
EXIT	Exits NDMCOM.
FC	Changes and/or reissues previously typed commands.
HELP	Accesses the interactive Connect:Direct HP NonStop Help facility.
HISTORY	Displays up to the last 100 commands issued.
LIST	Displays the contents of an edit file.
LOGON	Logs on to NDMCOM.
OBEY	Executes a series of HP NonStop and Connect:Direct HP NonStop commands, except FC, contained in an edit file.
OBEYVOLUME	Defines the default volume used for expansion of the obey file name.
OPEN	Opens the NDMSRVR process.
OUT	Changes the default output file.
PRINTER	Defines the print file name.
PROCVOLUME	Defines the default volume used for expansion of the Process file name.
RUN	Executes any user-written or system programs without exiting NDMCOM.
SYMBOL	Builds, deletes, and displays symbolic substitution values for use in Connect:Direct HP NonStop.
TIME	Retrieves the current day, date, and time.
VERSION	Displays or prints the version, release, and maintenance level for the NDMCOM currently running.
VOLUME	Defines the current default volume.

<sup>†</sup> Refer to the *Controlling the Environment* chapter in the *Connect:Direct HP NonStop User Guide and Reference* for command syntax and parameter descriptions for environment commands.

## Message Commands

Use Connect:Direct HP NonStop message commands to insert, delete, display, modify, and print messages. Refer to *Using Connect:Direct HP NonStop* in the *Connect:Direct HP NonStop User Guide and Reference* for syntax and parameter descriptions for displaying and printing messages. Refer to *Modifying the Message File* in the *Connect:Direct HP NonStop Administration Guide* for syntax and parameter descriptions for modifying messages.

## Flow of Connect:Direct HP NonStop Operations

The following shows the processing flow for a SUBMIT command.


- ❖ The SUBMIT command is issued through NDMCOM.

```
CD.49.>SUBMIT FILE $VOL.SEND.FILE
```


- ❖ The command submits the file, \$VOL.SEND.FILE. The file contains Process statements.

```
SEND    PROCESS  SNODE=MVS.NODE
STEP01  COPY     FROM (DSN=$SYS.TAN.TXT) -
        TO      (DSN=MVS.FILE SNODE)
```

- ❖ The Process is sent to the server. The server then places the Process on the TCQ, responds to NDMCOM with the Process number (PNUMBER), and routes the Process to an available session manager. In the following figure, the server returns a PNUMBER of 5 to NDMCOM.



- ❖ The session manager reads the Process from the TCQ and executes it.



- ❖ While the Process is queued, or during execution, you can display Process status by issuing the SELECT PROCESS command.

```
CD.50.>SELECT PROCESS PNUMBER=5
```

Refer to *Managing Processes* in the *Connect:Direct HP NonStop User Guide and Reference* for sample output from the SELECT PROCESS command.

- ❖ After Process execution, you can display the results of the operation by issuing the SELECT STATISTICS command. Refer to *Viewing System Files* in the *Connect:Direct HP NonStop User Guide and Reference* for sample output from the SELECT STATISTICS command.

```
CD.51.>SELECT STATISTICS PNUMBER=5
```

---

# Using Connect:Direct HP NonStop

This chapter provides the following information used for basic Connect:Direct HP NonStop operation:

- ❖ Running Connect:Direct HP NonStop
- ❖ Issuing commands
- ❖ Using macros
- ❖ Connect:Direct HP NonStop Process statements
- ❖ Connect:Direct HP NonStop operation
- ❖ Accessing the message file

The tables in this chapter list and define all Connect:Direct HP NonStop commands.

---

## Running Connect:Direct HP NonStop

NDMCOM is the Connect:Direct HP NonStop command line user interface to the NDM server. RUN NDMCOM starts this user interface. You can run NDMCOM in interactive or background mode. Refer to *Issuing Commands through NDMCOM* on page 28 for command syntax and examples for both modes.

When you run NDMCOM, you open the indicated server, if that server is running. The server processes commands. Contact the system administrator if the server is down or you are not authorized to run it.

If you want to use a different server and the server you specified is not running, issue the OPEN command to open another server. Refer to *Opening the Server Process* on page 53 for the syntax of the OPEN command.

You are not required to specify a server when starting NDMCOM. If you do not specify a server, the default server is opened.

## Changing Ownership of NDMCOM

Ownership of the current NDMCOM session provides the basis for the ownership and security attributes. The last user to log on to NDMCOM owns the NDMCOM session.

You can override security for accessing files by defining a PNODEID parameter in a Process or in a SUBMIT command. For syntax and parameter descriptions for Process statements, refer to the Processes web site at <http://www.sterlingcommerce.com/documentation/processes/processhome.html>. For syntax and parameter descriptions of the SUBMIT command, see *Submitting a Process for Execution* on page 93.

---

**Note:** You can also use the Connect:Direct Browser User Interface to build, submit, and monitor Connect:Direct Processes from an Internet browser, such as Microsoft Internet Explorer. See the documentation for that product for more information.

---

## Changing the Default Server Process Name

The default Connect:Direct HP NonStop server process name is \$NDMS. You can change the NDMSRVR parameter to a different server name by issuing the PARAM command from the TACL prompt. The new process name can be up to six characters long and must have a \$ as the first character.

In the following example, the NDMSRVR name is set to \$NDMJV using the TACL PARAM command.

```
TACL>PARAM NDMSRVR $NDMJV
TACL>RUN NDMCOM
Connect:Direct (TM) 3.3.0.0
COPYRIGHT (C) 1988-1999, 2003 Sterling Commerce, Inc.
CD.1.>OPEN $NDMJV
  SAPI125I:(RC=0,FDBK="0")
NDM server opened.
CD.2.>
```

After you issue the PARAM command and invoke NDMCOM, Connect:Direct HP NonStop echoes the command to open the server.

## Changing the Command Prompt

The Connect:Direct HP NonStop command prompt is CD.n>, where *n* represents the next command number followed by a period (.). For example, CD.49.>.

You can customize the prompt by setting the parameter NDMPROMPT to the appropriate string from the command interpreter. In the following example, the NDMPROMPT is set to CD, followed by the initials of the user, JV, a greater than sign (>), and a space. Use quotation marks (" ") when you are including spaces in the prompt.

```
TACL>PARAM NDMPROMPT "JV > "
TACL>RUN NDMCOM
Connect:Direct (TM) 3.2.0.0
COPYRIGHT (C) 1988-2003 Sterling Commerce, Inc.
CD.1.JV >OPEN $NDMJV
  SAPI125I:(RC=0,FDBK="0")
NDM server opened.
CD.2.JV >
```

---

## Issuing Commands through NDMCOM

You can issue commands through NDMCOM using either of the following methods:

- ❖ In interactive mode from the command line. Interactive mode enables you to issue a command and receive an immediate response.

- ❖ In background mode using a disk input file (an OBEY file). Background mode enables you to include a series of Connect:Direct HP NonStop commands in an OBEY file.

The following sections describe running NDMCOM in interactive and background modes.

---

**Note:** To run NDMCOM in conjunction with an application program interface (API), refer to *Connect:Direct HP NonStop Management Programming Guide*.

---

## Running NDMCOM in Interactive Mode

Issue the following command to run NDMCOM as a high-pin process in the interactive mode from TACL. You can issue multiple commands in the interactive mode by concatenating the commands and delimiting each command with a semicolon (;).

```
TACL>RUN NDMCOM /highpin on/ server ;command... | ;command...
```

Always precede the command with RUN.

## Parameters

Following are the NDMCOM interactive mode parameters:

Parameter	Description
highpin	Runs NDMCOM as a high-pin process when this parameter is set to on.
server	Specifies the HP NonStop process name of the NDMSRVR. If you omit this parameter, the default server (\$NDMS) is assumed.
command	Specifies one command or a list of commands, separated by semicolons (;). After execution of these commands, type additional commands from the NDMCOM prompt. Issuing the command to run NDMCOM in the interactive mode changes the command prompt from TACL to the Connect:Direct HP NonStop command prompt.

## Example

The following example shows how to run NDMCOM in interactive mode. The command to run NDMCOM and submit the file ACCT was issued from the TACL prompt. Connect:Direct HP NonStop responds with the version, the OPEN command, the opened server message, the SUBMIT command, and the message returned from the SUBMIT command. You can type additional Connect:Direct HP NonStop commands at the NDMCOM prompt.

```
TACL>RUN NDMCOM $NDMS1; SUBMIT FILE ACCT
Connect:Direct (TM) 3.3.0.0
COPYRIGHT (C) 1988-2003 Sterling Commerce, Inc.
CD.1.>OPEN $NDMS1
  SAPI125I : (RC=0, FDBK="0")
NDM server opened.
CD.2.>SUBMIT FILE ACCT
  SSRV1o1I : (RC=0, FDBK="0")SUBMIT command.
Process submitted successfully. Process number 1.
CD.3.>
```

## Running NDMCOM in Background Mode

To run NDMCOM in background mode, issue the following command from TACL. Multiple commands issued in background mode are concatenated, delimited by a semicolon (;).

```
TACL>RUN NDMCOM /runtime options/ server
```

## Parameters

Following are the parameters for the background mode:

Parameter	Description
runtime options	Specifies any valid HP NonStop runtime options, except backup CPU. Refer to the <i>TACL Reference Manual</i> for additional information. IN—Specifies the name of a disk file containing Connect:Direct HP NonStop commands. OUT—Specifies the spooler or disk file to which output from NDMCOM is directed. NOWAIT—Specifies that control returns to your terminal immediately after the NDMCOM process is initiated. HIGHPIN—Specifies whether the NDMCOM process runs as a high- or low-pin process. <b>Note:</b> The IN file is required if you are going to run NDMCOM in background mode.
server	Specifies the server name. If this parameter is omitted, the default server (\$NDMS) is assumed.
command	Specifies one command or a list of commands, separated by semicolons (;). After execution of these commands, Connect:Direct HP NonStop reads additional commands from the standard input file unless the last command is EXIT.

## Example

The following example shows how to run NDMCOM in background mode. NDMIN includes all Connect:Direct HP NonStop commands. If the EXIT command is part of the NDMIN file contents, Connect:Direct HP NonStop passes control to the TACL prompt after command execution. NDMCOM directs all messages to the spooler location #NDMCOM.

```
TACL>RUN NDMCOM /IN NDMIN, OUT $$.#NDMCOM/ $NDMS
TACL>
```

## Using Connect:Direct HP NonStop Macros

Connect:Direct HP NonStop furnishes two sets of macros that provide greater functionality and flexibility in NDMCOM:

- ❖ Interactive mode macros include NDMRUN, NDMS, and NDMA
- ❖ Background mode macros include NDMSTART, CD, and NDMSTOP

Both sets of macros are in NDMINSTL.TACLNDM.

## Macros for Interactive Mode

Issue the command NDMRUN and the name of the server from the TACL prompt to execute the macros for the interactive mode. The macros enable you to issue HP NonStop commands from the TACL prompt without stopping NDMCOM and without NDMCOM interfering with your HP NonStop command output.

Macros for the interactive mode are as follows:

- ❖ Use NDMRUN to start NDMCOM in interactive mode.
- ❖ Use NDMS to suspend the NDMCOM process when you use the break key to exit NDMCOM. Issue this command once from the TACL prompt after you exit NDMCOM with the break key.
- ❖ Use NDMA to reactivate NDMCOM after you complete the appropriate TACL activities. Issue this command from the TACL prompt to reactivate the NDMCOM program and return to the NDMCOM prompt.

For example, to suspend NDMCOM without losing your history buffer from Connect:Direct HP NonStop, press the break key and type NDMS from the TACL prompt. To reactivate NDMCOM, type NDMA from the TACL prompt.

## Macros for Background Mode

Issue the command NDMSTART and the name of the server from the TACL prompt to execute the macros for the background mode. The macros enable you to pass commands to NDMCOM from your TACL prompt.

---

**WARNING:** For security considerations, do not leave Connect:Direct HP NonStop running in background mode.

---

The following macros are for background mode:

- ❖ Use NDMSTART to start NDMCOM in background (NOWAITed) mode.
- ❖ Use CD to communicate with NDMCOM in background mode. If you are using the macros for background mode, you must precede all Connect:Direct HP NonStop commands with CD.
- ❖ Use NDMSTOP to stop NDMCOM in background mode.

For example, if you started NDMCOM with the NDMSTART macro, use the CD macro to issue Connect:Direct HP NonStop commands. A sample SELECT PROCESS command follows:

```
CD SELECT PROCESS PNUMBER=n
```

You return to the TACL prompt after Connect:Direct HP NonStop displays results from the command at your terminal.

## Implementing Macros

Perform the following steps to implement either set of macros:

1. Determine the volume and subvolume where you want NDMCOM located. The default volume and subvolume name is \$SYSTEM.NDMOBJ.
2. If you want to modify the default location, edit NDMRUN or NDMSTART or both routines in NDMINSTL.TACLNDM and specify a different location for NDMCOM.

3. Type the following command from the TACL prompt:

```
LOAD / KEEP 1 / NDMINSTL.TACLNDM
```

4. Run the server.
5. Type NDMRUN or NDMSTART from the TACL prompt. If your server process name is different from the default of \$NDMS, specify it as part of the command. An example follows:

```
NDMSTART server-name
```

## Connect:Direct HP NonStop Process Statements

The following table lists Process statements and their functions. For complete information on the Process language and instructions on building a Process, see the Processes web site at <http://www.sterlingcommerce.com/documentation/processes/processhome.html>.

**Note:** Connect:Direct Browser User Interface allows you to build, submit, and monitor Connect:Direct Processes from an Internet browser, such as Microsoft Internet Explorer. See the documentation for that product for more information.

Process Statement	Function
COPY	Copies files from one node to another.
MODAL	Alters the sequence of Process execution based on the completion code of previous steps with the IF THEN, ELSE, EIF (end if), GOTO, and EXIT statements.
PROCESS	Defines general Process characteristics.
RUN JOB	Executes asynchronous operations on z/OS, VSE, and VM nodes.
RUN TASK	Creates and runs HP NonStop processes during Process execution and performs remote operating system commands.
SUBMIT	Submits another Process to either the PNODE or the SNODE during execution of a Process.
SYMBOL	Builds a symbolic substitution value.

A sample Process follows:

```
ONESTEP  PROCESSSNODE=HPNONSTOP.NODE
STEP     COPY FROM(SNODE DSN=$A.ACCT.DATA)
          CKPT=1k
          TO      (PNODE DSN=$B.JAN.DATA
                   DISP=RPL)
          COMPRESS
```



## Connect:Direct HP NonStop Operation

This section shows how you can apply various Connect:Direct HP NonStop functions.

The following sample Process copies a file from the primary node (PNODE) to the secondary node (SNODE). The PNODE is a HP NonStop node, and the SNODE is a z/OS node.

```

/*This sends accounting records to Boston.*/
DALLAS  PROCESSSNODE=BOSTON-
        SNODEID=(IBMUSER,PSWRD)
STEP1   COPY FROM(PNODE DSN=&FROM-
        DISP=SHR) -
        TO (SNODE DSN=&TO-
        DISP=RPL)
STEP2   IF (STEP1 GT 4) THEN
        EXIT
        EIF
STEP3   RUN JOB (DSN=IBM.PROGRAM SNODE)
STEP4   RUN TASK PGM=FUP SYSOPTS "PURGE &FROM!"

```

A description of each part of the sample Process follows:

- ❖ The first statement in the file is a PROCESS statement. The PROCESS statement defines DALLAS as the Process name and the secondary node as BOSTON (SNODE=BOSTON). The SNODEID parameter identifies the user ID and password for the BOSTON node. You do not need a SNODEID if the SNODE uses automatic user ID security resolution. Security is an administrative issue discussed in the *Defining and Maintaining Security* chapter in the *Connect:Direct HP NonStop Administration Guide*.
- ❖ Step 1 is a COPY statement. In this example, the &FROM and &TO file names are symbolic values that are resolved during submission of the Process. The ampersand (&) denotes symbolic values. The FROM file is allocated as SHR and the TO file as RPL. SHR specifies that the file is read by Connect:Direct HP NonStop and can also be read by concurrent users. RPL specifies that Connect:Direct HP NonStop replaces any existing file of the same name or creates the file if it does not exist.
- ❖ Step 2 uses modal logic to check the completion code of Step 1. If the completion code for Step 1 is greater than 4, then additional Process execution is cancelled. If the completion code for Step 1 is less than or equal to 4, Step 3 runs.
- ❖ Step 3 executes the RUN JOB statement to run the IBM.PROGRAM on the SNODE.
- ❖ Step 4 starts the RUN TASK statement that runs the FUP utility in batch mode to purge the file named by the symbolic value. By default, the RUN TASK statement executes on the PNODE.

## Submitting the Process to the TCQ

The following command submits the Process for execution. In this command string, the symbolic values (&FROM and &TO) are constructed and passed to the Process. A sample SUBMIT command and the Connect:Direct HP NonStop response follow:

```

CD.3.>SUBMIT FILE $A.NDMPROCX.DALLAS &FROM=$A.SMITH.AC
&TO=JONES.CNTL(AC)
      SSRV101I: (RC=0, FDBK="0")

Thursday - January 28, 1999 - 09:33:42.870
      SSRV101I: (RC=0, FDBK="0")
Process submitted successfully. Process number : 1

```

## Monitoring the Process Status in the TCQ

After you submit the Process for execution, you can issue the `SELECT PROCESS` command to monitor the data transmission activity. Connect:Direct HP NonStop generates a report with the Process name and number, submitter node and ID, destination node, and queue. When you type the `DETAIL` parameter as part of the command, you receive additional information. The following example is a `SELECT PROCESS` command:

```
SELECT PROCESS PNUMBER=1
```

Samples of the reports and commands that generate each of the report formats are available in Chapter 6, *Managing Processes*.

## Determining the Outcome of the Process

Upon completion of the Process, you can review the statistics log for the Process. Following is a sample command to generate a statistics log:

```
SELECT STATISTICS PNUMBER=1
```

Refer to the sample statistics log in Chapter 7, *Viewing System Files*.

## Exiting NDMCOM

Issue the `EXIT` command, to NDMCOM and return to the command interpreter. A sample command and Connect:Direct HP NonStop response follows:

```
EXIT
  SAPI220I: (RC=0,FDBK="0")
EXIT command successfully completed.
TAACL>
```

---

## Accessing the Message File

Connect:Direct HP NonStop has an online message program, where you can display, modify, and print messages. A sample message is in `MESSAGE` in the `NDMSAMP` subvolume of the distribution tape.

For the syntax for inserting, deleting, and modifying messages, refer to the *Modifying the Message File* chapter in *Connect:Direct HP NonStop Administration Guide*.

Syntax for displaying and printing message text follows.

## Displaying Messages

The message file, NDMMMSG, displays message text when supplied with a message identifier. Use the following commands to display messages:

```
TACL>RUN NDMMMSG msgfile-name
?DISPLAY msgid
```

Parameters are as follows:

Parameter	Description
NDMMMSG	Indicates the Connect:Direct HP NonStop message program.
msgfile-name	Indicates the file of Connect:Direct HP NonStop messages.
DISPLAY	Specifies the command that displays a message in the Connect:Direct HP NonStop message file. Input the command at the ? prompt. You can use MSG interchangeably with DISPLAY.
msgid	Specifies the message identifier for a particular message.

To exit the message program, type **CTRL-Y**.

You can also use the HELP command to display messages. For syntax and parameter descriptions, refer to the description of the HELP command in Chapter 4, *Controlling the Environment*.

## Printing Messages

Use the following commands to print Connect:Direct HP NonStop messages:

```
TACL>RUN NDMMMSG /OUT $$.#OUTMSG/ msgfile-name
GET msgid|*
```

Following are the parameters for printing messages:

Parameter	Description
RUN NDMMMSG	Indicates the Connect:Direct HP NonStop message program.
OUT \$\$.#OUTMSG	Specifies the output spool location.
msgfile-name	Specifies a file of Connect:Direct HP NonStop messages.
GET	Copies the specified message to the spooler for printing.
msgid	Identifies the message identifier for a particular message.
asterisk (*)	The indicator that specifies all messages in the message file.



---

# Queuing Processes

This chapter describes the following information about the Transmission Control Queue (TCQ):

- ❖ Understanding the Transmission Control Queue
- ❖ Managing Processes in the TCQ
- ❖ Scheduling Connect:Direct HP NonStop activity

---

## Understanding the Transmission Control Queue

The TCQ controls Process execution. After Processes are submitted, they are stored in the TCQ. The TCQ consists of two key-sequenced files and an in-memory queue, which controls access. The TCQ consists of eleven queues. Following are the TCQ queues:

Queue	Description
B (Bad)	An error occurred during initiation of Process execution. This error can occur because of a security error or some other unrecoverable error.
C (Call)	The Process executes after a connection is established with the other node. You cannot specify a start date or time.
E (Execution)	The Process is currently executing.
H (Hold)	The Process remains in the Hold queue until you release it.
I (Initial)	A copy of the Process executes when you start the server.
P (Pending)	Pnode Processes pending execution (PEXC). A session is being requested with another node but has not yet been established.
R (Retain)	A copy of the Process is retained after execution. You can later release a copy of this Process for execution.
S (Suspend)	The SUSPEND PROCESS command suspends the Process. You can later release the Process for execution.
T (Timer)	The Process executes at a specified start date and time.
W (Wait)	The Process awaits execution.

Queue	Description
RETTIMER (Retain-Timer)	The Process executes periodically, either daily or weekly. A copy of the Process is released for execution at the end of the period specified.

## Managing Processes in the TCQ

After you submit a Process, you can monitor its status, modify specific characteristics, retrieve the original source for a Process, and stop its execution by using the appropriate commands. For example, you can change the destination of a particular file or stop an executing Process. The commands summarized in the following table allow you to perform such tasks.

Command	Definition
CHANGE PROCESS	Changes the status and modifies specific characteristics of a <i>nonexecuting</i> Process in the TCQ.
DELETE PROCESS	Removes a <i>nonexecuting</i> Process from the TCQ.
FLUSH PROCESS	Deletes an <i>executing</i> Process.
SELECT PROCESS	Monitors Processes in the TCQ, and any currently running Processes. You can specify the search criteria and the form of the information presented. You can also reconstruct the source for a Process in the TCQ so you can easily update the script without having to start from scratch.
SUSPEND PROCESS	Places an <i>executing</i> Process in the hold queue. You can later release the held Process.

## Scheduling Connect:Direct HP NonStop Activity

Connect:Direct HP NonStop places a Process in the appropriate queue based on scheduling parameters. Specify the following scheduling parameters in the PROCESS statement or SUBMIT command:

- ❖ HOLD=Yes|No|Call
- ❖ RETAIN=Yes|No|Initial
- ❖ STARTT=(date|day, hh:mm:ssXM)

The following table illustrates how scheduling parameters affect the queues:

If the Process Is Submitted with	Placed in Queue	Comment
None of the scheduling parameters specified	Wait	The Process remains in the Wait queue until a session is started with an adjacent node.
RETAIN=YES	Retain	The Process executes once and stays in the queue. You can specify a day or time or both for the Process to start.

If the Process Is Submitted with	Placed in Queue	Comment
RETAIN=NO	Wait	If you specify no other parameters, the Process remains in the Wait queue until a session is started with an adjacent node. RETAIN=NO is the default.
RETAIN=INITIAL	Initial	A copy of the Process remains in the queue and executes every time the server is initialized.
RETAIN=YES and HOLD=NO or CALL	Retain	A copy of the Process remains in the queue and is executed when released. Connect:Direct HP NonStop ignores the HOLD parameter.
HOLD=YES	Hold	You can execute the Process by specifying CHANGE PROCESS PNAME=filename HOLD=NO. You can specify RELEASE instead of HOLD=NO.
HOLD=NO	Wait	If no other parameters are specified, the Process remains in the Wait queue until a session is started with an adjacent node. HOLD=NO is the default.
HOLD=CALL	Call	The Process remains in the queue until the destination node starts a session with the local node.
STARTT (a start time and day, date, or both)	Timer	When the scheduled time and date arrive, Connect:Direct HP NonStop moves the Process to the specified Wait queue for execution. For more information on how dates can be entered as parameter values, see <i>Date Formats</i> on page 81.





---

# Controlling the Environment

Use environment commands to change and define the Connect:Direct HP NonStop environment or to facilitate the use of NDMCOM. You can issue these commands at any time during Connect:Direct HP NonStop operation. For example, to change the volume during a session or invoke TEDIT, use the environment commands.

This chapter describes the environment commands. The table in *Environment Commands* on page 24 lists the commands and summarizes the tasks each command can perform.

---

**Note:** Some Connect:Direct HP NonStop environment commands are familiar to users of the HP NonStop operating system. For more information on those commands, refer to the HP NonStop documentation.

---

---

## Recalling and Reissuing Commands

Use the ! (exclamation point) command to recall and reissue a previously issued command without modifications. Issue this command like the familiar TACL command. You can request a specific line by typing its command number, a relative number, or a command abbreviation.

Typing the ! without one of the parameters recalls and reissues the last command entered.

### Format

Following is the ! command format:

!	command number
	-command number
	command string

### Required Parameters

The ! command has no required parameters.

## Optional Parameters

Following are the optional parameters for the ! command:

Parameter	Description
command number	Specifies an absolute command number.
-command number	Specifies a relative command number.
command string	Specifies a command abbreviation. The command abbreviation must uniquely identify the command and must start from the beginning of the command.

## Examples

Following are examples of optional parameters for the ! command:

Command Syntax	Description
CD.18.>!	Recalls and reissues the previous command.
CD.27.>! 12	Recalls and reissues previous command 12 in the current history stack.
CD.32.>! -6	Recalls and reissues the sixth command back from the current command prompt.
CD.35.>! sub	Recalls and reissues the most recent command that begins with the entered text string.

## Invoking the HP NonStop Text Editor (TEDIT)

Use the EDIT command to invoke the HP NonStop text editor, TEDIT. For instructions on using the text editor, refer to the HP NonStop Operating System documentation.

### Format

Following is the EDIT command format:

EDIT	filename parameters
------	---------------------

### Required Parameters

The EDIT command has no required parameters.

## Optional Parameters

Following are optional parameters for the EDIT command:

Parameter	Description
filename	Specifies any edit file name (code 101).
parameters	Specifies any TEDIT option/commands. <b>Note:</b> If you are executing editor commands, NDMCOM cannot concatenate multiple commands when the editor is using Connect:Direct HP NonStop delimiters such as (;) for search values.

## Examples

The following command invokes TEDIT and displays the TEDIT initial Help screen:

```
CD.2.>EDIT
```

The following command invokes TEDIT and accesses MYFILE in read mode:

```
CD.3.>EDIT MYFILE R
```

The following command invokes TEDIT, accesses MYFILE in read/write mode, and searches for the text string entered:

```
CD.4.>EDIT MYFILE; SEARCH TEXT
```

---

## Exiting NDMCOM

Use the EXIT command to exit NDMCOM. After you issue the EXIT command, Connect:Direct HP NonStop passes control to TAFL. You can also use the **CTRL-Y** (control Y) key sequence to exit NDMCOM.

## Format

Following is the EXIT command format:

```
Exit
```

## Required Parameters

The EXIT command has no required parameters.

## Optional Parameters

The EXIT command has no optional parameters.

## Examples

The following example displays the results from issuing the EXIT command. Connect:Direct HP NonStop exits NDMCOM, displays the confirmation message indicating successful completion of the command, and returns you to the default command interpreter.

```
CD.5.>EXIT
  SAPI220I: (RC=0, FDBK="0")
CD.6.>EXIT command successfully completed.
TA CL>
```

---

## Changing and Reissuing Commands

Use the FC command to change and reissue a previously entered command. This command is valid only in an interactive environment. If you enter the FC command, Connect:Direct HP NonStop displays the previous command, along with two periods. You can reissue the command by pressing **Enter**, or you can edit and then reissue the command. For further information on this command, refer to the HP NonStop documentation.

Enter FC with no parameters to recall the last command entered.

## Format

Following is the FC command format:

```
FC          command number
           -command number
           command string
```

## Required Parameters

The FC command has no required parameters.

## Optional Parameters

Optional parameters for the FC command are:

Parameter	Description
command number	Refers to the command-line number in the history buffer you want to retrieve.
-command number	Refers to the relative command-line number in the history buffer you want to retrieve.
command string	Identifies the most recent command line in the history buffer beginning with the specified text.

## Examples

Following is a sample listing of previously issued commands. Examples using the FC command against this buffer follow the figure.

```
1..OPEN $NDMS
2..TIME
3..ENV
4..SUB PROC=TOBOSTON
5..SEL PROC PNAME=TODALLAS DETAIL
6..HISTORY
```

Enter FC and a line number to repeat the requested line number. The prompt number does not change until you enter and execute the correction or change.

```
CD.7.>FC 4
CD.7.>SUB PROC=TOBOSTON
CD.7..      TODALLAS
CD.7.>SUB PROC=TODALLAS
CD.7..
```

Enter FC and a portion of the command string to repeat the requested line. The prompt number does not change until you enter and execute the correction.

```
CD.8.>FC SE
CD.8.>SEL PROC PNAME=TODALLES DETAIL
CD.8..      A
CD.8.>SEL PROC PNAME=TODALLAS DETAIL
CD.8..
```

---

## Accessing the Connect:Direct HP NonStop Help Facility

Use the HELP command to access the interactive Connect:Direct HP NonStop Help facility. For help using a specific Connect:Direct HP NonStop command or Process statement, enter the command or Process statement name after the HELP command or Browser pull-down menu. For a listing of all Connect:Direct HP NonStop commands and statements, enter ALL after the HELP command.

Enter the HELP command without a parameter to display the format and optional parameters for the HELP command.

### Format

Following is the HELP command format:

```
HElp          ALL
              command
              messageid
```

## Required Parameters

The HELP command has no required parameters.

## Optional Parameters

Optional parameters for the HELP command are:

Parameter	Description
ALL	Specifies that you want a list of all commands and Process statements.
command	Specifies the command for which you want help information.
messageid	Specifies that you want message text displayed for the message ID supplied.

## Examples

The following command displays the syntax and required and optional parameters for the INSERT USER command:

```
CD.2.>HELP INSERT USER
```

Following is a sample display:

```
CD.2.>help ins user
SCMD016H:
INSert
USER

Insert User commands insert a user record
in the C:D Authorization file.

/*****
** Command Syntax **
*****/
<command syntax follows>

CD.3.>
```

---

## Displaying Previous Commands

Use the HISTORY command to display up to the last 100 commands issued during the session.

### Format

Following is the HISTORY command format:

```
HISTORY          nnn
```

### Required Parameters

The HISTORY command has no required parameters.

### Optional Parameters

The HISTORY command has the following optional parameter:

Parameter	Description
nnn	Indicates the number of commands you want to display. The default is 10 commands.

### Examples

A sample listing of previously issued commands follows:

```
1.. OPEN $NDMJV
2.. TIME
3.. ENV
4.. SUB PROC TODALLAS
5.. SEL PROC PNAME=TODALLAS DETAIL
6.. DEL PROC WHERE PNAME=TODALLAS
7.. SUB PROC TOAUSTIN
8.. SEL PROC PNAME=TOAUSTIN DETAIL
9.. CH PROC PNAME=TOAUSTIN DEST=DALLAS
10.. SEL PROC PNAME=TOAUSTIN DETAIL
11.. SUB PROC TOBOSTON
12.. SEL NET NODE=DENVER LU=LU2
13.. UPD NET ADJACENT.NODE=DENVER MAXRETRY=15
14.. HISTORY 15
```

---

## Displaying Edit File Contents

Use the LIST command to display the contents of an edit file.

### Format

Following is the LIST command format:

```
LIST          \system.$volume.subvol.filename
```

### Required Parameters

The LIST command has the following required parameter:

Parameter	Description
\system.\$volume.subvol.filename	Specifies the system, volume, subvolume, and file name of the edit file. The fully qualified file name can contain 1–34 characters. The system name is a maximum of 8 characters, including the backslash; volume name is a maximum of 8 characters, including the dollar sign; and subvolume is a maximum of 8 characters. The file name portion of the parameter is 1–8 characters in length and must begin with an alphabetic character. <b>Note:</b> If you specify the system name, the volume name can only be a maximum of 7 characters, including the \$. If you do not specify the system name, the volume name can be up to 8 characters. This limitation is a HP NonStop restriction.

### Optional Parameters

The LIST command has no optional parameters.

### Examples

The following command displays the contents of the file JAN on the BACKUP subvolume in the \$B volume.

```
CD.3.>LIST $B.BACKUP.JAN
FILE=$B.ACCT.DATA
DSN=MVS.ACCT.JAN
SNODE=MVS.NODE.NAME
3 RECORDS TRANSFERRED
```

---

## Signing On as Another User within NDMCOM

Use the LOGON command from an NDMCOM prompt to sign on as another user. If the new user is defined in the authorization file (AUTHFILE), the values assigned to that user ID override those of the previous user.

If the new user is not defined in the authorization file, but a default user record exists (NDM.DEFAULT), the new user is added to the authorization file with the default attributes defined in the default record.



## Format

Following is the LOGON command format:

```
LOgon                (group.user|alias) , password
```

## Required Parameters

The LOGON command has no required parameters.

## Optional Parameters

Optional parameters for the LOGON command are:

Parameter	Description
group.user	Specifies the group name and user ID you are using to sign on to Connect:Direct HP NonStop. If you do not specify this parameter, Connect:Direct HP NonStop uses the current user ID for the HP NonStop session. The maximum length is 17 characters, including the period (.) separating your group name and user ID. If you do not enter the group.user, the current group.user is assumed.
alias	Specifies the user records to select in the AUTHFILE. You can enter 1–17 alphanumeric characters including underscores, hyphens, and periods. The first character <i>must</i> be alphanumeric.
password	Specifies your password. The maximum length is 8 characters, beginning with an alphabetic character. Passwords are case-sensitive. If you do not enter the password and NDMCOM is running in interactive mode, Connect:Direct HP NonStop prompts you for your password. Connect:Direct HP NonStop encrypts the password as it is entered. If you are running in background mode, ensure that you are defined as a user in the AUTHFILE.

## Examples

The following example shows a LOGON command with both the group.user and password values specified. The values are separated with a comma (,).

```
CD.3.>logon SUPER.OPER,password
      SAPI114I: (RC=0, FDBK="0")
LOGON successful.
CD.4.>
```

The following example shows a LOGON command with only group.user values specified. Connect:Direct HP NonStop responds with a prompt for the password. If you are entering a password interactively, the cursor does not move, and the password is not displayed.

```
CD.4.>logon SUPER.OPER
Password :
      SAPI114I: (RC=0, FDBK="0")
LOGON successful.
CD.5.>
```

The following example shows a LOGON command with both alias and password values specified. The values are separated with a comma (,).

```
CD.3.>logon this_is_an_alias,password
      SAPI114I: (RC=0, FDBK="0")
LOGON successful.
CD.4.>
```

---

## Executing the Obey Command

Use the OBEY command to execute a series of commands in an edit file. The file can contain any combination of the following:

- ❖ Any Connect:Direct HP NonStop command, except the FC command
- ❖ Environment commands
- ❖ HP NonStop commands if preceded by the RUN command

---

**Note:** If you do not fully qualify the file name, by including the system, volume, and subvolume names, Connect:Direct HP NonStop expands the file name using the obeyvolume value as specified in the AUTHFILE. If the obeyvolume value is not set (blank), Connect:Direct HP NonStop expands the file name from the current volume and subvolume.

---

## Format

Following is the OBEY command format:

```
Obey                \system.$volume.subvol.filename
```

## Required Parameters

The OBEY command has the following required parameter:

---

Parameter	Description
\system.\$volume.subvol.filename	<p>Specifies the system, volume, subvolume, and file name of the obey file. The fully qualified file name can contain 1–34 characters. The system name is a maximum of 8 characters, including the backslash; volume name is a maximum of 8 characters, including the dollar sign; and subvolume is a maximum of 8 characters. The file name portion of the parameter is 1–8 characters in length and must begin with an alphabetic character.</p> <p><b>Note:</b> If you specify the system name, the volume name is a maximum of 7 characters, including the \$. If you do not specify the system name, the volume name is up to 8 characters. This limitation is a HP NonStop restriction.</p>


---

## Optional Parameters

The OBEY command has no optional parameters.

## Examples

An example of records inside an obey file named OBEYFILE follows:



Assume that you issued the command to run OBEYFILE. The following example shows the commands that are automatically issued against this file:

```

CD.1.>OBEY OBEYFILE
CD.2.>TIME
    Tuesday - October 13, 2003- 14:00:36:640
CD.3.>SUBMIT PROCESS=TODALLAS
    Tuesday - October 13, 2003 - 14:00:43.870
    SSRV101I: (RC=0,FDBK="0")
    Process submitted successfully.  Process number: 188
CD.4.>TIME
    Tuesday - October 13, 2003- 14:01:45:600
CD.5.>RUN FUP COPY $A.SMITH.OBEYFILE
    TIME
    SUBMIT PROCESS=TODALLAS
    TIME
    RUN FUP COPY $A.SMITH.OBEYFILE
    4 records transferred
CD.6.>

```

An explanation follows:

- ❖ At the CD.1.> prompt, you issued the OBEY command.
- ❖ At the CD.2.> prompt, Connect:Direct HP NonStop echos the first record read from OBEYFILE and then invokes the TIME command.
- ❖ At the CD.3.> prompt, Connect:Direct HP NonStop reads and displays the second record, which invokes the SUBMIT command.
- ❖ At the CD.4.> prompt, Connect:Direct HP NonStop reads and displays the third record, which invokes the TIME command.
- ❖ At the CD.5.> prompt, Connect:Direct HP NonStop reads and displays the fourth record, which invokes the RUN command.

---

## Defining the Default Obey Volume

Use the OBEYVOLUME command to define the default obey volume used for expansion of the obey file name. If you issue the OBEYVOLUME command without specifying a system, volume, or subvolume, Connect:Direct HP NonStop expands the file name from the saved volume. The saved volume is the volume.subvolume from where you executed NDMCOM.

---

**Note:** The OBEYVOLUME command is a temporary command and is reset after stopping and restarting Connect:Direct HP NonStop. To maintain the setting, issue the UPDATE USER command, and specify an obey volume.

---

### Format

Following is the OBEYVOLUME command format:

OBEYVOLUME	\system.\$volume.subvol
------------	-------------------------

### Required Parameters

The OBEYVOLUME command has no required parameters.

### Optional Parameters

Optional parameters for the OBEYVOLUME command are:

Parameter	Description
\system.\$volume.subvol	Specifies the system, volume, and subvolume for the obeyvolume. The system name is a maximum of 8 characters, including the backslash; volume name is a maximum of 8 characters, including the dollar sign; and subvolume is a maximum of 8 characters. <b>Note:</b> If you specify the system name, the volume name is a maximum of 7 characters, including the \$. If you do not specify the system name, the volume name is up to 8 characters. This limitation is a HP NonStop restriction.

## Examples

The following command changes the OBEYVOLUME to the specified volume:

```
CD.17.>obeyvolume $system.batch
SAPI136I: (RC=0, FDBK="0")
OBEYVOLUME changed to \ESCAPE.$SYSTEM.BATCH
CD.18.>
```

The following command sets the OBEYVOLUME to the saved volume:

```
CD.18.>obeyvolume
SAPI136I: (RC=0, FDBK="0")
OBEYVOLUME changed to $DSMSCM.T3206CNT
CD.19.>
```

---

## Opening the Server Process

Use the OPEN command to open the server process. The server must be running to execute any other Connect:Direct HP NonStop commands. If the server that you are attempting to access during the invocation of NDMCOM is not running, then issue the OPEN command to choose a server currently running. You do not have to exit Connect:Direct HP NonStop. Refer to *Issuing Commands through NDMCOM* on page 28 for information on invoking NDMCOM.

### Format

Following is the OPEN command format:

```
Open ndmsrvr-name
```

### Required Parameters

The OPEN command has the following required parameter:

Parameter	Description
ndmsrvr-name	Specifies the processname of the Connect:Direct HP NonStop server process.

### Optional Parameters

The OPEN command has no optional parameters.

## Examples

Assume that you issued the command to run NDMCOM and open the server \$NDMJ. Connect:Direct HP NonStop displays the product name and its release, version, modification, and maintenance level, respectively.

Connect:Direct HP NonStop automatically issues the OPEN command for the specified server. Because it does not exist, Connect:Direct HP NonStop displays a message that is followed by the Connect:Direct HP NonStop prompt. You can then issue the OPEN command to attempt to open another server.

```

TACL>NDMCOM $NDMJ
Connect:Direct (TM) 3.3.0.0
COPYRIGHT (C) 1988-2003 Sterling Commerce, Inc.
CD.1.>OPEN $NDMJ
NDM server process "$NDMJ" does not exist
CD.2.>OPEN $NDMJV
  SAPI125I: (RC=0,FDBK="0")
NDM server opened.

```

---

## Changing the Output File

Use the OUT command to change the output file during the current session. The default is your home terminal.

Enter the OUT command without a parameter to return to the output file at startup, typically your home terminal.

### Format

Following is the OUT command format:

```

OUT          filename

```

### Required Parameters

The OUT command has no required parameters.

### Optional Parameter

The OUT command has the following optional parameter:

Parameter	Description
filename	Specifies the name of the file where Connect:Direct HP NonStop appends the output. If the specified data file does not exist, Connect:Direct HP NonStop creates an edit file of the same name.

## Examples

The following command redirects the output from terminal location \$SCOR.#L05 to \$S.#EXAMPLE, a spooler file. \$SCOR.#L05 was the most recent value for output (STDOUT) during the session.

```
CD.23.>out $s.#comout
CD.24.>
```

The following command shows the results when you issue the OUT command without a parameter. Connect:Direct HP NonStop returns the value of STDOUT to the startup value, which was \$SCOR.#L05 (home terminal).

```
CD.24.>out
SAPI213I: (RC=0, FDBK="0")
OUTPUT file \ESCAPE.$S.#COMOUT closed.
SAPI215I: (RC=0, FDBK="0")
OUTPUT file is \ESCAPE.$ZNTC0.#WINCWO
CD.25.>
```

---

## Defining Print File Names

Use the PRINTER command to define print file names. Issue this command to change the default printer defined in your initialization parameters file. Recycle the server to return the print file to the setting in the initialization parameters file.

### Format

Following is the PRINTER command format:

```
PRInter          printer
```

### Required Parameter

The PRINTER command has the following required parameter:

Parameter	Description
printer	Specifies the name of the print file (spooler). If you omit this value, Connect:Direct HP NonStop displays an error message.

### Optional Parameters

The PRINTER command has no optional parameters.

## Examples

The following command changes the default printer name in the initialization parameters file to \$\$.#PRINT:

```
CD.25.>printer $s.#print
  SAPI140I: (RC=0, FDBK="0")
Default printer changed to "$$.#PRINT"
CD.26.>
```

---

## Defining the Default Volume For Expansion of Process File Names

Use the PROCVOLUME command to define the default volume for expansion of Process file names. If you do not set the procvolume value and leave it blank, Connect:Direct HP NonStop expands the file name from the saved volume. If you change procvolume during the session and enter the PROCVOLUME command without a parameter, you set your procvolume to your saved volume.

---

**Note:** The PROCVOLUME command is a temporary command and is reset after stopping and restarting Connect:Direct HP NonStop. To maintain the setting, issue the UPDATE USER command, and change the default procvolume.

---

## Format

Following is the PROCVOLUME command format:

```
PROCVOLUME          \system.$volume.subvol
```

## Required Parameters

The PROCVOLUME command has no required parameters.

## Optional Parameters

The PROCVOLUME command has the following optional parameter:

---

Parameter	Description
\system.\$volume.subvol	Specifies the system, volume, and subvolume for the Process volume. The system name is a maximum of 8 characters, including the backslash (\); volume name is a maximum of 8 characters, including the \$; and subvolume is a maximum of 8 characters. <b>Note:</b> If you specify the system name, the volume name can only be a maximum of 7 characters, including the \$. If you do not specify the system name, the volume name can be up to 8 characters. This limitation is a HP NonStop restriction.

---



## Examples

The following command defines the default volume for Processes:

```
CD.26.>procvol $system.userproc
SAPI137I: (RC=0, FDBK="0")
PROCVOLUME changed to \ESCAPE.$SYSTEM.USERPROC
CD.27.>
```

The following command sets the default volume for Processes to the saved volume:

```
CD.27.>procvol
SAPI137I: (RC=0, FDBK="0")
PROCVOLUME changed to $DSMSCM.T3206CNT
CD.28.>
```

---

## Executing Programs without Exiting NDMCOM

Use the RUN command to execute programs on HP NonStop without exiting NDMCOM. Examples of the programs are FUP, SCF, INSTALL, PERUSE, or any user-written programs. After terminating execution of these programs, Connect:Direct HP NonStop passes control to NDMCOM and displays the Connect:Direct HP NonStop prompt.

### Format

Following is the RUN command format:

```
RUn          program
              /run-options/
              parameters
```

### Required Parameter

The RUN command has the following required parameter:

Parameter	Description
program	Specifies the fully qualified name including system, volume, subvolume, and file name of the program.

## Optional Parameters

Optional parameters for the RUN command are:

Parameter	Description
/run-options/	Specifies the options you want to execute with the RUN command. Refer to the HP NonStop Operating System documentation for valid options.
parameters	Specifies one or more program parameters to pass to the program in the startup message. Refer to the HP NonStop Operating System documentation for valid parameters.

## Examples

The following command executes SCF and lists devices:

```
RUN SCF LISTDEV
```

Following is a sample display:

```
CD.28.>run scf listdev
SCF - T9082G02 - (14JAN02) (03JAN02) - 07/23/2004 11:42:41 System \ESCAPE
Copyright Compaq Computer Corporation 1986 - 2002

LDev Name      PPID   BPID   Type   RSize Pri Program
0 $0           0,5    1,5    ( 1,0 ) 102 201 \ESCAPE.$SYSTEM.SYS03.OSIMAGE
1 $NCP        0,17   1,14   (62,0 )   1 199 \ESCAPE.$SYSTEM.SYS03.NCPOBJ
3 $YMIOP      0,256  1,256  ( 6,4 )   80 205 \ESCAPE.$SYSTEM.SYS03.OSIMAGE
5 $Z0         0,7    1,7    ( 1,2 ) 102 200 \ESCAPE.$SYSTEM.SYS03.OSIMAGE

<remaing text not displayed>

255 $BK       1,463  0,0    (46,0 ) 6144 155 \ESCAPE.$SYSTEM.SYSTEM.PCMGR
291 $BDST     1,398  0,0    ( 1,30) 132 154 \ESCAPE.$SYSTEM.SYS03.EMSDIST

Total Errors = 0   Total Warnings = 0
CD.29.>
```

## Managing Symbols

Use SYMBOL commands to insert, delete, or display symbols in the Connect:Direct HP NonStop environment. You cannot modify existing symbols. To change a symbol, you must delete the original and insert a new symbol.

Symbols are stored in memory for the duration of NDMCOM. You can create an obey file containing all of your symbols and execute it after you enter NDMCOM, or you can incorporate the symbols in the NDMRUN and NDMSTART macros. The symbols are then established as part of your Connect:Direct HP NonStop environment every time you run the NDMRUN macro to enter NDMCOM. Refer to *Using Connect:Direct HP NonStop Macros* on page 30 for a description and implementation instructions for macros.

To use a symbol in the Connect:Direct HP NonStop environment, place an ampersand (&) in front of the symbol. If Connect:Direct HP NonStop encounters an ampersand plus 1–17 alphanumeric characters, it substitutes the string represented by that ampersand and the alphanumeric characters.

For example, if you define the symbol spp for the SELECT PROCESS PNUMBER, when you issue the command &spp 12, Connect:Direct HP NonStop displays a status report for Process number 12.

To separate two symbols with a period (.), you must use two periods. For example, if the value of the symbol VOL is \$B and the value of symbol SUBVOL is NDM, then &VOL.&SUBVOL results in \$B.NDM.

---

**Note:** All examples in this section refer to the sample display of symbols in *Examining Symbols* on page 61.

---

## Inserting Symbols

Use the INSERT SYMBOL command to insert symbols in the Connect:Direct HP NonStop environment.

### Format

Following is the INSERT SYMBOL command format:

```
INSert SYMbol      symbol-name symbol-value
```

### Required Parameter

The INSERT SYMBOL command has the following required parameter:

Parameter	Description
symbol-name	Specifies the 1–17 alphanumeric character name of the symbol.

### Optional Parameter

The INSERT SYMBOL command has the following optional parameter:

Parameter	Description
symbol-value	Specifies the symbolic substitution value. The value can be a maximum of 256 alphanumeric characters. This value defaults to null.

### Examples

The following command inserts the symbol FROMDSN for \$data04.archive.file1:

```
CD.12.>insert symbol FROMDSN $data04.archive.file1
CD.13.>
```

---

## Deleting Symbols

Use the DELETE SYMBOL command to delete symbols from your Connect:Direct HP NonStop environment.

### Format

Following is the DELETE SYMBOL command format:

```
DELEte SYMbol      symbol-name
```

### Required Parameter

The DELETE SYMBOL command has the following required parameter:

Parameter	Description
symbol-name	Specifies the 1–17 alphanumeric character name of the symbol.

### Optional Parameters

The DELETE SYMBOL command has no optional parameters.

### Examples

The following command deletes the symbol FROMDSN:

```
CD.33.>del symbol FROMDSN
CD.34.>
```

---

## Examining Symbols

Use the SELECT SYMBOL command to examine symbols in the Connect:Direct HP NonStop environment. Issue this command without a symbol-name parameter to display all the symbols for the environment.

### Format

Following is the SELECT SYMBOL command format:

```
SElect  SYMbol          OUT=filename
                               PRINT
                               symbol-name
```

### Required Parameters

The SELECT SYMBOL command has no required parameters.

### Optional Parameters

Optional parameters for the SELECT SYMBOL command are:

Parameter	Description
OUT=filename	Directs the symbol information to the specified output file.
PRINT	Directs the output to the printer.
symbol-name	Specifies the 1–17 alphanumeric character name of the symbol.

## Examples

The following command displays the current Connect:Direct HP NonStop symbols.

```
CD.3.>sel symbol
```

A sample display follows:

```
CD.3.>sel symbol
```

SYMBOLS	PARAMETERS
FUP	RUN FUP
IS	INSERT SYMBOL
P	RUN PERUSE
SCF	RUN SCF
SEC	SELECT SECURITY
SN	SELECT NETMAP
SPP	SELECT PROCESS PNUMBER
SS	SELECT STATISTICS
ST	SELECT TYPE
SYM	SELECT SYMBOL

```
CD.4.>
```

---

# Viewing System Information

Use the environment commands to retrieve system information. You can issue these commands at any time during Connect:Direct HP NonStop operation.

This chapter explains the function, format, and parameters of environment commands that retrieve system information. The commands are presented in alphabetical order. An example of each command follows the parameter descriptions.

---

**Note:** Some Connect:Direct HP NonStop environment commands are familiar to users of the HP NonStop operating system. For more information on those commands, refer to the HP NonStop Operating System documentation.

---

---

## Displaying the Status of Connect:Direct HP NonStop Components

Use the STATUS command to display the status of the following components in your Connect:Direct HP NonStop system:

- ❖ Nodes
- ❖ LUs
- ❖ Processes in the CALL, WAIT, and TIMER queues
- ❖ TCP listen ports

### Format

Following is the STATUS command format:

---

```
STATUS          LU* | lu-name
                NODE* | node-name
                q w
                q c
                q t
                tcp
```

---

## Required Parameters

The STATUS command has no required parameters.

## Optional Parameters

Optional parameters for the STATUS command are:

Parameter	Description
lu* lu-name	Specifies the LUs whose status you want to see. STATUS LU *—Specifies all LUs. STATUS LU lu-name—Indicates a specific LU.
node* node-name	Specifies the nodes whose status you want to see. STATUS NODE node*—Specifies all nodes. STATUS NODE node-name—Indicates a specific node.
q w	Retrieves the status of all Processes in the WAIT queue.
q c	Retrieves the status of all Processes in the CALL queue.
q t	Retrieves the status of all Processes in the TIMER queue.
tcp	Retrieves the status of all TCP listen ports.

## Examples

The following command displays the status of the LU named TCP01.

```
CD.7.>status lu tcp01
```

Following is the sample output from the STATUS LU TCP01 command:

```
=====
                STATUS of Connect:Direct HP NonStop version 3.5.00
=====
** HEAP SIZE : 147456
LU      => \NONSTP.TCP01                Logmode=> TANLOG   Type   => TCP.S
Tracefile => NONE
SM Trace => OFF
Snode   =>
TCP Procs =>          $ZTC0              $ZTC1              $ZSAM1
STATE   => STOP      ProcNum=> 0         ProcName>
SM name=>          File Num> 0         Term   => \NONSTP.$ZTN0.#WINJS8
writes => 0        &PQE   => 0         &SNODEB=> 0       PS     => 1
AVAIL   => N        BUSY   => N         QUIESCE=> Y
ERROR   => N        RETRY  => N         USE     => A
MAXSES  => 0        SESLIM => 0       SESCNT => 0
SNODE NAME      SNODE NAME      SNODE NAME      SNODE NAME
CD.DEV.SABCD1   CD45A             CSG.PROD390      GLOBAL
IT.USER2.34     IT.USER2.35      ADJ_NODE-TW     ADJ_NODE2ND
NONSTOP.USER1.34 NSTOP.USER1.343  OLLIE.USER1.360 OS400.USER1.351
OS400.USER1.360 OS400.USER1.361 Q2A.ZOS.V4700   QA160SUN3600
QAOPTSOL3800    S7.USER1.343     S7.USER1.35     SC.DUB.MABCD1
TANDEM.GLOBAL   TESTADAPTER-1    TSC4.USER1.340  TSC4.USER1.341
TSC4.USER1.350  TSC5.USER1.332  TSC5.USER1.340  TSC5.USER1.341
TSC5.USER1.350  WINLT.USER1.440
```



The following command displays the status of the node named s7.USER1.35:

```
CD.11.>status node s7.USER1.35
```

Following is the sample output from the STATUS NODE S7.USER1.35 command:

```
=====
                STATUS of Connect:Direct HP NonStop version 3.5.00
=====
** HEAP SIZE : 147456
SNODE => S7.USER1.35          APPLID => JSS735      PARSES => 0
APINODE=> N                   CRC      => N          DELETE => N
DOMAIN => N                   PLEX   =>          QUIESCE=> N
DYN DNS=> N
IPADDR 1 => fd00:0:0:20a0::35  PORTNUM => 7132
LU list=> LU NAME              RUNNING   DELETE    CLASS  STATUS
          \NONSTP.$LU0TNDM.#LU012  N         N         1      STOP
          \NONSTP.$LU0TNDM.#LU013  N         N         2      STOP
          \NONSTP.TCP01             N         N         3      STOP
          \NONSTP.TCP02             N         N         4      STOP
          \NONSTP.TCP03             N         N         5      STOP
          \NONSTP.TCP04             N         N         6      STOP
          \NONSTP.TCP30D            N         N         7      STOP
          \NONSTP.TCP31D            N         N         8      STOP
          \NONSTP.TCP32D            N         N         9      STOP
          \NONSTP.TCP33D            N         N        10     STOP
          \NONSTP.TCP34D            N         N        11     STOP
          \NONSTP.TCP35D            N         N        12     STOP
          \NONSTP.TCP36D            N         N        13     STOP
          \NONSTP.TCP37D            N         N        14     STOP
          \NONSTP.TCP38D            N         N        15     STOP
          \NONSTP.TCP39D            N         N        16     STOP
```

The following command displays the status of all TCP listen ports:

```
CD.7.>status tcp
```

Following is the sample output from the STATUS TCP command:

```

=====
                STATUS of Connect:Direct HP NonStop version 3.5.00
=====
** HEAP SIZE : 98304
** TIME : 07/16/2008 12:53:41.16

TCPBUFFSIZE 8740

----- TCP LISTEN PROCESSES / PORTS -----
\NONSTP.$ZTC0 , IPv4, Port 11364 : Available ; Accept posted
IP = 10.20.161.34
\NONSTP.$ZTC0 , IPv4, Port 17132 : Available ; Accept posted
IP = 10.20.161.34
\NONSTP.$ZSAM1, IPv6, Port 17132 : Available ; Accept posted
IP = 10.20.160.34
IP = fd00::20a0:a00:8eff:fe05:fd02
IP = fd00:0:0:20a0::34
\NONSTP.$ZSAM1, IPv6, Port 11364 : Available ; Accept posted
IP = 10.20.160.34
IP = fd00::20a0:a00:8eff:fe05:fd02
IP = fd00:0:0:20a0::34
\NONSTP.$ZTC1 , IPv6, Port 17132 : Available ; Accept posted
IP = 10.20.160.33
\NONSTP.$ZTC1 , IPv6, Port 11364 : Available ; Accept posted
IP = 10.20.160.33
\NONSTP.$ZSAM2, IPv6, Port 17132 : Available ; Accept posted
IP = fd00:0:0:20a1::34
\NONSTP.$ZSAM2, IPv6, Port 11364 : Available ; Accept posted
IP = fd00:0:0:20a1::34
\NONSTP.$ZTC0 , IPv4, Port 2002 : Available ; Accept posted
IP = 10.20.161.34
\NONSTP.$ZTC0 , IPv4, Port 2001 : Available ; Accept posted
IP = 10.20.161.34
\NONSTP.$ZTC0 , IPv4, Port 2010 : Available ; Accept posted
IP = 10.20.161.34
\NONSTP.$ZTC0 , IPv4, Port 2011 : Available ; Accept posted
IP = 10.20.161.34

```

## Displaying Logging Information

Use the DISPLAY LOGGING command to display the following:

- ❖ Setting for EMS, which controls whether events are logged to EMS
- ❖ Setting for STATS, which controls whether events are logged to the Connect:Direct HP NonStop statistics file
- ❖ Name of the collector process

The optional parameters for DISPLAY LOGGING allow you to determine how the information is presented. Unless otherwise specified, Connect:Direct HP NonStop displays the output. You can direct the output to a HP NonStop file or to a printer.

## Format

Following is the DISPLAY LOGGING command format:

DISplay LOGging	FILE OUT=filename PRint
-----------------	-------------------------------

## Required Parameters

The DISPLAY LOGGING command has no required parameters.

## Optional Parameters

Optional parameters for the DISPLAY LOGGING command are:

Parameter	Description
FILE	Specifies that Connect:Direct HP NonStop passes back the selected unformatted control block (CB) logging records.
OUT=filename	Specifies the file where Connect:Direct HP NonStop routes the output.
PRint	Specifies that Connect:Direct HP NonStop routes the output of the DISPLAY LOGGING command to the default printer. Printed output is in tabular format.

## Examples

The following command displays output to the home terminal:

```
DISPLAY LOGGING
```

Following is the sample output from the DISPLAY LOGGING command:

```
CD.2.>display logging
=====
07/26/2008                L O G G I N G                16:05:20
=====
STATISTICS ==>>> ON          EMS ==>>> OFF          COLLECTOR ==>>> $0

CD.3.>
```

In this example, all records written to the Connect:Direct HP NonStop statistics file are also written to EMS. The default EMS collector, \$0, is the collector to use for generating event-messages.

---

## Monitoring Statistics File Information

Use the DISPLAY STATINFO command to monitor the following information in a statistics file:

- ❖ File size
- ❖ Number of extents allocated and available
- ❖ Percentage of the file used
- ❖ Settings for the following:
  - ◆ STATCRITERIA (deletion criteria)
  - ◆ STATMIDNITE (midnight processing)
  - ◆ STATPERCENT (maximum allowable percentage the statistics files is utilized before NDMSTDL is created)

Connect:Direct HP NonStop displays the most recent time and date that NDMSTDL executed.

If you issue the DISPLAY STATINFO command without one of the optional parameters, detailed information about the statistics files is displayed.

---

**Note:** The statistics files are key-sequenced files. After the NDMSTDL program runs, the statistics from the DISPLAY STATINFO command may not show a change in the Percentage used or End of File fields, because of the structure of HP NonStop key-sequenced files.

---

Use the UPDATE STATISTICS command to update settings for STATCRITERIA, STATMIDNITE, and STATPERCENT. For syntax and parameter descriptions for the UPDATE STATISTICS command, refer to the *Optimizing Performance* chapter in the *Connect:Direct HP NonStop Administration Guide*.

## Format

Following is the DISPLAY STATINFO command format:

```
DISplay STATinfo      FILE
                       OUT=filename
                       PRINT
                       SHORT
```

## Required Parameters

The DISPLAY STATINFO command has no required parameters.



A sample of the display follows:

```

CD.4.>display statinfo
=====
07/26/2008                      S T A T I N F O                      16:07:11
=====
STATCRITERIA ==>> 8D           STATPERCENT ==>> 50%           STATMIDNITE ==>> ON
-----
*****
* NDMSTD L has not executed since *
*   the Server was initialized   *
*****
-----
FILEINFO for file "\ESCAPE.$work02.ndm34.STATFILE"
Primary Extent Size ==>          100           Maximum Ext. ==> 100
Secondary Extent Size ==>          100           Ext. Allocated ==> 44
Maximum File Size ==>       20480000           End of File ==> 1507328
Percentage Used ==>          7.74%
-----
FILEINFO for file "\ESCAPE.$work02.ndm34.STATSRCH"
Primary Extent Size ==>          120           Maximum Ext. ==> 100
Secondary Extent Size ==>          120           Ext. Allocated ==> 5
Maximum File Size ==>       45056000           End of File ==> 2334720
Percentage Used ==>          3.18%
-----
FILEINFO for file "\ESCAPE.$WORK02.ndm34.STATSRCO"
Primary Extent Size ==>          120           Maximum Ext. ==> 100
Secondary Extent Size ==>          120           Ext. Allocated ==> 12
Maximum File Size ==>       24576000           End of File ==> 2768896
Percentage Used ==>          11.65%
-----
CD.5.>

```

---

## Displaying Initialization Parameters

Use the DISPLAY PARMS command to display the current settings of the initialization parameters and to permanently save changes made using the UPDATE PARM command to the initialization parameters file.

### Format

Following is the DISPLAY PARMS command format:

---

DISplay Parms	FILE
	OUT=filename
	PRint

---

### Required Parameters

The DISPLAY PARMS command has no required parameters.

### Optional Parameters

Optional parameters for the DISPLAY PARMS command are as follows:

---

Parameter	Description
FILE	Specifies that Connect:Direct HP NonStop saves the initialization settings to an output file.
OUT=filename	Specifies the output file where Connect:Direct HP NonStop creates the new initialization parameters file.
PRint	Specifies that Connect:Direct HP NonStop routes the output of the DISPLAY PARMS command to the default printer. Printed output is in tabular format.

---

## Saving Changes to the Initialization Parameters File

To modify initialization parameters and save them to the initialization parameters file:

1. Use the DISPLAY PARMS command to review your current settings.
2. Update the initialization parameters using the UPDATE PARM command. For more information about the UPDATE PARMS command, see *Starting and Stopping Connect:Direct HP NonStop* in the *Connect:Direct HP NonStop Installation Guide*.

---

**Caution:** Although the changes made using the UPDATE PARM command take effect immediately, they are not saved to the initialization parameters file. If you restart Connect:Direct before your changes are saved to the initialization parameters file, the old settings are used.

---

3. To make these changes permanent, use the DISPLAY PARMS command with the OUT or FILE option to create a new initialization parameters file with the changed values.

## Examples

The following command displays the current initialization parameter settings:

```
CD.4.>DISPLAY PARMS
```

Following is the output from the DISPLAY PARMS command:

```

=====
*08/07/2008                      I N I T P A R M S                      12:51:09
=====
*Server $js350, started on Thursday - August 7,2008 at 12:31:15.080
ALLOC-RETRY-INT      300
ALLOC-RETRY-MAX      3
API                  OFF
APIMGR               $DEV.j3500OBJ.APIMGR
APINAME              $AM
APIOUT               $d.#API
AUTHFILE             \NONSTP.$DEV.js35.AUTHFILE
CDLOBJ               \NONSTP.$DEV.j3500DAT.NDMCDL
CKPTFILE             \NONSTP.$DEV.js35.CKPTFILE
CKITVL               0K
CMPRLEVEL            6
COLLECTOR            $0
CRC                  ON
CRCOVERRIDE          YES
DEFAULTS             \NONSTP.$DEV.J3500OBJ
DOMAINSERVER         YES
EMS                  ON
FILENAMEEXT          NO
INFOFILE             \NONSTP.$DEV.js35.INFOFILE
LICENSE_FILE         \NONSTP.$DEV.JS35.LICENSE
LNODE                NSTOP.TEST.350
LOG-TCP-CONN-RQ     YES
MEMLEVEL             8
MSGFILE             \NONSTP.$DEV.j3500DAT.MSGFILE
NDMSMGR              $DEV.J3500OBJ.NDMSMGR
NDMSTDLD             $DEV.j3500OBJ.NDMSTDLD
NTXAPPLID           JSNS35
NTXOFFERS            2
NTXWINDOW            100
NETFILE             \NONSTP.$DEV.JS35.NETFILE
NETMAPCHECK          NO
NTXBLKSIZE           4096
NTXOUT              $d.#NTXOUT
OSSFILES             YES
PORTNUM              11364
PRINTER              $d.#SM
PRTYDEF              10
QUIESCE              YES
RUNTASKMSGID        SRTT010I

```



SECFILE	\NONSTP.\$DEV.JS35.SECFILE
SECUREPL	\NONSTP.\$DEV.j3500SPL
SENDNULLRECS	NO
SENDOPENFILE	WARN
SMNAME	\$JH
SMOUT	\$d.#SMOUT
STATCRITERIA	10D
STATFILE	\NONSTP.\$DEV.JS35.STATFILE
STATMIDNITE	ON
STATPERCENT	50
STATS	ON
STATSRCH	\NONSTP.\$DEV.JS35.STATSRCH
STDIN	\NONSTP.\$DEV.JS35.NDMINIT
STDOUT	\NONSTP.\$D.#JS350
STUTIL	\$DEV.j3500OBJ.STUTIL
TCPBUFFSIZE	16000
TCPNAME	\$ZTC0
TCQ	WARM
TCQFILE	\NONSTP.\$DEV.js35.TCQHFILE
TCQXFILE	\NONSTP.\$DEV.js35.TCQXFILE
TYPEFILE	\NONSTP.\$DEV.JS35.TYPEFILE
WINDOWSIZE	15
WTRETRIES	00:03:00
XLFILE	\NONSTP.\$DEV.JS35.XLFILE
TCPLISTEN1	\$ZTC0 17132
TCPLISTEN2	\$ZSAM1 17132
TCPLISTEN3	\$ZSAM1 11364
TCPLISTEN4	\$ZTC1 17132
TCPLISTEN5	\$ZTC1 11364
TCPLISTEN6	\$ZSAM2 17132
TCPLISTEN7	\$ZSAM2 11364

---

## Displaying the Current Connect:Direct HP NonStop Environment

Use the ENVIRONMENT command to display the current Connect:Direct HP NonStop environment, including the current volume, default system, current obey volume and default Connect:Direct HP NonStop Process volume, as set up in the authorization file (AUTHFILE).

### Format

Following is the ENVIRONMENT command format:

```
ENVIRONMENT
```

### Required Parameters

The ENVIRONMENT command has no required parameters.

### Optional Parameters

The ENVIRONMENT command has no optional parameters.

## Examples

The following command displays the current Connect:Direct HP NonStop environment:

```
CD.2.>ENVIRONMENT
```

A sample Connect:Direct HP NonStop environment follows. The display includes global and user-defined symbols:

```
CD.2.>env
System      : \ESCAPE
Volume      : $DSMSCM.NDM34
Saved volume : $DSMSCM.NDM34
Obey volume : $DSMSCM.NDM34
Proc volume : \ESCAPE.$DSMSCM.NDMPROC
Printer     : $$.#SM
NDMCDL file : \ESCAPE.$work02.NDMOBJ.NDMCDL
USER id    : NDM.USER
NDM Server  : \ESCAPE.$CDV34

Global Symbols :

SYMBOLS                PARAMETERS
-----
DEFAULTS                $DSMSCM.NDM34
LOCALNODE               S7.LOCAL.34
OBEYVOL                 $DSMSCM.NDM34
PROCVOL                 \ESCAPE.$DSMSCM.NDMPROC
STDIN                   \ESCAPE.$ZNTCO.#WINCD0
STDOUT                  \ESCAPE.$ZNTCO.#WINCD0
USERNAME                NDM.USER
USERNUMBER              157.214

User Symbols :

SYMBOLS                PARAMETERS
-----
++ the symbolic variable list is EMPTY
CD.3.>
```

Modify global symbols with the various environment commands described in the following table:

Symbol	Definition	Command to Change Value
DEFAULTS	Displays the current volume.	VOLUME
LOCAL NODE	Displays the local node.	Cannot change the value of the local node. You must delete the local node and use the INSERT NETMAP LOCAL.NODE command to create a new local node with the new name.
OBEYVOL	Displays the default volume used for expansion of the obey file name.	OBEYVOLUME

Symbol	Definition	Command to Change Value
PROCVOL	Displays the default volume used for expansion of the Process file name.	PROCVOL
STDIN	Displays the standard input file.	Cannot change the value of STDIN
STDOUT	Displays the standard output file.	Cannot change the value of STDOUT
USERNAME	Displays the user name used to logon.	LOGON
USERNUMBER	Displays the user number used to logon.	LOGON

---

## Obtaining the Current System Time

Use the TIME command to retrieve the current day, date, and time from the system.

### Format

Following is the TIME command format:

```
TIME
```

### Required Parameters

The TIME command has no required parameters.

### Optional Parameters

The TIME command has no optional parameters.

### Example

The following command displays the day, date, and time stamp:

```
CD.2.>time
Monday - July 26, 2008 - 16:15:24.770
CD.3.>
```

---

## Obtaining the Current NDMCOM Version

Use the VERSION command in NDMCOM to retrieve the version, release, and maintenance level of the currently running NDMCOM executable. To identify versions of other executables such as NDMSMGR, use the VPROC utility at a TACL prompt.

```
> VPROC NDMSMGR
```

### Format

Following is the VERSION command format:

```
VERsion
```

### Required Parameters

The VERSION command has no required parameters.

### Optional Parameters

The VERSION command has no optional parameters.

### Example

The following command displays release information:

```
CD.52.>ver
Connect:Direct HP NonStop version 3.5.00
COPYRIGHT (C) 1991, 2008 Sterling Commerce, Inc.

CD.53.>
```

---

## Defining the Current Volume

Use the VOLUME command to define the current volume during the Connect:Direct HP NonStop session. If you do not specify a parameter, Connect:Direct HP NonStop sets the current volume to the HP NonStop volume at startup.

## Format

Following is the VOLUME command format:

```
VOLume          \system.$volume.subvol
```

## Required Parameters

The VOLUME command has no required parameters.

## Optional Parameter

The VOLUME command has the following optional parameter:

Parameter	Description
\system.\$volume.subvol	Specifies the system, volume, and subvolume for the Connect:Direct HP NonStop volume. The system name is a maximum of 8 characters, including the backslash (\); volume name is a maximum of 8 characters, including the \$; and subvolume is a maximum of 8 characters. <b>Note:</b> If you specify the system name, the volume name is a maximum of 7 characters, including the \$. If you do not specify the system name, the volume name is up to 8 characters. This limitation is a HP NonStop restriction.

## Example

The following command defines the actual working volume for the current session:

```
CD.2.>volume $audit.ndmproc
SAPI138I: (RC=0, FDBK="0")
Current default VOLUME changed to \ESCAPE.$AUDIT.NDMPROC
CD.3.>
```



---

# Managing Processes

This chapter details format and parameters for Process control commands. *User and Administrator Commands* on page 23 provides a list of the commands with a summary of the tasks each command can perform. These commands are presented in alphabetical order. An example of each command follows the parameter descriptions.

---

**Note:** You can also use the Connect:Direct Browser User Interface to build, submit, and monitor Connect:Direct Processes from an Internet browser, such as Microsoft Internet Explorer. See the documentation for that product for more information.

---

---

## Changing Processes

Use the CHANGE PROCESS command to modify Process priority and queue status or to change such job characteristics as destination node, start time, and start date of a nonexecuting Process.

To create a valid command, you must specify *at least one* of the following parameters: LASTPNUMBER, PNAME, PNUMBER, or SUBMITTER. LASTPNUMBER is exclusive of all other required parameters.

## Format

Following is the CHANGE PROCESS command format:

---

CHange PROCess	<b>LAstpnumber</b> † <b>PNAME=name</b>   (list)† <b>PNUMber=number</b>   (list)† <b>SUBmitter=(nodeid,group.user)</b>   (nodeid,alias) DEST=destination node HOLD=Yes  <u>No</u>  Call CLASS=n PLEXCLASS=string PRTY=n RETAIN=Yes  <u>No</u>  Initial STARTT= ([date day] [, hh:mm:ssXM]) RELEASE
----------------	--

---

## Required Parameters

Required parameters for the CHANGE PROCESS command are:

Parameter	Description
LAstpnumber	Enables you to change the last Process submitted during the current NDMCOM session.
PNAME=name (list)	Specifies the name of the Process or a list of Process names. Enclose the list in parentheses, and separate each value with a space or comma (,).
PNUMber=number (list)	Specifies the number of the Process or a list of Process numbers. Enclose the list in parentheses, and separate each value with a space or comma (,). The range is 1–99999.
SUBmitter=(nodeid, group.user)   (nodeid, alias)	Specifies the node ID and guardian userid of the submitting user, or the node ID and alias of the submitting user. <b>Note:</b> You cannot use a wildcard with this parameter.

## Optional Parameters

Optional parameters for the CHANGE PROCESS command are:

Parameter	Description
CLASS=n	Enables you to change the class of the specified Process in the TCQ. Processes remain in the TCQ until a Session Manager with a class greater than or equal to the class of the Process becomes available. If no such Session Manager becomes available, the Process remains pending in the TCQ. Use the CLASS parameter to delay or expedite the execution of a Process that has already been submitted.
DEST=destination-node	Enables you to change the destination node (SNODE) of a Process in the TCQ.
HOLD=Yes No Call	Specifies that Connect:Direct HP NonStop places the Process in the Hold queue. Refer to <i>Connect:Direct HP NonStop Components</i> on page 13 for a description of the TCQ. Yes—Specifies that the Process remains in the Hold queue until one of the following events occur: <ul style="list-style-type: none"> <li>• A CHANGE PROCESS command releases the Process.</li> <li>• A DELETE PROCESS command deletes the Process.</li> </ul> If you specify both HOLD=Yes and a STARTT value, the HOLD specification takes precedence. Therefore, Connect:Direct HP NonStop places a Process submitted with HOLD=Yes on the Hold queue, even if you specify a start time. No—Specifies that the Process is executed as soon as possible. Call—Specifies that Connect:Direct HP NonStop holds the Process until the specified node starts a Process with the HP NonStop node. <b>Note:</b> Connect:Direct HP NonStop ignores the HOLD parameter when you specify RETAIN=Yes with HOLD=No or Call.
PLEXCLASS=string	Specifies a user-defined class containing up to 8 characters associated with a Connect:Direct/Server in a Connect:Direct/Plex environment. This represents a type of server to which you want to submit a Process, for example, TAPE. You may want to modify the PLEXCLASS attribute of a job in the TCQ if the SNODE application rejected the initial process execution because the PLEXCLASS value specified was incorrect.



Parameter	Description
PRTY=n	Specifies a new Process priority in the TCQ. High numbers indicate high priorities; low numbers indicate low priorities. Connect:Direct HP NonStop uses the PRTY parameter for Process selection and not for determining the priority during transmission. The range is from 0–15.
RETAIN=Yes No Initial	<p>Specifies whether Connect:Direct HP NonStop retains a copy of the Process in the TCQ for re-execution after the Process is executed.</p> <p>Yes—Specifies that the system retains the Process after execution. Define RETAIN=Yes in conjunction with the STARTT parameter to specify the day and time to re-execute the Process.</p> <p><b>Note:</b> Do not define a date value in the STARTT parameter when you specify RETAIN=Yes.</p> <p>No—Specifies that the system deletes the Process after execution.</p> <p>Initial—Specifies that the system retains the Process in the TCQ for automatic execution every time Connect:Direct HP NonStop is initialized.</p> <p><b>Note:</b> Do not define the STARTT parameter when you specify RETAIN=Initial.</p>
STARTT=([date day] [,hh:mm:ssXM])	<p>Specifies that the Process is executed on the specified date, day, or time. The date, day, and time are positional parameters. If you do not specify the date or day, a comma (,) must precede the time.</p> <p><b>Note:</b> Do not define the STARTT parameter when you specify RETAIN=Initial.</p> <p>When you do not use delimiters (/ or .), you must specify single-digit days and months in double-digit format. Without delimiters, January 5, 1997 is represented as 01051997 or 19970105.</p> <p>If you only specify the date, the time defaults to 00:00.</p> <p><b>Note:</b> Do not define a date in the STARTT parameter when you specify RETAIN=Yes.</p> <p>date—Specifies the day (dd), month (mm), year (yy), and century (cc).</p> <p>day—Specifies the day of the week. Valid names are MOnday, TUESday, WEDnesday, THURsday, FRIday, SATurday, and SUNday. If you specify the day of the week with RETAIN=Yes— the Process is executed the same day every week.</p> <p>hh:mm:ssXM—Indicates the time of day in hours (hh), minutes (mm), and seconds (ss) that the Process is released for execution. XM can be set to AM or PM. Express the hour in either 12- or 24-hour format. If you use the 12-hour format, then you must specify AM or PM. The default is the 24-hour format.</p> <p>You can also specify the relative values TODAY or TOMORROW and NOON or MIDNIGHT. For more information, see <i>Date Formats</i> on page 81.</p>
RELEASE	Specifies that a held, retained, or suspended Process is moved to the Wait queue for execution.

## Date Formats

Define the date in one of the following formats:

Order	Format
year,month,day	ccyymmdd ccyy/mm/dd ccyy.mm.dd

Order	Format
month.day.year	mmddyy mm/dd/yy mm.dd.yy mmdccyy mm/dd/ccyy mm.dd.ccyy
Julian dates	yyddd (Julian date) yy/ddd (Julian date) yy.ddd (Julian date) ccyyddd (Julian date) ccyy/ddd (Julian date) ccyy.ddd (Julian date)

## Examples

The following command changes the Process named ACCTPROC to a new destination node called mvsnod.b. CUPERTINO. The Process is scheduled for execution at 11:00 pm on December 12, 2008:

```
CD.17.>change process pname acctproc startt=(12/12/2008,23:00:00) dest=mvsnod.b
      SSRV135I: (RC=0, FDBK="0")
Process 77401 changed
      SAPI204I: (RC=0, FDBK="0")
Change command successfully completed.
CD.18.>
```

The following command moves Process number 37 from the Hold or Timer queue to the Wait queue for execution:

```
CD.12.>ch proc pnum 37 release
      SSRV135I: (RC=0, FDBK="0")
Process 37 changed
      SAPI204I: (RC=0, FDBK="0")
Change command successfully completed.
CD.13.>
```

The following command changes a Process submitter class from 4 to 2.

```

CD.7.>SEL PROC DETAIL
=====
3.5.00          S E L E C T   P R O C E S S
=====
Process Name    => S75CRC      Submitter=> NSTOP.TEST.350   NDM.USER
Process Number  => 36140       Snode    => S7.TEST.35       Queue   => Timer
Submitter Class => 4          PlexClass=>                  Priority=> 10
Process File    => \NONSTP.$DEV.JSPROC.S75SMALL   Retain  =>

-----
CD.8.>Change PROC PNUM 36140 CLASS=2
SSRV135I: (RC=0, FDBK="0")
Process 36140 changed
SAPI204I: (RC=0, FDBK="0")
Change command successfully completed.
CD.9.>sel proc detail
=====
3.5.00          S E L E C T   P R O C E S S
=====
Process Name    => S75CRC      Submitter=> NSTOP.TEST.350   NDM.USER
Process Number  => 36140       Snode    => S7.TEST.35       Queue   => Timer
Submitter Class => 2          PlexClass=>                  Priority=> 10
Process File    => \NONSTP.$DEV.JSPROC.S75SMALL   Retain  =>
-----

```

## Deleting Processes

Use the DELETE PROCESS command to remove a nonexecuting Process from the TCQ. To create a valid command, you must specify *at least one* of the parameters LASTPNUMER, PNAME, PNUMBER, SUBMITTER, or DESTINATION. LASTPNUMBER is exclusive of all other required parameters.

### Format

Following is the DELETE PROCESS command format:

---

```

DELEte PROCess      LAstpnumber†
                    PNAME=name | (list) †
                    PNUMber=number | (list) †
                    SUBmitter=(nodeid,group.user) | (nodeid,alias)
                    DESTination=nodeid | (list)

```

---

## Required Parameters

Required parameters for the DELETE PROCESS command are as follows:

Parameter	Description
LAstpnumber	Enables you to delete the last Process submitted during the current NDMCOM session.
PNAME=name (list)	Specifies the name of the Process or a list of Process names. Enclose the list in parentheses, and separate each value with a space or comma (,).
PNUmber=number (list)	Specifies the number of the Process or a list of Process numbers. Enclose the list in parentheses, and separate each value with a space or comma (,). The range is from 1–99999.
SUBmitter=nodeid.group.user  (nodeid,alias)	Specifies the node ID and guardian user ID of the submitting user, or the node ID and alias of the submitting user. <b>Note:</b> You cannot use a wildcard with this parameter.
DESTination   SNODE=nodeid (list)	Enables you to delete the Process or list of Processes for a specific SNODE from the Transmission Control Queue (TCQ) with one command. Enclose the list in parentheses, and separate each value with a space or comma (,). DESTination is an alias for SNODE; you can use either to delete Process(es) for a specific SNODE. <b>Note:</b> SEL PROC is only one letter away from DEL PROC and the letters S and D are adjacent on the US keyboard. Be careful when selecting Processes for display that you not accidentally delete them.

## Optional Parameters

The DELETE PROCESS command has no optional parameters.

## Example

### Delete Processes by PNAME

The following command deletes all non-executing Processes with the name FN131A:

```
CD.19.>del proc pname fn131a
  SSRV133I: (RC=0, FDBK="0")
Process 77407 deleted
  SSRV133I: (RC=0, FDBK="0")
Process 77408 deleted
  SSRV133I: (RC=0, FDBK="0")
Process 77409 deleted
  SAPI205I: (RC=0, FDBK="0")
DELeTe command successfully completed.
CD.20.>
```

## Delete Processes by SNODE

The following command deletes all non-executing Processes on the SNODE OS400.test.361. Note that the DELete PROCess command specifies SNODE as the keyword.

```

CD.3.>sel proc detail
=====
3.5.00                S E L E C T    P R O C E S S
=====
Process Name    => TO400          Submitter=> NSTOP.TEST.350   DEV.USER
Process Number  => 36088          Snode    => OS400.TEST.361   Queue   => Hold
Submitter Class => NONE          PlexClass=>                  Priority=> 10
Process File    => \NONSTP.$DEV.T5PROC.TO400   Retain   =>
CD.4.>del proc snode OS400.test.361
  SSRV133I: (RC=0, FDBK="0")
  Process 36088 deleted
  SAPI205I: (RC=0, FDBK="0")
  DElete command successfully completed.

```

---

## Deleting an Executing Process

Use the FLUSH PROCESS command to delete an executing Process. If you submit a Process with the parameter RETAIN=Yes, the flushed Process remains on the TCQ for execution at the next scheduled time. If you submit the Process with the parameter RETAIN=No, Connect:Direct HP NonStop removes the flushed Process from the TCQ and you must resubmit it for execution. Refer to *Understanding the Transmission Control Queue* on page 37 for a description of the TCQ.

To create a valid command, you must fully qualify *at least one* of the following parameters: LASTPNUMBER, PNAME, PNUMBER, or SUBMITTER.

## Format

Following is the FLUSH PROCESS command format:

---

```

FLUSH PROCess      LAstpnumber†
                   PNAME=name | (list)†
                   PNUMber=number | (list)†
                   SUBmitter=(nodeid,group.user) | (nodeid,alias)†
                   FORCE

```

---

## Required Parameters

The required parameters for the FLUSH PROCESS command are:

Parameter	Description
LASTpnumber	Enables you to flush the last Process submitted during the current NDMCOM session. LASTPNUMBER is exclusive of all other required parameters.
PNAME=name (list)	Specifies the name of the Process or a list of Process names. Enclose the list in parentheses, and separate each value with a space or comma (,).

Parameter	Description
PNUmber=number (list)	Specifies the number of the Process or a list of Process numbers. Enclose the list in parentheses, and separate each value with a space or comma (.). The range is 1–99999.
SUBmitter=(nodeid,group.user)   (nodeid,alias)	Specifies the node ID and guardian userid of the submitting user, or the node ID and alias of the submitting user. <b>Note:</b> You cannot use a wildcard in conjunction with this parameter.

## Optional Parameter

The FLUSH PROCESS command has the following optional parameter:

Parameter	Description
FORCE	Enables you to flush a Process that is waiting for unavailable resources.

## Example

The following command flushes Process PNUM 7002.

```
CD.42.>flush proc pnum 7002
SSRV130I: (RC=0, FDBK="0")
Process 7002 flushed
SAPI206I: (RC=0, FDBK="0")
FLUSH command successfully completed.
CD.43.>
```

## Determining the Number of the Last Submitted Process

Use the LASTPNUMBER command to determine quickly the number of the last Process submitted during the current NDMCOM session.

### Format

Following is the LASTPNUMBER command format:

```
LAstpnumber
```

## Required Parameters

The LASTPNUMBER command has no required parameters.

## Optional Parameters

The LASTPNUMBER command has no optional parameters.

## Example

The following example shows the output from issuing the LASTPNUMBER command:

```
CD.77.>lastp
Last Process Number Submitted: 1312
CD.78.>
```

---

## Resetting the Last Process Number in the TCQ

The SETPNUM utility is a batch program supplied with the Connect:Direct HP NonStop installation file set. It may be used to reset the LASTPNUMBER value stored in the TCQ header file. Process numbers are normally assigned sequentially and increment from 1 to 99999, but the SETPNUM utility can change the current value at the user's discretion. The program is normally run from a TACL prompt. It is not necessary to stop Connect:Direct HP NonStop to run SETPNUM.

## Format

Following is the SETPNUM command format:

---

```
[RUN] SETPNUM tcqxfile nnnnn
```

---

## Required Parameters

Following are the SETPNUM command required parameters.

Parameter	Description
tcqxfile	The name of the TCQ header file (the one with an alternate key file).
nnnnn	The new value to be assigned to LASTPNUMBER.

## Optional Parameters

The SETPNUM command has no optional parameters.

## Example

The following example illustrates the SETPNUM command. After the utility executes, the next Process submitted on the local node would be assigned Process number 5001.

```
$WORK02 NDM34 378> setpnum tcqxfile 5000
PID: 1,392 $SYSTEM.SYSTEM.SETPNUM

Updating the TCQ Header File \ESCAPE.$WORK02.NDM34.tcqxfile.

The LAST PNUMBER is currently set to the value 79399.

The LAST PNUMBER has been successfully updated to the value 5000.

Normal Termination ...

$WORK02 NDM34 379>
```

---

## Monitoring Processes

Use the SELECT PROCESS command to monitor both executing Processes and Processes waiting for execution. Connect:Direct HP NonStop generates a report that includes the Process name and number, submitter node and ID, destination node, and the queue based on the selection criteria specified. You can print or display the report online.

### Format

Following is the SELECT PROCESS command format:

---

```
SELEct PROCess      DEST=node| (list)
                    PNAME=name| (list)
                    PNUMBER=number| (list)
                    SUBmitter=(nodeid,group.user) | (nodeid,alias)
                    QUEUE=ALL|BAD|CALL|EXEC|HOLD|INITIAL|PENDING|RETAIN|SUSPEND|
                        TIMER|WAIT|RETTIMER
                    OUT=filename
                    PRINT
                    FILE
                    DETail
                    LAspnumber
                    SOURCE
```

---

### Required Parameters

The SELECT PROCESS command has no required parameters.

---

**Note:** If you do not specify an optional parameter, Connect:Direct HP NonStop selects all Processes executing or waiting for execution.

---



## Optional Parameters

Optional parameters for the SELECT PROCESS command are:

Parameter	Description
DEST=node (list)	Specifies that Connect:Direct HP NonStop search for the Process by destination node name. You can specify a list of destinations. Enclose the list in parentheses, and separate each value with a space or comma (.).
PNAME=name (list)	Specifies the name of the Process or a list of Process names. Enclose the list in parentheses, and separate each value with a space or comma (.).
PNUMBER=number (list)	Specifies the number of the Process or a list of Process numbers. Enclose the list in parentheses, and separate each value with a space or comma (.). The range is from 1–99999.
SUBmitter= (nodeid,group.user)  (nodeid,alias)	Specifies the node name and user ID in group.user format or node name and alias of the Process submitter. <b>Note:</b> You cannot use a wildcard with this parameter.
QUEUE=ALL  BAD CALL   EXEC  HOLD   INITIAL  PENDING   RETAIN   SUSPEND   TIMER   WAIT   RETTIMER	Specifies to select all Processes on a certain queue. If you do not specify the QUEUE parameter, Connect:Direct HP NonStop includes all queues in the report. Refer to Chapter 3, <i>Queuing Processes</i> , for a description of each queue. <b>Note:</b> You can also enter the first letter of a Queue status as a shortcut, such as QUEUE=H to select all Processes being held.
OUT=filename	Specifies the file where Connect:Direct HP NonStop routes the output.
PRint	Specifies that Connect:Direct HP NonStop route the output of the SELECT PROCESS command to the default printer. Printed output is in tabular format.
FILE	Specifies that Connect:Direct HP NonStop pass back the selected unformatted control block (CB) records.
DETail	Specifies that Connect:Direct HP NonStop generate a detailed report of the selected Process(es). Refer to the section <i>Detailed Report</i> on page 91 for a sample detailed report.
LAstnumber	Specifies to select the last Process submitted.
SOURCE	Recreates the original Process script as it was submitted to create the entry in the Transmission Control Queue (TCQ). This is useful if the source of the original Process is no longer available. The SOURCE keyword produces the Process from the selected TCQ entry. Use with the OUT parameter to route the Process script output to a specified file. If OUT is not specified, the Process script is routed to the requesting terminal. For an example, see <i>Script Source Recovery</i> on page 90. <b>Note:</b> Passwords are not recovered from the TCQ: they show as XXXXXXXX.

## Example

### Script Source Recovery

In this example, assume that the following script is contained in a file called test01 and has been submitted and run from the RETAIN queue for some time:

```
test01 PROCESS SNODE=FRAN.3600  snodeid=(CDDV3500,CDDV3500) CLASS = 1
        SYMBOL      &FROM= /home/tmp/fromtand.txt
        SYMBOL      &TO1 = \NONSTP.$dev.jsdata.UNIXTST3 -
nstp34ps COPY FROM (ioexit=abc sql=abc dbparms=123 -
                   PNODE DISP=(SHR,KEEP,KEEP)) -
                   TO (ioexit=(abc, parm1) dbparms=987 sql=cde -
                      SNODE DISP=(shr,keep,keep))
```

Now, you need to modify the Process but have no idea where the original Process script is. To recover the script and not have to start from scratch, use the SOURCE parameter in the SELECT PROCESS command. To save the output in a file which you can edit, specify the OUT parameter and call the output file *newtest01*. To accomplish this, you execute the following command:

```
SEL PROC TEST01 SOURCE OUT=NEWTEST01
```

The output is as follows:

```
TEST01      PROCESS SNODE=FRAN.3600      -
            SNODEID=(CDDV3500,XXXXXXXX) -
            PNODEID=(DEV.USER,XXXXXXXX) -
            CLASS=1
NSTP34PS    COPY FROM (PNODE -
            DISP=(S,K,K) -
            IOEXIT=\NONSTP.$DEV.SFDATA.ABC -
            SQL=(ABC ) -
            DBPARMS=(123 ))-
            TO (SNODE -
            DISP=(S,K,K) -
            IOEXIT=(ABC, PARM1) -
            SQL=(CDE ) -
            DBPARMS=(987 ))
```

Note that passwords are not recovered; they display as X's.

### Short Report

The following command displays a short report for the specified Process number.

```
SELECT PROCESS PNUMBER=1
```

Output from the preceding command follows:

```

CD.5.>sel proc pnum=1
=====
PNAME      PNUM      SUBMITTER NODE      SUBMITTER ID      OTHER NODE      QUEUE
=====
DALLAS     1         S74.DALLAS          OPR.SMITH         IBM.MVS         Wait
CD.6.>

```

The following table contains a description of each field in the report:

Parameter	Description
PNAME	Specifies the label on the PROCESS statement.
PNUMBER	Specifies the Process number Connect:Direct HP NonStop or an adjacent node assigns when the Process is successfully submitted.
SUBMITTER NODE	Specifies the name of the node submitting the Process.
SUBMITTER ID	Specifies the HP NonStop user name of the submitter.
OTHER NODE	Specifies the name of the other node participating in the transmission.
QUEUE	Indicates the state of the submitted Process(es).

## Detailed Report

The following command displays a detailed report for a specified Process number:

```

SELECT PROCESS PNUMBER=1 DETAIL

```

Output from the preceding command follows:

```

CD.13.>sel proc pnum=1 detail
=====
3.5.00          S E L E C T   P R O C E S S
=====
Process Name    => DALLAS      Submitter=> S74.DALLAS      OPR.SMITH
Process Number  => 1           Snode   => IBM.MVS         Queue   => Exec
Submitted Class => NONE        PlexClass=> TAPE           Priority=> 10
Schedule time   => 09:18:15.0 Date/Day => 07.27.2004
Process File    => \ESCAPE.$A.NDMPROCX.DALLAS      Retain  =>
Executing LU    => \ESCAPE.$L1.#L02
CRC Check       => ON
Step Name       => PULL          Function => COPY            Exec node =>
Execution Class => 1           State   => Exec Prc+PC\Recv data_ru
--->=SENDING
FROM FILE      => BARTON.DATA.ACH
TO FILE        => \ESCAPE.$DATA04.ACHDATA.TODAY
FILE SIZE      => 819200
Rcvd:Bytes=> 102400          Recs=> 128
Xmit Bytes=> 114688         RUs  => 28
-----
CD.14.>

```

The following table contains a description of each field in the report:

<b>Parameter</b>	<b>Description</b>
Process Name	Specifies the label on the PROCESS statement.
Submitter	Specifies the name of the node submitting the Process. In this example, OPR.SMITH is the HP NonStop user name of the submitter.
Process Number	Specifies the number Connect:Direct HP NonStop assigns when the Process is successfully submitted.
Snode	Specifies the name of the other node participating in the transmission.
Queue	Indicates the state of the submitted Process.
Submitted Class	Defines the class of the submitted Process.
PlexClass	Specifies a user-defined class associated with a Connect:Direct/Server in a Connect:Direct/Plex environment, for example, TAPE.
Priority	Indicates the priority of the Process in the TCQ. This priority, used for Process selection, does not affect HP NonStop priority.
Schedule time	Indicates the time a Process is scheduled for execution. This field is only used if a Process is submitted with a STARTT parameter.
Date/Day	Indicates the day or date or both that a Process is scheduled for execution. This field is only used if a Process is submitted with a STARTT parameter.
Process File	Specifies the name of the file containing the submitted Process.
Retain	Indicates that the Process was submitted with the RETAIN parameter, which keeps a copy of a Process in the TCQ after it is executed.
Executing LU	Specifies the name assigned to the executing SNAX, NETEX LU, TCP LU, or ICE LU.
CRC Check	Indicates whether Cyclic Redundancy Checking (CRC) checking is enabled.
Step Name	Specifies the name of the label in the Process that is currently being executed.
Function	Describes the Connect:Direct HP NonStop internal task being performed.
Exec node	Specifies a node on which to perform the function specified in the Process being executed.
Execution Class	Defines the session used for the transfer.
State	Specifies the stage of Process execution.
SENDING	Defines the direction of the data transmission.
FROM FILE	Specifies the name of the file being transmitted.
TO FILE	Specifies the name of the file to receive the transmission.
FILE SIZE	Indicates the size of the file.
Rcvd:Bytes	Indicates the number of bytes received during the session.
Rcvd:Recs	Indicates the number of records received.
Xmit Bytes	Indicates the number of bytes transmitted during the session (including Connect:Direct HP NonStop control information and access method overhead).
Xmit:RUs	Indicates the number of request units transmitted.

---

## Submitting a Process for Execution

Use the SUBMIT command to submit a Process to the TCQ for execution. Optional parameters specified on the SUBMIT command override any corresponding parameters specified on the PROCESS statement.

### Format

Following is the SUBMIT command format:

---

```
SUBMIT          DSN=filename†
                FILE=filename†
                PROC=filename†
                CLASS=n
                HOLD=Yes|No|Call
                NEWNAME=newname
                PACCT='pnode-accounting-data'
                PLEXCLASS=string
                PNODE=primary-node-name
                PNODEID=(id,pswd)
                PRTY=n
                RETAIN=Yes|No|Initial
                SACCT='snode-accounting-data'
                SNODE=secondary-node-name
                SNODEID=(id|alias[,pswd][,newpswd])
                STARTT=([date|day][,hh:mm:ssXM])
                &symbolic_name_1=variable-string-1
                &symbolic_name_2=variable-string-2
                .
                .
                .
                &symbolic_name_n=variable-string-n
```

---

† To create a valid command, you must fully qualify *at least one* of the following required parameters: PROC, DSN, or FILE.

### Required Parameters

Required parameters for the SUBMIT command are:

---

Parameter	Description
DSN=filename	Specifies the name of the file that contains the Process. If the name is not fully qualified, Connect:Direct HP NonStop searches for the file name in the procvolume (PROCVOL) set in the environment. If it is not located, Connect:Direct HP NonStop searches for the file name in the current volume and subvolume.
FILE=filename	Specifies the name of the file that contains the Process. If the name is not fully qualified, Connect:Direct HP NonStop searches for the file name in the procvolume (PROCVOL) set in the environment. If it is not located, Connect:Direct HP NonStop searches for the file name in the current volume and subvolume.
PROC=filename	Specifies the name of the file that contains the Process. If the name is not fully qualified, Connect:Direct HP NonStop searches for the file name in the procvolume (PROCVOL) set in the environment. If it is not located, Connect:Direct HP NonStop searches for the file name in the current volume and subvolume.

---

## Optional Parameters

Optional parameters for the SUBMIT command are:

Parameter	Description
CLASS=n	Determines the node-to-node session on which a Process can execute. Each LU has an assigned default class value that enables a Process to execute on an LU having a matching class value or on LUs with higher class values. Class numbers are assigned in the order in which LUs appear in the network map. If you specify a class of 1, a Process runs on the first available LU. If you do not specify a CLASS value in the PROCESS statement or in this command, CLASS defaults to the default class specified in the PARSESS parameter of the adjacent node network map record.
HOLD=Yes No Call	Specifies that Connect:Direct HP NonStop place the Process in the Hold queue. Yes—Specifies that the Process remain in the Hold queue until a CHANGE PROCESS command releases the Process or a DELETE PROCESS command deletes the Process. If you specify both HOLD=Yes and a STARTT value, the HOLD specification takes precedence. Therefore, Connect:Direct HP NonStop places a Process submitted with HOLD=Yes on the Hold queue, even if you specify a start time. No—Specifies that the Process is executed as soon as possible. This is the default. Call—Specifies that Connect:Direct HP NonStop hold the Process until the specified node starts a Process with the HP NonStop node.
NEWNAME=newname	Specifies the new name given to the Process. The default is the label on the PROCESS statement.
PACCT='pnode-accounting-data'	Specifies the accounting data for the PNODE. The maximum length of the accounting data is 256 characters. If special characters are part of the accounting data, enclose the string in single quotation marks.
PLEXCLASS=string	Specifies a user-defined class containing up to 8 characters associated with a Connect:Direct/Server in a Connect:Direct/Plex environment. This represents a type of server to which you want to submit a Process, for example, TAPE.
PNODE=primary-node-name	Specifies the 1–16 alphanumeric character name of the primary node. The PNODE controls the execution of the Process. <b>Note:</b> The PNODE must be the same as the submitter node. The default value for PNODE is the value defined in the PROCESS statement.
PNODEID=(id alias,pswd)	Specifies security user IDs and passwords at the PNODE. id—Specifies the HP NonStop group number and user number. These numbers can range from 0–255 and are separated by a period (.). Other operating environments limit the security ID to 1–8 alphanumeric characters. alias—Specifies the user records to select in the AUTHFILE. You can enter 1–17 alphanumeric characters including underscores, hyphens, and periods. The first character <i>must</i> be alphabetic. pswd—Specifies the current security password. This parameter is used by the security exit to validate the current security password and is 1–8 alphabetic characters.
PRTY=n	Specifies the Process priority in the TCQ. High numbers indicate high priorities; low numbers indicate low priorities. Connect:Direct HP NonStop uses the PRTY parameter for Process selection and not for determining the priority during transmission. The range is from 0–15. If you do not specify PRTY, the default is the priority defined during Connect:Direct HP NonStop installation.

Parameter	Description
RETAIN=Yes  <u>No</u> Initial	<p>Specifies whether Connect:Direct HP NonStop retains a copy of the Process in the TCQ for reexecution after the Process is executed.</p> <p><b>Yes</b>—Specifies that the system retains the Process after execution. Define RETAIN=Yes in conjunction with the STARTT parameter to specify the day and time to reexecute the Process.</p> <p>If you specify RETAIN=Yes, Connect:Direct HP NonStop automatically holds the Process until you release it, unless you include the STARTT parameter in your Process.</p> <p><b>Note:</b> Do not define a date value in the STARTT parameter when you specify RETAIN=Yes.</p> <p><b>No</b>—Specifies that the system deletes the Process after execution.</p> <p><b>Initial</b>—Specifies that the system retains the Process in the TCQ for automatic execution every time Connect:Direct HP NonStop is initialized. This is the default.</p> <p><b>Note:</b> Do not define the STARTT parameter when you specify RETAIN=Initial.</p>
SACCT='snode-accounting-data'	<p>Specifies the accounting data for the SNODE. The maximum length of the accounting data is 256 characters. If you include special characters in the accounting data, enclose the string in single quotation marks.</p>
SNODE=secondary-node-name	<p>Specifies a 1–16 alphanumeric character name is the node name of the secondary node.</p>
SNODEID=(id alias [,pswd] [,newpswd])	<p>Specifies security USERIDs and security passwords at the SNODE.</p> <p><b>Note:</b> For Connect:Direct HP NonStop, the security USERIDs and passwords are case sensitive.</p> <p><b>id</b>—Specifies the HP NonStop group number and user number. These numbers can range from 0–255 and are separated by a period (.). Other operating environments limit the security ID to 1–8 alphanumeric characters.</p> <p><b>alias</b>—Specifies the user records to select in the AUTHFILE. You can enter 1–17 alphanumeric characters including underscores, hyphens, and periods. The first character <i>must</i> be alphabetic.</p> <p><b>pswd</b>—Specifies the current security password. The security exit uses this parameter to validate the current security password. The password can range from 1–8 alphanumeric characters.</p> <p><b>Note:</b> The VSE (prior to release 2.1.00) nodes and VM nodes only recognize passwords specified in uppercase alphanumeric characters.</p> <p><b>newpswd</b>—Specifies the new security password and can be used by the security system to change the current security password to the new security password (1–8 alphanumeric characters). You can only change the password on the HP NonStop node if SAFEGUARD is running.</p> <p><b>Note:</b> If the SNODE is an OS/400 node, Connect:Direct HP NonStop ignores this subparameter.</p>

Parameter	Description
STARTT=( <i>[date day][,hh:mm:ssXM]</i> )	<p>Specifies the date, day, or time to begin the Process. The date, day, and time are positional parameters. If you do not specify the date or day, a comma (,) must precede the time.</p> <p><b>Note:</b> Do not define the STARTT parameter when you specify RETAIN=Initial.</p> <p><i>date</i>—Specifies the day (dd), month (mm), year (yy), and century (cc). When you do not use delimiters (/ or.), you must specify single-digit days and months in double-digit format. Without delimiters, January 5, 1997 is represented as 01051997 or 19970105.</p> <p>If you only specify the date, the time defaults to 00:00.</p> <p><b>Note:</b> Do not define a date in the STARTT parameter when you specify RETAIN=Yes.</p> <p><i>day</i>—Specifies the day of the week. Valid names are MOneday, TUEsday, WEDnesday, THURsday, FRIday, SATurday, and SUNday. If you specify the day of the week with RETAIN=Yes, the Process is executed the same day every week. If you specify only the day value, the time defaults to 00:00. For example, if you submit a Process on Monday, with Monday as the only STARTT parameter, the Process does not run until the following Monday.</p> <p><i>hh:mm:ssXM</i>—Indicates the time of day in hours (hh), minutes (mm), and seconds (ss). You can set XM to AM or PM. You can express the hour in either 12- or 24-hour format. If you use 12-hour format, then you must specify AM or PM. The default is the 24-hour format. If you define hh:mm:ssXM with RETAIN=Yes, the Process is executed the same time every day. Minutes and seconds are not required.</p> <p>You can also specify the relative values TODAY or TOMORROW and NOON or MIDNIGHT.</p> <p>For more information, see <i>Date Formats</i> on page 81.</p>
&symbolic_name_1=variable-string-1 &symbolic_name_2=variable-string-2 . . . &symbolic_name_n=variable-string-n	<p>Specifies the default value to substitute for the symbolic parameter in the Process.</p> <p>You can specify a null value when the equal (=) sign is immediately followed by a comma (,). Enclose a symbolic parameter containing special characters in single quotation marks.</p>

## Examples

The following command submits the Process named PAYROLL. Because the RETAIN=Yes parameter is specified, the Process is retained after execution. Process accounting data is specified for the PNODE:

```

CD.31.>sub proc=payroll retain=y pacct='1959,DEPT-27'
Tuesday - July 27, 2008 - 09:26:04.020
  SSRV101I: (RC=0, FDBK="0")
Process submitted successfully. Process number : 612
File name      : \ESCAPE.$A.NDMPROCX.PAYROLL
Process name   : PAYROLL      Submit time : 07/27/2008 09:26:03.75
CD.32.>

```



The following command submits the Process named COPYSEQ, which copies the file, MYFILE, to Chicago. The value for &DSN (MYFILE) is substituted in the Process. Here is the command followed by the output:

```

CD.43.>sub proc=copysseq snode=chicago &dsn=myfile
Tuesday - July 27, 2008 - 10:12:15.137
  SSRV101I: (RC=0, FDBK="0")
Process submitted successfully. Process number : 637
File name      : \ESCAPE.$A.NDMPROCX.COPYSEQ
Process name   : COPYSEQ      Submit time : 07/27/2008 10:12:15.14
CD.44.>

```

---

## Moving an Executing Process to the Hold Queue

Use the SUSPEND PROCESS command to place an executing Process on the Hold queue. Release the held Process with the command CHANGE PROCESS RELEASE.

### Format

Following is the SUSPEND PROCESS command format:

---

```

SUSpend PROCess      LAs†tpnumber
                     PNAME=name | (list)†
                     PNUMber=number | (list)†
                     SUBmitter=(nodeid,group.user) | (nodeid,alias)†
                     FORCE

```

---

<sup>†</sup> To create a valid command, you must specify *at least one* of the following parameters: LAs<sup>†</sup>tpnumber, PNAME, PNUMber, or SUBmitter.

### Required Parameters

Required parameters for the SUSPEND PROCESS command are:

---

Parameter	Description
LAs <sup>†</sup> tpnumber	Enables you to suspend the last Process submitted. LAs <sup>†</sup> tpnumber is exclusive of all other required parameters.
PNAME=name (list)	Specifies the name of the Process or a list of Process names. Enclose the list in parentheses, and separate each value with a space or comma (,).
PNUMber=number (list)	Specifies the number of the Process or a list of Process numbers. Enclose the list in parentheses, and separate each value with a space or comma (,). The range is from 1–99999.
SUBmitter=(nodeid,group.user)   (nodeid,alias)	Specifies the node ID and guardian user ID of the submitting user, or the node ID and alias of the submitting user. <b>Note:</b> You cannot use a wildcard with this parameter.

---

## Optional Parameter

The SUSPEND PROCESS command has the following optional parameter:

Parameter	Description
FORCE	Enables you to suspend a Process that is waiting for unavailable resources.

## Examples

Following is an example of a SUSPEND command, using the Process number as the selection criterion.

```
CD.11.>suspend process pnum=5004
  SSRV131I: (RC=0, FDBK="0")
Process 5004 suspended
  SAPI209I: (RC=0, FDBK="0")
SUSpend command successfully completed.
CD.12.>
```

---

# Viewing System Files

This chapter details the formats and parameters required to view certain system files. *User and Administrator Commands* on page 23 provides a list of the user and administrative commands with a summary of the tasks each command can perform. These commands are presented in alphabetical order. An example of each command follows the parameter descriptions.

---

## Referencing the Network Map

Use the SELECT NETMAP command to reference the network map for definitions of local and adjacent nodes, API managers, LUs, or LOGMODES you are authorized to use.

You can specify whether the output from this command is displayed, printed, or sent to a file.

---

**Note:** Fields without information are excluded from the output.

---

## Format

Following is the SELECT NETMAP command format:

---

```
SElect NETmap          ADJacent=*|generic|(list)
                       NODE=*|generic|(list)
                       AMGR=*|generic|(list)
                       LU=*|generic|(list)
                       LOGMODE=name|generic|(list)
                       SOURCE
                       FILE
                       Print
                       OUT=filename
```

---

## Required Parameters

The SELECT NETMAP command has no required parameters. If a specific node or LU is not specified, Connect:Direct HP NonStop selects all network map entries, including nodes, API managers, LUs, and LOGMODES.

## Optional Parameters

Optional parameters for the SELECT NETMAP command are:

Parameter	Description
ADJacent=*  generic  (list)	<p>Specifies that only adjacent nodes are to be selected in the network map. *—Specifies all adjacent nodes.</p> <p><b>Note:</b> If you specify only an asterisk (*), the system displays (or prints) a report of the adjacent nodes you are authorized to use.</p> <p>generic—Specifies generic selection of node names for a partial match. To specify node names generically, type a 1–7 alphanumeric string plus an asterisk (*). For example, if your network includes nodes named PHOENIX, SANDIEGO, SANFRAN, and TUCSON, a specification of SAN* provides information about the SANDIEGO and SANFRAN nodes.</p> <p>list—Specifies multiple node names. Enclose the list in parentheses, and separate each value with a space or comma (.). You can also specify wildcards for generic operands. For example:</p> <pre>sel net adj (a*, f*, denver)</pre>
NODE=*  generic  (list)	<p>Specifies the node names to be selected in the network map. *—Specifies all nodes.</p> <p><b>Note:</b> If you specify only an asterisk (*), the system displays (or prints) a report of the nodes you are authorized to use.</p> <p>generic—Specifies generic selection of node names for a partial match. To specify node names generically, type a 1–16 alphanumeric string plus an asterisk (*) with the first character alphabetic.</p> <p>list—Specifies multiple node names. Enclose the list in parentheses, and separate each value with a space or comma (.). You can also specify wildcards for generic operands. For example:</p> <pre>sel net adj (a*, f*, denver)</pre>
AMGR=*  generic  (list)	<p>Specifies that only API manager records are to be selected in the network map. *—Specifies all API manager records.</p> <p><b>Note:</b> If you specify only an asterisk (*), the system displays (or prints) a report of the AMGRs you are authorized to use.</p> <p>generic—Specifies generic selection of API manager records for a partial match. To specify AMGRs generically, type a 1–25 alphanumeric string plus an asterisk (*) with the first character alphabetic.</p> <p>list—Specifies multiple AMGRs. Enclose the list in parentheses, and separate each value with a space or comma (.). You can also specify wildcards for generic operands. For example:</p> <pre>sel net adj (a*, f*, denver)</pre>
LU=*  generic  (list)	<p>Specifies the LUs to select in the network map. *—Specifies all LU records.</p> <p><b>Note:</b> If you specify only an asterisk (*), the system displays (or prints) a report of the LUs you are authorized to use.</p> <p>generic—Specifies generic selection of LU records for a partial match. To specify LUs generically, type a 1–25 alphanumeric string plus an asterisk (*). You can fully qualify the name, which includes the system name if it differs from the home system.</p> <p>list—Specifies multiple LUs. Enclose the list in parentheses, and separate each value with a space or comma (.). You can also specify wildcards for generic operands. For example:</p> <pre>sel net adj (a*, f*, denver)</pre>

Parameter	Description
LOGMODE=* generic  (list)	<p>Specifies the LOGMODEs in the network map to select. *—Specifies all LOGMODEs.</p> <p><b>Note:</b> If you specify only an asterisk (*), the system displays (or prints) a report of the LOGMODEs you are authorized to use.</p> <p>generic—Specifies generic selection of LOGMODE records for a partial match. To specify LOGMODEs generically, type a 1–7 alphanumeric string plus an asterisk (*) with the first character alphabetic. You can fully qualify the name, which includes the system name if it differs from the home system. The system displays (or prints) a report of the LUs you are authorized to use.</p> <p>list—Specifies multiple LOGMODE names. Enclose the list in parentheses, and separate each value with a space or comma (,). You can also specify wildcards for generic operands. For example:</p> <pre>sel net adj (a*, f*, denver)</pre>
SOURCE	Specifies that Connect:Direct HP NonStop generates source statements from the network map.
FILE	Specifies that Connect:Direct HP NonStop pass back the selected unformatted control block (CB) network map records.
PRint	Specifies that Connect:Direct HP NonStop routes the output of the SELECT NETMAP command to the default printer. Printed output is in tabular format.
OUT=filename	Specifies the file where Connect:Direct HP NonStop routes the output.

## Examples

The following command displays the adjacent nodes with which HPNONSTOP.NODE can communicate. The asterisk specification lists all adjacent nodes in the network map. Connect:Direct HP NonStop directs the output to the ALLNODES file in the current volume and subvolume.

```
CD.17.>SELECT NETMAP NODE=* OUT=ALLNODES
```

Output from the preceding command follows:

```

CD.17.> sel net node=*
=====
3.5.00          S E L E C T   N E T W O R K   M A P
=====
Local Node      => HPNONSTOP.NODE
-----
Adjacent Node => CCAPI
Node Type      => NDM.API
Maxretry       => 7
IPaddr         => 10.20.4.131
API Mgr List   => \ESCAPE.CCENTER
-----
Adjacent Node => CD.OS390.1STBANK
Node Type      => NDM.zOS
Maxretry       => 7
Applid         => M1CDD7F7
IPaddr         => 10.20.129.145
Portnum        => 8039
Secure         => PAYROLL
CRC Check      => ON
TCPNAME        => $ZTC0
LU List        => \ESCAPE.$TKN6.#LU24082      \ESCAPE.$TKN6.#LU24083
                \ESCAPE.TCP01              \ESCAPE.TCP02
-----
Adjacent Node => K2000.TEST.NODE
Node Type      => NDM.NonStop
Maxretry       => 3
Def Ses Class  => 5
IPaddr         => k2002
Portnum        => 6132
LU List        => \ESCAPE.TCP03              \ESCAPE.TCP04
-----
Adjacent Node => CATCH.ALL
Node Type      => NDM.DOMAIN
Maxretry       => 7
IPaddr         => 10.23.0.0
IPMask         => 255.255.0.0
LU List        => \ESCAPE.$TCP.#L24
-----
CD.18.>

```

The following command uses the SOURCE parameter to scan the network map and automatically generate an HP NonStop obey file. The generated file contains INSert NETmap and RELate NETmap commands that are necessary to rebuild the network map. Use this command to convert and reload your netmap if you are converting from any currently supported release of Connect:Direct HP NonStop.

```
SEL NET SOURCE OUT=name of obey file to be generated
```

---

## Examining User Records in the Security File

Use the SELECT SECURITY command to examine user records in the security file.

The parameters used with the SELECT SECURITY command allow you to determine search criteria and the format of the information presented. You can specify search criteria by SNODE (adjacent node name) or USER (USERID on the adjacent node). You cannot select security records by the local USERID.

If you do not specify an optional parameter, Connect:Direct HP NonStop displays the contents of the security file.

### Format

Following is the SELECT SECURITY command format:

---

```
SElect SEcurity      FILE
                    OUT=filename
                    PRint
                    SNODE=adjacent-nodename| (list)
                    USER=adjacent-node-userid| (list)
```

---

### Required Parameters

The SELECT SECURITY command has no required parameters.

### Optional Parameters

Optional parameters for the SELECT SECURITY command are:

Parameter	Description
FILE	Specifies that Connect:Direct HP NonStop pass back the selected unformatted control block (CB) security records.
OUT=filename	Specifies the file where Connect:Direct HP NonStop routes the output.
PRint	Specifies that Connect:Direct HP NonStop print rather than display the output of the SELECT SECURITY command. Printed output is in tabular format. Connect:Direct HP NonStop routes the output to the default printer.
SNODE=adjacent-nodename (list)	Specifies to select security records by adjacent (secondary) node name. adjacent-nodename—Specifies the name of the adjacent node and is a maximum of 16 characters. list—Specifies multiple adjacent node names. Enclose the list in parentheses, and separate each value with a space or comma (,).
USER=adjacent-node-USERID (list)	Specifies to select security records by the USERID at the adjacent node. adjacent-node-USERID—Specifies the USERID at the adjacent node and is a maximum of 17 characters. list—Specifies multiple adjacent node USERIDs. Enclose the list in parentheses, and separate each value with a space or comma (,).

---

## Examples

The following command displays all user records in the security file:

```
CD.25.>SELECT SECURITY
```

The following command selects security records by SNODE and displays all user records for the adjacent node named BOSTON:

```
CD.26.>SELECT SECURITY SNODE=BOSTON
```

The following command selects all security records where the USERID is SMITH in the adjacent node:

```
CD.30.>SELECT SECURITY USER=SMITH
```

The following command selects all security records where the USERID is JONES or SMITH in the adjacent node:

```
CD.27.>SELECT SECURITY USER=(JONES, SMITH)
```

Output from the preceding command follows:

```
CD.27.>sel sec user=(JONES, SMITH)
=====
3.5.00          S E C U R I T Y   I N F O R M A T I O N
                    (by USER)
=====
Other User ID => JONES
Other Node   => BOSTON
Local User ID => OPR.JOHN
-----
Other User ID => SMITH
Other Node   => CHICAGO
Local User ID => OPR.BOB
-----
CD.28.>
```

---

## Examining Statistics Records

Use the SELECT STATISTICS command to examine statistics for Processes and to get information regarding LU status and internal messages. The type of information in the statistics report includes such data as date, Process name and number, PNODE, SNODE, return code, message ID, feedback, file name, short message text, and LU name. An example of a statistics log is displayed in the SELECT Statistics sample output on page 109. An explanation of each record follows the log.

The parameters used with the SELECT STATISTICS command allow you to determine search criteria and the format of the information presented. Unless otherwise specified, Connect:Direct HP NonStop displays the output. You can also direct the output to a HP NonStop file or route it to a printer.



If you do not indicate a search requirement with an optional parameter, Connect:Direct HP NonStop selects all statistics records. The volume of all records can be excessive.

## Format

Following is the SELECT STATISTICS command format:

---

```

SElect STATistics      CCOde=(condition, completion code)
                       EXCLUDE=MSG|NOTMSG|NOTCMD
                       INCLUDE=CMD
                       FILE
                       LAsTpnumber
                       OUT=filename
                       PNAME=name | <partial name>*
                       PNUMber=number
                       PPrint
                       SNOde=secondary-node-name | <partial name>*
                       STARTT=([date|day] [,hh:mm:ssXM])
                       STEPend
                       STOPT=([date|day] [,hh:mm:ssXM])
                       SUBmitter=nodeid, (group.user|alias)
                       SHORt

```

---

## Required Parameters

The SELECT STATISTICS command has no required parameters.

## Optional Parameters

Optional parameters for the SELECT STATISTICS command are as follows:

Parameter	Description
CCODE=(condition, completion code)	Specifies that Connect:Direct HP NonStop searches for statistics records by completion code. condition—Specifies a relationship to the completion code given in the subsequent positional parameter. The options for specifying condition are GT (greater than), LT (less than), EQ (equal to), NE (not equal to), GE (greater than or equal to), or LE (less than or equal to). completion code—Specifies a completion code value, which can range from 0–2,147,483,647 to allow for all values that can be passed after execution of the various Process statements. This last value represents a maximum 31-bit binary number. For example, if you specify CCODE=(GT,0), the selected statistics records are those in which the step completion code is greater than zero, as long as the records also meet other specified criteria.
EXCLUDE=MSG   NOTMSG   NOTCMD	Specifies whether Connect:Direct HP NonStop includes message panels, operator commands, and statistical information in the statistics log. MSG—Exclude all messages leaving only statistics in the statistics report. NOTMSG—Exclude all statistics leaving only messages in the statistics report. NOTCMD—Exclude all statistics leaving only commands in the statistics report.

Parameter	Description
INCLUDE=CMD	Specifies that Connect:Direct HP NonStop include previously executed commands along with statistical information in the statistics log. The INCLUDE= CMD option works with SEL STAT commands that return a range of time, such as SEL STAT by itself or with the STARTT or STOPTH options. It does not work with other qualifiers, such as PNUM or PNAME. It does not include any parameters, but it does identify the user, command, terminal and, usually, the target of the command.
FILE	Specifies that Connect:Direct HP NonStop passes back the selected unformatted control block (CB) statistics records.
LAstpnumber	Specifies to select statistics records for the last Process submitted.
OUT=filename	Specifies the file where Connect:Direct HP NonStop routes the output.
PNAME=name   <partial name>*	Specifies the name of the Process. You can specify the full name or use the wildcard character, *, to specify a partial name of the Process. Specify * to indicate all Processes. Specify the leading letters and numbers of a Process name followed by * to indicate a partial Process name.
PNUMber=number	Specifies the number of the Process. The range is from 1–99999.
PRint	Specifies that Connect:Direct HP NonStop route the output of the SELECT STATISTICS command to the default printer. Printed output is in tabular format.
SHORT	Displays a summary statistics report.
SNODE=secondary-node-name   <partial name>*	Indicates that Connect:Direct HP NonStop searches for statistics for the specified secondary node (SNODE). You can specify the full name or use the wildcard character, *, to specify a partial name of the SNODE. Specify * to indicate all SNODEs. Specify the leading letters and numbers of an SNODE name followed by * to indicate a partial SNODE name.
STARTT=([date day [,hh:mm:ssXM])	<p>Specifies that Connect:Direct HP NonStop search for statistics records starting with a designated starting date, day, and time. The date, day, and time are positional parameters. If you do not specify the date or day, a comma (,) must precede the time.</p> <p>If you do not specify the STARTT parameter, the search criterion consists of any time before the value you specify for the STOPTH parameter.</p> <p>date—Specifies the day (dd), month (mm), year (yy), and century (cc). When you do not use delimiters ( / or . ), you must specify single-digit days and months in double-digit format. Without delimiters, January 5, 1997 is 01051997 or 19970105. If you only specify the date, the time defaults to 00:00.</p> <p>day—Specifies the day of the week. Valid names are MOnday, TUESday, WEDnesday, THursday, FRiday, SATurday, and SUnDay. If you specify only the day value, the time defaults to 00:00.</p> <p>hh:mm:ssXM—Indicates the time of day in hours (hh), minutes (mm), and seconds (ss). You can set XM to AM or PM. The hour is expressed in either 12- or 24-hour format. If you use 12-hour format, then you must specify AM or PM. The default is the 24-hour format.</p> <p>You can also specify the relative values TODAY or TOMORROW and NOON or MIDNIGHT.</p> <p>For more information, see <i>Date Formats</i> on page 81.</p>
STEPend	Specifies that Connect:Direct HP NonStop only selects STEPEND records.

Parameter	Description
STOPT=( <i>[date day]</i> <i>[,hh:mm:ssXM]</i> )	<p>Specifies that Connect:Direct HP NonStop search for statistics records up to and including the designated date, day, and time positional parameters.</p> <p>If you do not specify the date or day, a comma (,) must precede the time. If you do not specify the STOPT parameter, Connect:Direct HP NonStop selects statistics until the present time. If you only specify time of day (not date) in the STOPT parameter, Connect:Direct HP NonStop selects all statistics through the most recent entry for that time of day.</p> <p><i>date</i>—Specifies the day (dd), month (mm), year (yy), and century (cc) When you do not use delimiters ( / or . ), you must specify single-digit days and months in double-digit format. Without delimiters, January 5, 1997 is 01051997 or 19970105. If you only specify the date, the time defaults to 00:00.</p> <p><i>day</i>—Specifies the day of the week. Valid names are MOnday, TUEsday, WEdnesday, THursday, FRiday, SATurday, and SUNday. If you specify only the day value, the time defaults to 00:00.</p> <p><i>hh:mm:ssXM</i>—Indicates the time of day in hours (hh), minutes (mm), and seconds (ss). You can set XM to AM or PM. The hour is expressed in either 12- or 24-hour format. If you use 12-hour format, then you must specify AM or PM. The default is the 24-hour format.</p> <p>You can also specify the relative values TODAY or TOMORROW and NOON or MIDNIGHT.</p> <p>For more information, see <i>Date Formats</i> on page 81.</p>
SUBmitter=( <i>nodeid,group.user</i> ) <i>(nodeid,alias)</i>	<p>Specifies the nodeid and group name (or number), USERID (or number), and alias of the Process submitter.</p> <p><i>group.*</i>—Searches all users of a specific group.</p> <p><i>*.*</i>—Searches all users of all groups.</p> <p><i>alias</i>—Specifies the user records to select in the AUTHFILE. Enter 1–17 alphanumeric characters including underscores, hyphens, and periods. The first character <i>must</i> be alphabetic.</p>
SHORT	Displays a summary statistics report.

## Examples

The following command searches for statistics records based on the partial Process name *s75\**:

```
CD.11.>SELECT STATISTICS PNAME s75* SHORT
```

Sample output from the preceding command follows:

```
CD.11.>SELECT STATISTICS PNAME s75* SHORT
=====
3.5.00
  DATE      TIME      PNUM  PNAME  EVENT      DESCRIPTION
=====
06.23.2008 14:07:12 36076 S75CRC PROCSTART
06.23.2008 14:07:13 36076 S75CRC STEPSTART S75CRC1 COPY
06.23.2008 14:07:13 36076 S75CRC STEPEND   S75CRC1 Completed successfully
06.23.2008 14:07:14 \ESCAPE.TCP01 MSG CPU S+ Handshake 0.83 secs, S+
06.23.2008 14:07:14 \ESCAPE.TCP01 MSG FMH7404 received, ending proces
06.23.2008 14:07:14 36076 S75CRC PROCEND   Process finished successfully
```

The following command searches for STEPEND statistics records for the last Process submitted:

```
CD.22.>SELECT STATISTICS STEPEND LASTPNUMBER
```

The following command searches only for commands previously executed.

```
CD.5.>sel stat exclude notcmd
```

This command generates the output shown in the following sample. This type of report, which excludes all statistical information leaving only commands entered by the operator, can be used to create an audit trail of events.

```
=====
3.5.00                S E L E C T    S T A T I S T I C S
=====
Date   => 07.14.2008  Time       => 14:11:53.35  COMMAND - CMDSTAT
User   => OPR.SMITH   \NONSTP.$ZTN0.#WINJS0  Command  => UPD_NETMAP
LU/Amgr => TCP01

Date   => 07.15.2008  Time       => 08:01:37.52  COMMAND - CMDSTAT
User   => OPR.SMITH   \NONSTP.$ZTN0.#WINJS0  Command  => UPD_NETMAP
LU/Amgr => TCP01

Date   => 07.15.2008  Time       => 08:21:17.79  COMMAND - CMDSTAT
User   => OPR.SMITH   \NONSTP.$ZTN0.#WINJS0  Command  => MODIFY
LU/Amgr => TCP01      RESUME

Date   => 07.15.2008  Time       => 12:05:47.51  COMMAND - CMDSTAT
User   => OPR.SMITH   \NONSTP.$ZTN0.#WINJS0  Command  => MODIFY
LU/Amgr => TCP01      RESUME
Trace=>  T:D:F:L:O\$TRACE

Date   => 07.15.2008  Time       => 12:05:57.64  COMMAND - CMDSTAT
User   => OPR.SMITH   \NONSTP.$ZTN0.#WINJS0  Command  => MODIFY
LU/Amgr => TCP01      QUIESCE

Date   => 07.15.2008  Time       => 12:07:16.87  COMMAND - CMDSTAT
User   => OPR.SMITH   \NONSTP.$ZTN0.#WINJS0  Command  => MODIFY
LU/Amgr => TCP01      QUIESCE

Date   => 07.15.2008  Time       => 12:08:18.81  COMMAND - CMDSTAT
User   => OPR.SMITH   \NONSTP.$ZTN0.#WINJS0  Command  => MODIFY
LU/Amgr => TCP01      QUIESCE
```

The following command searches for statistics records based on the Process number. The output is printed.

```
CD.37.>SELECT STATISTICS PNUM=1 PRINT
```

Sample output from the preceding command followed by an explanation of the records and their associated fields follows:

```
CD.37.>SEL STAT PNUM=1
=====
3.5.00          S E L E C T    S T A T I S T I C S
=====
Date   => 07.27.2008  Time       => 10:33:54.12  PROCESS - SUBMIT
Pnumber => 1          Node        => IBM.390          PlexClass =>
Pname  => DALLAS     Submitter => S74.DALLAS      OPR.SMITH
Rtncd  => 0          Message ID=> SSRV101I      Feedback  => 0
File   => \ESCAPE.$A.NDMPROCX.DALLAS
        SSRV101I: (RC=0, FDBK="0")
        Process submitted successfully. Process number : 1
        File name      : \ESCAPE.$A.NDMPROCX.DALLAS
        Process name  : DALLAS      Submit time : 07/27/2008 10:33:54.11
-----
Date   => 07.27.2008  Time       => 10:33:54.54  PROCESS - PROCSTART
Pnumber => 1          Snode       => IBM.390          Xnode     => P
Pname  => DALLAS     Submitter => S74.DALLAS      OPR.SMITH
Class  => 1          PlexClass  =>                CRC Check => ON
LU Name => \ESCAPE.TCP01
Portnum => 9041
IPaddr => 10.20.201.2
-----
Date   => 07.27.2008  Time       => 10:33:55.05  PROCESS - STEPSTART
Pnumber => 1          Snode       => IBM.390          Xnode     => P
Pname  => DALLAS     Submitter => S74.DALLAS      OPR.SMITH
Function=> COPY      Step Name  => PULL
From Snode DSN= PROJX1.DATA.REC800
To Pnode  DSN= \ESCAPE.$DATA03.PROJX1.REC800
-----
```

*Continued*

Continued

```

Date    => 07.27.2008   Time       => 10:33:57.98   PROCESS - STEPEND
Pnumber => 1             Xlate     =>                Start Date=> 07.27.2008
Pname   => DALLAS       Compress  => NO             End Date  => 07.27.2008
Msgid   => SCPA000I    Restart   => NO             Start Time=> 10:33:55.04
Rtncd   => 0           Link Stat => OK             End time  => 10:33:57.68
FDBK    => 0           Snode     => IBM.390       Direction => RECEIVING
Step     => PULL       Submitter => S74.DALLAS    OPR.SMITH
From Snode DSN= PROJX1.DATA.REC800
      FILE SIZE => 819200
      I/O Bytes=> 800000      Xmit Bytes=> 802000      RUsize=>4096
      I/O Recs => 1000      Xmit RUs  =>                Comp%=> 0.00
To Pnode DSN= \ESCAPE.$DATA03.PROJX1.REC800
      I/O Bytes=> 800000      Xmit Bytes=> 802000
      I/O Recs => 1000      Xmit RUs  => 196          Comp%=> 0.00
                          Bytes/Sec => 343347.6

      SCPA000I: (RC=0, FDBK="0")
      Copy operation successful.
      A copy operation completed successfully.

SYSTEM ACTION:

RESPONSE:      None.
.....
Date    => 07.27.2008   Time       => 10:33:58.25   PROCESS - STEPSTART
Pnumber => 1             Snode      => IBM.390       Xnode     => P
Pname   => DALLAS       Submitter  => S74.DALLAS    OPR.SMITH
Function=> RUNTASK     Step Name  => REPORT

-----
Date    => 07.27.2008   Time       => 10:34:00.65   PROCESS - STEPEND
Pnumber => 1             Node       => IBM.390       PlexClass =>
Pname   => DALLAS       Submitter  => S74.DALLAS    OPR.SMITH
Rtncd   => 0           Message ID=> SRTT010I     Feedback  => 0
Program => \ESCAPE.$SYSTEM.SYSTEM.PUTMSG
      SRTT010I: (RC=0, FDBK="0")

Run Task Process $Z6962 terminated normally.

-----
Date    => 07.27.2008   Time       => 10:34:00.83   MESSAGE - MSG
Pnumber => 1             Node       => IBM.390       PlexClass =>
Pname   => DALLAS       Submitter  => S74.DALLAS    OPR.SMITH
LU Name => \ESCAPE.TCP01
Exit step, ending process execution - (execute_process)

-----
Date    => 07.27.2008   Time       => 10:34:01.14   PROCESS - PROCEND
Pnumber => 1             Snode      => IBM.390       Xnode     => P
Pname   => DALLAS       Submitter  => S74.DALLAS    OPR.SMITH
Rtncd   => 0           Message ID=> SSMT000I     Feedback  => 0
      SSMT000I: (RC=0, FDBK="0")
End of C:D Process.

-----
CD.38.>

```

The various elements of the statistics log are divided into eight records: SUBMIT, PROCSTART, STEPSTART and STEPEND for the COPY function, STEPSTART and STEPEND for the RUNTASK function, MSG, and PROCEND. Other records not included in the sample output include: SESSSTART, SESEND, and COMMAND.

## PROCESS-SUBMIT Record

The PROCESS-SUBMIT record provides statistics detailing the submittal of the Process. The following table contains a description of each line in the record:

Line	Description
Date	Indicates the date the Process is submitted to the TCQ.
Time	Indicates the time the Process is submitted to the TCQ.
PROCESS-SUBMIT	Specifies the label describing this phase of the submitted Process.
Pnumber	Specifies the Process number Connect:Direct HP NonStop assigns when the Process is submitted successfully.
Node	Specifies the secondary node name.
PlexClass	Specifies a user-defined class associated with a Connect:Direct/Server in a Connect:Direct/Plex environment, for example, TAPE.
Pname	Specifies the label on the PROCESS statement.
Submitter	Specifies the name of the node submitting the Process. In this example OPR.SMITH is the HP NonStop user name of the submitter.
Rtncd	Specifies the completion code for the step. Zero (0) indicates successful completion of a step.
Message ID	Specifies the identification number of the message in the online message file.
Feedback	Specifies optional information for diagnostic purposes.
File	Specifies the name of the file containing the Process being submitted.
SSRV1011	Specifies the identification number of the message in the online message file. The text is displayed below the message ID number. In this case, the Process was submitted successfully. The return code and feedback are repeated as part of the message text.
Process number 1	Repeated as part of the message text and is the Process number Connect:Direct HP NonStop assigns when the Process is submitted successfully.
File name	Specifies the name of the file containing the Process being submitted.
Process name	Specifies the label on the PROCESS statement.
Submit time	Indicates the date and time the Process is submitted to the TCQ.

## PROCESS-PROCSTART Record

The PROCESS-PROCSTART record provides statistics about the start of the Process. The following table contains a description of each line in the record:

Line	Description
Date	Indicates the date the Process started running.
Time	Indicates the time the Process started running.
PROCESS-PROCSTART	Specifies the label describing this phase of the submitted Process.

Line	Description
Pnumber	Specifies the Process number Connect:Direct HP NonStop assigns when the Process is submitted successfully.
Snode	Specifies the secondary node name.
Xnode	Indicates the node with Process control. In this example, the Xnode is the PNODE.
Pname	Specifies the label on the PROCESS statement.
Submitter	Specifies the name of the node submitting the Process. In this example, OPR.SMITH is the HP NonStop user name of the submitter.
Class	Defines the session used.
PlexClass	Specifies a user-defined class associated with a Connect:Direct/Server in a Connect:Direct/Plex environment, for example, TAPE.
CRC Check	Indicates whether Cyclic Redundancy Checking (CRC) is enabled.
LU Name	Specifies the name assigned to the LU in the network map file.
Portnum	Indicates the TCP/IP port number used in the session.
IPaddr	Indicates the IP address used in the session.

## PROCESS-STEPSTART Record

The PROCESS-STEPSTART record provides statistics detailing the start of a step of a Process. The following table contains a description of each line in the record for the PULL step of the COPY function:

Line	Description
Date	Indicates the date the particular step of a Process started running.
Time	Indicates the time the particular step of a Process started running.
PROCESS-STEPSTART	Specifies the label describing this phase of the submitted Process.
Pnumber	Specifies the Process number Connect:Direct HP NonStop assigns when the Process is submitted successfully.
Snode	Specifies the secondary nodename.
Xnode	Indicates the node transmitting the data during this step. In this example, the Xnode is the PNODE.
Pname	Specifies the label on the PROCESS statement.
Submitter	Specifies the name of the node submitting the Process. In this example, OPR.SMITH is the HP NonStop user name of the submitter.
Function	Specifies the subroutine name for the particular step in the Process. This name is part of the internals of Connect:Direct HP NonStop and is used for diagnostic purposes. In this case, it identifies the COPY statement entered as part of the Process.
Step Name	Specifies the label in the Process.



<b>Line</b>	<b>Description</b>
From Snode DSN	Specifies the name of the data set or file from which the data is being transmitted. In this example, the Process is being submitted from the SNODE. May include a file name extension to indicate the type of data contained in the file.
To Pnode DSN	Specifies the name of the data set or file that is receiving the transmission. In this example, the Process is being sent to the PNODE. May include a file name extension to indicate the type of data contained in the file.

## PROCESS-STEPEND Record

The PROCESS-STEPEND record provides statistics detailing the end of a step of a Process. The following table contains a description of each line in the record for the PULL step of the COPY function:

<b>Line</b>	<b>Description</b>
Date	Indicates the date the particular step of a Process stopped running.
Time	Indicates the time the particular step of a Process stopped running.
PROCESS-STEPEND	Specifies the label describing this phase of the submitted Process.
Pnumber	Specifies the Process number Connect:Direct HP NonStop assigns when the Process is submitted successfully.
Xlate	Indicates translation from ASCII to EBCDIC or EBCDIC to ASCII. If the field is blank, no translation occurred.
Start Date	Indicates the date the Process started running.
Pname	Specifies the label on the PROCESS statement.
Compress	Indicates whether you requested compression of the transmitted data.
End Date	Specifies the ending date for the particular step in the Process.
Msgid	Specifies the identification number of the message in the online message file.
Restart	Indicates whether there was a breakdown in the transmission and the Process was restarted.
Start Time	Indicates the time the Process started running.
Rtnck	Specifies the completion code for the step. Zero (0) indicates successful completion of a step.
Link Stat	Indicates the status of the communications link to the node to which you are transmitting. Values for this field are OK and failed.
End time	Specifies the ending time for the particular step in the Process.
FDBK	Specifies optional feedback information for diagnostic purposes.
Snode	Specifies the secondary node name.
Direction	Specifies the direction of the file transfer. Values for this field are SEND and RECEIVE.
Step	Specifies the label name as assigned in the Process.
Submitter	Specifies the name of the node submitting the Process. In this example, OPR.SMITH is the USERID of the submitter.

Line	Description
From Snode DSN=	Specifies the name of the data set or file from which the data is being transmitted. In this example, the Process is being submitted from the SNODE. May include a file name extension to indicate the type of data contained in the file.
FILE SIZE	Indicates the size of the file.
I/O Bytes	Indicates the number of bytes read or written from disk.
Xmit Bytes	Indicates the number of bytes sent or received during the session, including Connect:Direct HP NonStop control information.
RU size	Specifies the amount of data that can be sent and received at one time.
I/O Recs	Indicates the number of actual records read or written.
Xmit RUs	Indicates the number of request units transmitted.
Comp%	Indicates the compression percentage.
To Pnode DSN=	Specifies the name of the data set or file that is receiving the transmission. In this example, the Process is being sent to the PNODE. May include a file name extension to indicate the type of data contained in the file.
I/O Bytes	Indicates the number of bytes read or written from disk.
Xmit Bytes	Indicates the number of bytes sent or received during the session, including Connect:Direct HP NonStop control information.
I/O Recs	Indicates the number of actual records read or written.
Xmit RUs	Indicates the number of request units transmitted.
Comp%	Indicates the compression percentage.
Bytes/sec	Indicates the transmission speed of bytes per second. <b>Note:</b> For backup or restore operations, the bytes-per-second field in the stepend record does not accurately reflect the speed at which data is transmitted across the communication line. The time that enables you to calculate this rate includes overhead that is inherent in the backup or restore operation.
SCPA0001	Specifies the identification number of the message in the online message file. The text is displayed below the message ID number. In this example, the COPY finished successfully.

## PROCESS-STEPSTART Record

The PROCESS-STEPSTART record provides statistics detailing the start of a step of a Process. The following table contains a description of each line in the record for the REPORT step of the RUNTASK function:

Line	Description
Date	Indicates the date the particular step of a Process started running.
Time	Indicates the time a particular Process step started running.
PROCESS-STEPSTART	Specifies the label describing this phase of the submitted Process.
Pnumber	Specifies the Process number Connect:Direct HP NonStop assigns when the Process is submitted successfully.

<b>Line</b>	<b>Description</b>
Snode	Specifies the secondary node name.
Xnode	Indicates the node that is transmitting the data during this step. In this example, the Xnode is the PNODE.
Pname	Specifies the label on the PROCESS statement.
Submitter	Specifies the name of the node submitting the Process. In this example, OPR.SMITH is the HP NonStop user name of the submitter.
Function	Specifies the subroutine name for the particular step in the Process. This name is part of the internals of Connect:Direct HP NonStop and is used for diagnostic purposes. In this example, it identifies the RUN TASK statement entered as part of the Process.
Step Name	Specifies the label in the Process.

## PROCESS-STEPEND Record

The PROCESS-STEPEND record provides statistics detailing the end of a step of a Process. The following table contains a description of each line in the record for the REPORT step of the RUNTASK function:

<b>Line</b>	<b>Description</b>
Date	Indicates the date the particular step of a Process stopped running.
Time	Indicates the time a particular Process step stopped running.
PROCESS-STEPEND	Describes this phase of the submitted Process.
Pnumber	Specifies the Process number Connect:Direct HP NonStop assigns when the Process is submitted successfully.
Node	Specifies the secondary node name.
PlexClass	Specifies a user-defined class associated with a Connect:Direct/Server in a Connect:Direct/Plex environment, for example, TAPE.
Pname	Specifies the label on the PROCESS statement.
Submitter	Specifies the name of the node submitting the Process. In this example, OPR.SMITH is the HP NonStop user name of the submitter.
Rtncd	Specifies the completion code for the step. Zero (0) indicates successful completion of a step.
Message ID	Specifies the identification number of the message in the online message file.
Feedback	Specifies optional feedback information for diagnostic purposes.
Program	Specifies the name of the HP NonStop program that you want to run.
SRTT010I	Specifies the identification number of the message in the online message file. The text is displayed below the message ID number. In this example, a WAITed RUN TASK completed successfully.

## MESSAGE-MSG Record

The MESSAGE-MSG record provides statistics detailing informational messages. The following table contains a description of each line in the record:

Line	Description
Date	Indicates the date of the message.
Time	Indicates the time of the message.
MESSAGE-MSG	Describes this phase of the submitted Process.
Pnumber	Specifies the Process number Connect:Direct HP NonStop assigns when the Process is submitted successfully.
Node	Specifies the secondary node name.
PlexClass	Specifies a user-defined class associated with a Connect:Direct/Server in a Connect:Direct/Plex environment, for example, TAPE.
Pname	Specifies the label on the PROCESS statement.
Submitter	Specifies the name of the node submitting the Process. In this example, OPR.SMITH is the HP NonStop user name of the submitter.
LU Name	Specifies the name assigned to the LU in the network map file.
Exit step, ending process execution - (execute_process)	<p>Specifies the message that execution is complete.</p> <p><b>Note:</b> If the LOGCPU TIME initialization parameter is specified, both general CPU usage statistics and statistics for Secure+ activities such as handshake and encryption are included in the MSG record, for example,</p> <p style="padding-left: 40px;">CPU S+ Handshake 0.04 secs, S+ Crypting 0.09 secs, total 0.13 secs.</p> <p><b>Note:</b> If the LOG-TCP-CONN-RQ initialization parameter is specified, all connection attempts from trading partners as well as attempts to connect to adjacent nodes are logged and included in the MSG record, for example,</p> <p style="padding-left: 40px;">TCPPROC \NONSTP.\$ZTC0, IP fd00::20a0:209:6bff:fe65:9a73 error Invalid function</p>

## PROCESS-PROCEND Record

The PROCESS-PROCEND record provides statistics detailing the end of the Process. The following table contains a description of each line in the record:

Line	Description
Date	Indicates the date the Process ended.
Time	Indicates the time the Process ended.
PROCESS-PROCEND	Specifies the label describing this phase of the submitted Process.
Pnumber	Specifies the Process number Connect:Direct HP NonStop assigns when the Process is submitted successfully.

Line	Description
Snode	Specifies the secondary node name.
Xnode	Indicates the node transmitting the data during this step. In this example, the Xnode is the PNODE.
Pname	Specifies the label on the PROCESS statement.
Submitter	Specifies the name of the node submitting the Process. In this example, OPR.SMITH the HP NonStop user name of the submitter.
Rtncd	Specifies the completion code for the step. Zero (0) indicates successful completion of a step.
Message ID	Specifies the identification number of the message in the online message file.
Feedback	Specifies optional information for diagnostic purposes.
SSMT000I	Specifies the identification number of the message in the online message file. In this example, the message indicates that it is the end of the Process.

## Examining Type File Records

Use the SELECT TYPE command to examine a given record in the type file. The type file contains records that define the file attributes for new files. Connect:Direct HP NonStop uses these attributes when you specify a particular typekey as part of a COPY statement in a Process.

The parameters used with the SELECT TYPE command allow you to determine search criteria and the form in which the information is presented.

If you do not specify the TYPEKEY parameter, all type records are selected.

### Format

Following is the SELECT TYPE command format:

```

SElect TYPE          FILE
                    OUT=filename
                    PPrint
                    TYPEKEY=typekey|generic| (list)

```

### Required Parameters

The SELECT TYPE command has no required parameters.



---

## Examining Authorization File Records

Use the SELECT USER command to examine records in the authorization file (AUTHFILE). You can specify the search criteria and the format of the information presented.

If you do not specify search criteria, Connect:Direct HP NonStop selects all user records.

---

**Note:** Fields without information are excluded from the output.

---

### Format

Following is the SELECT USER command format:

---

```
SElect USER          FILE
                    OUT=filename
                    PRint
                    USERID=group.user|generic|alias|(list)
```

---

### Required Parameters

The SELECT USER command has no required parameters.

### Optional Parameters

Optional parameters for the SELECT USER command are:

Line	Description
FILE	Specifies that Connect:Direct HP NonStop pass back the selected unformatted control block (CB) user records.
OUT=filename	Specifies the file where Connect:Direct HP NonStop routes the output.
PRint	Specifies that Connect:Direct HP NonStop route the output of the SELECT USER command to the default printer. Printed output is in tabular format.
USERID=group.user  generic alias (list)	Specifies the user records to select in the AUTHFILE. group.user—Specifies the group name (or number) and USERID (or number) of the user. generic—Specifies generic selection of users. To specify users generically, type a 1–7 alphanumeric character string plus an asterisk (*). The first character must be alphabetic. For example, if you specify a USERID of B, user records beginning with B are selected. If you specify only an asterisk (*), all user records in the AUTHFILE are selected. alias—Specifies the user records to select in the AUTHFILE. You can enter 1–17 alphanumeric characters including underscores, hyphens, and periods. The first character <i>must</i> be alphabetic. list—Specifies a list of users. Enclose the list in parentheses, and separate each value with a space or comma (,).

---

## Examples

The following command searches for user DALLAS.WILLIAM at the local (default) node:

```
CD.38.>SELECT USER USERID=DALLAS.WILLIAM
```

Following is the output from the SELECT USER command:

```
=====
                        U S E R   I N F O R M A T I O N
=====
USERID           =>    DALLAS.WILLIAM (202, 192)
NAME             =>    William Jones
PHONE           =>    ext.1111
VOLUME          =>    $DEV1.DATA
OBEYVOLUME      =>    $DEV1.NDMOBEY
PROCVOLUME      =>    $DEV1.PRODUCT

DEFAULT.AUTHORITY =>    A
SUBMIT          =>    Y      MODIFY           =>    Y
STOP.ALL        =>    N      STATISTICS        =>    A
UPDATE.LOGGING  =>    Y      UPDATE.STATISTICS  =>    Y

U S E R COMMANDS: Select  =>A   Insert =>A   Delete =>A   Update => A
T Y P E COMMANDS: Select  =>Y   Insert =>Y   Delete =>Y   Update => Y
S E C . COMMANDS: Select  =>Y   Insert =>Y   Delete =>Y   Update => Y
PROCESS COMMANDS:Select   =>A   Delete =>A   Change =>A   Flush  => A   Suspend => A
NETMAP  COMMANDS:Select   =>Y   Insert=> Y   Delete=> Y   Update => Y   Relate  => Y
```

Following is an example of the SELECT USER command with an alias specified:

```
CD.61.>SELECT USER USERID=this_is_an_alias
```

The following command uses the SOURCE parameter to scan the authorization file and automatically generate an HP NonStop obey file. The generated file contains the INSert USERS command that is necessary to rebuild the AUTHFILE. Use this command to convert and reload your AUTHFILE file if you are converting from any currently supported release of Connect:Direct HP NonStop.

```
SEL USER SOURCE OUT=name of obey file to rebuild the authorization file
```



## A

### **Adjacent Node**

An adjacent node is an entry in the Network Map that defines a Connect:Direct HP NonStop node with which the local Connect:Direct HP NonStop node can communicate. The adjacent node is also called a remote node.

### **AIMS**

The automated installation and management system (AIMS) is a menu-driven system that guides you through the installation procedure for Connect:Direct HP NonStop.

### **Application Programming Interface (API)**

The Application Programming Interface (API) is a Connect:Direct HP NonStop component that accepts commands and places them in an executable format.

### **API Manager**

An API manager is a network map entity, that handles communications sessions between Connect:Direct HP NonStop and external applications on a TCP/IP network. After the API manager has been set up, users of these other Sterling Commerce products can configure, control, and operate Connect:Direct HP NonStop from any host on a TCP/IP network.

### **AUTHFILE**

The authorization file contains records of user attribute defaults. Each record defines the features of Connect:Direct HP NonStop that you can access.

## B

### **Background Mode**

The background mode enables you to execute NDMCOM using a disk file containing Connect:Direct HP NonStop commands as input. All Connect:Direct HP NonStop commands, except the FC command, are used in this mode.

# C

## CB Function

The CB (Control Block) function is a group of statements that performs a specific task and often returns a value to the statement that calls it.

## C-string Control Block

The C-string control block (CB) is the data format that returns output generated by Connect:Direct HP NonStop Processes and commands to the API. A C-string control block consists of two or more fields.

## C-string Control Structure

The C-string control structure groups one or more related C-string control blocks.

## Checkpoint Restart

The checkpoint restart feature eliminates the need to retransmit an entire file in the event of a transmission failure. If a copy procedure is interrupted, Connect:Direct HP NonStop restarts that copy at the last checkpoint.

## Command Line Interface

The command line interface is a Connect:Direct HP NonStop interface that enables you to submit Connect:Direct HP NonStop Processes and commands from your native command line environment.

## Commands

Connect:Direct HP NonStop commands initiate and monitor activity within the Connect:Direct HP NonStop system.

## Connect:Direct HP NonStop Commands

Connect:Direct HP NonStop commands use a command structure common to the rest of the Connect:Direct family of products. The commands are issued three ways: in interactive mode directly from the command line, in background mode by issuing the Connect:Direct HP NonStop OBEY command, or through an API.

## Connect:Direct HP NonStop Spooler Option

The Connect:Direct HP NonStop spooler option is a Connect:Direct HP NonStop application that permits an installation to transfer output spooler jobs automatically from a Connect:Direct HP NonStop node to a disk file on an adjacent node.

## Connect:Direct/Plex

Connect:Direct/Plex is a Connect:Direct OS/390 (zOS) system consisting of a Connect:Direct/Manager and one or more Connect:Direct/Servers in a TCP/IP environment. Connect:Direct HP NonStop can establish sessions with Connect:Direct/Plex.

## Cyclic Redundancy Checking (CRC)

CRC is a method used to validate data integrity during data transfers between Connect:Direct nodes across a TCP/IP network. CRC can be controlled using any of the following options:

- ❖ A global initialization parameter
- ❖ An adjacent node definition
- ❖ A Process statement parameter
- ❖ A SUBMIT command parameter

## D

### Domain Server

Connect:Direct HP NonStop can be configured to handle inbound connection requests from a TCP domain, that is, a range of IP addresses, using the ADJ NODE record type NDM.DOMAIN. This allows the application to recognize connection requests from IP addresses that are not explicitly configured in the network map, as long as they fall within one of the defined domains.

### Downstream Connection

See Receiving Connection.

### Dynamic LUs

Connect:Direct HP NonStop starts dynamic LUs as needed and automatically stops them upon Process completion. Dynamic LUs are options when using TCP/IP.

## E

### EMS Filters

The EMS filters provide a programmatic method for selecting events for processing.

### Environment Commands

These commands enable you to perform various Connect:Direct HP NonStop functions, such as displaying environment values and invoking TEDIT. Some environment commands allow you to set specific environment parameter values in NDMCOM. These values remain in effect only for the duration of the current session, unless they are changed by you or another user logs on to the same NDMCOM.

### ERR Control Block

The ERR control block is the first control block of an error control structure (ERRCS). The beginning and ending fields are: CB ! ERR ! and CBEND ! ERR !. The two other required fields in the ERR control block are: *N* (number) field and *T* (top message) field. *N* specifies the number of messages in the ERRCS; *T* specifies the number of the most important message.

### Error Control Structure (ERRCS)

The error control structure (ERRCS) is a particular C-string control structure designed to identify the messages occurring when executing Connect:Direct HP NonStop Processes and commands.

## Event Management Service (EMS)

Event management performs event-collection, logging, and distribution in the distributed systems management (DSM) environment.

## F

### FASTLOAD

This Connect:Direct HP NonStop function can reduce disk I/O overhead. It is used when the Connect:Direct HP NonStop node is the destination. With FASTLOAD, Connect:Direct HP NonStop passes data through SPI to FUP to load into a destination data file. The feature is particularly useful for key-sequenced files, but it is also supported for entry-sequenced and relative record files.

### Field

A field is two null-terminated strings—key and data. Two or more fields make up a C-string control block.

## I

### I/O Exit Support

This support provides exit points for user-written programs to serve as application interfaces for data transfers.

### Interactive Mode

This mode enables you to issue commands through NDMCOM and receive an immediate response.

## L

### Local Node

The local node is the Connect:Direct HP NonStop server.

## M

### Message Commands

The message commands allow you to display, add, delete, modify, and print Connect:Direct HP NonStop messages from the command interpreter (TACL).

### Message Control Blocks

Message control blocks are part of an ERRCS. These blocks are sequenced as they occur. The fields in a message control block are CB ! En !, FDBK ! fb !, RC ! rc !, MSGID ! msgid !, and OK ! od ! (optional keyword ! optional data !).

## N

### **NDMCOM**

NDMCOM is the Connect:Direct HP NonStop user interface.

### **NDMMON**

The monitor Process (NDMMON) ensures nonstop operation of Connect:Direct HP NonStop.

### **NDMSTDL**

The statistics deletion program (NDMSTDL) ensures sufficient space is available to write statistics records in the statistics files. It deletes records from STATFILE and STASTRCH based on user-specified deletion criteria and maximum percentage of file capacity.

### **NETEX Option**

NETEX is a connection option for Connect:Direct OS/390.

### **Network Map**

The network map (netmap) is a file that identifies all valid Connect:Direct nodes in the network. One network map is associated with each Connect:Direct HP NonStop local node. The netmap has one entry for each of the other Connect:Direct nodes to which the local Connect:Direct HP NonStop node communicates. The netmap entries also contain the rules or protocol that the nodes adhere to when communicating.

### **Node**

A node is any site in a network from which information distribution is initiated.

## P

### **Primary Node**

The primary node (PNODE) is the Connect:Direct HP NonStop node on which the Process is submitted. The primary node is also referred to as the controlling node or initiating node, but is not necessarily interpreted as the sending node, because PNODE can be the receiver. In every Process, one PNODE and one SNODE are specified. The submitter of a Process is always the PNODE.

### **PNODE=SNODE Transmission**

This transmission enables you to create a Process to send data to another file on your node. In this type of transmission, your node is both the PNODE and the SNODE.

### **Primary Logical Unit**

The primary logical unit (PLU) is the logical unit that controls an LU to LU session. The PLU formats and sends an NLD request that begins a session.

## Process (Source File)

A Process is a series of statements that initiate Connect:Direct activity, such as copying files, running jobs, and so on.

## Process Statements

Process statements are instructions for transferring files, running operating system jobs, executing programs, or submitting other Connect:Direct HP NonStop Processes. You use Process statements to build a Connect:Direct HP NonStop Process.

# R

## Receiving Connection

The receiving connection is a connection between Connect:Direct HP NonStop and other nodes (AS/400—TCP only) where the Connect:Direct HP NonStop node supports the primary functions of the data link and the HP NonStop LU functions as a primary LU (PLU).

## Remote Node

A remote node is an entry in the network map that defines a Connect:Direct node with which the local Connect:Direct HP NonStop node can communicate. The remote node is also called an adjacent node.

## Retry Interval

The retry interval is the interval at which retries are performed as a part of the checkpoint-restart feature.

# S

## SECFILE

The security file (SECFILE) relates the node name and user ID assigned to an incoming Connect:Direct HP NonStop operation to a HP NonStop user ID.

## Secondary Logical Unit

The secondary logical unit (SLU) is the logical unit that functions under the control of a PLU. The SLU accepts the incoming NLD request from the PLU.

## Secondary Node

The secondary node (SNODE) is the Connect:Direct HP NonStop node that interacts with the primary node (PNODE) during Process execution. SNODE is also referred to as the participating (non controlling) or partner node. Every Process has one PNODE and one SNODE.

## Secure Point of Entry

The secure point of entry enables Processes from other nodes to be written without the use of passwords.

**Sending Connection**

The sending connection is between HP NonStop and the IBM 370 nodes (OS/390, VM, VSE) where the IBM node supports the primary functions of the data link and the IBM LU functions as a primary LU (PLU).

**Server**

The server (NDMSRVR) is responsible for processing command requests, communicating with the session manager when work is placed in the transmission control queue, and accepting session establishment requests from remote nodes.

**Session Manager**

The session manager (NDMSMGR) is responsible for establishing communication sessions, performing standard session management functions, and executing Processes.

**SNA (Systems Network Architecture)**

A network architecture designed to provide compatibility among a wide variety of hardware and software products that enable you to build complex networks. It defines protocols, standards, and message formats to which different hardware and software products must conform.

**SNA Primary**

SNA primary defines the LU as a primary LU (PLU).

**SNA Secondary**

SNA secondary defines the LU as a secondary LU (SLU).

**SNAX Passthrough**

SNAX passthrough is a function of the SNAX line access software that permits interaction between a host application program and an SNA device connected to a HP NonStop system. The Connect:Direct HP NonStop system, which is not a Connect:Direct HP NonStop node, appears to the host as a cluster controller.

**SNODE**

The secondary node (SNODE) is the node participating in Process execution initiated by another node (the PNODE).

**Statistics File**

The statistics file holds Connect:Direct HP NonStop statistics records that document the history of a Process.

**Statistics Facility**

The Connect:Direct HP NonStop statistics facility records Connect:Direct HP NonStop activities.

**Static LUs**

Static LUs are user-controlled and are quiesced and resumed with the MODIFY command. Static LUs are options when using TCP/IP.

## T

### **Transmission Control Queue**

The Transmission Control Queue (TCQ) holds information about Connect:Direct HP NonStop Processes that are currently executing or scheduled to execute in the future.

### **TCP/IP Option**

TCP/IP is a connectivity option for Connect:Direct OS/390, UNIX, OpenVMS, VSE, OS/400, Stratus VOS, and Windows, and HP NonStop nodes.

### **Type File**

The type file contains records that define file attributes for new files.

## U

### **Upstream Connection**

See Sending Connection.



## Symbols

! command 41  
-command number 42  
command number 42  
command string 42  
examples 42  
\$NDMS, default server name 28  
&symbolic\_name parameter  
SUBMIT command 96

## A

AIMS (Automated Installation and Management System)  
description 15  
alias parameter, LOGON command 49  
ALL parameter, HELP command 46  
API manager 100  
Application Program Interface (API) 15  
Authorization file, converting and reloading 120

## B

Background mode  
macros 31  
running NDMCOM 30  
Bad queue 37

## C

Call queue 37  
CCODE parameter, SELECT STATISTICS  
command 105  
CD macro 31  
CHANGE PROCESS command  
CLASS=n 80  
DEST 80

examples 81  
general description 79  
HOLD 80  
LASTPNUMBER 80  
PLEXCLASS parameter 80  
PNAME 80  
PNUMBER 80  
PRTY 81  
RELEASE 81  
RETAIN 81  
STARTT 81  
SUBMITTER 80

### Changing

ownership of NDMCOM 27  
the command prompt 28  
the default server process 28

### CLASS parameter

SUBMIT command 94

### command number parameter

! command 42  
FC command 44

### command parameter, HELP command 46

### Command prompt, changing 28

### Command string parameter

! command 42  
FC command 44

### Commands

environment 24  
environment SYMBOL, DELETE SYMBOL 60  
environment, ! 41  
environment, DISPLAY STATINFO 68  
environment, EDIT 42  
environment, ENVIRONMENT 73  
environment, EXIT 43  
environment, general 63  
environment, HELP 45  
environment, HISTORY 47  
environment, LIST 48  
environment, LOGON 48

- environment, OBEY 50
- environment, OBEYVOLUME 52
- environment, OPEN 53
- environment, OUT 54
- environment, PRINTER 55
- environment, PROCVOLUME 56
- environment, RUN 57
- environment, SELECT SYMBOL 61
- environment, SYMBOL general 58
- environment, TIME 75
- environment, VERSION 76
- environment, VOLUME 76
- general 22
- message 25, 35
- user and administrator 23
- user, CHANGE PROCESS 79
- user, DELETE PROCESS 83
- user, DISPLAY LOGGING 66
- user, FLUSH PROCESS 85
- user, LASTPNUMBER 86, 87
- user, SELECT NETMAP 99
- user, SELECT PROCESS 88
- user, SELECT SECURITY 103
- user, SELECT STATISTICS 104
- user, SELECT TYPE 117
- user, SELECT USER 119
- user, STATUS 63
- user, SUBMIT 93
- user, SUSPEND PROCESS 97

Components of Connect:Direct HP NonStop 13

Conditional logic 33

Connect:Direct/Plex 116

Connect:Direct HP NonStop

- changing the command prompt 28
- components 13
- concepts 16
- flow of operations 25
- functionality and scenario of operation 33
- functionality, example 33
- functionality, monitoring the Process status 34
- Process example 33
- submitting the Process 33

Connect:Direct NonStop

- determining results from Process execution 34
- Process statements 32

Connect:Direct Secure+ Option 17, 19

Connect:Direct Spooler option description 15

Connect:Direct user interface 14

- Connect:Direct/Plex 17
- Connect:DirectPlex 80, 92, 94, 111, 112, 115
- COPY statement 32

## D

Default server 27

- \$NDMS 27
- changing 28

DELETE PROCESS command

- DEST 84
- examples 84
- general description 83
- LASTPNUMBER 84
- PNAME 84
- PNUMBER 84
- SUBmitter 84

DELETE SYMBOL command

- examples 60
- general description 60
- symbol-name 60

DEST parameter

- CHANGE PROCESS command 80
- SELECT PROCESS command 89

DETAIL parameter, SELECT PROCESS command 89

DISPLAY command, and viewing messages 35

DISPLAY LOGGING command

- examples 64, 65, 67
- FILE 67
- general description 63, 66
- OUT 67
- PRINT 67

DISPLAY STATINFO command

- examples 69
- FILE 69
- format 68
- general description 68
- OUT 69
- PRINT 69
- SHORT 69

Displaying messages 35

Domain Nodes 17

DSN parameter

- SUBMIT command 93

**E**

- EDIT command
  - examples 43
  - filename 43
  - general description 42
  - parameters 43
- ENVIRONMENT command
  - examples 74
  - general description 73
- Environment commands 24
  - ! 41
  - DISPLAY STATINFO 68
  - EDIT 42
  - ENVIRONMENT 73
  - EXIT 43
  - general 63
  - HELP 45
  - HISTORY 47
  - LIST 48
  - LOGON 48
  - OBEY 50
  - OBEYVOLUME 52
  - OPEN 53
  - OUT 54
  - PRINTER 55
  - PROCVOLUME 56
  - RUN 57
  - SYMBOL, DELETE SYMBOL 60
  - SYMBOL, general 58
  - SYMBOL, SELECT SYMBOL 61
  - TIME 75
  - VERSION 76
  - VOLUME 76
- Examples
  - ! command 42
  - CHANGE PROCESS command 81
  - DELETE PROCESS command 84
  - DELETE SYMBOL command 60
  - DISPLAY LOGGING command 64, 65, 67
  - DISPLAY STATINFO 69
  - EDIT command 43
  - ENVIRONMENT command 74
  - EXIT command 44
  - FC command 45
  - FLUSH PROCESS command 86
  - HELP command 46
  - HISTORY command 47
  - INSERT SYMBOL command 59
  - LASTPNUMBER command 87, 88
  - LIST command 48
  - LOGON command 49
  - OBEY command 51
  - OBEYVOLUME command 53
  - OPEN command 54
  - OUT command 55
  - PRINTER command 56
  - PROCVOLUME command 57
  - RUN command 58
  - SELECT NETMAP command 101
  - SELECT PROCESS command 90
  - SELECT SECURITY command 104
  - SELECT STATISTICS command 107
  - SELECT SYMBOL command 62
  - SELECT TYPE command 118
  - SELECT USER command 120
  - SUBMIT command 96
  - SUSPEND PROCESS command 98
  - TIME command 75
  - VERSION command 76
  - VOLUME command 77
- EXCLUDE parameter, SELECT STATISTICS command 105
- Execution queue 37
- EXIT command
  - examples 44
  - general description 43
- Exit I/O, description 15
- Exiting from NDMCOM 34

**F**

- FC command
  - command number 44
  - command number 44
  - command string 44
  - examples 45
  - general description 44
- File ownership 27
- FILE parameter
  - DISPLAY LOGGING command 67
  - DISPLAY STATINFO command 69
  - SELECT NETMAP command 101
  - SELECT PROCESS command 89
  - SELECT SECURITY command 103
  - SELECT STATISTICS command 106
  - SELECT TYPE command 118
  - SELECT USER command 119
  - SUBMIT command 93

filename parameter  
 EDIT command 43  
 OUT command 54

FLUSH PROCESS command  
 examples 86  
 FORCE 86  
 general description 85  
 LASTPNUMBER 85  
 PNAME 85  
 PNUMBER 85  
 SUBMITTER 86

FORCE parameter  
 FLUSH PROCESS command 86  
 SUSPEND PROCESS command 98

## G

GET command and printing messages 35  
 group.user parameter 49

## H

HELP command  
 ALL 46  
 command 46  
 examples 46  
 format 45  
 general description 45  
 messageid 46

HISTORY command  
 examples 47  
 general description 47  
 nnn 47

HOLD parameter  
 CHANGE PROCESS command 80  
 SUBMIT command 94

Hold queue 37

## I

I/O exit, description 15

Initial queue 37

INSERT SYMBOL command  
 examples 59  
 general description 59  
 symbol-name 59  
 symbol-name parameter 59

Interactive mode  
 macros 31

running NDMCOM 29

## L

LASTPNUMBER command  
 examples 87, 88  
 general description 86, 87

LASTPNUMBER parameter  
 CHANGE PROCESS command 80  
 DELETE PROCESS command 84  
 FLUSH PROCESS command 85  
 SELECT PROCESS command 89  
 SELECT STATISTICS command 106  
 SUSPEND PROCESS command 97

LIST command  
 examples 48  
 system.\$volume.subvol.filename 48

List of  
 environment commands 24  
 user and administrator commands 23

LOGMODE parameter  
 SELECT NETMAP command 101

LOGON command  
 alias 49  
 examples 49  
 general description 48  
 group.user 49  
 password 49

LU parameter, SELECT NETMAP command 100

## M

Macros  
 description 30  
 for background mode 31  
 for interactive mode 31  
 implementing 31

Manipulating Processes in the TCQ 38

Message commands 25, 35

messageid parameter, HELP command 46

Messages  
 displaying 35  
 modifying 34  
 printing 35

Modal logic 33

Modal statements 32

MSG command and viewing messages 35

**N**

NDMA macro 31

NDMCOM  
 description 14, 27  
 exiting 34  
 issuing commands 28  
 macros for background mode 31  
 macros for interactive mode 31  
 reactivating 31  
 running in background mode 30  
 running in interactive mode 29  
 suspending 31

NDMMON, description 14

NDMPROMPT parameter 28

NDMRUN macro 31

NDMS macro 31

NDMSMGR description 15

NDMSRVR  
 description 14  
 identifying in NDMCOM 29, 30

ndmsrvr-name parameter 53

NDMSTART macro 31

NDMSTDL  
 description 15

NDMSTOP macro 31

Network map  
 converting and reloading 102  
 general 16

NEWNAME parameter, SUBMIT command 94

nnn parameter, HISTORY command 47

NODE parameter, SELECT NETMAP command 100

**O**

OBEY command  
 examples 51  
 general description 50  
 system.\$volume.subvol.filename 50

OBEYVOLUME command  
 examples 53  
 general description 52  
 system.\$volume.subvol 52

Online message file 34

OPEN command  
 examples 54  
 general description 53  
 ndmsrvr-name 53

OUT command  
 examples 55  
 filename 54  
 general description 54

OUT parameter  
 DISPLAY LOGGING command 67  
 DISPLAY STATINFO command 69  
 SELECT NETMAP command 101  
 SELECT PROCESS command 89  
 SELECT SECURITY command 103  
 SELECT STATISTICS command 106  
 SELECT SYMBOL command 61  
 SELECT TYPE command 118  
 SELECT USER command 119

**P**

PACCT parameter, SUBMIT command 94

PARAM command 28

Parameters  
 &symbolic\_name, SUBMIT command 96  
 ALL, HELP command 46  
 CCODE, SELECT STATISTICS command 105  
 CLASS, SUBMIT command 94  
 -command number, ! command 42  
 command number, ! command 42  
 -command number, FC command 44  
 command number, FC command 44  
 command string, ! command 42  
 command string, FC command 44  
 DEST, CHANGE PROCESS command 80  
 DEST, SELECT PROCESS command 89  
 DETAIL, SELECT PROCESS command 89  
 DSN, SUBMIT command 93  
 EDIT command 43  
 EXCLUDE, SELECT STATISTICS command 105  
 FILE, DISPLAY LOGGING command 67  
 FILE, DISPLAY STATINFO command 69  
 FILE, SELECT NETMAP command 101  
 FILE, SELECT PROCESS command 89  
 FILE, SELECT SECURITY command 103  
 FILE, SELECT STATISTICS command 106  
 FILE, SELECT TYPE command 118  
 FILE, SELECT USER command 119  
 FILE, SUBMIT command 93  
 filename, EDIT command 43

- filename, OUT command 54
- FORCE, FLUSH PROCESS command 86
- FORCE., SUSPEND PROCESS command 98
- group.user 49
- HELP command 46
- HOLD, CHANGE PROCESS command 80
- HOLD, SUBMIT command 94
- LASTPNUMBER, CHANGE PROCESS command 80
- LASTPNUMBER, DELETE PROCESS command 84
- LASTPNUMBER, FLUSH PROCESS command 85
- LASTPNUMBER, SELECT PROCESS command 89
- LASTPNUMBER, SELECT STATISTICS command 106
- LASTPNUMBER, SUSPEND PROCESS command 97
- LOGMODE, SELECT NETMAP command 101
- LU, SELECT NETMAP command 100
- messageid, HELP command 46
- ndmsrvr-name parameter, OPEN command 53
- NEWNAME, SUBMIT command 94
- nnn, HISTORY command 47
- NODE, SELECT NETMAP command 100
- OUT, DISPLAY LOGGING command 67
- OUT, DISPLAY STATINFO command 69
- OUT, SELECT NETMAP command 101
- OUT, SELECT PROCESS command 89
- OUT, SELECT SECURITY command 103
- OUT, SELECT STATISTICS command 106
- OUT, SELECT SYMBOL command 61
- OUT, SELECT TYPE command 118
- OUT, SELECT USER command 119
- PACCT, SUBMIT command 94
- password, LOGON command 49
- PNAME, CHANGE PROCESS command 80
- PNAME, DELETE PROCESS command 84
- PNAME, FLUSH PROCESS command 85
- PNAME, SELECT PROCESS command 89
- PNAME, SELECT STATISTICS command 106
- PNAME, SUSPEND PROCESS command 97
- PNODE, SUBMIT command 94
- PNODEID, SUBMIT command 94
- PNUMBER, CHANGE PROCESS command 80
- PNUMBER, DELETE PROCESS command 84
- PNUMBER, FLUSH PROCESS command 85
- PNUMBER, SELECT PROCESS command 89
- PNUMBER, SELECT STATISTICS command 106
- PNUMBER, SUSPEND PROCESS command 97
- PRINT, DISPLAY LOGGING command 67
- PRINT, DISPLAY STATINFO command 69
- PRINT, SELECT NETMAP command 101
- PRINT, SELECT PROCESS command 89
- PRINT, SELECT SECURITY command 103
- PRINT, SELECT STATISTICS command 106
- PRINT, SELECT SYMBOL command 61
- PRINT, SELECT TYPE command 118
- PRINT, SELECT USER command 119
- printer, PRINTER command 55
- PROC, SUBMIT command 93
- program, RUN command 57
- PRTY, CHANGE PROCESS command 81
- PRTY, SUBMIT command 94
- QUEUE, SELECT PROCESS command 89
- RELEASE, CHANGE PROCESS command 81
- RETAIN, CHANGE PROCESS command 81
- RETAIN, SUBMIT command 95
- RUN command 58
- run-options, RUN command 58
- SACCT, SUBMIT command 95
- SHORT, DISPLAY STATINFO command 69
- SNODE, SELECT SECURITY command 103
- SNODE, SELECT STATISTICS command 106
- SNODE, SUBMIT command 95
- SNODEID, SUBMIT command 95
- SOURCE, SELECT NETMAP command 101
- STARTT, CHANGE PROCESS command 81
- STARTT, SELECT STATISTICS command 106
- STARTT, SUBMIT command 96
- STEPEND, SELECT STATISTICS command 106
- STOPT, SELECT STATISTICS command 107
- SUBMITTER, CHANGE PROCESS command 80
- SUBMITTER, DELETE PROCESS command 84
- SUBMITTER, FLUSH PROCESS command 86
- SUBMITTER, SELECT PROCESS command 89
- SUBMITTER, SELECT STATISTICS command 107
- SUBMITTER, SUSPEND PROCESS command 97
- symbol-name, DELETE SYMBOL 60
- symbol-name, INSERT SYMBOL 59
- symbol-name, SELECT SYMBOL 61
- system.\$volume.subvol, OBEYVOLUME command 52
- system.\$volume.subvol, PROCVOLUME command 56
- system.\$volume.subvol, VOLUME command 77
- system.\$volume.subvol.filename, LIST command 48
- system.\$volume.subvol.filename, OBEY command 50
- TYPEKEY, SELECT TYPE command 118
- USER, SELECT SECURITY command 103
- USERID, SELECT USER command 119
- password parameter, LOGON command 49
- Pending queue 37

PLEXCLASS parameter 92, 111, 112, 115  
 CHANGE PROCESS command 80  
 SUBMIT command 94

**PNAME** parameter

CHANGE PROCESS command 80  
 DELETE PROCESS command 84  
 FLUSH PROCESS command 85  
 SELECT PROCESS command 89  
 SELECT STATISTICS command 106  
 SUSPEND PROCESS command 97

**PNODE** parameter, SUBMIT command 94

**PNODEID** parameter, SUBMIT command 94

**PNUMBER** parameter

CHANGE PROCESS command 80  
 DELETE PROCESS command 84  
 FLUSH PROCESS command 85  
 SELECT PROCESS command 89  
 SELECT STATISTICS command 106  
 SUSPEND PROCESS command 97

**PRINT** parameter

DISPLAY LOGGING command 67  
 DISPLAY STATINFO command 69  
 SELECT NETMAP command 101  
 SELECT PROCESS command 89  
 SELECT SECURITY command 103  
 SELECT STATISTICS command 106  
 SELECT SYMBOL command 61  
 SELECT TYPE command 118  
 SELECT USER command 119

**PRINTER** command

examples 56  
 general description 55  
 printer 55

printer parameter, PRINTER command 55

Printing messages 35

**PROC** parameter, SUBMIT command 93

**Process**

example 33  
 language definition 16

**PROCESS** statement 32

**PROCVOLUME** command

examples 57  
 general description 56  
 system.\$volume.subvol 56

program parameter, RUN command 57

**PRTY** parameter

CHANGE PROCESS command 81  
 SUBMIT command 94

## Q

**QUEUE** parameter, SELECT PROCESS command 89

## R

Recalling commands, ! command 41

Reexecuting commands, ! command 41

**RELEASE** parameter, CHANGE PROCESS  
 command 81

**RETAIN** parameter

CHANGE PROCESS command 81  
 SUBMIT command 95

Retain queue 37

Retain Timer queue 38

**RUN** command 58

/run-options/ 58  
 examples 58  
 general description 57  
 Parameters 58  
 program 57

**RUN JOB** statement 32

**RUN TASK** statement 32

**Running NDMCOM**

description 27  
 in background mode 30  
 in interactive mode 29  
 macros for background mode 31  
 macros for interactive mode 31

## S

**SACCT** parameter, SUBMIT command 95

**SAFEGUARD**, using to change password 95

**Security considerations**

changing ownership of NDMCOM 27  
 file ownership 27

**SELECT NETMAP** command

examples 101  
 FILE 101  
 general description 99  
 LOGMODE 101  
 LU 100  
 NODE 100

- OUT 101
- PRINT 101
- SOURCE 101
- SELECT PROCESS command
  - DEST 89
  - DETAIL 89
  - examples 90
  - FILE 89
  - general description 88
  - LASTPNUMBER 89
  - OUT 89
  - PNAME 89
  - PNUMBER 89
  - PRINT 89
  - QUEUE 89
  - SOURCE 89
  - SUBMITTER 89
- SELECT SECURITY command
  - examples 104
  - FILE 103
  - general description 103
  - OUT 103
  - PRINT 103
  - SNODE 103
  - USER 103
- SELECT STATISTICS command
  - CCODE 105
  - examples 107
  - EXCLUDE 105
  - FILE 106
  - general description 104
  - LASTPNUMBER 106
  - OUT 106
  - PNAME 106
  - PNUMBER 106
  - PRINT 106
  - SHORT 106
  - SNODE 106
  - STARTT 106
  - STEPEND 106
  - STOPT 107
  - SUBMITTER 107
- SELECT SYMBOL command
  - examples 62
  - general description 61
  - OUT 61
  - PRINT 61
  - symbol-name parameter 61
- SELECT TYPE command
  - examples 118
- FILE 118
  - general description 117
- OUT 118
- PRINT 118
- TYPEKEY 118
- SELECT USER command
  - examples 120
  - FILE 119
  - general description 119
  - OUT 119
  - PRINT 119
  - USERID 119
- Server (NDMSRVR) description 14
- Session manager (NDMSMGR)
  - description 15
- Session Redirection 17
- SHORT parameter, DISPLAY STATINFO
  - command 69
- SNODE parameter
  - SELECT SECURITY command 103
  - SELECT STATISTICS command 106
  - SUBMIT command 95
- SNODEID parameter
  - SUBMIT command 95
- SOURCE parameter, SELECT NETMAP
  - command 101
- STARTT parameter
  - CHANGE PROCESS command 81
  - SELECT STATISTICS command 106
  - SUBMIT command 96
- Statistics deletion program 15
- Statistics log
  - message 116
  - Process stepend record 113, 115
  - Process stepstart record 112, 114
  - Process submit record 111
  - PROCESS-PROCSTART record 111
- Statistics log, end of Process record 116
- STATUS command
  - examples 65
- STEPEND parameter, SELECT STATISTICS
  - command 106
- STOPT parameter, SELECT STATISTICS
  - command 107
- SUBMIT command



&symbolic\_name 96  
 CLASS 94  
 DSN 93  
 examples 96  
 FILE 93  
 general description 93  
 HOLD 94  
 NEWNAME 94  
 PACCT 94  
 PLEXCLASS parameter 94  
 PNODE 94  
 PNODEID 94  
 PROC 93  
 PRTY 94  
 RETAIN 95  
 SACCT 95  
 SNODE 95  
 SNODEID 95  
 STARTT 96  
 SUBMIT statement 32  
 SUBMITTER parameter  
   CHANGE PROCESS command 80  
   DELETE PROCESS command 84  
   FLUSH PROCESS command 86  
   SELECT PROCESS command 89  
   SELECT STATISTICS command 107  
   SUSPEND PROCESS command 97  
 SUSPEND PROCESS command  
   examples 98  
   FORCE 98  
   general description 97  
   LASTPNUMBER 97  
   PNAME 97  
   PNUMBER 97  
   SUBMITTER 97  
 Suspend queue 37  
 SYMBOL statement 32  
 symbol-name parameter  
   DELETE SYMBOL 60  
   INSERT SYMBOL 59  
   SELECT SYMBOL 61  
 symbol-value parameter, INSERT SYMBOL  
   command 59  
 system.\$volume.subvol parameter  
   OBEYVOLUME command 52  
   PROCVOLUME command 56  
   VOLUME command 77  
 system.\$volume.subvol.filename parameter  
   LIST command 48  
   OBEY command 50

## T

TIME command  
   examples 75  
   format 75  
   general description 75  
 Timer queue 37  
 Transmission Control Queue (TCQ)  
   and commands 38  
 TYPEKEY parameter, SELECT TYPE command 118

## U

User and administrator commands 23  
 User commands  
   CHANGE PROCESS 79  
   DELETE PROCESS 83  
   DISPLAY LOGGING 63, 66  
   FLUSH PROCESS 85  
   LASTPNUMBER 86, 87  
   SELECT NETMAP 99  
   SELECT PROCESS 88  
   SELECT SECURITY 103  
   SELECT STATISTICS 104  
   SELECT TYPE 117  
   SELECT USER 119  
   SUBMIT 93  
   SUSPEND PROCESS 97  
 User file, converting and reloading 120  
 User interface 14  
 USER parameter, SELECT SECURITY command 103  
 USERID parameter, SELECT USER command 119

## V

VERSION command  
   examples 76  
   general description 76  
 VOLUME command  
   examples 77  
   general description 76  
   system.\$volume.subvol 77

## W

Wait queue 37

