A Consumer Library Interface to DWARF

UNIX International Programming Languages Special Interest Group

1. INTRODUCTION

This document describes an interface to *libdwarf*, a library of functions to provide access to DWARF debugging information records, DWARF line number information, DWARF address range and global names information, weak names information, DWARF frame description information, DWARF static function names, DWARF static variables, and DWARF type information.

1.1 Purpose and Scope

The purpose of this document is to document a library of functions to access DWARF debugging information. There is no effort made in this document to address the creation of these records as those issues are addressed separately.

Additionally, the focus of this document is the functional interface, and as such, implementation as well as optimization issues are intentionally ignored.

1.2 Definitions

DWARF debugging information entries (DIE) are the segments of information placed in the .debug_* sections by compilers, assemblers, and linkage editors that, in conjunction with line number entries, are necessary for symbolic source-level debugging. Refer to the document "DWARF Debugging Information Format" from UI PLSIG for a more complete description of these entries.

This document adopts all the terms and definitions in "DWARF Debugging Information Format" version 2. It focuses on the implementation at Silicon Graphics Computer Systems. Although we believe the interface is general enough to be of interest to other vendors too, there are a few places where changes may need to be made.

1.3 Overview

The remaining sections of this document describe the proposed interface to libdwarf, first by describing the purpose of additional types defined by the interface, followed by descriptions of the available operations. This document assumes you are thoroughly familiar with the information contained in the *DWARF Debugging Information Format* document.

We separate the functions into several categories to emphasize that not all consumers want to use all the functions. We call the categories Debugger, Internal-level, High-level, and Miscellaneous not because one is more important than another but as a way of making the rather large set of function calls easier to understand.

Unless otherwise specified, all functions and structures should be taken as being designed for Debugger consumers.

The Debugger Interface of this library is intended to be used by debuggers. The interface is low-level (close to dwarf) but suppresses irrelevant detail. A debugger will want to absorb all of some sections at startup and will want to see little or nothing of some sections except at need. And even then will probably want to absorb only the information in a single compilation unit at a time. A debugger does not care about implementation details of the library.

The Internal-level Interface is for a DWARF prettyprinter and checker. A thorough prettyprinter will want to know all kinds of internal things (like actual FORM numbers and actual offsets) so it can check for appropriate structure in the DWARF data and print (on request) all that internal information for human users and libdwarf authors and compiler-writers. Calls in this interface provide data a debugger does not care about.

The High-level Interface is for higher level access (it's not really a high level interface!). Programs such as disassemblers will want to be able to display relevant information about functions and line numbers without having to invest too much effort in looking at DWARF.

The miscellaneous interface is just what is left over: the error handler functions.

The following is a brief mention of the changes in this libdwarf from the libdwarf draft for DWARF Version 1.

1.4 Items Changed

dwarf_nextglob(), dwarf_globname(), and dwarf_globdie() were all changed to operate on the items in the .debug_pubnames section.

All functions were modified to return solely an error code. Data is returned through pointer arguments. This makes writing safe and correct library-using-code far easier. For justification for this approach, see the book by Steve Maguire titled "Writing Solid Code" at your bookstore.

1.5 Items Removed

Dwarf_Type was removed since types are no longer special.

dwarf_typeof() was removed since types are no longer special.

Dwarf_Ellist was removed since element lists no longer are a special format.

Dwarf_Bounds was removed since bounds have been generalized.

dwarf_nextdie() was replaced by dwarf_next_cu_header() to reflect the real way dwarf is organized. The dwarf_nextdie() was only useful for getting to compilation unit beginnings, so it does not seem harmful to remove it in favor of a more direct function.

dwarf_childcnt() is removed on grounds that no good use was apparent.

dwarf_prevline() and dwarf_nextline() were removed on grounds this is better left to a debugger to do. Similarly, dwarf dieline() was removed.

dwarf_is1stline() was removed as it was not meaningful for the revised dwarf line operations.

Any libdwarf implementation might well decide to support all the removed functionality and to retain the DWARF Version 1 meanings of that functionality. This would be difficult because the original libdwarf draft specification used traditional C library interfaces which confuse the values returned by successful calls with exceptional conditions like failures and 'no more data' indications.

1.6 Revision History

March 93 Work on dwarf2 SGI draft begins

June 94 The function returns are changed to return an error/success code only.

2. Types Definitions

2.1 General Description

The *libdwarf.h* header file contains typedefs and preprocessor definitions of types and symbolic names used to reference objects of *libdwarf*. The types defined by typedefs contained in *libdwarf.h* all use the convention of adding <code>Dwarf_</code> as a prefix and can be placed in three categories:

- Scalar types: The scalar types defined in *libdwarf.h* are defined primarily for notational convenience and identification. Depending on the individual definition, they are interpreted as a value, a pointer, or as a flag.
- Aggregate types: Some values can not be represented by a single scalar type; they must be represented by a collection of, or as a union of, scalar and/or aggregate types.
- Opaque types: The complete definition of these types is intentionally omitted; their use is as handles for query operations, which will yield either an instance of another opaque type to be used in another query, or an instance of a scalar or aggregate type, which is the actual result.

2.2 Scalar Types

The following are the defined by *libdwarf.h*:

Dwarf_Ptr is an address for use by the host program calling the library, not for representing pc-values/addresses within the target object file. Dwarf_Addr is for pc-values within the target object file. The sample scalar type assignments above are for a *libdwarf.h* that can read and write 32-bit or 64-bit binaries on a 32-bit or 64-bit host machine. The types must be defined appropriately for each implementation of libdwarf. A description of these scalar types in the SGI/MIPS environment is given in Figure 1.

NAME	SIZE	ALIGNMENT	PURPOSE
Dwarf_Bool	4	4	Boolean states
Dwarf_Off	8	8	Unsigned file offset
Dwarf_Unsigned	8	8	Unsigned large integer
Dwarf_Half	2	2	Unsigned medium integer
Dwarf_Small	1	1	Unsigned small integer
Dwarf_Signed	8	8	Signed large integer
Dwarf_Addr	8	8	Program address
			(target program)
Dwarf_Ptr	4 8	4 8	Dwarf section pointer
		•	(host program)
Dwarf_Handler	4 8	4 8	Pointer to
		•	error handler function

Figure 1. Scalar Types

2.3 Aggregate Types

The following aggregate types are defined by the SGI libdwarf.h: Dwarf_Loc, Dwarf_Locdesc, Dwarf_Block, Dwarf_Frame_Op. While most of libdwarf acts on or returns simple values or opaque pointer types, this small set of structures seems useful.

2.3.1 Location Record

The Dwarf Loc type identifies a single atom of a location description or a location expression.

```
typedef struct {
    Dwarf_Small lr_atom;
    Dwarf_Unsigned lr_number;
    Dwarf_Unsigned lr_number2;
    Dwarf_Unsigned lr_offset;
} Dwarf Loc;
```

The lr_atom identifies the atom corresponding to the DW_OP_* definition in *dwarf.h* and it represents the operation to be performed in order to locate the item in question.

The lr_number field is the operand to be used in the calculation specified by the lr_atom field; not all atoms use this field. Some atom operations imply signed numbers so it is necessary to cast this to a Dwarf Signed type for those operations.

The lr_number2 field is the second operand specified by the lr_atom field; only DW_OP_BREGX has this field. Some atom operations imply signed numbers so it may be necessary to cast this to a Dwarf Signed type for those operations.

The lr_offset field is the byte offset (within the block the location record came from) of the atom specified by the lr_atom field. This is set on all atoms. This is useful for operations DW_OP_SKIP and DW OP BRA.

2.3.2 Location Description

The Dwarf_Locdesc type represents an ordered list of Dwarf_Loc records used in the calculation to locate an item. Note that in many cases, the location can only be calculated at runtime of the associated program.

The ld_lopc and ld_hipc fields provide an address range for which this location descriptor is valid. Both of these fields are set to *zero* if the location descriptor is valid throughout the scope of the item it is associated with. These addresses are virtual memory addresses, not offsets-from-something. The virtual memory addresses do not account for dso movement (none of the pc values from libdwarf do that, it is up to the consumer to do that).

The ld_cents field contains a count of the number of Dwarf_Loc entries pointed to by the ld_s field.

The ld s field points to an array of Dwarf Loc records.

2.3.3 Data Block

The Dwarf_Block type is used to contain the value of an attribute whose form is either DW_FORM_block1, DW_FORM_block2, DW_FORM_block4, DW_FORM_block8, or DW FORM block. Its intended use is to deliver the value for an attribute of any of these forms.

The bl len field contains the length in bytes of the data pointed to by the bl data field.

The bl_data field contains a pointer to the uninterpreted data. Since we use a Dwarf_Ptr here one must copy the pointer to some other type (typically an unsigned char *) so one can add increments to index through the data. The data pointed to by bl data is not necessarily at any useful alignment.

2.3.4 Frame Operation Codes

The Dwarf_Frame_Op type is used to contain the data of a single instruction of an instruction-sequence of low-level information from the section containing frame information. This is ordinarily used by Internal-level Consumers trying to print everything in detail.

```
typedef struct {
     Dwarf_Small fp_base_op;
     Dwarf_Small fp_extended_op;
     Dwarf_Half fp_register;
     Dwarf_Signed fp_offset;
     Dwarf_Offset fp_instr_offset;
} Dwarf_Frame_Op;
```

fp_base_op is the 2-bit basic op code. fp_extended_op is the 6-bit extended opcode (if fp_base_op indicated there was an extended op code) and is zero otherwise.

fp_register is any (or the first) register value as defined in the Call Frame Instruction Encodings figure in the dwarf document. If not used with the Op it is 0.

fp_offset is the address, delta, offset, or second register as defined in the Call Frame Instruction Encodings figure in the dwarf document. If this is an address then the value should be cast to (Dwarf_Addr) before being used. In any implementation this field *must* be as large as the larger of Dwarf_Signed and Dwarf_Addr for this to work properly. If not used with the op it is 0.

fp_instr_offset is the byte_offset (within the instruction stream of the frame instructions) of this operation. It starts at 0 for a given frame descriptor.

2.3.5 Macro Details Record

The Dwarf_Macro_Details type gives information about a single entry in the .debug.macinfo section.

```
struct Dwarf_Macro_Details_s {
   Dwarf_Off     dmd_offset;
   Dwarf_Small     dmd_type;
   Dwarf_Signed     dmd_lineno;
   Dwarf_Signed     dmd_fileindex;
   char *     dmd_macro;
};
typedef struct Dwarf_Macro_Details_s Dwarf_Macro_Details;
```

dmd offset is the byte offset, within the .debug_macinfo section, of this macro information.

dmd_type is the type code of this macro info entry (or 0, the type code indicating that this is the end of macro information entries for a compilation unit. See DW_MACINFO_define, etc in the DWARF document.

dmd lineno is the line number where this entry was found, or 0 if there is no applicable line number.

dmd_fileindex is the file index of the file involved. This is only guaranteed meaningful on a DW_MACINFO_start_file dmd_type. Set to -1 if unknown (see the functional interface for more details).

dmd_macro is the applicable string. For a DW_MACINFO_define this is the macro name and value. For a DW_MACINFO_undef, or this is the macro name. For a DW_MACINFO_vendor_ext this is the vendor-defined string value. For other dmd_types this is 0.

2.4 Opaque Types

The opaque types declared in *libdwarf.h* are used as descriptors for queries against dwarf information stored in various debugging sections. Each time an instance of an opaque type is returned as a result of a *libdwarf* operation (Dwarf_Debug excepted), it should be free'd, using dwarf_dealloc() when it is no longer of use. Some functions return a number of instances of an opaque type in a block, by means of a

pointer to the block and a count of the number of opaque descriptors in the block: see the function description for deallocation rules for such functions. The list of opaque types defined in *libdwarf.h* that are pertinent to the Consumer Library, and their intended use is described below.

```
typedef struct Dwarf Debug s* Dwarf Debug;
```

An instance of the <code>Dwarf_Debug</code> type is created as a result of a successful call to <code>dwarf_init()</code>, or <code>dwarf_elf_init()</code>, and is used as a descriptor for subsequent access to most <code>libdwarf</code> functions on that object. The storage pointed to by this descriptor should be not be free'd, using the <code>dwarf_dealloc()</code> function. Instead free it with <code>dwarf_finish()</code>.

```
typedef struct Dwarf_Die_s* Dwarf_Die;
```

An instance of a <code>Dwarf_Die</code> type is returned from a successful call to the <code>dwarf_siblingof()</code>, <code>dwarf_child</code>, or <code>dwarf_offdie()</code> function, and is used as a descriptor for queries about information related to that DIE. The storage pointed to by this descriptor should be free'd, using <code>dwarf_dealloc()</code> with the allocation type <code>DW_DLA_DIE</code> when no longer needed.

```
typedef struct Dwarf Line s* Dwarf Line;
```

Instances of <code>Dwarf_Line</code> type are returned from a successful call to the <code>dwarf_srclines()</code> function, and are used as descriptors for queries about source lines. The storage pointed to by these descriptors should be individually free'd, using <code>dwarf_dealloc()</code> with the allocation type <code>DW DLA LINE</code> when no longer needed.

```
typedef struct Dwarf Global s* Dwarf Global;
```

Instances of <code>Dwarf_Global</code> type are returned from a successful call to the <code>dwarf_get_globals()</code> function, and are used as descriptors for queries about global names (pubnames). The storage pointed to by these descriptors should be individually free'd, using <code>dwarf_dealloc()</code> with the allocation type <code>DW_DLA_GLOBAL</code>, when no longer needed.

```
typedef struct Dwarf Weak s* Dwarf Weak;
```

Instances of <code>Dwarf_Weak</code> type are returned from a successful call to the SGI-specific <code>dwarf_get_weaks()</code> function, and are used as descriptors for queries about weak names. The storage pointed to by these descriptors should be individually free'd, using <code>dwarf_dealloc()</code> with the allocation type <code>DW_DLA_WEAK</code> when no longer needed.

```
typedef struct Dwarf Func s* Dwarf Func;
```

Instances of <code>Dwarf_Func</code> type are returned from a successful call to the <code>SGI-specific</code> <code>dwarf_get_funcs()</code> function, and are used as descriptors for queries about static function names. The storage pointed to by these descriptors should be individually free'd, using <code>dwarf_dealloc()</code> with the allocation type <code>DW DLA FUNC</code>, when no longer needed.

```
typedef struct Dwarf Type s* Dwarf Type;
```

Instances of <code>Dwarf_Type</code> type are returned from a successful call to the SGI-specific <code>dwarf_get_types()</code> function, and are used as descriptors for queries about user defined types. The storage pointed to by this descriptor should be individually free'd, using <code>dwarf_dealloc()</code> with the allocation type <code>DW DLA TYPENAME</code> when no longer needed.

```
typedef struct Dwarf_Var_s* Dwarf_Var;
```

Instances of <code>Dwarf_Var</code> type are returned from a successful call to the SGI-specific <code>dwarf_get_vars()</code> function, and are used as descriptors for queries about static variables. The storage pointed to by this descriptor should be individually free'd, using <code>dwarf_dealloc()</code> with the allocation type <code>DW DLA VAR</code> when no longer needed.

```
typedef struct Dwarf Error s* Dwarf Error;
```

This descriptor points to a structure that provides detailed information about errors detected by libdwarf. Users typically provide a location for libdwarf to store this descriptor for the user to obtain more information about the error. The storage pointed to by this descriptor should be free'd, using dwarf dealloc() with the allocation type DW DLA ERROR when no longer needed.

```
typedef struct Dwarf Attribute s* Dwarf Attribute;
```

Instances of Dwarf_Attribute type are returned from a successful call to the dwarf_attrlist(), or dwarf_attr() functions, and are used as descriptors for queries about attribute values. The storage pointed to by this descriptor should be individually free'd, using dwarf dealloc() with the allocation type DW DLA ATTR when no longer needed.

```
typedef struct Dwarf Abbrev s* Dwarf Abbrev;
```

An instance of a <code>Dwarf_Abbrev</code> type is returned from a successful call to <code>dwarf_get_abbrev()</code>, and is used as a descriptor for queries about abbreviations in the <code>.debug_abbrev</code> section. The storage pointed to by this descriptor should be free'd, using <code>dwarf_dealloc()</code> with the allocation type <code>DW DLA ABBREV</code> when no longer needed.

```
typedef struct Dwarf Fde s* Dwarf Fde;
```

Instances of Dwarf_Fde type are returned from a successful call to the dwarf_get_fde_list(), dwarf_get_fde_for_die(), or dwarf_get_fde_at_pc() functions, and are used as descriptors for queries about frames descriptors. The storage pointed to by these descriptors should be individually free'd, using dwarf_dealloc() with the allocation type DW_DLA_FDE when no longer needed.

```
typedef struct Dwarf_Cie_s* Dwarf_Cie;
```

Instances of <code>Dwarf_Cie</code> type are returned from a successful call to the <code>dwarf_get_fde_list()</code> function, and are used as descriptors for queries about information that is common to several frames. The storage pointed to by this descriptor should be individually free'd, using <code>dwarf_dealloc()</code> with the allocation type <code>DW DLA CIE</code> when no longer needed.

```
typedef struct Dwarf Arange s* Dwarf Arange;
```

Instances of Dwarf_Arange type are returned from successful calls to the dwarf_get_aranges(), or dwarf_get_arange() functions, and are used as descriptors for queries about address ranges. The storage pointed to by this descriptor should be individually free'd, using dwarf_dealloc() with the allocation type DW DLA ARANGE when no longer needed.

3. Error Handling

The method for detection and disposition of error conditions that arise during access of debugging information via *libdwarf* is consistent across all *libdwarf* functions that are capable of producing an error.

This section describes the method used by *libdwarf* in notifying client programs of error conditions.

Most functions within *libdwarf* accept as an argument a pointer to a <code>Dwarf_Error</code> descriptor where a <code>Dwarf_Error</code> descriptor is stored if an error is detected by the function. Routines in the client program that provide this argument can query the <code>Dwarf_Error</code> descriptor to determine the nature of the error and perform appropriate processing.

A client program can also specify a function to be invoked upon detection of an error at the time the library is initialized (see <code>dwarf_init()</code>). When a <code>libdwarf</code> routine detects an error, this function is called with two arguments: a code indicating the nature of the error and a pointer provided by the client at initialization (again see <code>dwarf_init()</code>). This pointer argument can be used to relay information between the error handler and other routines of the client program. A client program can specify or change both the error handling function and the pointer argument after initialization using <code>dwarf_seterrhand()</code> and <code>dwarf_seterrarg()</code>.

In the case where *libdwarf* functions are not provided a pointer to a <code>Dwarf_Error</code> descriptor, and no error handling function was provided at initialization, *libdwarf* functions terminate execution by calling abort (3C).

The following lists the processing steps taken upon detection of an error:

- 1. Check the error argument; if not a *NULL* pointer, allocate and initialize a Dwarf_Error descriptor with information describing the error, place this descriptor in the area pointed to by error, and return a value indicating an error condition.
- 2. If an errhand argument was provided to dwarf_init() at initialization, call errhand() passing it the error descriptor and the value of the errarg argument provided to dwarf_init(). If the error handling function returns, return a value indicating an error condition.
- 3. Terminate program execution by calling abort (3C).

In all cases, it is clear from the value returned from a function that an error occurred in executing the function, since DW_DLV_ERROR is returned.

As can be seen from the above steps, the client program can provide an error handler at initialization, and still provide an error argument to *libdwarf* functions when it is not desired to have the error handler invoked.

If a libdwarf function is called with invalid arguments, the behaviour is undefined. In particular, supplying a NULL pointer to a libdwarf function (except where explicitly permitted), or pointers to invalid addresses or uninitialized data causes undefined behaviour; the return value in such cases is undefined, and the function may fail to invoke the caller supplied error handler or to return a meaningful error number. Implementations also may abort execution for such cases.

3.1 Returned values in the functional interface

Values returned by libdwarf functions to indicate success and errors are enumerated in Figure 2. The DW_DLV_NO_ENTRY case is useful for functions need to indicate that while there was no data to return there was no error either. For example, dwarf_siblingof() may return DW_DLV_NO_ENTRY to indicate that that there was no sibling to return.

SYMBOLIC NAME	VALUE	MEANING
DW_DLV_ERROR	1	Error
DW_DLV_OK	0	Successful call
DW_DLV_NO_ENTRY	-1	No applicable value

Figure 2. Error Indications

Each function in the interface that returns a value returns one of the integers in the above figure.

If DW_DLV_ERROR is returned and a pointer to a Dwarf_Error pointer is passed to the function, then a Dwarf_Error handle is returned thru the pointer. No other pointer value in the interface returns a value. After the Dwarf_Error is no longer of interest, a dwarf_dealloc(dbg,dw_err,DW_DLA_ERROR) on the error pointer is appropriate to free any space used by the error information.

If DW DLV NO ENTRY is returned no pointer value in the interface returns a value.

If DW_DLV_OK is returned the Dwarf_Error pointer, if supplied, is not touched, but any other values to be returned through pointers are returned. In this case calls (depending on the exact function returning the error) to dwarf_dealloc() may be appropriate once the particular pointer returned is no longer of interest.

Pointers passed to allow values to be returned thru them are uniformly the last pointers in each argument list

All the interface functions are defined from the point of view of the writer-of-the-library (as is traditional for UN*X library documentation), not from the point of view of the user of the library. The caller might code:

Dwarf_Line line;
Dwarf_Signed ret_loff;
Dwarf_Error err;
int retval = dwarf_lineoff(line,&ret_loff,&err);

for the function defined as

int dwarf_lineoff(Dwarf_Line line,Dwarf_Signed *return_lineoff,
 Dwarf_Error* err);

and this document refers to the function as returning the value thru *err or *return_lineoff or uses the phrase "returns in the location pointed to by err". Sometimes other similar phrases are used.

4. Memory Management

Several of the functions that comprise *libdwarf* return pointers (opaque descriptors) to structures that have been dynamically allocated by the library. To aid in the management of dynamic memory, the function dwarf_dealloc() is provided to free storage allocated as a result of a call to a *libdwarf* function. This section describes the strategy that should be taken by a client program in managing dynamic storage.

4.1 Read-only Properties

All pointers (opaque descriptors) returned by or as a result of a *libdwarf Consumer Library* call should be assumed to point to read-only memory. The results are undefined for *libdwarf* clients that attempt to write to a region pointed to by a value returned by a *libdwarf Consumer Library* call.

4.2 Storage Deallocation

See the section "Returned values in the functional interface", above, for the general rules where calls to dwarf_dealloc() is appropriate.

In some cases the pointers returned by a *libdwarf* call are pointers to data which is not free-able. The library knows from the allocation type provided to it whether the space is freeable or not and will not free inappropriately when <code>dwarf_dealloc()</code> is called. So it is vital that <code>dwarf_dealloc()</code> be called with the proper allocation type.

For most storage allocated by <code>libdwarf</code>, the client can free the storage for reuse by calling <code>dwarf_dealloc()</code>, providing it with the <code>Dwarf_Debug</code> descriptor specifying the object for which the storage was allocated, a pointer to the area to be free-ed, and an identifier that specifies what the pointer points to (the allocation type). For example, to free a <code>Dwarf_Die</code> <code>die</code> belonging the the object represented by <code>Dwarf_Debug</code> <code>dbg</code>, allocated by a call to <code>dwarf_siblingof()</code>, the call to <code>dwarf_dealloc()</code> would be:

```
dwarf_dealloc(dbg, die, DW_DLA_DIE);
```

To free storage allocated in the form of a list of pointers (opaque descriptors), each member of the list should be deallocated, followed by deallocation of the actual list itself. The following code fragment uses an invocation of <code>dwarf_attrlist()</code> as an example to illustrate a technique that can be used to free storage from any <code>libdwarf</code> routine that returns a list:

The Dwarf_Debug returned from dwarf_init() or dwarf_elf_init() cannot be free'd using dwarf_dealloc(). The function dwarf_finish() will deallocate all dynamic storage associated with an instance of a Dwarf_Debug type. In particular, it will deallocate all dynamically allocated space associated with the Dwarf Debug descriptor, and finally make the descriptor invalid.

An Dwarf_Error returned from dwarf_init() or dwarf_elf_init() in case of a failure cannot be free'd using dwarf_dealloc(). The only way to free the Dwarf_Error from either of those calls is to use *free(3)* directly. Every Dwarf_Error must be free'd by dwarf_dealloc() except those returned by dwarf init() or dwarf_elf_init().

The codes that identify the storage pointed to in calls to dwarf dealloc() are described in figure 3.

IDENTIFIER	USED TO FREE
DW_DLA_STRING	char*
DW_DLA_LOC	Dwarf_Loc
DW_DLA_LOCDESC	Dwarf_Locdesc
DW_DLA_ELLIST	Dwarf_Ellist (not used)
DW_DLA_BOUNDS	Dwarf_Bounds (not used)
DW_DLA_BLOCK	Dwarf_Block
DW_DLA_DEBUG	Dwarf_Debug (do not use)
DW_DLA_DIE	Dwarf_Die
DW_DLA_LINE	Dwarf_Line
DW_DLA_ATTR	Dwarf_Attribute
DW_DLA_TYPE	Dwarf_Type (not used)
DW_DLA_SUBSCR	Dwarf_Subscr (not used)
DW_DLA_GLOBAL	Dwarf_Global
DW_DLA_ERROR	Dwarf_Error
DW_DLA_LIST	a list of opaque descriptors
DW_DLA_LINEBUF	Dwarf_Line* (not used)
DW_DLA_ARANGE	Dwarf_Arange
DW_DLA_ABBREV	Dwarf_Abbrev
DW_DLA_FRAME_OP	Dwarf_Frame_Op
DW_DLA_CIE	Dwarf_Cie
DW_DLA_FDE	Dwarf_Fde
DW_DLA_LOC_BLOCK	Dwarf_Loc Block
DW_DLA_FRAME_BLOCK	Dwarf_Frame Block (not used)
DW_DLA_FUNC	Dwarf_Func
DW_DLA_TYPENAME	Dwarf_Type
DW_DLA_VAR	Dwarf_Var
DW_DLA_WEAK	Dwarf_Weak

Figure 3. Allocation/Deallocation Identifiers

5. Functional Interface

This section describes the functions available in the *libdwarf* library. Each function description includes its definition, followed by one or more paragraph describing the function's operation.

The following sections describe these functions.

5.1 Initialization Operations

These functions are concerned with preparing an object file for subsequent access by the functions in *libdwarf* and with releasing allocated resources when access is complete.

5.1.1 dwarf_init()

```
int dwarf_init(
    int fd,
    Dwarf_Unsigned access,
    Dwarf_Handler errhand,
    Dwarf_Ptr errarg,
    Dwarf_Debug * dbg,
    Dwarf Error *error)
```

When it returns DW_DLV_OK, the function dwarf_init() returns thru dbg a Dwarf_Debug descriptor that represents a handle for accessing debugging records associated with the open file descriptor fd. DW_DLV_NO_ENTRY is returned if the object does not contain DWARF debugging information. DW_DLV_ERROR is returned if an error occurred. The access argument indicates what access is allowed for the section. The DW_DLC_READ parameter is valid for read access (only read access is defined or discussed in this document). The errhand argument is a pointer to a function that will be invoked whenever an error is detected as a result of a *libdwarf* operation. The errarg argument is passed as an argument to the errhand function. The file descriptor associated with the fd argument must refer to an ordinary file (i.e. not a pipe, socket, device, /proc entry, etc.), be opened with the at least as much permission as specified by the access argument, and cannot be closed or used as an argument to any system calls by the client until after dwarf_finish() is called. The seek position of the file associated with fd is undefined upon return of dwarf_init().

With SGI IRIX, by default it is allowed that the app close() fd immediately after calling dwarf_init(), but that is not a portable approach (that it works is an accidental side effect of the fact that SGI IRIX uses ELF_C_READ_MMAP in its hidden internal call to elf_begin()). The portable approach is to consider that fd must be left open till after the corresponding dwarf_finish() call has returned.

Since <code>dwarf_init()</code> uses the same error handling processing as other <code>libdwarf</code> functions (see <code>Error Handling</code> above), client programs will generally supply an <code>error</code> parameter to bypass the default actions during initialization unless the default actions are appropriate.

5.1.2 dwarf elf init()

```
int dwarf_elf_init(
    Elf * elf_file_pointer,
    Dwarf_Unsigned access,
    Dwarf_Handler errhand,
    Dwarf_Ptr errarg,
    Dwarf_Debug * dbg,
    Dwarf_Error *error)
```

The function <code>dwarf_elf_init()</code> is identical to <code>dwarf_init()</code> except that an open <code>Elf * pointer</code> is passed instead of a file descriptor. In systems supporting <code>ELF</code> object files this may be more space or time-efficient than using <code>dwarf_init()</code>. The client is allowed to use the <code>Elf * pointer</code> for its own purposes without restriction during the time the <code>Dwarf_Debug</code> is open, except that the client should not <code>elf_end()</code> the pointer till after <code>dwarf_finish</code> is called.

5.1.3 dwarf_get_elf()

When it returns DW DLV OK, the function dwarf get elf() returns thru the pointer elf the Elf

* handle used to access the object represented by the <code>Dwarf_Debug</code> descriptor <code>dbg</code>. It returns <code>DW DLV ERROR</code> on error.

Because int dwarf_init() opens an Elf descriptor on its fd and dwarf_finish() does not close that descriptor, an app should use dwarf_get_elf and should call elf_end with the pointer returned thru the Elf** handle created by int dwarf init().

This function is not meaningful for a system that does not used the Elf format for objects.

5.1.4 dwarf_finish()

The function <code>dwarf_finish()</code> releases all <code>Libdwarf</code> internal resources associated with the descriptor dbg, and invalidates dbg. It returns <code>DW_DLV_ERROR</code> if there is an error during the finishing operation. It returns <code>DW DLV OK</code> for a successful operation.

Because int dwarf_init() opens an Elf descriptor on its fd and dwarf_finish() does not close that descriptor, an app should use dwarf_get_elf and should call elf_end with the pointer returned thru the Elf** handle created by int dwarf init().

5.2 Debugging Information Entry Delivery Operations

These functions are concerned with accessing debugging information entries.

5.2.1 Debugging Information Entry Debugger Delivery Operations

5.2.2 dwarf_next_cu_header()

The function dwarf_next_cu_header() returns DW_DLV_ERROR if it fails, and DW_DLV_OK if it succeeds.

If it succeeds, *next_cu_header is set to the offset in the .debug_info section of the next compilation-unit header if it succeeds. On reading the last compilation-unit header in the .debug_info section it contains the size of the .debug_info section. The next call to dwarf_next_cu_header() returns DW_DLV_NO_ENTRY without reading a compilation-unit or setting *next_cu_header. Subsequent calls to dwarf_next_cu_header() repeat the cycle by reading the first compilation-unit and so on

The other values returned through pointers are the values in the compilation-unit header. If any of cu_header_length, version_stamp, abbrev_offset, or address_size is NULL, the argument is ignored (meaning it is not an error to provide a NULL pointer).

5.2.3 dwarf_siblingof()

The function <code>dwarf_siblingof()</code> returns <code>DW_DLV_ERROR</code> and sets the <code>error</code> pointer on error. If there is no sibling it returns <code>DW_DLV_NO_ENTRY</code>. When it succeeds, <code>dwarf_siblingof()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_sib</code> to the <code>Dwarf_Die</code> descriptor of the sibling of <code>die</code>. If <code>die</code> is <code>NULL</code>, the <code>Dwarf_Die</code> descriptor of the first die in the compilation-unit is returned. This die has the <code>DW_TAG</code> compile unit tag.

5.2.4 dwarf_child()

The function <code>dwarf_child()</code> returns <code>DW_DLV_ERROR</code> and sets the <code>error</code> die on error. If there is no child it returns <code>DW_DLV_NO_ENTRY</code>. When it succeeds, <code>dwarf_child()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_kid</code> to the <code>Dwarf_Die</code> descriptor of the first child of <code>die</code>. The function <code>dwarf_siblingof()</code> can be used with the return value of <code>dwarf_child()</code> to access the other children of <code>die</code>.

5.2.5 dwarf_offdie()

The function <code>dwarf_offdie()</code> returns <code>DW_DLV_ERROR</code> and sets the <code>error</code> die on error. When it succeeds, <code>dwarf_offdie()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_die</code> to the the <code>Dwarf_Die</code> descriptor of the debugging information entry at <code>offset</code> in the section containing debugging information entries i.e the <code>.debug_info</code> section. A return of <code>DW_DLV_NO_ENTRY</code> means that the <code>offset</code> in the section is of a byte containing all 0 bits, indicating that there is no abbreviation code. Meaning this 'die offset' is not the offset of a real die, but is instead an offset of a null die, a padding die, or of some random zero byte: this should not be returned in normal use. It is the user's responsibility to make sure that <code>offset</code> is the start of a valid debugging information entry. The result of passing it an invalid offset could be chaos.

5.3 Debugging Information Entry Query Operations

These queries return specific information about debugging information entries or a descriptor that can be used on subsequent queries when given a <code>Dwarf_Die</code> descriptor. Note that some operations are specific to debugging information entries that are represented by a <code>Dwarf_Die</code> descriptor of a specific type. For example, not all debugging information entries contain an attribute having a name, so consequently, a call to <code>dwarf_diename()</code> using a <code>Dwarf_Die</code> descriptor that does not have a name attribute will return <code>DW_DLV_NO_ENTRY</code>. This is not an error, i.e. calling a function that needs a specific attribute is not an error for a die that does not contain that specific attribute.

There are several methods that can be used to obtain the value of an attribute in a given die:

- 1. Call dwarf_hasattr() to determine if the debugging information entry has the attribute of interest prior to issuing the query for information about the attribute.
- 2. Supply an error argument, and check its value after the call to a query indicates an unsuccessful return, to determine the nature of the problem. The error argument will indicate whether an error occurred, or the specific attribute needed was missing in that die.
- 3. Arrange to have an error handling function invoked upon detection of an error (see dwarf_init()).
- 4. Call dwarf_attrlist() and iterate through the returned list of attributes, dealing with each one as appropriate.

5.3.1 dwarf_tag()

The function <code>dwarf_tag()</code> returns the *tag* of <code>die</code> thru the pointer <code>tagval</code> if it succeeds. It returns <code>DW DLV OK</code> if it succeeds. It returns <code>DW DLV ERROR</code> on error.

5.3.2 dwarf_dieoffset()

When it succeeds, the function <code>dwarf_dieoffset()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the position of <code>die</code> in the section containing debugging information entries (the <code>return_offset</code> is a section-relative offset). In other words, it sets <code>return_offset</code> to the offset of the start of the debugging information entry described by <code>die</code> in the section containing die's i.e .debug_info. It returns <code>DW_DLV_ERROR</code> on error.

5.3.3 dwarf_die_CU_offset()

The function <code>dwarf_die_CU_offset()</code> is similar to <code>dwarf_dieoffset()</code>, except that it puts the offset of the DIE represented by the <code>Dwarf_Die die</code>, from the start of the compilation-unit that it belongs to rather than the start of <code>.debug_info</code> (the <code>return_offset</code> is a CU-relative offset).

5.3.4 dwarf_diename()

When it succeeds, the function <code>dwarf_diename()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_name</code> to a pointer to a null-terminated string of characters that represents the name attribute of <code>die</code>. It returns <code>DW_DLV_NO_ENTRY</code> if <code>die</code> does not have a name attribute. It returns <code>DW_DLV_ERROR</code> if an error occurred. The storage pointed to by a successful return of <code>dwarf_diename()</code> should be free'd using the allocation type <code>DW_DLA_STRING</code> when no longer of interest (see <code>dwarf_dealloc())</code>.

5.3.5 dwarf_attrlist()

Dwarf_Bool *return_bool,
Dwarf Error *error)

When it returns DW_DLV_OK, the function dwarf_attrlist() sets attrbuf to point to an array of Dwarf_Attribute descriptors corresponding to each of the attributes in die, and returns the number of elements in the array thru attrcount. DW_DLV_NO_ENTRY is returned if the count is zero (no attrbuf is allocated in this case). DW_DLV_ERROR is returned on error. On a successful return from dwarf_attrlist(), each of the Dwarf_Attribute descriptors should be individually free'd using dwarf_dealloc() with the allocation type DW_DLA_ATTR, followed by free-ing the list pointed to by *attrbuf using dwarf_dealloc() with the allocation type DW_DLA_LIST, when no longer of interest (see dwarf dealloc()).

Freeing the attrlist:

When it succeeds, the function <code>dwarf_hasattr()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_bool</code> to <code>non-zero</code> if <code>die</code> has the attribute <code>attr</code> and <code>zero</code> otherwise. If it fails, it returns <code>DW_DLV_ERROR</code>.

5.3.7 dwarf_attr()

When it returns DW_DLV_OK, the function dwarf_attr() sets *return_attr to the Dwarf_Attribute descriptor of die having the attribute attr. It returns **W_DLV_NO_ENTRY** if attr is not contained in die. It returns **W_DLV_ERROR** if an error occurred.

5.3.8 dwarf lowpc()

The function <code>dwarf_lowpc()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_lowpc</code> to the low program counter value associated with the <code>die</code> descriptor if <code>die</code> represents a debugging information entry with this attribute. It returns <code>DW_DLV_NO_ENTRY</code> if <code>die</code> does not have this attribute. It returns <code>DW_DLV_RO_ENTRY</code> if <code>die</code> does not have this attribute. It returns <code>DW_DLV_RO_ENTRY</code> if <code>die</code> does not have this attribute.

5.3.9 dwarf_highpc()

The function <code>dwarf_highpc()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_highpc</code> the high program counter value associated with the <code>die</code> descriptor if <code>die</code> represents a debugging information entry with this attribute. It returns <code>DW_DLV_NO_ENTRY</code> if <code>die</code> does not have this attribute. It returns <code>DW_DLV_NO_ENTRY</code> if <code>die</code> does not have this attribute. It returns <code>DW_DLV_RO_ENTRY</code> if <code>die</code> does not have this attribute.

5.3.10 dwarf_bytesize()

When it succeeds, <code>dwarf_bytesize()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_size</code> to the number of bytes needed to contain an instance of the aggregate debugging information entry represented by <code>die.</code> It returns <code>DW_DLV_NO_ENTRY</code> if <code>die</code> does not contain the byte size attribute <code>DW_AT_byte_size</code>. It returns <code>DW_DLV_ERROR</code> if an error occurred.

5.3.11 dwarf bitsize()

When it succeeds, dwarf_bitsize() returns DW_DLV_OK and sets *return_size to the number of bits occupied by the bit field value that is an attribute of the given die. It returns DW_DLV_NO_ENTRY if die does not contain the bit size attribute DW_AT_bit_size. It returns DW_DLV_ERROR if an error occurred.

5.3.12 dwarf_bitoffset()

When it succeeds, <code>dwarf_bitoffset()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_size</code> to the number of bits to the left of the most significant bit of the bit field value. This bit offset is not necessarily the net bit offset within the structure or class, since <code>DW_AT_data_member_location</code> may give a byte offset to this <code>DIE</code> and the bit offset returned through the pointer does not include the bits in the byte offset. It returns <code>DW_DLV_NO_ENTRY</code> if <code>die</code> does not contain the bit offset attribute <code>DW_AT_bit_offset</code>. It returns <code>DW_DLV_RO_ENTRY</code> if <code>die</code> are reror occurred.

5.3.13 dwarf_srclang()

When it succeeds, dwarf_srclang() returns DW_DLV_OK and sets *return_lang to a code indicating the source language of the compilation unit represented by the descriptor die. It returns DW_DLV_NO_ENTRY if die does not represent a source file debugging information entry (i.e. contain the attribute DW AT language). It returns DW DLV ERROR if an error occurred.

5.3.14 dwarf_arrayorder()

When it succeeds, dwarf_arrayorder() returns DW_DLV_OK and sets *return_order a code indicating the ordering of the array represented by the descriptor die. It returns DW_DLV_NO_ENTRY if die does not contain the array order attribute DW_AT_ordering. It returns DW_DLV_ERROR if an error occurred.

5.4 Attribute Form Queries

Based on the attribute's form, these operations are concerned with returning uninterpreted attribute data. Since it is not always obvious from the return value of these functions if an error occurred, one should always supply an error parameter or have arranged to have an error handling function invoked (see dwarf_init()) to determine the validity of the returned value and the nature of any errors that may have occurred.

A Dwarf_Attribute descriptor describes an attribute of a specific die. Thus, each Dwarf Attribute descriptor is implicitly associated with a specific die.

5.4.1 dwarf_hasform()

The function <code>dwarf_hasform()</code> returns <code>DW_DLV_OK</code> and and puts a <code>non-zero</code> value in the <code>*return_hasform</code> boolean if the attribute represented by the <code>Dwarf_Attribute</code> descriptor <code>attr</code> has the attribute form <code>form</code>. If the attribute does not have that form <code>zero</code> is put into <code>*return_hasform</code>. <code>DW_DLV_ERROR</code> is returned on error.

5.4.2 dwarf whatform()

When it succeeds, <code>dwarf_whatform()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_form</code> to the attribute form code of the attribute represented by the <code>Dwarf_Attribute</code> descriptor <code>attr</code>. It returns <code>DW_DLV_ERROR</code> on error.

5.4.3 dwarf_whatattr()

When it succeeds, dwarf_whatattr() returns DW_DLV_OK and sets *return_attr to the attribute code represented by the Dwarf_Attribute descriptor attr. It returns DW_DLV_ERROR on error.

5.4.4 dwarf_formref()

When it succeeds, <code>dwarf_formref()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the CU-relative offset represented by the descriptor <code>attr</code> if the form of the attribute belongs to the <code>REFERENCE</code> class. <code>attr</code> must be a CU-local reference, not form <code>DW_FORM_ref_addr</code>. It is an error for the form to not belong to this class or to be form <code>DW_FORM_ref_addr</code>. It returns <code>DW_DLV_ERROR</code> on error. See also <code>dwarf_global_formref</code> below.

5.4.5 dwarf_global_formref()

When it succeeds, <code>dwarf_global_formref()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the <code>.debug_info-section-relative</code> offset represented by the descriptor <code>attr</code> if the form of the attribute belongs to the <code>REFERENCE</code> class. <code>attr</code> can be any legal <code>REFERENCE</code> class form including <code>DW_FORM_ref_addr</code>. It is an error for the form to not belong to this class. It returns <code>DW_DLV_ERROR</code> on error. See also <code>dwarf formref</code> above.

5.4.6 dwarf_formaddr()

When it succeeds, <code>dwarf_formaddr()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_addr</code> to the address represented by the descriptor <code>attr</code> if the form of the attribute belongs to the <code>ADDRESS</code> class. It is an error for the form to not belong to this class. It returns <code>DW_DLV_ERROR</code> on error.

5.4.7 dwarf_formflag()

When it succeeds, dwarf_formflag() returns DW_DLV_OK and sets *return_bool 1 (i.e. true) (if the attribute has a non-zero value) or 0 (i.e. false) (if the attribute has a zero value). It returns DW_DLV_ERROR on error or if the attr does not have form flag.

5.4.8 dwarf_formudata()

The function <code>dwarf_formudata()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_uvalue</code> to the <code>Dwarf_Unsigned</code> value of the attribute represented by the descriptor <code>attr</code> if the form of the attribute belongs to the <code>CONSTANT</code> class. It is an error for the form to not belong to this class. It returns <code>DW_DLV_ERROR</code> on error.

5.4.9 dwarf_formsdata()

The function <code>dwarf_formsdata()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_svalue</code> to the <code>Dwarf_Signed</code> value of the attribute represented by the descriptor <code>attr</code> if the form of the attribute belongs to the <code>CONSTANT</code> class. It is an error for the form to not belong to this class. If the size of the data attribute referenced is smaller than the size of the <code>Dwarf_Signed</code> type, its value is sign extended.

It returns DW DLV ERROR on error.

5.4.10 dwarf formblock()

The function <code>dwarf_formblock()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_block</code> to a pointer to a <code>Dwarf_Block</code> structure containing the value of the attribute represented by the descriptor <code>attr</code> if the form of the attribute belongs to the <code>BLOCK</code> class. It is an error for the form to not belong to this class. The storage pointed to by a successful return of <code>dwarf_formblock()</code> should be free'd using the allocation type <code>DW_DLA_BLOCK</code>, when no longer of interest (see <code>dwarf_dealloc()</code>). It returns <code>DW_DLV_ERROR</code> on error.

5.4.11 dwarf_formstring()

The function <code>dwarf_formstring()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_string</code> to a pointer to a null-terminated string containing the value of the attribute represented by the descriptor <code>attr</code> if the form of the attribute belongs to the <code>STRING</code> class. It is an error for the form to not belong to this class. The storage pointed to by a successful return of <code>dwarf_formstring()</code> should be free'd using the allocation type <code>DW_DLA_STRING</code> when no longer of interest (see <code>dwarf_dealloc())</code>. It returns <code>DW_DLV_ERROR</code> on error.

5.4.11.1 dwarf_loclist()

The function <code>dwarf_loclist()</code> sets *llbuf to point to an array of <code>Dwarf_Locdesc</code> pointers corresponding to each of the location expressions in a location list, and sets *listlen to the number of elements in the array and returns <code>DW_DLV_OK</code> if the attribute is appropriate. It returns <code>DW_DLV_ERROR</code> on error. <code>dwarf_loclist()</code> works on <code>DW_AT_location</code>, <code>DW_AT_vtable_elem_location</code>, <code>DW_AT_vt</code>

Storage allocated by a successful call of <code>dwarf_loclist()</code> should be deallocated when no longer of interest (see <code>dwarf_dealloc()</code>). The block of <code>Dwarf_Loc</code> structs pointed to by the <code>ld_s</code> field of each <code>Dwarf_Locdesc</code> structure should be deallocated with the allocation type <code>DW_DLA_LOC_BLOCK</code>. This should be followed by deallocation of the <code>llbuf</code> using the allocation type <code>DW_DLA_LOC_BLOCK</code>.

```
Dwarf_Signed lcnt;
Dwarf_Locdesc *llbuf;
int lres;

if ((lres = dwarf_loclist(someattr, &llbuf,&lcnt &error)) == DW_DLV_OK) {
    for (i = 0; i < lcnt; ++i) {
        /* use llbuf[i] */

        /* Deallocate Dwarf_Loc block of llbuf[i] */
        dwarf_dealloc(dbg, llbuf[i].ld_s, DW_DLA_LOC_BLOCK);

    }
    dwarf_dealloc(dbg, llbuf, DW_DLA_LOCDESC);
}</pre>
```

5.5 Line Number Operations

These functions are concerned with accessing line number entries, mapping debugging information entry objects to their corresponding source lines, and providing a mechanism for obtaining information about line number entries. Although, the interface talks of "lines" what is really meant is "statements". In case there is more than one statement on the same line, there will be at least one descriptor per statement, all with the same line number. If column number is also being represented they will have the column numbers of the start of the statements also represented.

There can also be more than one Dwarf_Line per statement. For example, if a file is preprocessed by a language translator, this could result in translator output showing 2 or more sets of line numbers per translated line of output.

5.5.1 Get A Set of Lines

The function returns information about every source line for a particular compilation-unit. The compilation-unit is specified by the corresponding die.

5.5.1.1 dwarf_srclines()

The function <code>dwarf_srclines()</code> places all line number descriptors for a single compilation unit into a single block, sets <code>*linebuf</code> to point to that block, sets <code>*linecount</code> to the number of descriptors in this block and returns <code>DW_DLV_OK</code>. The compilation-unit is indicated by the given <code>die</code> which must be a compilation-unit die. It returns <code>DW_DLV_ERROR</code> on error. On successful return, each line number information structure pointed to by an entry in the block should be free'd using <code>dwarf_dealloc()</code> with the allocation type <code>DW_DLA_LINE</code> when no longer of interest. Also the block of descriptors itself should be free'd using <code>dwarf_dealloc()</code> with the allocation type <code>DW_DLA_LIST</code> when no longer of interest.

5.5.2 Get the set of Source File Names

The function returns the names of the source files that have contributed to the compilation-unit represented by the given DIE. Only the source files named in the statement program prologue are returned.

When it succeeds <code>dwarf_srcfiles()</code> returns <code>DW_DLV_OK</code> and puts the number of source files named in the statement program prologue indicated by the given <code>die</code> into <code>*srccount</code>. Source files defined in the statement program are ignored. The given <code>die</code> should have the tag <code>DW_TAG_compile_unit</code>. The location pointed to by <code>srcfiles</code> is set to point to a list of pointers to null-terminated strings that name the source files. On a successful return from this function, each of the strings returned should be individually free'd using <code>dwarf_dealloc()</code> with the allocation type <code>DW_DLA_STRING</code> when no longer of interest. This should be followed by free-ing the list using <code>dwarf_dealloc()</code> with the allocation type <code>DW_DLA_LIST</code>. It returns <code>DW_DLV_ERROR</code> on error. It returns <code>DW_DLV_NO_ENTRY</code> if there is no corresponding statement program (i.e., if there is no line information).

5.5.3 Get information about a Single Table Line

The following functions can be used on the Dwarf_Line descriptors returned by dwarf_srclines() to obtain information about the source lines.

5.5.3.1 dwarf_linebeginstatement()

The function <code>dwarf_linebeginstatement()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_bool</code> to <code>non-zero</code> (if <code>line</code> represents a line number entry that is marked as beginning a statement). or <code>zero</code> ((if <code>line</code> represents a line number entry that is not marked as beginning a statement). It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.5.3.2 dwarf_lineendsequence()

The function <code>dwarf_lineendsequence()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_bool</code> nonzero if <code>line</code> represents a line number entry that is marked as ending a text sequence) or zero ((if <code>line</code> represents a line number entry that is not marked as ending a text sequence). It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW DLV NO ENTRY</code>.

5.5.3.3 dwarf_lineno()

The function <code>dwarf_lineno()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_lineno</code> to the source statement line number corresponding to the descriptor <code>line</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.5.3.4 dwarf_lineaddr()

The function <code>dwarf_lineaddr()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_lineaddr</code> to the address associated with the descriptor <code>line</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW DLV NO ENTRY</code>.

5.5.3.5 dwarf_lineoff()

The function <code>dwarf_lineoff()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_lineoff</code> to the column number at which the statement represented by <code>line</code> begins. It sets <code>return_lineoff</code> to <code>-I</code> if the column number of the statement is not represented (meaning the producer library call was given zero as the column number).

On error it returns DW_DLV_ERROR. It never returns DW_DLV_NO_ENTRY.

5.5.3.6 dwarf_linesrc()

The function <code>dwarf_linesrc()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_linesrc</code> to a pointer to a null-terminated string of characters that represents the name of the source-file where <code>line</code> occurs. It returns <code>DW_DLV_ERROR</code> on error.

If the applicable file name in the line table Statement Program Prolog does not start with a '/' character the string in DW_AT_comp_dir (if applicable and present) or the applicable directory name from the line Statement Program Prolog is prepended to the file name in the line table Statement Program Prolog to make a full path.

The storage pointed to by a successful return of dwarf_linesrc() should be free'd using dwarf_dealloc() with the allocation type DW_DLA_STRING when no longer of interest. It never returns DW DLV NO ENTRY.

5.5.3.7 dwarf_lineblock()

The function <code>dwarf_lineblock()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_linesrc</code> to non-zero (i.e. true)(if the line is marked as beginning a basic block) or zero (i.e. false) (if the line is marked as not beginning a basic block). It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.6 Global Name Space Operations

These operations operate on the .debug_pubnames section of the debugging information.

5.6.1 Debugger Interface Operations

5.6.1.1 dwarf_get_globals()

The function <code>dwarf_get_globals()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_count</code> to the count of pubnames represented in the section containing pubnames i.e. <code>.debug_pubnames</code>. It also stores at <code>*globals</code>, a pointer to a list of <code>Dwarf_Global</code> descriptors, one for each of the pubnames in the <code>.debug_pubnames</code> section. It returns <code>DW_DLV_ERROR</code> on error. It returns <code>DW_DLV_NO_ENTRY</code> if the <code>.debug_pubnames</code> section does not exist.

On a successful return from this function, the Dwarf Global descriptors should be individually free'd

using dwarf_dealloc() with the allocation type DW_DLA_GLOBAL, followed by the deallocation of the list itself with the allocation type DW DLA LIST when the descriptors are no longer of interest.

5.6.1.2 dwarf_globname()

The function <code>dwarf_globname()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_name</code> to a pointer to a null-terminated string that names the pubname represented by the <code>Dwarf_Global</code> descriptor, <code>global</code>. It returns <code>DW_DLV_ERROR</code> on error. On a successful return from this function, the string should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.6.1.3 dwarf_global_die_offset()

The function <code>dwarf_global_die_offset()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the offset in the section containing <code>DIE</code>'s, i.e. <code>.debug_info</code>, of the <code>DIE</code> representing the pubname that is described by the <code>Dwarf_Global</code> descriptor, <code>glob</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.6.1.4 dwarf_global_cu_offset()

The function <code>dwarf_global_cu_offset()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the offset in the section containing <code>DIE</code>'s, i.e. <code>.debug_info</code>, of the compilation-unit header of the compilation-unit that contains the pubname described by the <code>Dwarf_Global</code> descriptor, <code>global</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.6.1.5 dwarf_get_cu_die_offset_given_cu_header_offset()

The function dwarf_get_cu_die_offset_given_cu_header_offset() returns DW_DLV_OK and sets *out_cu_die_offset to the offset of the compilation-unit DIE given the offset in_cu_header_offset of a compilation-unit header. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO ENTRY.

This effectively turns a compilation-unit-header offset into a compilation-unit DIE offset (by adding the size of the applicable CU header). This function is also sometimes useful with the dwarf_weak_cu_offset(), dwarf_func_cu_offset(), dwarf_type_cu_offset(), and int dwarf_var_cu_offset() functions.

```
dwarf_get_cu_die_offset_given_cu_header_offset() added Rev 1.45, June, 2001.
```

This function is declared as 'optional' in libdwarf.h on IRIX systems so the _MIPS_SYMBOL_PRESENT predicate may be used at run time to determine if the version of libdwarf linked into an application has this function.

5.6.1.6 dwarf_global_name_offsets()

The function <code>dwarf_global_name_offsets()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_name</code> to a pointer to a null-terminated string that gives the name of the pubname described by the <code>Dwarf_Global</code> descriptor <code>global</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. It also returns in the locations pointed to by <code>die_offset</code>, and <code>cu_offset</code>, the offsets of the DIE representing the pubname, and the DIE representing the compilation-unit containing the pubname, respectively. On a successful return from <code>dwarf_global_name_offsets()</code> the storage pointed to by <code>return_name</code> should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

5.7 Weak Name Space Operations

These operations operate on the .debug_weaknames section of the debugging information.

These operations are SGI specific, not part of standard DWARF.

5.7.1 Debugger Interface Operations

5.7.1.1 dwarf_get_weaks()

The function <code>dwarf_get_weaks()</code> returns <code>DW_DLV_OK</code> and sets <code>*weak_count</code> to the count of weak names represented in the section containing weak names i.e. <code>.debug_weaknames</code>. It returns <code>DW_DLV_ERROR</code> on error. It returns <code>DW_DLV_NO_ENTRY</code> if the section does not exist. It also stores in <code>*weaks</code>, a pointer to a list of <code>Dwarf_Weak</code> descriptors, one for each of the weak names in the <code>.debug_weaknames</code> section. On a successful return from this function, the <code>Dwarf_Weak</code> descriptors should be individually free'd using <code>dwarf_dealloc()</code> with the allocation type <code>DW_DLA_WEAK</code>, followed by the deallocation of the list itself with the allocation type <code>DW_DLA_LIST</code> when the descriptors are no longer of interest.

5.7.1.2 dwarf_weakname()

The function <code>dwarf_weakname()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_name</code> to a pointer to a null-terminated string that names the weak name represented by the <code>Dwarf_Weak</code> descriptor, weak. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. On a successful return from this function, the string should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

The function <code>dwarf_weak_die_offset()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the offset in the section containing <code>DIE</code>'s, i.e. <code>.debug_info</code>, of the <code>DIE</code> representing the weak name that is described by the <code>Dwarf_Weak</code> descriptor, <code>weak</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO ENTRY</code>.

5.7.1.3 dwarf_weak_cu_offset()

The function <code>dwarf_weak_cu_offset()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the offset in the section containing <code>DIE</code>'s, i.e. <code>.debug_info</code>, of the compilation-unit header of the compilation-unit that contains the weak name described by the <code>Dwarf_Weak</code> descriptor, <code>weak</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.7.1.4 dwarf_weak_name_offsets()

```
int dwarf_weak_name_offsets(
    Dwarf_Weak weak,
    char ** weak_name,
    Dwarf_Off *die_offset,
    Dwarf_Off *cu_offset,
    Dwarf_Error *error)
```

The function <code>dwarf_weak_name_offsets()</code> returns <code>DW_DLV_OK</code> and sets <code>*weak_name</code> to a pointer to a null-terminated string that gives the name of the weak name described by the <code>Dwarf_Weak</code> descriptor <code>weak</code>. It also returns in the locations pointed to by <code>die_offset</code>, and <code>cu_offset</code>, the offsets of the DIE representing the weakname, and the DIE representing the compilation-unit containing the weakname, respectively. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. On a successful return from <code>dwarf_weak_name_offsets()</code> the storage pointed to by <code>weak_name</code> should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

5.8 Static Function Names Operations

This section is SGI specific and is not part of standard DWARF version 2.

These function operate on the .debug_funcnames section of the debugging information. The .debug_funcnames section contains the names of static functions defined in the object, the offsets of the DIEs that represent the definitions of the corresponding functions, and the offsets of the start of the compilation-units that contain the definitions of those functions.

5.8.1 Debugger Interface Operations

5.8.1.1 dwarf_get_funcs()

The function <code>dwarf_get_funcs()</code> returns <code>DW_DLV_OK</code> and sets <code>*func_count</code> to the count of static function names represented in the section containing static function names, i.e. <code>.debug_funcnames</code>. It also stores, at <code>*funcs</code>, a pointer to a list of <code>Dwarf_Func</code> descriptors, one for each of the static functions in the <code>.debug_funcnames</code> section. It returns <code>DW_DLV_NOCOUNT</code> on error. It returns <code>DW_DLV_NO_ENTRY</code> if the <code>.debug_funcnames</code> section does not exist. On a successful return from this function, the <code>Dwarf_Func</code> descriptors should be individually free'd using <code>dwarf_dealloc()</code> with

the allocation type DW_DLA_FUNC, followed by the deallocation of the list itself with the allocation type DW DLA LIST when the descriptors are no longer of interest.

5.8.1.2 dwarf_funcname()

The function <code>dwarf_funcname()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_name</code> to a pointer to a null-terminated string that names the static function represented by the <code>Dwarf_Func</code> descriptor, <code>func</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. On a successful return from this function, the string should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

5.8.1.3 dwarf_func_die_offset()

The function <code>dwarf_func_die_offset()</code>, returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the offset in the section containing <code>DIE</code>'s, i.e. <code>.debug_info</code>, of the <code>DIE</code> representing the static function that is described by the <code>Dwarf_Func</code> descriptor, <code>func</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.8.1.4 dwarf_func_cu_offset()

The function <code>dwarf_func_cu_offset()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the offset in the section containing <code>DIE</code>'s, i.e. <code>.debug_info</code>, of the compilation-unit header of the compilation-unit that contains the static function described by the <code>Dwarf_Func</code> descriptor, <code>func</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.8.1.5 dwarf_func_name_offsets()

The function <code>dwarf_func_name_offsets()</code> returns <code>DW_DLV_OK</code> and sets <code>*func_name</code> to a pointer to a null-terminated string that gives the name of the static function described by the <code>Dwarf_Func</code> descriptor <code>func</code>. It also returns in the locations pointed to by <code>die_offset</code>, and <code>cu_offset</code>, the offsets of the DIE representing the static function, and the DIE representing the compilation-unit containing the static function, respectively. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. On a successful return from <code>dwarf_func_name_offsets()</code> the storage pointed to by <code>func_name</code> should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

5.9 User Defined Type Names Operations

This section is SGI specific and is not part of standard DWARF version 2.

These functions operate on the .debug_typenames section of the debugging information. The .debug_typenames section contains the names of file-scope user-defined types, the offsets of the DIEs that represent the definitions of those types, and the offsets of the compilation-units that contain the definitions of those types.

5.9.1 Debugger Interface Operations

5.9.1.1 dwarf_get_types()

The function <code>dwarf_get_types()</code> returns <code>DW_DLV_OK</code> and sets <code>*typecount</code> to the count of user-defined type names represented in the section containing user-defined type names, i.e. .debug_typenames. It also stores at <code>*types</code>, a pointer to a list of <code>Dwarf_Type</code> descriptors, one for each of the user-defined type names in the .debug_typenames section. It returns <code>DW_DLV_NOCOUNT</code> on error. It returns <code>DW_DLV_NO_ENTRY</code> if the .debug_typenames section does not exist. On a successful return from this function, the <code>Dwarf_Type</code> descriptors should be individually free'd using <code>dwarf_dealloc()</code> with the allocation type <code>DW_DLA_TYPENAME</code>, followed by the deallocation of the list itself with the allocation type <code>DW_DLA_LIST</code> when the descriptors are no longer of interest.

5.9.1.2 dwarf_typename()

The function <code>dwarf_typename()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_name</code> to a pointer to a null-terminated string that names the user-defined type represented by the <code>Dwarf_Type</code> descriptor, <code>type</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. On a successful return from this function, the string should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

5.9.1.3 dwarf_type_die_offset()

The function <code>dwarf_type_die_offset()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the offset in the section containing <code>DIE</code>'s, i.e. <code>.debug_info</code>, of the <code>DIE</code> representing the user-defined type that is described by the <code>Dwarf_Type</code> descriptor, <code>type</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.9.1.4 dwarf_type_cu_offset()

The function <code>dwarf_type_cu_offset()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_offset</code> to the offset in the section containing <code>DIE</code>'s, i.e. <code>.debug_info</code>, of the compilation-unit header of the compilation-unit that contains the user-defined type described by the <code>Dwarf_Type</code> descriptor, <code>type</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.9.1.5 dwarf_type_name_offsets()

The function <code>dwarf_type_name_offsets()</code> returns <code>DW_DLV_OK</code> and sets <code>*returned_name</code> to a pointer to a null-terminated string that gives the name of the user-defined type described by the <code>Dwarf_Type</code> descriptor <code>type</code>. It also returns in the locations pointed to by <code>die_offset</code>, and <code>cu_offset</code>, the offsets of the DIE representing the user-defined type, and the DIE representing the compilation-unit containing the user-defined type, respectively. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. On a successful return from <code>dwarf_type_name_offsets()</code> the storage pointed to by <code>returned_name</code> should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

5.10 User Defined Static Variable Names Operations

This section is SGI specific and is not part of standard DWARF version 2.

These functions operate on the .debug_varnames section of the debugging information. The .debug_varnames section contains the names of file-scope static variables, the offsets of the DIEs that represent the definitions of those variables, and the offsets of the compilation-units that contain the definitions of those variables.

5.10.1 Debugger Interface Operations

5.10.1.1 dwarf_get_vars()

The function <code>dwarf_get_vars()</code> returns <code>DW_DLV_OK</code> and sets <code>*var_count</code> to the count of file-scope static variable names represented in the section containing file-scope static variable names, i.e. .debug_varnames. It also stores, at <code>*vars</code>, a pointer to a list of <code>Dwarf_Var</code> descriptors, one for each of the file-scope static variable names in the .debug_varnames section. It returns <code>DW_DLV_ERROR</code> on error. It returns <code>DW_DLV_NO_ENTRY</code> if the .debug_varnames section does not exist. On a successful return from this function, the <code>Dwarf_Var</code> descriptors should be individually free'd using <code>dwarf_dealloc()</code> with the allocation type <code>DW_DLA_VAR</code>, followed by the deallocation of the list itself with the allocation type <code>DW_DLA_VAR</code>, follower of interest.

5.10.1.2 dwarf_varname()

The function <code>dwarf_varname()</code> returns <code>DW_DLV_OK</code> and sets <code>*returned_name</code> to a pointer to a null-terminated string that names the file-scope static variable represented by the <code>Dwarf_Var</code> descriptor, <code>var</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. On a successful return from this function, the string should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

5.10.1.3 dwarf_var_die_offset()

The function <code>dwarf_var_die_offset()</code> returns <code>DW_DLV_OK</code> and sets <code>*returned_offset</code> to the offset in the section containing <code>DIE</code>'s, i.e. <code>.debug_info</code>, of the <code>DIE</code> representing the file-scope static variable that is described by the <code>Dwarf_Var</code> descriptor, <code>var</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.10.1.4 dwarf_var_cu_offset()

The function <code>dwarf_var_cu_offset()</code> returns <code>DW_DLV_OK</code> and sets <code>*returned_offset</code> to the offset in the section containing <code>DIE</code>'s, i.e. <code>.debug_info</code>, of the compilation-unit header of the compilation-unit that contains the file-scope static variable described by the <code>Dwarf_Var</code> descriptor, <code>var</code>. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>.

5.10.1.5 dwarf_var_name_offsets()

The function <code>dwarf_var_name_offsets()</code> returns <code>DW_DLV_OK</code> and sets <code>*returned_name</code> to a pointer to a null-terminated string that gives the name of the file-scope static variable described by the <code>Dwarf_Var</code> descriptor <code>var</code>. It also returns in the locations pointed to by <code>die_offset</code>, and <code>cu_offset</code>, the offsets of the DIE representing the file-scope static variable, and the DIE representing the compilation-unit containing the file-scope static variable, respectively. It returns <code>DW_DLV_ERROR</code> on error. It never returns <code>DW_DLV_NO_ENTRY</code>. On a successful return from <code>dwarf_var_name_offsets()</code> the storage pointed to by <code>returned_name</code> should be free'd using <code>dwarf_dealloc()</code>, with the allocation type <code>DW_DLA_STRING</code> when no longer of interest.

5.11 Macro Information Operations

5.11.1 General Macro Operations

5.11.1.1 dwarf_find_macro_value_start()

```
char *dwarf_find_macro_value_start(char * macro_string);
```

Given a macro string in the standard form defined in the DWARF document ("name <space> value" or "name(args) < space> value") this returns a pointer to the first byte of the macro value. It does not alter the string pointed to by macro_string or copy the string: it returns a pointer into the string whose address was passed in.

5.11.2 Debugger Interface Macro Operations

Macro information is accessed from the .debug_info section via the DW_AT_macro_info attribute (whose value is an offset into .debug_macinfo).

No Functions yet defined.

5.11.3 Low Level Macro Information Operations

5.11.3.1 dwarf_get_macro_details()

dwarf_get_macro_details() returns DW_DLV_OK and sets entry_count to the number of details records returned through the details pointer. The data returned thru details should be freed by a call to dwarf_dealloc() with the allocation type DW_DLA_STRING. If DW_DLV_OK is returned, the entry_count will be at least 1, since a compilation unit with macro information but no macros will have at least one macro data byte of 0.

dwarf_get_macro_details() begins at the macro_offset offset you supply and ends at the end of a compilation unit or at maximum_count detail records (whichever comes first). If maximum count is 0, it is treated as if it were the maximum possible unsigned integer.

dwarf_get_macro_details() attempts to set dmd_fileindex to the correct file in every details record. If it is unable to do so (or whenever the current file index is unknown, it sets dmd_fileindex to -1.

dwarf_get_macro_details() returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if there is no more macro information at that macro_offset. If macro_offset is passed in as 0, a DW_DLV_NO_ENTRY return means there is no macro information.

5.12 Low Level Frame Operations

These functions provide information about stack frames to be used to perform stack traces. The information is an abstraction of a table with a row per instruction and a column per register and a column for the canonical frame address (CFA, which corresponds to the notion of a frame pointer), as well as a column for the return address. Each cell in the table contains one of the following:

- 1. A register + offset(a)(b)
- 2. A register(c)(d)
- 3. A marker (DW_FRAME_UNDEFINED_VAL) meaning register value undefined
- 4. A marker (DW_FRAME_SAME_VAL) meaning register value same as in caller
- (a) When the column is DW_FRAME_CFA_COL: the register number is a real hardware register, not a reference to DW_FRAME_CFA_COL, not DW_FRAME_UNDEFINED_VAL, and not DW_FRAME_SAME_VAL. The CFA rule value should be the stack pointer plus offset 0 when no other value makes sense. A value of DW_FRAME_SAME_VAL would be semi-logical, but since the CFA is not a real register, not really correct. A value of DW_FRAME_UNDEFINED_VAL would imply the CFA is undefined -- this seems to be a useless notion, as the CFA is a means to finding real registers, so those real registers should be marked DW_FRAME_UNDEFINED_VAL, and the CFA column content (whatever register it specifies) becomes unreferenced by anything.
- (b) When the column is not DW_FRAME_CFA_COL, the 'register' will and must be DW_FRAME_CFA_COL, implying that to get the final location for the column one must add the offset here plus the DW_FRAME_CFA_COL rule value.
- (c) When the column is DW_FRAME_CFA_COL, then the register number is (must be) a real hardware register . If it were DW_FRAME_UNDEFINED_VAL or DW_FRAME_SAME_VAL it would be a marker, not a register number.

(d) When the column is not DW_FRAME_CFA_COL, the register may be a hardware register. It will not be DW_FRAME_CFA_COL.

There is no 'column' for DW_FRAME_UNDEFINED_VAL or DW_FRAME_SAME_VAL.

Figure 3 is machine dependent and represents MIPS cpu register assignments.

NAME	value	PURPOSE
DW_FRAME_CFA_COL	0	column used for CFA
DW_FRAME_REG1	1	integer regster 1
DW_FRAME_REG2	2	integer register 2
		obvious names and values here
DW_FRAME_REG30	30	integer register 30
DW_FRAME_REG31	31	integer register 31
DW_FRAME_FREG0	32	floating point register 0
DW_FRAME_FREG1	33	floating point register 1
		obvious names and values here
DW_FRAME_FREG30	62	floating point register 30
DW_FRAME_FREG31	63	floating point register 31
DW_FRAME_RA_COL	64	column recording ra
DW_FRAME_UNDEFINED_	VAL1034	register val undefined
DW_FRAME_SAME_VAL	1035	register same as in caller

Figure 4. Frame Information Rule Assignments

The following table shows SGI/MIPS specific special cell values: these values mean that the cell has the value *undefined* or *same value* respectively, rather than containing a *register* or *register+offset*.

NAME	value	PURPOSE
DW_FRAME_UNDEFINED_VAL	1034	means undefined value.
		Not a column or register value
DW_FRAME_SAME_VAL	1035	means 'same value' as
		caller had. Not a column or
		register value

Figure 5. Frame Information Special Values

5.12.0.1 dwarf_get_fde_list()

dwarf_get_fde_list() stores a pointer to a list of Dwarf_Cie descriptors in *cie_data, and the count of the number of descriptors in *cie_element_count. There is a descriptor for each CIE in the .debug_frame section. Similarly, it stores a pointer to a list of Dwarf_Fde descriptors in *fde_data, and the count of the number of descriptors in *fde_element_count. There is one

descriptor per FDE in the .debug_frame section. dwarf_get_fde_list() returns DW_DLV_EROR on error. It returns DW_DLV_NO_ENTRY if it cannot find frame entries. It returns DW_DLV_OK on a successful return.

On successful return, each of the structures pointed to by a descriptor should be individually free'd using dwarf_dealloc() with either the allocation type DW_DLA_CIE, or DW_DLA_FDE as appropriate when no longer of interest. Each of the blocks of descriptors should be free'd using dwarf_dealloc() with the allocation type DW_DLA_LIST when no longer of interest.

```
Dwarf Signed cnt;
Dwarf Cie *cie data;
Dwarf Signed cie count;
Dwarf Fde *fde data;
Dwarf Signed fde count;
int fres;
if ((fres = dwarf get fde list(dbg, &cie data, &cie count,
                &fde data, &fde count, &error)) == DW DLV OK) {
        for (i = 0; i < cie count; ++i) {
                /* use cie[i] */
                dwarf_dealloc(dbg, cie_data[i], DW_DLA_CIE);
        for (i = 0; i < fde count; ++i) {
                /* use fde[i] */
                dwarf dealloc(dbg, fde data[i], DW DLA FDE);
        dwarf dealloc(dbg, cie data, DW DLA LIST);
        dwarf dealloc(dbg, fde data, DW DLA LIST);
}
```

5.12.0.2 dwarf_get_fde_list_eh()

dwarf_get_fde_list_eh() is identical to dwarf_get_fde_list() except that dwarf_get_fde_list_eh() reads the GNU ecgs section named .eh_frame (C++ exception handling information).

dwarf_get_fde_list_eh() stores a pointer to a list of Dwarf_Cie descriptors in *cie_data, and the count of the number of descriptors in *cie_element_count. There is a descriptor for each CIE in the .debug_frame section. Similarly, it stores a pointer to a list of Dwarf_Fde descriptors in *fde_data, and the count of the number of descriptors in *fde_element_count. There is one descriptor per FDE in the .debug_frame section. dwarf_get_fde_list() returns DW_DLV_EROR on error. It returns DW_DLV_NO_ENTRY if it cannot find exception handling entries. It returns DW DLV OK on a successful return.

On successful return, each of the structures pointed to by a descriptor should be individually free'd using dwarf_dealloc() with either the allocation type DW_DLA_CIE, or DW_DLA_FDE as appropriate when no longer of interest. Each of the blocks of descriptors should be free'd using dwarf dealloc() with the allocation type DW DLA LIST when no longer of interest.

5.12.0.3 dwarf_get_cie_of_fde()

dwarf_get_cie_of_fde() stores a Dwarf_Cie into the Dwarf_Cie that cie_returned
points at.

If one has called dwarf_get_fde_list and does not wish to dwarf_dealloc() all the individual FDEs immediately, one must also avoid dwarf_dealloc-ing the CIEs for those FDEs not immediately dealloc'd. Failing to observe this restriction will cause the FDE(s) not dealloced to become invalid: an FDE contains (hidden in it) a CIE pointer which will be be invalid (stale, pointing to freed memory) if the CIE is dealloc'd. The invalid CIE pointer internal to the FDE cannot be detected as invalid by libdwarf. If one later passes an FDE with a stale internal CIE pointer to one of the routines taking an FDE as input the result will be failure of the call (returning DW_DLV_ERROR) at best and it is possible a coredump or worse will happpen (eventually).

dwarf_get_cie_of_fde() returns DW_DLV_OK if it is successful (it will be unless fde is the NULL pointer). It returns DW DLV ERROR if the fde is invalid (NULL).

Each Dwarf_Fde descriptor describes information about the frame for a particular subroutine or function.

int dwarf get fde for die is SGI/MIPS specific.

5.12.0.4 dwarf_get_fde_for_die()

When it succeeds, <code>dwarf_get_fde_for_die()</code> returns <code>DW_DLV_OK</code> and sets <code>*return_fde</code> to a <code>Dwarf_Fde</code> descriptor representing frame information for the given <code>die</code>. It looks for the <code>DW_AT_MIPS_fde</code> attribute in the given <code>die</code>. If it finds it, is uses the value of the attribute as the offset in the <code>.debug_frame</code> section where the FDE begins. If there is no <code>DW_AT_MIPS_fde</code> it returns <code>DW_DLV_NO_ENTRY</code>. If there is an error it returns <code>DW_DLV_ERROR</code>.

5.12.0.5 dwarf_get_fde_range()

On success, <code>dwarf_get_fde_range()</code> returns <code>DW_DLV_OK</code>. The location pointed to by <code>low_pc</code> is set to the low pc value for this function. The location pointed to by <code>func_length</code> is set to the length of the function in bytes. This is essentially the length of the text section for the function. The location pointed to by <code>fde_bytes</code> is set to the address where the FDE begins in the <code>.debug_frame</code> section. The location pointed to by <code>fde_byte_length</code> is set to the length in bytes of the portion of <code>.debug_frame</code> for this FDE. This is the same as the value returned by <code>dwarf_get_fde_range</code>. The location pointed to by <code>cie_offset</code> is set to the offset in the <code>.debug_frame</code> section of the CIE used by this FDE. The location pointed to by <code>cie_index</code> is set to the index of the CIE used by this FDE. The index is the index of the CIE in the list pointed to by <code>cie_data</code> as set by the function <code>dwarf_get_fde_list()</code>. However, if the function <code>dwarf_get_fde_for_die()</code> was used to obtain the given <code>fde</code>, this index may not be correct. The location pointed to by <code>fde_offset</code> is set to the offset of the start of this FDE in the <code>.debug_frame</code> section.

<code>dwarf_get_fde_range()</code> returns <code>DW_DLV_ERROR</code> on error.

5.12.0.6 dwarf_get_cie_info()

```
int dwarf get cie info(
       Dwarf Cie
                        cie,
       Dwarf_Unsigned *bytes_in_cie,
       Dwarf Small *version,
                      **augmenter,
        char
       Dwarf Unsigned *code alignment factor,
       Dwarf Signed *data alignment factor,
        Dwarf Half
                       *return_address_register_rule,
        Dwarf Ptr
                       *initial instructions,
        Dwarf Unsigned *initial instructions length,
       Dwarf Error
                       *error);
```

dwarf_get_cie_info() is primarily for Internal-level Interface consumers. If successful, it returns DW_DLV_OK and sets *bytes_in_cie to the number of bytes in the portion of the frames section for the CIE represented by the given Dwarf_Cie descriptor, cie. The other fields are directly taken from the cie and returned, via the pointers to the caller. It returns DW DLV ERROR on error.

5.12.0.7 dwarf_get_fde_instr_bytes()

dwarf_get_fde_instr_bytes() returns DW_DLV_OK and sets *outinstrs to a pointer to a set of bytes which are the actual frame instructions for this fde. It also sets *outlen to the length, in bytes, of the frame instructions. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. The intent is to allow low-level consumers like a dwarf-dumper to print the bytes in some fashion. The

memory pointed to by outinstrs must not be changed and there is nothing to free.

5.12.0.8 dwarf_get_fde_info_for_reg()

dwarf_get_fde_info_for_reg() returns DW_DLV_OK and sets *offset_relevant to nonzero if the offset is relevant for the row specified by pc_requested and column specified by table_column, for the FDE specified by fde. The intent is to return the rule for the given pc value and register. The location pointed to by register_num is set to the register value for the rule. The location pointed to by offset is set to the offset value for the rule. If offset is not relevant for this rule, *offset_relevant is set to zero. Since more than one pc value will have rows with identical entries, the user may want to know the earliest pc value after which the rules for all the columns remained unchanged. Recall that in the virtual table that the frame information represents there may be one or more table rows with identical data (each such table row at a different pc value). Given a pc_requested which refers to a pc in such a group of identical rows, the location pointed to by row_pc is set to the lowest pc value within the group of identical rows. The value put in *register_num any of the DW_FRAME_* table columns values specified in libdwarf.h or dwarf.h.

```
dwarf get fde info for regreturns DW DLV ERROR if there is an error.
```

It is usable with either dwarf_get_fde_n() or dwarf_get_fde_at_pc().

5.12.0.9 dwarf_get_fde_info_for_all_regs()

dwarf_get_fde_info_for_all_regs() returns DW_DLV_OK and sets *reg_table for the row specified by pc_requested for the FDE specified by fde. The intent is to return the rules for decoding all the registers, given a pc value. reg_table is an array of rules, one for each register specified in dwarf.h. The rule for each register contains three items - dw_regnum which denotes the register value for that rule, dw_offset which denotes the offset value for that rule and dw_offset_relevant which is set to zero if offset is not relevant for that rule. See dwarf get fde info fo reg() for a description of row pc.

```
dwarf get fde info for all regs returns DW DLV ERROR if there is an error.
```

int dwarf get fde info for all regs is SGI/MIPS specific.

5.12.0.10 dwarf_get_fde_n()

5.12.0.11 dwarf_get_fde_at_pc()

dwarf_get_fde_at_pc() returns DW_DLV_OK and sets returned_fde to a Dwarf_Fde descriptor for a function which contains the pc value specified by pc_of_interest. In addition, it sets the locations pointed to by lope and hipe to the low address and the high address covered by this FDE, respectively. It returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if pc_of_interest is not in any of the FDEs represented by the block of Dwarf_Fde descriptors pointed to by fde_data. This function cannot be used unless the block of Dwarf_Fde descriptors has been created by a call to dwarf_get_fde list().

5.12.0.12 dwarf_expand_frame_instructions()

dwarf_expand_frame_instructions() is a High-level interface function which expands a frame instruction byte stream into an array of Dwarf_Frame_Op structures. To indicate success, it returns DW_DLV_OK. The address where the byte stream begins is specified by instruction, and the length of the byte stream is specified by i_length. The location pointed to by returned_op_list is set to point to a table of returned_op_count pointers to Dwarf_Frame_Op which contain the frame instructions in the byte stream. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. After a successful return, the array of structures should be freed using dwarf_dealloc() with the allocation type DW_DLA_FRAME_BLOCK (when they are no longer of interest).

5.13 Location Expression Evaluation

An "interpreter" which evaluates a location expression is required in any debugger. There is no interface defined here at this time.

One problem with defining an interface is that operations are machine dependent: they depend on the interpretation of register numbers and the methods of getting values from the environment the expression is applied to.

It would be desirable to specify an interface.

5.13.1 Location List Internal-level Interface

5.13.1.1 dwarf_get_loclist_entry()

```
int dwarf_get_loclist_entry(
    Dwarf_Debug dbg,
    Dwarf_Unsigned offset,
    Dwarf_Addr *hipc_offset,
    Dwarf_Addr *lopc_offset,
    Dwarf_Ptr *data,
    Dwarf_Unsigned *entry_len,
    Dwarf_Unsigned *next_entry,
    Dwarf_Error *error)
```

dwarf_dwarf_get_loclist_entry() returns DW_DLV_OK if successful. DW_DLV_ERROR is returned on error. The function reads a location list entry starting at offset and returns through pointers (when successful) the high pc hipc_offset, low pc lopc_offset, a pointer to the location description data data, the length of the location description data entry_len, and the offset of the next location description entry next_entry. When hipc and lopc are zero, this is the end of a particular location list.

The hipc_offset, low pc lopc_offset are offsets from the beginning of the current procedure, not genuine pc values.

5.14 Abbreviations access

These are Internal-level Interface functions. Debuggers can ignore this.

5.14.1 dwarf_get_abbrev()

The function <code>dwarf_get_abbrev()</code> returns <code>DW_DLV_OK</code> and sets <code>*returned_abbrev</code> to <code>Dwarf_Abbrev</code> descriptor for an abbreviation at offset <code>*offset</code> in the abbreviations section (i.e. .debug_abbrev) on success. The user is responsible for making sure that a valid abbreviation begins at offset in the abbreviations section. The location pointed to by <code>length</code> is set to the length in bytes of the abbreviation in the abbreviations section. The location pointed to by <code>attr_count</code> is set to the number of attributes in the abbreviation. An abbreviation entry with a length of 1 is the 0 byte of the last abbreviation entry of a compilation unit. <code>dwarf_get_abbrev()</code> returns <code>DW_DLV_ERROR</code> on error.

5.14.2 dwarf_get_abbrev_tag()

If successful, dwarf_get_abbrev_tag() returns DW_DLV_OK and sets *return_tag to the tag of the given abbreviation. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.14.3 dwarf get abbrev code()

If successful, dwarf_get_abbrev_code() returns DW_DLV_OK and sets *return_code to the abbreviation code of the given abbreviation. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

5.14.4 dwarf_get_abbrev_children_flag()

The function <code>dwarf_get_abbrev_children_flag()</code> returns <code>DW_DLV_OK</code> and sets <code>returned_flag</code> to <code>DW_children_no</code> (if the given abbreviation indicates that a die with that abbreviation has no children) or <code>DW_children_yes</code> (if the given abbreviation indicates that a die with that abbreviation has a child). It returns <code>DW_DLV_ERROR</code> on error.

5.14.5 dwarf_get_abbrev_entry()

If successful, dwarf_get_abbrev_entry() returns DW_DLV_OK and sets *attr_num to the attribute code of the attribute whose index is specified by index in the given abbreviation. The index starts at 0. The location pointed to by form is set to the form of the attribute. The location pointed to by offset is set to the byte offset of the attribute in the abbreviations section. It returns DW_DLV_NO_ENTRY if the index specified is outside the range of attributes in this abbreviation. It returns DW_DLV_ERROR on error.

5.15 String Section Operations

The .debug_str section contains only strings. Debuggers need never use this interface: it is only for debugging problems with the string section itself.

5.15.1 dwarf_get_str()

The function <code>dwarf_get_str()</code> returns <code>DW_DLV_OK</code> and sets <code>*returned_str_len</code> to the length of the string, not counting the null terminator, that begins at the offset specified by <code>offset</code> in the <code>.debug_str</code> section. The location pointed to by <code>string</code> is set to a pointer to this string. The next string in the <code>.debug_str</code> section begins at the previous <code>offset + 1 + *returned_str_len</code>. A zero-length string is NOT the end of the section. If there is no <code>.debug_str</code> section, <code>DW_DLV_NO_ENTRY</code> is returned. If there is an error, <code>DW_DLV_ERROR</code> is returned.

5.16 Address Range Operations

These functions provide information about address ranges. Address ranges map ranges of pc values to the corresponding compilation-unit die that covers the address range.

5.16.1 dwarf_get_aranges()

The function dwarf_get_aranges() returns DW_DLV_OK and sets *returned_arange_count to the count of the number of address ranges in the .debug_aranges section. It sets *aranges to point to a block of Dwarf_Arange descriptors, one for each address range. It returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if there is no

.debug_aranges section.

The function <code>dwarf_get_arange()</code> takes as input a pointer to a block of <code>Dwarf_Arange</code> pointers, and a count of the number of descriptors in the block. It then searches for the descriptor that covers the given <code>address</code>. If it finds one, it returns <code>DW_DLV_OK</code> and sets <code>*returned_arange</code> to the descriptor. It returns <code>DW_DLV_ERROR</code> on error. It returns <code>DW_DLV_NO_ENTRY</code> if there is no .debug_aranges entry covering that address.

5.16.2 dwarf get cu die offset()

The function <code>dwarf_get_cu_die_offset()</code> takes a <code>Dwarf_Arange</code> descriptor as input, and if successful returns <code>DW_DLV_OK</code> and sets <code>*returned_cu_die_offset</code> to the offset in the .debug_info section of the compilation-unit <code>DIE</code> for the compilation-unit represented by the given address range. It returns <code>DW_DLV_ERROR</code> on error.

5.16.3 dwarf_get_arange_cu_header_offset()

The function <code>dwarf_get_arange_cu_header_offset()</code> takes a <code>Dwarf_Arange</code> descriptor as input, and if successful returns <code>DW_DLV_OK</code> and sets <code>*returned_cu_header_offset</code> to the offset in the <code>.debug_info</code> section of the compilation-unit header for the compilation-unit represented by the given address range. It returns <code>DW_DLV_ERROR</code> on error.

This function added Rev 1.45, June, 2001.

This function is declared as 'optional' in libdwarf.h on IRIX systems so the _MIPS_SYMBOL_PRESENT predicate may be used at run time to determine if the version of libdwarf linked into an application has this function.

5.16.4 dwarf_get_arange_info()

The function <code>dwarf_get_arange_info()</code> returns <code>DW_DLV_OK</code> and stores the starting value of the address range in the location pointed to by <code>start</code>, the length of the address range in the location pointed to by <code>length</code>, and the offset in the .debug_info section of the compilation-unit DIE for the compilation-unit represented by the address range. It returns <code>DW_DLV_ERROR</code> on error.

5.17 General Low Level Operations

This function is low-level and intended for use only by programs such as dwarf-dumpers.

5.17.1 dwarf_get_address_size()

The function <code>dwarf_get_address_size()</code> returns <code>DW_DLV_OK</code> on success and sets the <code>*addr_size</code> to the size in bytes of an address. In case of error, it returns <code>DW_DLV_ERROR</code> and does not set <code>*addr size</code>.

5.18 Utility Operations

These functions aid in the management of errors encountered when using functions in the *libdwarf* library and releasing memory allocated as a result of a *libdwarf* operation.

5.18.1 dwarf_errno()

The function <code>dwarf_errno()</code> returns the error number corresponding to the error specified by error.

5.18.2 dwarf_errmsg()

The function <code>dwarf_errmsg()</code> returns a pointer to a null-terminated error message string corresponding to the error specified by <code>error</code>. The string returned by <code>dwarf_errmsg()</code> should not be deallocated using <code>dwarf_dealloc()</code>.

The set of errors enumerated in Figure 3 below were defined in Dwarf 1. These errors are not used by the current implementation of Dwarf 2.

SYMBOLIC NAME	DESCRIPTION
DW_DLE_NE	No error (0)
DW_DLE_VMM	Version of DWARF information newer than libdwarf
DW_DLE_MAP	Memory map failure
DW_DLE_LEE	Propagation of libelf error
DW_DLE_NDS	No debug section
DW_DLE_NLS	No line section
DW_DLE_ID	Requested information not associated with descriptor
DW_DLE_IOF	I/O failure
DW_DLE_MAF	Memory allocation failure
DW_DLE_IA	Invalid argument
DW_DLE_MDE	Mangled debugging entry
DW_DLE_MLE	Mangled line number entry
DW_DLE_FNO	File descriptor does not refer to an open file
DW_DLE_FNR	File is not a regular file
DW_DLE_FWA	File is opened with wrong access
DW_DLE_NOB	File is not an object file
DW_DLE_MOF	Mangled object file header
DW_DLE_EOLL	End of location list entries
DW_DLE_NOLL	No location list section
DW_DLE_BADOFF	Invalid offset
DW_DLE_EOS	End of section
DW_DLE_ATRUNC	Abbreviations section appears truncated
DW_DLE_BADBITC	Address size passed to dwarf bad

Figure 6. List of Dwarf Error Codes

The set of errors returned by SGI Libdwarf functions is listed below. Some of the errors are SGI specific.

SYMBOLIC NAME	DESCRIPTION
DW_DLE_DBG_ALLOC	Could not allocate Dwarf_Debug struct
DW_DLE_FSTAT_ERROR	Error in fstat()-ing object
DW_DLE_FSTAT_MODE_ERROR	Error in mode of object file
DW_DLE_INIT_ACCESS_WRONG	Incorrect access to dwarf_init()
DW_DLE_ELF_BEGIN_ERROR	Error in elf_begin() on object
DW_DLE_ELF_GETEHDR_ERROR	Error in elf_getehdr() on object
DW_DLE_ELF_GETSHDR_ERROR	Error in elf_getshdr() on object
DW_DLE_ELF_STRPTR_ERROR	Error in elf_strptr() on object
DW_DLE_DEBUG_INFO_DUPLICATE	Multiple .debug_info sections
DW_DLE_DEBUG_INFO_NULL	No data in .debug_info section
DW_DLE_DEBUG_ABBREV_DUPLICATE	Multiple .debug_abbrev sections
DW_DLE_DEBUG_ABBREV_NULL	No data in .debug_abbrev section
DW_DLE_DEBUG_ARANGES_DUPLICATE	Multiple .debug_arange sections
DW_DLE_DEBUG_ARANGES_DULLL	No data in .debug_arange section
DW_DLE_DEBUG_LINE_DUPLICATE	Multiple .debug_line sections
DW_DLE_DEBUG_LINE_NULL	No data in .debug_line section
DW_DLE_DEBUG_LOC_DUPLICATE	Multiple .debug_loc sections
DW_DLE_DEBUG_LOC_NULL DW_DLE_DEBUG_MACINEO_DUBLICATE	No data in .debug_loc section Multiple .debug_macinfo sections
DW_DLE_DEBUG_MACINFO_DUPLICATE	•
DW_DLE_DEBUG_MACINFO_NULL	No data in .debug_macinfo section
DW_DLE_DEBUG_PUBNAMES_DUPLICATE	Multiple .debug_pubnames sections
DW_DLE_DEBUG_PUBNAMES_NULL	No data in .debug_pubnames section
DW_DLE_DEBUG_STR_DUPLICATE	Multiple .debug_str sections
DW_DLE_DEBUG_STR_NULL	No data in .debug_str section
DW_DLE_CU_LENGTH_ERROR	Length of compilation-unit bad
DW_DLE_VERSION_STAMP_ERROR	Incorrect Version Stamp
DW_DLE_ABBREV_OFFSET_ERROR	Offset in .debug_abbrev bad
DW_DLE_ADDRESS_SIZE_ERROR	Size of addresses in target bad
DW_DLE_DEBUG_INFO_PTR_NULL	Pointer into .debug_info in DIE null
DW_DLE_DIE_NULL	Null Dwarf_Die
DW_DLE_STRING_OFFSET_BAD	Offset in .debug_str bad
DW_DLE_DEBUG_LINE_LENGTH_BAD	Length of .debug_line segment bad
DW_DLE_LINE_PROLOG_LENGTH_BAD	Length of .debug_line prolog bad
DW_DLE_LINE_NUM_OPERANDS_BAD	Number of operands to line instr bad
DW_DLE_LINE_SET_ADDR_ERROR	Error in DW_LNE_set_address instruction
DW_DLE_LINE_EXT_OPCODE_BAD	Error in DW_EXTENDED_OPCODE instruction
DW_DLE_DWARF_LINE_NULL	Null Dwarf_line argument
DW_DLE_INCL_DIR_NUM_BAD	Error in included directory for given line
DW_DLE_LINE_FILE_NUM_BAD	File number in .debug_line bad
DW_DLE_ALLOC_FAIL	Failed to allocate required structs
DW_DLE_DBG_NULL	Null Dwarf_Debug argument
DW_DLE_DEBUG_FRAME_LENGTH_BAD	Error in length of frame
DW_DLE_FRAME_VERSION_BAD	Bad version stamp for frame
DW_DLE_CIE_RET_ADDR_REG_ERROR	Bad register specified for return address
DW_DLE_FDE_NULL	Null Dwarf_Fde argument
DW_DLE_FDE_DBG_NULL	No Dwarf_Debug associated with FDE
DW_DLE_CIE_NULL	Null Dwarf_Cie argument
DW_DLE_CIE_DBG_NULL	No Dwarf_Debug associated with CIE
DW_DLE_FRAME_TABLE_COL_BAD	Bad column in frame table specified
	Bad column in frame table specified

Figure 7. List of Dwarf 2 Error Codes (continued)

SYMBOLIC NAME	DESCRIPTION
DW_DLE_PC_NOT_IN_FDE_RANGE	PC requested not in address range of FDE
DW_DLE_CIE_INSTR_EXEC_ERROR	Error in executing instructions in CIE
DW_DLE_FRAME_INSTR_EXEC_ERROR	Error in executing instructions in FDE
DW_DLE_FDE_PTR_NULL	Null Pointer to Dwarf_Fde specified
DW_DLE_RET_OP_LIST_NULL	No location to store pointer to Dwarf_Frame_Op
DW_DLE_LINE_CONTEXT_NULL	Dwarf_Line has no context
DW_DLE_DBG_NO_CU_CONTEXT	dbg has no CU context for dwarf_siblingof()
DW_DLE_DIE_NO_CU_CONTEXT	Dwarf_Die has no CU context
DW_DLE_FIRST_DIE_NOT_CU	First DIE in CU not DW_TAG_compilation_unit
DW_DLE_NEXT_DIE_PTR_NULL	Error in moving to next DIE in .debug_info
DW_DLE_DEBUG_FRAME_DUPLICATE	Multiple .debug_frame sections
DW_DLE_DEBUG_FRAME_NULL	No data in .debug_frame section
DW_DLE_ABBREV_DECODE_ERROR	Error in decoding abbreviation
DW_DLE_DWARF_ABBREV_NULL	Null Dwarf_Abbrev specified
DW_DLE_ATTR_NULL	Null Dwarf_Attribute specified
DW_DLE_DIE_BAD	DIE bad
DW_DLE_DIE_ABBREV_BAD	No abbreviation found for code in DIE
DW_DLE_ATTR_FORM_BAD	Inappropriate attribute form for attribute
DW_DLE_ATTR_NO_CU_CONTEXT	No CU context for Dwarf_Attribute struct
DW_DLE_ATTR_FORM_SIZE_BAD	Size of block in attribute value bad
DW_DLE_ATTR_DBG_NULL	No Dwarf_Debug for Dwarf_Attribute struct
DW_DLE_BAD_REF_FORM	Inappropriate form for reference attribute
DW_DLE_ATTR_FORM_OFFSET_BAD	Offset reference attribute outside current CU
DW_DLE_LINE_OFFSET_BAD	Offset of lines for current CU outside .debug_line
DW_DLE_DEBUG_STR_OFFSET_BAD	Offset into .debug_str past its end
DW_DLE_STRING_PTR_NULL	Pointer to pointer into .debug_str NULL
DW_DLE_PUBNAMES_VERSION_ERROR	Version stamp of pubnames incorrect
DW_DLE_PUBNAMES_LENGTH_BAD	Read pubnames past end of .debug_pubnames
DW_DLE_GLOBAL_NULL	Null Dwarf_Global specified
DW_DLE_GLOBAL_CONTEXT_NULL	No context for Dwarf_Global given
DW_DLE_DIR_INDEX_BAD	Error in directory index read
DW_DLE_LOC_EXPR_BAD	Bad operator read for location expression
DW_DLE_DIE_LOC_EXPR_BAD	Expected block value for attribute not found
DW_DLE_OFFSET_BAD	Offset for next compilation-unit in .debug_info bad
DW_DLE_MAKE_CU_CONTEXT_FAIL	Could not make CU context
DW_DLE_ARANGE_OFFSET_BAD	Offset into .debug_info in .debug_aranges bad
DW_DLE_SEGMENT_SIZE_BAD	Segment size should be 0 for MIPS processors
DW DLE ARANGE LENGTH BAD	Length of arange section in .debug_arange bad
DW_DLE_ARANGE_DECODE_ERROR	Aranges do not end at end of .debug_aranges
DW_DLE_ARANGES_NULL	NULL pointer to Dwarf_Arange specified
DW DLE ARANGE NULL	NULL pointer to Dwarf_Arange specified NULL Dwarf_Arange specified
DW_DLE_NO_FILE_NAME	No file name for Dwarf_Line struct
DW_DLE_NO_COMP_DIR	No Compilation directory for compilation-unit
DW_DLE_CU_ADDRESS_SIZE_BAD	CU header address size not match Elf class
DW_DLE_ELF_GETIDENT_ERROR	Error in elf_getident() on object
DW_DLE_ELF_GETIDENT_ERROR DW_DLE_NO_AT_MIPS_FDE	DIE does not have DW_AT_MIPS_fde attribute
DW_DLE_NO_CIE_FOR_FDE	No CIE specified for FDE
	No CIE specified for FDE No abbreviation for the code in DIE found
DW_DLE_DIE_ABBREV_LIST_NULL DW_DLE_DEPLIC_FUNCNAMES_DUBLICATE	
DW_DLE_DEBUG_FUNCNAMES_DUPLICATE	Multiple .debug_funcnames sections
DW_DLE_DEBUG_FUNCNAMES_NULL	No data in .debug_funcnames section

Figure 8. List of Dwarf 2 Error Codes (continued)

SYMBOLIC NAME	DESCRIPTION
DW_DLE_DEBUG_FUNCNAMES_VERSION_ERROR	Version stamp in .debug_funcnames bad
DW_DLE_DEBUG_FUNCNAMES_LENGTH_BAD	Length error in reading .debug_funcnames
DW_DLE_FUNC_NULL	NULL Dwarf_Func specified
DW_DLE_FUNC_CONTEXT_NULL	No context for Dwarf_Func struct
DW_DLE_DEBUG_TYPENAMES_DUPLICATE	Multiple .debug_typenames sections
DW_DLE_DEBUG_TYPENAMES_NULL	No data in .debug_typenames section
DW_DLE_DEBUG_TYPENAMES_VERSION_ERROR	Version stamp in .debug_typenames bad
DW_DLE_DEBUG_TYPENAMES_LENGTH_BAD	Length error in reading .debug_typenames
DW_DLE_TYPE_NULL	NULL Dwarf_Type specified
DW_DLE_TYPE_CONTEXT_NULL	No context for Dwarf_Type given
DW_DLE_DEBUG_VARNAMES_DUPLICATE	Multiple .debug_varnames sections
DW_DLE_DEBUG_VARNAMES_NULL	No data in .debug_varnames section
DW_DLE_DEBUG_VARNAMES_VERSION_ERROR	Version stamp in .debug_varnames bad
DW_DLE_DEBUG_VARNAMES_LENGTH_BAD	Length error in reading .debug_varnames
DW_DLE_VAR_NULL	NULL Dwarf_Var specified
DW_DLE_VAR_CONTEXT_NULL	No context for Dwarf_Var given
DW_DLE_DEBUG_WEAKNAMES_DUPLICATE	Multiple .debug_weaknames section
DW_DLE_DEBUG_WEAKNAMES_NULL	No data in .debug_varnames section
DW_DLE_DEBUG_WEAKNAMES_VERSION_ERROR	Version stamp in .debug_varnames bad
DW_DLE_DEBUG_WEAKNAMES_LENGTH_BAD	Length error in reading .debug_weaknames
DW_DLE_WEAK_NULL	NULL Dwarf_Weak specified
DW_DLE_WEAK_CONTEXT_NULL	No context for Dwarf_Weak given

Figure 9. List of Dwarf 2 Error Codes

This list of errors is not necessarily complete; additional errors might be added when functionality to create debugging information entries are added to *libdwarf* and by the implementors of *libdwarf* to describe internal errors not addressed by the above list. Some of the above errors may be unused. Errors may not have the same meaning in different implementations.

5.18.3 dwarf_seterrhand()

The function <code>dwarf_seterrhand()</code> replaces the error handler (see <code>dwarf_init())</code> with <code>errhand</code>. The old error handler is returned. This function is currently unimplemented.

5.18.4 dwarf_seterrarg()

The function <code>dwarf_seterrarg()</code> replaces the pointer to the error handler communication area (see <code>dwarf_init())</code> with <code>errarg</code>. A pointer to the old area is returned. This function is currently unimplemented.

5.18.5 dwarf_dealloc()

```
void dwarf_dealloc(
          Dwarf_Debug dbg,
          void* space,
          Dwarf_Unsigned type)
```

The function <code>dwarf_dealloc</code> frees the dynamic storage pointed to by <code>space</code>, and allocated to the given <code>Dwarf_Debug</code>. The argument type is an integer code that specifies the allocation type of the region pointed to by the <code>space</code>. Refer to section 4 for details on <code>libdwarf</code> memory management.

CONTENTS

1.	INTI	RODUCTION	1
	1.1	Purpose and Scope	1
	1.2	Definitions	1
	1.3	Overview	1
	1.4	Items Changed	2
	1.5	Items Removed	2
	1.6	Revision History	2
_	_	•	_
2.		s Definitions	2
	2.1	General Description	3
	2.2	Scalar Types	3
	2.3	Aggregate Types	4
		2.3.1 Location Record	4
		2.3.2 Location Description	5
		2.3.3 Data Block	5
		2.3.4 Frame Operation Codes	5
		2.3.5 Macro Details Record	6
	2.4	Opaque Types	6
2		Transition	0
3.		Handling	8
		Returned values in the functional interface	9
4.	Mem	ory Management	10
	4.1	Read-only Properties	10
	4.2	Storage Deallocation	10
_			
5.			12
	5.1		12
			12
			13
		-6 · - · · · · · · · · · · · · · · · · ·	13
			14
	5.2		14
			14
			14
		5.2.3 dwarf_siblingof()	15
		5.2.4 dwarf_child()	15
			15
	5.3		15
		5.3.1 dwarf_tag()	16
		5.3.2 dwarf_dieoffset()	16
		5.3.3 dwarf_die_CU_offset()	16
			16
		_	17
			17
			18
			18
		– 1 V	18
		- C 1 V	18
		– ,	18
		_	19
			19 19
			19 19
		J.J.14 UWali affavorueru	19

5.4	Attribut	e Form Q	ueries .																		19
		dwarf_has																			20
		dwarf_wh																			20
		dwarf_wh																			20
		dwarf_for																			20
		dwarf_glo																			20
		dwarf_for																			21
		dwarf_for																			21
					•																
		dwarf_for																			21
		dwarf_for																			21
		dwarf_for																			22
		dwarf_for																			22
	4	5.4.11.1	dwarf_lo	clist()				•								•					22
5.5	Line Nu	ımber Ope	erations																		23
	5.5.1	Get A Set																			23
		5.5.1.1	dwarf_sr	clines() .																23
		Get the se	t of Source	e File	Name	20			Ī								Ī	Ī	Ī		24
	5.5.3	Get inforn	nation abo	out a S	inale	Tahl	e I ii	ne	•	•	•	• •	•	•	•	•	•	•	•	•	24
																					25
			dwarf_lii																		
		5.5.3.2	dwarf_lii																		25
		5.5.3.3	dwarf_lii																		25
		5.5.3.4	dwarf_lii																		25
	4	5.5.3.5	dwarf_lii	neoff()			•	•	•	•						•			•		25
	4	5.5.3.6	dwarf_lii	nesrc()																	26
	4	5.5.3.7	dwarf_lii																		26
5.6	Global I	Name Spa			•																26
		Debugger																			26
		5.6.1.1	dwarf_ge																		26
		5.6.1.2	dwarf_gl	obnom	(a13()	•	•	•	•	•	•	• •	•	•	•	•	•	•	•	•	27
		5.6.1.3	dwari_gr	obol d	ic()	· ·		•	•	•	•	• •	•	•	•	•	•	•	•	•	27
			dwarf_gl																		
		5.6.1.4	dwarf_gl																		27
		5.6.1.5	dwarf_ge																		28
		5.6.1.6	dwarf_gl																		28
5.7	Weak N	lame Spac	e Operati	ons .			•	•	•	•					•	•			•		28
	5.7.1 I	Debugger	Interface	Opera	tions																28
		5.7.1.1	dwarf_ge	et_wea	ks()																29
		5.7.1.2	dwarf_w																		29
		5.7.1.3																			30
		5.7.1.4	dwarf_w														•	•	•	•	30
5.8		unction N					.,										•	•	•	•	30
J.6		Debugger												•	•	•	•	•	•	•	30
				-					•	•	•	• •	•	•	•	•	•	•	•	•	
		5.8.1.1	dwarf_ge		.,				•	•	•	• •	•	•	•	•	•	•	•	•	30
		5.8.1.2	dwarf_fu		*/			•	•	•	•		•	•	•	•	•	•	•	•	31
		5.8.1.3	dwarf_fu				•	•	•	•	•		•	•	•	•	•	•	•	•	31
		5.8.1.4	dwarf_fu					•	•	•			•		•	•	•		•	•	31
	4	5.8.1.5	dwarf_fu	nc_na	me_o	ffsets	s()													•	32
5.9	User De	fined Typ	e Names	Opera	tions																32
		Debugger																			32
		5.9.1.1	dwarf_ge				_														32
		5.9.1.2	dwarf_ty							•		•	•	٠		-		•	-	•	33
		5.9.1.2	dwarf_ty	-			•	•	•	•	•	• •	•	•	•	•	•	•	•	•	33
			•	-			•	•	•	•	•	• •	•	•	•	•	•	•	•	•	
		5.9.1.4	dwarf_ty	-										•	•	•	•	•	•	•	33
-		5.9.1.5	dwarf_ty	-				-	•	•	•		•	•	•	•	•	•	•	•	33
5 10	Licer De	fined Stat	nc Variah	Ie Nan	വലം (1)	nerat	1000														3/

	5.10.1 Debugger Interface Operations	34
	5.10.1.1 dwarf_get_vars()	34
	5.10.1.2 dwarf_varname()	35
	5.10.1.3 dwarf_var_die_offset()	
	5.10.1.4 dwarf_var_cu_offset()	
	5.10.1.5 dwarf_var_name_offsets()	
5 1 1	Macro Information Operations	36
).II	5.11.1 General Macro Operations	36
	5.11.1 dwarf_find_macro_value_start()	36
	5.11.2 Debugger Interface Macro Operations	36
	5.11.3 Low Level Macro Information Operations	36
	5.11.3.1 dwarf_get_macro_details()	36
5.12	Low Level Frame Operations	37
	5.12.0.1 dwarf_get_fde_list()	38
	5.12.0.2 dwarf_get_fde_list_eh()	39
	5.12.0.3 dwarf_get_cie_of_fde()	40
	5.12.0.4 dwarf_get_fde_for_die()	40
	5.12.0.5 dwarf_get_fde_range()	40
	5.12.0.6 dwarf_get_cie_info()	41
	5.12.0.7 dwarf_get_fde_instr_bytes()	41
	5.12.0.8 dwarf_get_fde_info_for_reg()	42
	5.12.0.9 dwarf_get_fde_info_for_all_regs()	42
	5.12.0.10 dwarf_get_fde_n()	42
	5.12.0.11 dwarf_get_fde_at_pc()	43
	5.12.0.12 dwarf_expand_frame_instructions()	43
5 13	Location Expression Evaluation	44
).13	5.13.1 Location List Internal-level Interface	
	5.13.1.1 dwarf_get_loclist_entry()	
5 1 1	Abbreviations access	45
).14		45
	5.14.1 dwarf_get_abbrev()	
	5.14.2 dwarf_get_abbrev_tag()	45
	5.14.3 dwarf_get_abbrev_code()	45
	5.14.4 dwarf_get_abbrev_children_flag()	
	5.14.5 dwarf_get_abbrev_entry()	
5.15	String Section Operations	
	5.15.1 dwarf_get_str()	
	Address Range Operations	
	5.16.1 dwarf_get_aranges()	
	5.16.2 dwarf_get_cu_die_offset()	47
	5.16.3 dwarf_get_arange_cu_header_offset()	47
	5.16.4 dwarf_get_arange_info()	48
5.17	General Low Level Operations	48
	5.17.1 dwarf_get_address_size()	48
5.18	Utility Operations	48
	5.18.1 dwarf_errno()	48
	5.18.2 dwarf_errmsg()	48
	5.18.3 dwarf_seterrhand()	52
	5.18.4 dwarf seterrarg()	52
	5.18.5 dwarf dealloc()	52

LIST OF FIGURES

Figure 1.	Scalar Types	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	4
Figure 2.	Error Indications	•					•	•				•					10
Figure 3.	Allocation/Deallocation Identifiers	•					•	•				•	•				12
Figure 4.	Frame Information Rule Assignments .	•					•	•				•					38
Figure 5.	Frame Information Special Values $$. $$.	•					•	•				•	•				38
Figure 6.	List of Dwarf Error Codes	•					•	•				•	•				49
Figure 7.	List of Dwarf 2 Error Codes (continued)	•					•	•				•	•				50
Figure 8.	List of Dwarf 2 Error Codes (continued)	•					•	•				•	•				51
Figure 9.	List of Dwarf 2 Error Codes																52

A Consumer Library Interface to DWARF

UNIX International Programming Languages Special Interest Group

ABSTRACT

This document describes an interface to a library of functions to access DWARF debugging information entries and DWARF line number information. It does not make recommendations as to how the functions described in this document should be implemented nor does it suggest possible optimizations.

The document is oriented to reading DWARF version 2. There are certain sections which are SGI-specific (those are clearly identified in the document). We would propose this to the PLSIG committee as the basis for a standard libdwarf interface, but as of this writing, the committee is dormant.

This document are subject to change.

rev 1.48, 31 Mar 2002

^{0.} UNIX is a registered trademark of UNIX System Laboratories, Inc. in the United States and other countries.