

IBM Security Verify Governance Identity
Manager

*IBM DB2 Adapter Installation and
Configuration Guide*



Contents

- Figures..... V**

- Tables..... vii**

- Chapter 1. Overview..... 1**
 - Features.....1
 - Architecture.....1
 - Supported configurations..... 2

- Chapter 2. Planning..... 5**
 - Roadmap..... 5
 - Roadmap..... 7
 - Roadmap..... 9
 - Roadmap..... 10
 - Prerequisites..... 12
 - Software downloads..... 14
 - Installation worksheet..... 15

- Chapter 3. Installing in the virtual appliance..... 17**

- Chapter 4. Installing..... 19**
 - Installing the dispatcher.....19
 - Installing the adapter binaries or connector.....20
 - Installing 3rd party client libraries.....22
 - Setting up the adapter environment..... 23
 - Restarting the adapter service..... 25
 - Importing the adapter profile.....26
 - Importing the adapter profile.....29
 - Importing the adapter profile.....31
 - Importing the adapter profile.....33
 - Importing attribute mapping file.....36
 - Adding a connector.....37
 - Enabling connectors.....40
 - Reviewing and setting channel modes for each new connector.....42
 - Attribute Mapping.....45
 - Creating an adapter service/target.....47
 - Creating an adapter service/target.....50
 - Creating an adapter service/target.....53
 - Service/Target form details.....55
 - Installing the adapter language package.....59
 - Verifying that the adapter is working correctly.....60
 - Verifying that the adapter is working correctly.....62

- Chapter 5. Upgrading..... 65**
 - Upgrading the dispatcher..... 65
 - Upgrading the adapter profile..... 65

- Chapter 6. Configuring..... 67**
 - Customizing the adapter profile..... 67

Editing adapter profiles on the UNIX or Linux operating system.....	68
Chapter 7. Troubleshooting.....	69
Techniques for troubleshooting problems.....	69
Error messages and problem solving.....	71
Chapter 8. Uninstalling.....	73
Deleting the adapter profile.....	73
Chapter 9. Reference.....	75
Adapter attributes and object classes.....	75
Adapter attributes by operations.....	79
Database login add.....	80
Database login change.....	81
Database login delete.....	81
Database login suspend.....	81
Database login restore.....	82
Ping.....	82
Reconciliation.....	82
Special attributes.....	82
Index.....	83

Figures

- 1. The architecture of the IBM DB2 Adapter..... 2
- 2. Example of a single server configuration..... 3
- 3. Example of multiple server configuration..... 3

Tables

1. Preinstallation road map.....	5
2. Installation and configuration roadmap.....	5
3. Prerequisites to install the adapter.....	13
4. Required information to install the adapter.....	15
5. Adapter package contents.....	17
6. Prerequisites for enabling a connector.....	40
7. Required privileges and their descriptions.....	55
8. Ports.....	56
9. Warning and error messages	71
10. Attributes, descriptions, and corresponding data types.....	75
11. Add request attributes.....	80
12. Change request attributes.....	81
13. Delete request attributes.....	81
14. Suspend request attributes.....	81
15. Restore attributes.....	82
16. Ping attributes.....	82
17. Reconciliation attributes.....	82

Chapter 1. Overview

An adapter is an interface between a managed resource and the Identity server. The IBM DB2 Adapter enables communication between the Identity server and the IBM DB2.

Adapters can be installed on the managed resource. The Identity server manages access to the resource by using the security system. Adapters function as trusted virtual administrators on the target operating system. The adapter creates, suspends, restores user accounts, and other functions that administrators run manually. The adapter runs as a service, independently of whether you are logged on to the Identity server.

Features

The adapter automates several administrative and management tasks.

- Reconciling user accounts and other support data
- Adding user accounts
- Modifying user account attributes
- Suspending, restoring, and deleting user accounts

Related concepts

Architecture

Several components are involved in running and using the adapter. Install all these components so that the adapter can function correctly.

Supported configurations

The adapter supports both single and multiple server configurations.

Architecture

Several components are involved in running and using the adapter. Install all these components so that the adapter can function correctly.

- Dispatcher
- Security Directory Integrator connector
- IBM® Security Verify Adapter profile

You need to install the Dispatcher and the adapter profile; however, the Security Directory Integrator connector might already be installed with the base Security Directory Integrator product.

[Figure 1 on page 2](#) describes the components that work together to complete the user account management tasks in a Security Directory Integrator environment.




Figure 1. The architecture of the IBM DB2 Adapter

For more information about Security Directory Integrator, see the *Quick Start Guide* in the [IBM Security Verify Identity](#) product documentation.

Related concepts

Features

The adapter automates several administrative and management tasks.

Supported configurations

The adapter supports both single and multiple server configurations.

Supported configurations

The adapter supports both single and multiple server configurations.

In a single server configuration, the adapter is installed on only one server. In a multiple server configuration, the adapter is installed on several different servers.

The fundamental components in each environment are:

- The Identity server
- The IBM Security Directory Integrator server
- The managed resource
- The adapter

The adapter must be installed directly on the server that runs the Security Directory Integrator server.

Single server configuration

The Identity server, the Security Directory Integrator server, and the IBM DB2 Adapter are installed on one server to establish communication with the managed resource. The managed resource is installed on a different server as described [Figure 2 on page 3](#).




Figure 2. Example of a single server configuration

Multiple server configuration

In multiple server configuration, the Identity server, the Security Directory Integrator server, and the IBM DB2 are installed on different servers. The Security Directory Integrator server and the IBM DB2 Adapter are installed on the same server as described in [Figure 3 on page 3](#).



Figure 3. Example of multiple server configuration

Related concepts

Features

The adapter automates several administrative and management tasks.

Architecture

Several components are involved in running and using the adapter. Install all these components so that the adapter can function correctly.

Chapter 2. Planning

Installing and configuring the adapter involves several steps that you must complete in a specific sequence. Follow the roadmap for the main tasks.

Use the Preinstallation roadmap to prepare the environment.

Task	For more information, see
Verify that your environment meets the software and hardware requirements for the adapter.	“Prerequisites” on page 12.
Obtain the installation software.	Software download.
Obtain the necessary information for the installation and configuration.	“Installation worksheet” on page 15.

Use the Installation and configuration roadmap to complete the actual installation and configuration of the adapter.

Task	For more information, see
Install the dispatcher.	“Installing the dispatcher” on page 19.
Install the connector.	“Installing the adapter binaries or connector” on page 20
Import the adapter profile into the Identity server.	Importing the adapter profile
Create an adapter service.	Creating an adapter service
Configure the adapter.	Chapter 6, “Configuring,” on page 67

Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 6.x

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

Pre-installation

Complete these tasks.

1. Verify that your environment meets the software and hardware requirements for the adapter. See *Prerequisites*.
2. Obtain the installation software. See *Software downloads*.
3. Obtain the necessary information for the installation and configuration. See *Installation worksheet*.

Installation

Complete these tasks.

1. Install the dispatcher.
2. Install the adapter binaries or connector.
3. Install 3rd party client libraries.
4. Set up the adapter environment.

5. Restart the adapter service.
6. Import the adapter profile.
7. Create an adapter service/target.
8. Install the adapter language package.
9. Verify that the adapter is working correctly.

Upgrade

To upgrade the adapter, do a complete re-installation of the adapter. Follow the *Installation roadmap*.

Configuration

Complete these tasks.

1. Configure secure communication between the Identity server and the adapter.
 - a. Configure 1-way authentication.
 - b. Configure 2-way authentication.
2. Configure secure communication between the adapter and the managed target.
 - a. Configure 1-way authentication.
 - b. Configure 2-way authentication.
3. Configure the adapter.
4. Modify the adapter profiles.
5. Customize the adapter.

Troubleshooting

See the following topics.

- Techniques for troubleshooting problems
- Configure debugging
- Logs
- Error messages and problem solving

Uninstallation

Complete these tasks.

1. Stop the adapter service.
2. Remove the adapter binaries or connector.
3. Remove 3rd party client libraries.
4. Delete the adapter service/target.
5. Delete the adapter profile.

Reference

See the following topics.

- Adapter attributes and object classes
- Adapter attributes by operations
- Special attributes

Related concepts

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 7.x](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Privileged Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Governance Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Prerequisites](#)

Verify that your environment meets the software and hardware requirements for the adapter.

[Software downloads](#)

Download the software through your account at the IBM Passport Advantage website.

[Installation worksheet](#)

The installation worksheet lists the information that is required to install and configure the adapter.

Complete this worksheet before you start the installation procedure for ease of reference. Make a copy of the worksheet for each adapter instance you install.

Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 7.x

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

Pre-installation

Complete these tasks.

1. Verify that your environment meets the software and hardware requirements for the adapter. See *Prerequisites*.
2. Obtain the installation software. See *Software downloads*.
3. Obtain the necessary information for the installation and configuration. See *Installation worksheet*.

Installation

Complete these tasks.

1. Install the dispatcher.
2. Install the adapter binaries or connector.
3. Install 3rd party client libraries.
4. Set up the adapter environment.
5. Restart the adapter service.
6. Import the adapter profile.
7. Create an adapter service/target.
8. Install the adapter language package.
9. Verify that the adapter is working correctly.

Upgrade

To upgrade the adapter, do a full installation of the adapter. Follow the *Installation roadmap*.

Configuration

Complete these tasks.

1. Configure secure communication between the Identity server and the adapter.

- a. Configure 1-way authentication.
 - b. Configure 2-way authentication.
2. Configure secure communication between the adapter and the managed target.
 - a. Configure 1-way authentication.
 - b. Configure 2-way authentication.
 3. Configure the adapter.
 4. Modify the adapter profiles.
 5. Customize the adapter.

Troubleshooting

See the following topics.

- Techniques for troubleshooting problems
- Configure debugging
- Logs
- Error messages and problem solving

Uninstallation

Complete these tasks.

1. Stop the adapter service.
2. Remove the adapter binaries or connector.
3. Remove 3rd party client libraries.
4. Delete the adapter service/target.
5. Delete the adapter profile.

Reference

See the following topics.

- Adapter attributes and object classes
- Adapter attributes by operations
- Special attributes

Related concepts

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 6.x](#)
Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Privileged Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Governance Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Prerequisites](#)

Verify that your environment meets the software and hardware requirements for the adapter.

[Software downloads](#)

Download the software through your account at the IBM Passport Advantage website.

[Installation worksheet](#)

The installation worksheet lists the information that is required to install and configure the adapter. Complete this worksheet before you start the installation procedure for ease of reference. Make a copy of the worksheet for each adapter instance you install.

Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Privileged Identity Manager

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

Pre-installation

Complete these tasks.

1. Verify that your environment meets the software and hardware requirements for the adapter. See *Prerequisites*.
2. Obtain the installation software. See *Software downloads*.
3. Obtain the necessary information for the installation and configuration. See *Installation worksheet*.

Installation

Complete these tasks.

1. Install the dispatcher.
2. Install the adapter binaries or connector.
3. Install 3rd party client libraries.
4. Set up the adapter environment.
5. Restart the adapter service.
6. Import the adapter profile.
7. Create an adapter service/target.
8. Install the adapter language package.
9. Verify that the adapter is working correctly.

Upgrade

To upgrade the adapter, do a complete re-installation of the adapter. Follow the *Installation roadmap*.

Configuration

Complete these tasks.

1. Configure secure communication between the Identity server and the adapter.
 - a. Configure 1-way authentication.
 - b. Configure 2-way authentication.
2. Configure secure communication between the adapter and the managed target.
 - a. Configure 1-way authentication.
 - b. Configure 2-way authentication.
3. Configure the adapter.
4. Modify the adapter profiles.
5. Customize the adapter.

Troubleshooting

See the following topics.

- Techniques for troubleshooting problems
- Configure debugging
- Logs
- Error messages and problem solving

Uninstallation

Complete these tasks.

1. Stop the adapter service.
2. Remove the adapter binaries or connector.
3. Remove 3rd party client libraries.
4. Delete the adapter service/target.
5. Delete the adapter profile.

Reference

See the following topics.

- Adapter attributes and object classes
- Adapter attributes by operations
- Special attributes

Related concepts

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 6.x](#)
Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 7.x](#)
Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Governance Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

Prerequisites

Verify that your environment meets the software and hardware requirements for the adapter.

Software downloads

Download the software through your account at the IBM Passport Advantage website.

Installation worksheet

The installation worksheet lists the information that is required to install and configure the adapter.

Complete this worksheet before you start the installation procedure for ease of reference. Make a copy of the worksheet for each adapter instance you install.

Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Governance Identity Manager

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

Note: There is a separate instruction for installing, upgrading or uninstalling adapters from the IBM Security Verify Governance Identity Manager virtual appliance.

Pre-installation

Complete these tasks.

1. Verify that your environment meets the software and hardware requirements for the adapter. See *Prerequisites*.
2. Obtain the installation software. See *Software downloads*.
3. Obtain the necessary information for the installation and configuration. See *Installation worksheet*.

Installation

Complete these tasks.

1. Install the dispatcher.
2. Install the adapter binaries or connector.
3. Install 3rd party client libraries.
4. Set up the adapter environment.
5. Restart the adapter service.
6. Import the adapter profile.
7. Load attribute mapping.
8. Set account defaults.
9. Create an adapter service/target.
10. Install the adapter language package.
11. Verify that the adapter is working correctly.

Upgrade

To upgrade the adapter, do a full installation of the adapter. Follow the *Installation roadmap*.

Configuration

Complete these tasks.

1. Configure secure communication between the Identity server and the adapter.
 - a. Configure 1-way authentication.
 - b. Configure 2-way authentication.
2. Configure secure communication between the adapter and the managed target.
 - a. Configure 1-way authentication.
 - b. Configure 2-way authentication.
3. Configure the adapter.
4. Modify the adapter profiles.
5. Customize the adapter.

Troubleshooting

See the following topics.

- Techniques for troubleshooting problems
- Configure debugging
- Logs
- Error messages and problem solving

Uninstallation

Complete these tasks.

1. Stop the adapter service.
2. Remove the adapter binaries or connector.
3. Remove 3rd party client libraries.
4. Delete the adapter service/target.
5. Delete the adapter profile.

Reference

See the following topics.

- Adapter attributes and object classes
- Adapter attributes by operations
- Special attributes

Related concepts

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 6.x](#)
Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 7.x](#)
Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Privileged Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Prerequisites](#)

Verify that your environment meets the software and hardware requirements for the adapter.

[Software downloads](#)

Download the software through your account at the IBM Passport Advantage website.

[Installation worksheet](#)

The installation worksheet lists the information that is required to install and configure the adapter.

Complete this worksheet before you start the installation procedure for ease of reference. Make a copy of the worksheet for each adapter instance you install.

Prerequisites

Verify that your environment meets the software and hardware requirements for the adapter.

[Table 3 on page 13](#) identifies the software and operating system prerequisites for the adapter installation.

Ensure that you install the adapter on the same workstation as the IBM Security Directory Integrator server.

Table 3. Prerequisites to install the adapter

Prerequisite	Description
Directory Integrator	<ul style="list-style-type: none"> • IBM Security Directory Integrator Version 7.1.1 + 7.1.1-TIV-TDI-FP0004 + 7.2.0-ISS-SDI-LA0008 • IBM Security Directory Integrator Version 7.2 <p>Note:</p> <ul style="list-style-type: none"> • Earlier versions of IBM Security Directory Integrator that are still supported might function properly. However, to resolve any communication errors, you must upgrade your Directory Integrator release to the versions that the adapter officially supports. • The adapter supports IBM Security Directory Integrator 7.2, which is available only to customers who have the correct entitlement. Contact your IBM representative to find out whether you have the entitlement to download IBM Security Directory Integrator 7.2.
Identity server	<p>The following servers are supported:</p> <ul style="list-style-type: none"> • Identity server Version 10.0 • Identity server Version 10.0 • IBM Security Privileged Identity Manager Version 2.0 • Identity server Version 10.0
IBM DB2	<p>A Linux, UNIX, or Windows system that runs the IBM DB2 with one of following versions:</p> <ul style="list-style-type: none"> • IBM DB2 v9.5.x • IBM DB2 v9.7.x • IBM DB2 v10.1 • IBM DB2 v10.5 <p>Note: IBM DB2 on z/OS or iSeries is not supported.</p>
IBM DB2 JDBC Driver	<p>JDBC Driver</p> <p>Note: The driver file names are:</p> <ul style="list-style-type: none"> • db2jcc.jar • db2jcc_license_cu.jar
Network Connectivity	<p>Install the adapter on a workstation that can communicate with the IBM Security Verify Identity IBM Security Verify Governance Identity Manager IBM Security Privileged Identity Manager service through the TCP/IP network.</p>
System Administrator Authority	<p>To complete the adapter installation procedure, you must have system administrator authority.</p>
Security Directory Integrator adapters solution directory	<p>A Security Directory Integrator adapters solution directory is a Security Directory Integrator work directory for adapters. See the <i>Dispatcher Installation and Configuration Guide</i>.</p>

Table 3. Prerequisites to install the adapter (continued)

Prerequisite	Description
IBM DB2 Account, for example db2admin.	<p>You must provide a IBM DB2 account and password for every IBM DB2 instance that the adapter manages.</p> <p>The IBM DB2 account must have the following IBM DB2 privileges:</p> <p>DBADM Database administrator authority</p> <p>SECADM Security administrator authority</p>

Install the IBM DB2 Adapter and the appropriate IBM DB2 JDBC drivers on the same workstation as the Security Directory Integrator.

For information about the prerequisites and supported operating systems for Security Directory Integrator, see the *IBM Security Directory Integrator 7.1: Administrator Guide*.

Related concepts

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 6.x](#)
Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 7.x](#)
Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Privileged Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Governance Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

Software downloads

Download the software through your account at the IBM Passport Advantage website.

Installation worksheet

The installation worksheet lists the information that is required to install and configure the adapter. Complete this worksheet before you start the installation procedure for ease of reference. Make a copy of the worksheet for each adapter instance you install.

Software downloads

Download the software through your account at the IBM Passport Advantage website.

Go to [IBM Passport Advantage](#).

See the corresponding *IBM Security Verify Identity**IBM Security Verify Governance Identity Manager**IBM Security Privileged Identity Manager Download Document* for instructions.

Note:

You can also obtain additional adapter information from IBM Support.

Related concepts

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 6.x](#)
Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 7.x](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Privileged Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Governance Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

Prerequisites

Verify that your environment meets the software and hardware requirements for the adapter.

Installation worksheet

The installation worksheet lists the information that is required to install and configure the adapter.

Complete this worksheet before you start the installation procedure for ease of reference. Make a copy of the worksheet for each adapter instance you install.

Installation worksheet

The installation worksheet lists the information that is required to install and configure the adapter.

Complete this worksheet before you start the installation procedure for ease of reference. Make a copy of the worksheet for each adapter instance you install.

Table 4. Required information to install the adapter

Required information	Description	Value
IBM Security Directory Integrator Home Directory	The <i>ITDI_HOME</i> directory contains the <i>jars/connectors</i> subdirectory that contains adapter JAR files. For example, the <i>jars/connectors</i> subdirectory contains the JAR file for the UNIX adapter.	<p>If Security Directory Integrator is automatically installed with your IBM Security Verify Governance Identity Manager IBM Security Privileged Identity Manager product, the default directory path for Security Directory Integrator is as follows:</p> <p>Windows:</p> <ul style="list-style-type: none"> For version 7.1: <i>drive\Program Files\IBM\TDI\V7.1</i> For version 7.1.1: <i>drive\Program Files\IBM\TDI\V7.1.1</i> <p>UNIX:</p> <ul style="list-style-type: none"> For version 7.1: <i>/opt/IBM/TDI/V7.1</i> For version 7.1.1: <i>/opt/IBM/TDI/V7.1.1</i>

Table 4. Required information to install the adapter (continued)

Required information	Description	Value
Adapters solution directory	When you install the dispatcher, the adapter prompts you to specify a file path for the adapters solution directory. For more information about the solution directory, see the <i>Dispatcher Installation and Configuration Guide</i> .	The default solution directory is at: Windows <ul style="list-style-type: none"> For version 7.1: <code>drive\Program Files\IBM\TDI\V7.1\isimsoln</code> For version 7.1.1: <code>drive\Program Files\IBM\TDI\V7.1.1\isimsoln</code> UNIX: <ul style="list-style-type: none"> For version 7.1: <code>/opt/IBM/TDI/V7.1/isimsoln</code> For version 7.1.1: <code>/opt/IBM/TDI/V7.1.1/isimsoln</code>

Related concepts

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 6.x](#)
 Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Identity 7.x](#)
 Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Privileged Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

[Roadmap for IBM Security Directory Integrator based adapters, for IBM Security Verify Governance Identity Manager](#)

Follow this section when using the guide to install, configure, troubleshoot, or uninstall the adapter.

Prerequisites

Verify that your environment meets the software and hardware requirements for the adapter.

Software downloads

Download the software through your account at the IBM Passport Advantage website.

Chapter 3. Installing in the Verify Governance Identity Manager virtual appliance

For Verify Governance Identity Manager target management, you can install an IBM Security Verify Adapters or a custom adapter on the built-in Security Directory Integrator in the virtual appliance instead of installing the adapter externally. As such, there is no need to manage a separate virtual machine or system.

About this task

This procedure is applicable for a selected list of Identity Adapters. See the Identity Adapters product documentation at http://www.ibm.com/support/knowledgecenter/SSIGMP_1.0.0/com.ibm.itim_pim.doc/c_adapters_intro.htm to determine which adapters are supported in Identity Governance and Intelligence, and which can be installed on the virtual appliance.

All Identity Governance and Intelligence supported adapters can be installed externally on the virtual appliance. Depending on the adapter, an external Security Directory Integrator may be required.

See the corresponding *Adapter Installation and Configuration Guide* for the specific prerequisites, installation and configuration tasks, and issues and limitations. See the *Adapters Release Notes* for any updates to these references.

Procedure

1. Download the adapter package from the IBM Passport Advantage.
For example, Adapter-*<Adaptername>*.zip.

The adapter package includes the following files:

Files	Descriptions
bundledefinition.json	The adapter definition file. It specifies the content of the package, and the adapter installation and configuration properties that are required to install and update the adapter.
Adapter JAR profile	An Security Directory Integrator adapter always include a JAR profile which contains: <ul style="list-style-type: none">• targetProfile.json<ul style="list-style-type: none">– Service provider configuration– Resource type configuration– SCIM schema extensions– List of assembly lines• A set of assembly lines in XML files• A set of forms in XML files• Custom properties that include labels and messages for supported languages. Use the Target Administration module to import the target profile.

Table 5. Adapter package contents (continued)	
Files	Descriptions
Additional adapter specific files	<p>Examples of adapter specific files:</p> <ul style="list-style-type: none"> • Connector jar files • Configuration files • Script files • Properties files <p>The file names are specified in the adapter definition file along with the destination directory in the virtual appliance.</p>

2. From the top-level menu of the **Appliance Dashboard**, click **Configure > SDI Management**.
3. Select the instance of the Security Directory Integrator for which you want to manage the adapters and click **Manage > SDI Adapters**
 The **SDI Adapters** window is displayed with a table that list the name, version, and any comments about the installed adapters.
4. On the **SDI Adapters** window, click **Install**.
5. On the **File Upload** window, click **Browse** to locate the adapter package and then click **OK**.
 For example, Adapter-*<Adaptername>*.zip.
6. Provide the missing 3rd party libraries when prompted.
 - a) On the **File Upload** for Pre-requisite files window, click **Select Files**.
 A new **File Upload** window is displayed.
 - b) Browse and select all the missing libraries. For example, httpclient-4.0.1.jar
 - c) Click **Open**.
 The selected files are listed in the **File Upload** for Pre-requisite files window.
 - d) Click **OK**.
 The missing files are uploaded and the adapter package is updated with the 3rd party libraries.
7. Enable secure communication.
 - a) Select the instance of the Security Directory Integrator for which you want to manage the adapter.
 - b) Click **Edit**.
 - c) Click the **Enable SSL** check box.
 - d) Click **Save Configuration**.
8. Import the SSL certificate to the IBM Security Directory Integrator server.
 - a) Select the instance of the Security Directory Integrator for which you want to manage the adapter.
 - b) Click **Manage > Certificates**.
 - c) Click the **Signer** tab.
 - d) Click **Import**.
 The **Import Certificate** window is displayed.
 - e) Browse for the certificate file.
 - f) Specify a label for the certificate. It can be any name.
 - g) Click **Save**.

Chapter 4. Installing

Installing the adapter mainly involves importing the adapter profile and creating an adapter service. Depending on the adapter, several other tasks can be involved to completely install it.

All IBM Security Directory Integrator based adapters require the Dispatcher for the adapters to function correctly. If the Dispatcher is installed from a previous installation, do not reinstall it unless the Dispatcher is upgraded. See [Installing the dispatcher](#).

Depending on your adapter, the Security Directory Integrator connector might already be installed as part of the Security Directory Integrator product and no further action is required. If the connector is not pre-installed, install it after the Dispatcher.

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

If you already installed the RMI Dispatcher for another adapter, you do not need to reinstall it.

If you have not yet installed the RMI Dispatcher in the Security Directory Integrator environment, download the Dispatcher installer from the [IBM Passport Advantage](#) website. For more information about the installation, see the *Dispatcher Installation and Configuration Guide*.

Related concepts

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Before you begin

- The Dispatcher must be installed.

About this task

The adapter uses the IBM Security Directory Integrator JDBC connector. Follow the steps in the procedure to download and copy the JDBC Connector JAR. As such, you just need to install the Dispatcher. See the *IBM Security Dispatcher Installation and Configuration Guide*.

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

About this task

Procedure

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapter require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapter require file system and operating system configuration. This topic is not applicable for this adapter.

About this task

Procedure

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

The adapter does not exist as an independent service or a process. The adapter is added to the Dispatcher instance, which runs all the adapters that are installed on the same Security Directory Integrator instance.

See the topic about starting, stopping, and restarting the Dispatcher service in the *Dispatcher Installation and Configuration Guide*.

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapter require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Before you begin

- The Identity server is installed and running.
- You have root or administrator authority on the Identity server.
- The file to be imported must be a Java™ archive (JAR) file. The <Adapter>Profile.jar file includes all the files that are required to define the adapter schema, account form, service/target form, and profile properties. If necessary, you can extract the files from the JAR file, modify the files, and

repackage the JAR file with the updated files. The JAR file for IBM Security Identity Manager is located in the top level folder of the installation package.

About this task

Service definition files are also called adapter profile files.

If the adapter profile is not installed correctly, the adapter cannot function correctly. You cannot create a service with the adapter profile or open an account on the service. You must import the adapter profile again.

Procedure

1. Log on to the Identity server by using an account that has the authority to perform administrative tasks.
2. From the navigation tree, select **Configure System > Manage Service Types**.
The **Manage Service Types** page is displayed.
3. On the **Manage Service Types** page, click **Import**.
The **Import Service Type** page is displayed.
4. On the **Import Service Type** page, complete these steps:
 - a) In the **Service Definition File** field, type the directory location of the `<Adapter>Profile.jar` file, or click **Browse** to locate the file.
For example, if you are installing the IBM Security Verify Adapter for a Windows server that runs Active Directory, locate and import the ADProfileJAR file.
 - b) Click **OK** to import the file.

Results

A message indicates that you successfully submitted a request to import a service type.

What to do next

- The import occurs asynchronously, which means it might take some time for the service type to load into the Identity server from the properties files and to be available in other pages. On the **Manage Service Types** page, click **Refresh** to see the new service type. If the service type status is Failed, check the log files to determine why the import failed.
- If you receive a schema-related error, see the `trace.log` file for information about it. The `trace.log` file location is specified by the `handler.file.fileDir` property that is defined in the `enRoleLogging.properties` file. The `enRoleLogging.properties` file is in the Identity server `HOME\data` directory. .

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Before you begin

- You have root or administrator authority on the Identity server.
- The file to be imported must be a Java archive (JAR) file. The `<Adapter>Profile.jar` file includes all the files that are required to define the adapter schema, account form, service/target form, and profile properties. If necessary, you can extract the files from the JAR file, modify the files, and repackage the JAR file with the updated files. The JAR file for IBM Security Identity Manager is located in the top level folder of the installation package.

About this task

Service definition files are also called adapter profile files.

If the adapter profile is not installed correctly, the adapter cannot function correctly. You cannot create a service with the adapter profile or open an account on the service. You must import the adapter profile again.

The adapter profile is already imported into the IBM Security Verify Identity virtual appliance. Read the adapter release notes for any specific instructions before you import a new adapter profile on IBM Security Verify Identity.

Procedure

1. Log on to the Identity server by using an account that has the authority to perform administrative tasks.
2. From the navigation tree, select **Configure System > Manage Service Types**.
The **Manage Service Types** page is displayed.
3. On the **Manage Service Types** page, click **Import**.
The **Import Service Type** page is displayed.
4. On the **Import Service Type** page, complete these steps:
 - a) In the **Service Definition File** field, type the directory location of the `<Adapter>Profile.jar` file, or click **Browse** to locate the file.
For example, if you are installing the IBM Security Verify Adapter for a Windows server that runs Active Directory, locate and import the `ADProfileJAR` file.
 - b) Click **OK** to import the file.

Results

A message indicates that you successfully submitted a request to import a service type.

What to do next

- The import occurs asynchronously, which means it might take some time for the service type to load into the Identity server from the properties files and to be available in other pages. On the **Manage Service Types** page, click **Refresh** to see the new service type. If the service type status is Failed, check the log files to determine why the import failed.
- If you receive a schema-related error, see the `trace.log` file for information about it. The `trace.log` file location is specified by the `handler.file.fileDir` property that is defined in the

enRoleLogging.properties file. The enRoleLogging.properties file is in the Identity serverHOME\data directory. .

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Before you begin

- The IBM Security Privileged Identity Manager is installed and running.
- You have root or administrator authority on the IBM Security Privileged Identity Manager.
- The file to be imported must be a Java archive (JAR) file. The `<Adapter>Profile.jar` file includes all the files that are required to define the adapter schema, account form, service/target form, and profile properties. If necessary, you can extract the files from the JAR file, modify the files, and repackage the JAR file with the updated files. The JAR file for IBM Security Privileged Identity Manager is located in the top level folder of the installation package.

About this task

Service definition files are also called adapter profile files.

If the adapter profile is not installed correctly, the adapter cannot function correctly. You cannot create a service with the adapter profile or open an account on the service. You must import the adapter profile again.

Procedure

1. Log on to the IBM Security Privileged Identity Manager by using an account that has the authority to perform administrative tasks.
2. From the navigation tree, select **Configure System > Manage Service Types**.
The **Manage Service Types** page is displayed.
3. On the **Manage Service Types** page, click **Import**.
The **Import Service Type** page is displayed.
4. On the **Import Service Type** page, complete these steps:
 - a) In the **Service Definition File** field, type the directory location of the `<Adapter>Profile.jar` file, or click **Browse** to locate the file.
For example, if you are installing the IBM Security Verify Adapter for a Windows server that runs Active Directory, locate and import the ADProfileJAR file.

b) Click **OK** to import the file.

Results

A message indicates that you successfully submitted a request to import a service type.

What to do next

- The import occurs asynchronously, which means it might take some time for the service type to load into the Identity server from the properties files and to be available in other pages. On the **Manage Service Types** page, click **Refresh** to see the new service type. If the service type status is Failed, check the log files to determine why the import failed.
- If you receive a schema-related error, see the `trace.log` file for information about it. The `trace.log` file location is specified by the `handler.file.fileDir` property that is defined in the `enRoleLogging.properties` file. The `enRoleLogging.properties` file is in the Identity server `HOME\data` directory. .

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapter require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Before you begin

- The Identity server is installed and running.
- You have administrator authority on the Identity server.
- The file to be imported must be a Java archive (JAR) file. The `<Adapter>Profile.jar` file includes all the files that are required to define the adapter schema, account form, service/target form, and profile properties. If necessary, you can extract the files from the JAR file, modify the files, and repackage the JAR file with the updated files.

About this task

Target definition files are also called adapter profile files. The profile definition files are provided with the various IBM Security Verify Adapter. The adapter profile must be imported because it defines the types of resources that the Verify Governance Identity Manager server can manage.

The adapter profile definition file is used to create a target profile on the Verify Governance Identity Manager server and to establish communication with the adapter. If the adapter profile is not imported, you cannot create a connector for that adapter type.

An upload error might occur when no file is selected, or when the file is empty, or due to any upload operation error, such as a timeout or connection error. If the adapter profile is not installed correctly, the adapter cannot function correctly. You cannot create a connector with the adapter profile or open and account on the service. You must import the adapter profile again.

This task can be completed from the Enterprise Connectors module in the Administration Console. To import an adapter target profile, complete these steps:

Procedure

1. Log in to the Verify Governance Identity Manager Administration Console.
2. From the Administration Console, select **Enterprise Connectors**.
3. Select **Manage > Profiles**.
4. Optional: Click **Filter** to toggle the filter on to refine your search results, or click **Hide Filter** to toggle the filter off. When the filter is visible, you can specify search criteria for your requests, and then click **Search**.
5. Click **Actions > Import**.
6. On the **Import** page, complete these steps:
 - a) Select **Profile**.
 - b) Click **Browse** to locate the JAR file that you want to import.
 - c) Click **Upload file**.

A message indicates that you successfully imported a profile.
7. Click **Close**.

The new profile is displayed in the list of profiles.

Results

The upload is synchronous but has a timeout. The progress bar on the **Import** page accurately indicates the upload status. However, when a timeout is reached, the following message occurs: "The import is still in progress and will complete shortly. Close this window to proceed." If you see that message, allow a few minutes for the upload to complete and for the profile to be available.

What to do next

After the target profile is imported successfully, complete these tasks.

- Import the attribute mapping file. See [“Importing attribute mapping file”](#) on page 36.
- Create a connector that uses the target profile. See [“Adding a connector”](#) on page 37.

Related concepts

[Installing the dispatcher](#)

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

[Restarting the adapter service](#)

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

[Service/Target form details](#)

Complete the service/target form fields.

[Installing the adapter language package](#)

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

[Installing the adapter binaries or connector](#)

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

About this task

This task involves importing an account attribute mapping definition file, which is included in the adapter package. The imported file must be a DEF file.

Procedure

1. Log in to the Verify Governance Identity Manager Administration Console.
2. From the Administration Console, select **Enterprise Connectors**.
3. Select **Manage > Profiles**.
4. Optional: Click **Filter** to toggle the filter on to refine your search results, or click **Hide Filter** to toggle the filter off. When the filter is visible, you can specify search criteria for your requests, and then click **Search**.
5. Click **Actions > Import**.
6. On the **Import** page, complete these steps:
 - a) Select **Attribute Mapping**.
 - b) Click **Browse** to locate the attribute mapping file that you want to import.
 - c) Click **Upload file**.

A message indicates that you successfully imported the file.

7. Click **Close**.

Related concepts

[Installing the dispatcher](#)

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

[Restarting the adapter service](#)

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

[Service/Target form details](#)

Complete the service/target form fields.

[Installing the adapter language package](#)

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

[Installing the adapter binaries or connector](#)

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

[Installing 3rd party client libraries](#)

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

[Setting up the adapter environment](#)

In addition to 3rd party client libraries, some adapter require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Before you begin

Complete Importing the adapter profile.

Note: If you migrated from Verify Governance Identity Manager V5.2.2 or V5.2.2.1 and want to add or configure a connector, see *Adding and configuring a connector for each target* in the IBM Security Verify Governance Identity Manager product documentation.

About this task

The connectors consolidate, extract, and reconcile user identities, organization units, permissions, and user entitlements with the most common enterprise applications. Configure a connector to keep the Access Governance Core repository synchronized with the target system.

This task can be completed from the Enterprise Connectors module in the Administration Console.

Procedure

To add a connector, complete these steps.

1. Log in to the Verify Governance Identity Manager Administration Console.
2. From the Administration Console, select **Enterprise Connectors**.
3. Select **Manage > Connectors**.

A list of connectors is displayed on the **Connectors** tab.

4. Click **Filter** to toggle the filter on to refine your search results, or click **Hide Filter** to toggle the filter off. When the filter is visible, you can specify search criteria for your requests, and then click **Search**.
5. To view all of the columns in the list of connectors, expand the **Connectors** pane.
6. Click **Actions > Add**.

The **Connector Details** pane is enabled for your input.

7. On the **Connector Details** tab, complete these steps:
 - a) Assign a name and description for the connector.
 - b) Select the target profile type as **Identity Brokerage** and its corresponding target profile.
 - c) Select the entity, such as **Account** or **User**.

Depending on the connector type, this field might be preselected.
 - d) Optional: Select **Trace ON** and the corresponding **Trace Level** to enable trace logs.

The available trace levels are DEBUG, INFO, and ERROR.
 - e) Optional: Select **History ON** to save and track the connector usage.
 - f) Click **Save**.

The fields for enabling the channels for sending and receiving data are now visible.
 - g) Select and set the connector properties in the **Global Config** accordion pane.

For information about the global configuration properties, see [Global Config accordion pane](#).
 - h) Click **Save**. The fields for enabling the channels for sending and receiving data are now visible.

Results

The connector is saved and added to the list of connectors in the **Connectors** pane.

If you cannot create a connector with the target profile or open an account on an existing connector, the target profile was not installed correctly during the import. You must import the target profile again.

What to do next

Enable the channel modes to synchronize the data between the target systems and Verify Governance Identity Manager. For more information, see [“Enabling connectors” on page 40](#).

Related concepts

[Installing the dispatcher](#)

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Before you begin

Prerequisite	Find more information
A connector must exist in Verify Governance Identity Manager.	“Adding a connector” on page 37.
Ensure that you enabled the appropriate channel modes for the connector.	“Reviewing and setting channel modes for each new connector” on page 42.

Procedure

To enable a connector, complete these steps:

1. Log in to the Verify Governance Identity Manager Administration Console.
2. From the Administration Console, select **Enterprise Connectors**.
3. Select **Manage > Connectors**.
A list of connectors is displayed on the **Connectors** tab.
4. Optional: Click **Filter** to toggle the filter on to refine your search results, or click **Hide Filter** to toggle the filter off. When the filter is visible, you can specify search criteria for your requests, and then click **Search**.
5. Optional: To view all of the columns in the list of connectors, expand the **Connectors** pane.
6. Select the connector that you want to enable.
7. On the **Connector Details** tab, complete these steps:
 - a) Select the channel modes that you want to enable, and then click **Save**. Depending on the channels that you enable, the corresponding **Channel** tabs are displayed.

Enable write-to channel

Propagates every change in the Access Governance Core repository into the target system.

For connectors that are not HR feed, the check boxes for enabling the read-from channel and the write-to channel are available.

Enable read-from channel

Reads the INPUT EVENTS and USER DATA from the target system. Imports data from the target system to the Access Governance Core repository.

For HR feed connectors, only the check box for enabling the read-from channel is available.

Enable reconciliation

Synchronizes the modified data between the Access Governance Core repository and the target system.

Results

The connector is enabled

What to do next

Enable the channel modes to synchronize the data between the target systems and Verify Governance Identity Manager.

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

About this task

Note: Legacy Verify Governance Identity Manager Enterprise connectors use Reconciliation channel, whereas Identity Brokerage Enterprise connectors use Read From Channel and Change Log Sync.

For more information about any of tasks in the following steps, see the IBM® Security Identity Governance and Intelligence product documentation.

Procedure

To enable the read-from and write-to channels, and to set the change log synchronization schedule for each new connector, complete these steps in Verify Governance Identity Manager V5.2.3:

1. Log in to the Verify Governance Identity Manager Administration Console.
2. From the Administration Console, select **Enterprise Connectors**.
3. Select **Manage > Connectors**.
A list of connectors is displayed on the **Connectors** tab.
4. Optional: Click **Filter** to toggle the filter on to refine your search results, or click **Hide Filter** to toggle the filter off. When the filter is visible, you can specify search criteria for your requests, and then click **Search**.
5. Optional: To view all of the columns in the list of connectors, expand the **Connectors** pane.
6. Select the connector that you want to enable.
7. On the **Connector Details** tab, complete these steps:

- a) Select the channel modes that you want to enable, and then click **Save**. Depending on the channels that you enable, the corresponding **Channel** tabs are displayed, in which you can do more configuration, such as mapping attributes and setting up rules.

Enable write-to channel

Propagates every change in the Access Governance Core repository into the target system.

Enable read-from channel

Reads the INPUT EVENTS and USER DATA from the target system. Imports data from the target system to the Access Governance Core repository.

Enable reconciliation

Synchronizes the modified data between the Access Governance Core repository and the target system.

8. Select **Monitor > Change Log Sync Status**.

A list of connectors is displayed.

9. On the **Change Log Sync Status** tab, complete these steps:

- a) Optional: Click **Filter** to toggle the filter on to refine your search results, or click **Hide Filter** to toggle the filter off. When the filter is visible, you can specify search criteria for your requests, and then click **Search**.
- b) Select a connector, and click **Actions > Sync Now**.
The synchronization process begins.
- c) Optional: To view the status of the synchronization request, select **Sync History** in the right pane.
Information about the synchronization is displayed in the **Sync History** tab.

10. Set the change log synchronization schedule for each new connector that you migrated.

11. When the connector configuration is complete, enable the connector by completing these steps:

- a) Select **Manage > Connectors**.
- b) Select the connector that you want to enable, and then select the **Enable** check box in the **Connector Details** tab.
- c) Click **Save**.

For more information, see [“Enabling connectors” on page 40](#).

For Identity Brokerage connectors that are not HR feed, the check boxes for enabling the read-from channel and the write-to channel are available.

For Identity Brokerage HR feed connectors, only the check box for enabling the read-from channel is available.

12. Start the connector by selecting **Monitor > Connector Status**. Select the connector that you want to start, and then select **Actions > Start**.

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

About this task

This task involves an account attribute mapping definition file, which is included in the adapter package.

The file consists of Verify Governance Identity Manager account attributes and their equivalent attributes in the managed target. The file is structured as `<IGI_attribute> = <target_attribute>`.

The `<IGI_attribute>` is fixed and must not be modified. Edit only the `<target_attribute>`. Some `<IGI_attribute>` already has a fixed equivalent `<target_attribute>` of `eraccount`.

Some `<IGI_attribute>` do not have a defined `<target_attribute>` and you can assign the mapping. For example:

```
USER_TYPE=USER_TYPE
ATTR1=ATTR1
```

Note:

- The default mapping is already included out-of-the box. If there are no changes to the attribute mapping, there is no need to import the attribute mapping files.
- It might take up to 10 minutes for the attribute mapping changes to take effect once the file is imported.

Procedure

1. Open the mapping definition file by using any text editor.
2. Edit the mapping.
3. If the target attribute has a list of predefined values, use the following syntax to convert its values to the corresponding Verify Governance Identity Manager attribute values.

```
[conversion].<target_attribute>.<IGI_attribute> =
<target_attribute_value1>=<IGI_attribute_value1>;...;
<target_attribute_valuen>=<IGI_attribute_valuen>]
```

4. For attributes that contains date and time, use the following syntax to convert its values.
For example:

```
[conversion.date].erbirthdate.BIRTHDAY=[yyyyMMdd=dd/MM/yyyy HH:mm:ss]
[conversion.date].ACCOUNT_EXPIRY_DATE.ACCOUNT_EXPIRY_DATE=
[dd/MM/yyyy HH:mm:ss=dd/MM/yyyy HH:mm:ss]
```

5. Import the updated mapping definition file through the Enterprise Connectors module. For more information, see *Attribute-to-permission mapping service* in the IBM Security Verify Governance Identity Manager product documentation.
6. Map the following attributes for **Chanel-Write To** and **Chanel-Read From**

Attribute	Mapped Attribute
eruid	CODE
erpassword	PASSWORD

For more information, see *Mapping attributes for a connector* in the IBM Security Verify Governance Identity Manager product documentation.

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Before you begin

Complete [“Importing the adapter profile”](#) on page 26.

About this task

You must create an administrative user account for the adapter on the managed resource. You can provide the account information such as administrator name and password when you create the adapter service. Ensure that the account has sufficient privileges to administer the users. For information about creating an administrative account, see the documentation for the managed resource.

To create or change a service, you must use the service form to provide information for the service. Service forms might vary depending on the adapter. The service name and description that you provide for each service are displayed on the console. Therefore, it is important to provide values that make sense to your users and administrators.

Procedure

1. From the navigation tree, click **Manage Services**.
The **Select a Service** page is displayed.
2. On the **Select a Service** page, click **Create**.
The **Create a Service** wizard is displayed.
3. On the **Select the Type of Service** page, click **Search** to locate a business unit.
The **Business Unit** page is displayed.
4. On the **Business Unit** page, complete these steps:
 - a) Type information about the business unit in the **Search information** field.
 - b) Select a business type from the **Search by** list, and then click **Search**.
A list of business units that matches the search criteria is displayed.
If the table contains multiple pages, you can do the following tasks:
 - Click the arrow to go to the next page.
 - Type the number of the page that you want to view and click **Go**.

c) In the **Business Units** table, select business unit in which you want to create the service, and then click **OK**.

The **Select the Type of Service** page is displayed, and the business unit that you specified is displayed in the **Business unit** field.

5. On the **Select the Type of Service** page, select a service type, and then click **Next**.

If the table contains multiple pages, you can do the following tasks:

- Click the arrow to go to the next page.
- Type the number of the page that you want to view and click **Go**.

6. On either the **Service Information** or **General Information** page, specify the appropriate values for the service instance.

The content of the **General Information** page depends on the type of service that you are creating. The creation of some services might require more steps.

7. To create a service with NTLM authentication, the administrator login is in the following format:

```
<Domain Name>\<Login Name>
```

8. For NLTM authentication, select **Authentication** mode as 'Claims-Based Authentication.

9. On the **Dispatcher Attributes** page, specify information about the dispatcher attributes, and then click **Next** or **OK**.

The **Dispatcher Attributes** page is displayed only for IBM Security Directory Integrator based services.

10. Optional: On the **Access Information** page, select the **Define an Access** check box to activate the access definition fields. Select the type of access you want to enable.

Specify the expected access information and any other optional information such as description, search terms, more information, or badges.

11. On the **Status and Information** page, view information about the adapter and managed resource, and then click **Next** or **Finish**.

The adapter must be running to obtain the information.

12. On the **Configure Policy** page, select a provisioning policy option, and then click **Next** or **Finish**.

The provisioning policy determines the ownership types available for accounts. The default provisioning policy enables only Individual ownership type accounts. Additional ownership types can be added by creating entitlements on the provisioning policy.

Note: If you are creating a service for an identity feed, the **Configure Policy** page is not displayed.

13. Optional: On the **Reconcile Supporting Data** page, either do an immediate reconciliation for the service, or schedule a supporting data reconciliation, and then click **Finish**.

The **Reconcile Supporting Data** page is displayed for all services except for identity feed services.

The **supporting data only** reconciliation option retrieves only the supporting data for accounts. The supporting data includes groups that are defined on the service. The type of supporting data is defined in the adapter guide.

14. Optional: On the **Service Information** or **General Information** page, click **Test Connection** to validate that the data in the fields is correct, and then click **Next** or **Finish**.

If the connection fails, contact the analyst who is responsible for the computer on which the managed resource runs.

Results

A message is displayed, indicating that you successfully created the service instance for a specific service type.

Related concepts

[Installing the dispatcher](#)

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Before you begin

Complete [“Importing the adapter profile”](#) on page 29.

About this task

You must create an administrative user account for the adapter on the managed resource. You can provide the account information such as administrator name and password when you create the adapter service. Ensure that the account has sufficient privileges to administer the users. For information about creating an administrative account, see the documentation for the managed resource.

To create or change a service, you must use the service form to provide information for the service. Service forms might vary depending on the adapter. The service name and description that you provide for each service are displayed on the console. Therefore, it is important to provide values that make sense to your users and administrators.

Procedure

1. From the navigation tree, click **Manage Services**.
The **Select a Service** page is displayed.
2. On the **Select a Service** page, click **Create**.
The **Create a Service** wizard is displayed.
3. On the **Select the Type of Service** page, click **Search** to locate a business unit.
The **Business Unit** page is displayed.
4. On the **Business Unit** page, complete these steps:
 - a) Type information about the business unit in the **Search information** field.
 - b) Select a business type from the **Search by** list, and then click **Search**.
A list of business units that matches the search criteria is displayed.
If the table contains multiple pages, you can do the following tasks:
 - Click the arrow to go to the next page.
 - Type the number of the page that you want to view and click **Go**.
 - c) In the **Business Units** table, select business unit in which you want to create the service, and then click **OK**.
The **Select the Type of Service** page is displayed, and the business unit that you specified is displayed in the **Business unit** field.

5. On the **Select the Type of Service** page, select a service type, and then click **Next**.

If the table contains multiple pages, you can do the following tasks:

- Click the arrow to go to the next page.
 - Type the number of the page that you want to view and click **Go**.
6. On either the **Service Information** or **General Information** page, specify the appropriate values for the service instance.
The content of the **General Information** page depends on the type of service that you are creating. The creation of some services might require more steps.
 7. To create a service with NTLM authentication, the administrator login is in the following format:

```
<Domain Name>\<Login Name>
```

8. For NLTM authentication, select **Authentication** mode as 'Claims-Based Authentication.
9. On the **Dispatcher Attributes** page, specify information about the dispatcher attributes, and then click **Next** or **OK**.
The **Dispatcher Attributes** page is displayed only for IBM Security Directory Integrator based services.
10. Optional: On the **Access Information** page, select the **Define an Access** check box to activate the access definition fields. Select the type of access you want to enable.
Specify the expected access information and any other optional information such as description, search terms, more information, or badges.
11. On the **Status and Information** page, view information about the adapter and managed resource, and then click **Next** or **Finish**.
The adapter must be running to obtain the information.
12. On the **Configure Policy** page, select a provisioning policy option, and then click **Next** or **Finish**.
The provisioning policy determines the ownership types available for accounts. The default provisioning policy enables only Individual ownership type accounts. Additional ownership types can be added by creating entitlements on the provisioning policy.
Note: If you are creating a service for an identity feed, the **Configure Policy** page is not displayed.
13. Optional: On the **Reconcile Supporting Data** page, either do an immediate reconciliation for the service, or schedule a supporting data reconciliation, and then click **Finish**.
The **Reconcile Supporting Data** page is displayed for all services except for identity feed services.
The **supporting data only** reconciliation option retrieves only the supporting data for accounts. The supporting data includes groups that are defined on the service. The type of supporting data is defined in the adapter guide.
14. Optional: On the **Service Information** or **General Information** page, click **Test Connection** to validate that the data in the fields is correct, and then click **Next** or **Finish**.
If the connection fails, contact the analyst who is responsible for the computer on which the managed resource runs.

Results

A message is displayed, indicating that you successfully created the service instance for a specific service type.

Related concepts

[Installing the dispatcher](#)

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

[Restarting the adapter service](#)

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Before you begin

Complete [“Importing the adapter profile”](#) on page 31.

About this task

You must create an administrative user account for the adapter on the managed resource. You can provide the account information such as administrator name and password when you create the adapter service. Ensure that the account has sufficient privileges to administer the users. For information about creating an administrative account, see the documentation for the managed resource.

To create or change a service, you must use the service form to provide information for the service. Service forms might vary depending on the adapter. The service name and description that you provide for each service are displayed on the console. Therefore, it is important to provide values that make sense to your users and administrators.

Procedure

1. From the navigation tree, click **Manage Services**.
The **Select a Service** page is displayed.
2. On the **Services** table, click **Create**.
The **Create a Service** wizard is displayed.
3. On the **Select the Type of Service** page, click **Search** to locate a business unit.
The **Business Unit** page is displayed.
4. On the **Business Unit** page, complete these steps:
 - a) Type information about the business unit in the **Search information** field.
 - b) Select a business type from the **Search by** list, and then click **Search**.
A list of business units that matches the search criteria is displayed.
If the table contains multiple pages, you can do the following tasks:
 - Click the arrow to go to the next page.
 - Type the number of the page that you want to view and click **Go**.
 - c) In the **Business Units** table, select business unit in which you want to create the service, and then click **OK**.
The **Select the Type of Service** page is displayed, and the business unit that you specified is displayed in the **Business unit** field.
5. On the **Select the Type of Service** page, select a service type, and then click **Next**.
6. On the **Service Information** page, specify the appropriate values for the service instance.

The content of the **Service Information** page depends on the type of service that you are creating.

7. Click **Test Connection** to validate that the data in the fields is correct.

If the connection fails, contact the analyst who is responsible for the computer on which the managed resource runs.

8. Click **Finish**.

Results

A message is displayed, indicating that you successfully created the service instance for a specific service type.

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Service/Target form details

Complete the service/target form fields.

You must create a user account for the adapter on the managed resource. The accounts must be able to remotely connect to the IBM DB2 and must have sufficient privileges to administer IBM DB2 users.

Privilege	Description
DBADM	Database administrator authority
SEDADM	Security administrator authority

On the IBM DB2 Connection tab:

Service name

Specify a name that defines the adapter service on the Identity server.

Note: Do not use forward (/) or backward slashes (\) in the service name.

Description

Optional: Specify a description that identifies the service for your environment.

Tivoli® Directory Integrator location

Specify the URL for the IBM Security Directory Integrator instance. The valid syntax for the URL is `rmi://ip-address:port/ITDIDispatcher`, where *ip-address* is the IBM Security Directory Integrator host and *port* is the port number for the RMI Dispatcher.

The default URL for the default SDI1 instance is `rmi://localhost:1099/ITDIDispatcher`.

The following table shows the ports that are open in the firewall for every instance that is created. However, usage of these port numbers do not support high availability.

<i>Table 8. Ports</i>	
Instance	Ports
SDI1	1199, 1198, 1197, 1196, 1195, 1194
SDI2	2299, 2298, 2297, 2296, 2295, 2294
SDI3	3399, 3398, 3397, 3396, 3395, 3394
SDI4	4499, 4498, 4497, 4496, 4495, 4494
SDI5	5599, 5598, 5597, 5596, 5595, 5594
SDI6	6699, 6698, 6697, 6696, 6695, 6694
SDI7	7799, 7798, 7797, 7796, 7795, 7794
SDI8	8899, 8898, 8897, 8896, 8895, 8894
SDI9	9999, 9998, 9997, 9996, 9995, 9994
SDI10	11099, 11098, 11097, 11096, 11095, 11094

For a high availability implementation, use any of these port numbers.

- 1099
- 2099
- 3099

IBM DB2 Server Host

Specify the host workstation on which the IBM DB2 server is running.

IBM DB2 Server Port

Specify the TCP port on which the IBM DB2 server is running. You can specify 50000 to use the default DB2 port.

IBM DB2 Database Name

Specify the database name of the IBM DB2 database that you want to manage, for example SAMPLE.

IBM DB2 Administration User Account

Specify the name of the user who has access to the IBM DB2 resource and who can do administrative operations.

IBM DB2 Administration User Password

Specify the password for the user.

Do not manage tables

Select this check box if you do not want the list of tables to be retrieved during a reconciliation operation.

Note: To disable this feature, clear the **Do not manage tables** check box on the service form and perform the support data reconciliation operation.

Owner

Optionally, specify a user as a service owner.

Service Prerequisite

Specify a service that is prerequisite to this service.

On the Dispatcher Attributes tab:

Disable AL Caching

Select the check box to disable the assembly line caching in the dispatcher for the service. The assembly lines for the add, modify, delete, and test operations are not cached.

AL File System Path

Specify the file path from where the dispatcher loads the assembly lines. If you do not specify a file path, the dispatcher loads the assembly lines that are received from Identity server.

You can specify the following file path to load the assembly lines from the profiles directory of the Windows operating system: `c:\Files\IBM\TDI\V7.1\profiles`.

Alternatively, you can specify the following file path to load the assembly lines from the profiles directory of the UNIX and Linux operating system: `system: /opt/IBM/TDI/V7.1/profiles`.

Max Connection Count

Specify the maximum number of assembly lines that the dispatcher can run simultaneously for the service. Enter 10 if you want the dispatcher to run a maximum of 10 assembly lines simultaneously for the service. If you enter 0 in the **Max Connection Count** field, the dispatcher does not limit the number of assembly lines that are run simultaneously for the service.

On the Status and information tab

Contains read only information about the adapter and managed resource. These fields are examples. The actual fields vary depending on the type of adapter and how the service form is configured. The adapter must be running to obtain the information. Click **Test Connection** to populate the fields.

Last status update: Date

Specifies the most recent date when the Status and information tab was updated.

Last status update: Time

Specifies the most recent time of the date when the Status and information tab was updated.

Managed resource status

Specifies the status of the managed resource that the adapter is connected to.

Adapter version

Specifies the version of the adapter that the service uses to provision request to the managed resource.

Profile version

Specifies the version of the profile that is installed in the Identity server.

TDI version

Specifies the version of the Security Directory Integrator on which the adapter is deployed.

Dispatcher version

Specifies the version of the dispatcher.

Installation platform

Specifies summary information about the operating system where the adapter is installed.

Adapter account

Specifies the account that is running the adapter binary file.

Adapter up time: Date

Specifies the date when the adapter started.

Adapter up time: Time

Specifies the time of the date when the adapter started.

Adapter memory usage

Specifies the memory usage for running the adapter.

If the connection fails, follow the instructions in the error message. Also

- Verify the adapter log to ensure that the test request was successfully sent to the adapter.
- Verify the adapter configuration information.
- Verify service parameters for the adapter profile. Verify parameters such as the work station name or the IP address of the managed resource and the port.

Related concepts

[Installing the dispatcher](#)

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

See *Installing the adapter language pack* from the IBM Security Verify Identity product documentation.

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapter require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Procedure

1. Test the connection for the service that you created on the Identity serverIdentity server.
2. Run a full reconciliation from the Identity serverIdentity server.
3. Run all supported operations such as add, modify, and delete on one user account.
4. Verify the `ibmdi.log` file after each operation to ensure that no errors are reported.
5. Verify the `trace.log` file to ensure that no errors are reported when you run an adapter operation.

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapters require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Procedure

1. Test the connection for the service that you created on the Identity server.
2. Run a full reconciliation from the Identity server.
3. Run all supported operations such as add, modify, and delete on one user account.
4. Verify the `ibmdi.log` file after each operation to ensure that no errors are reported.
5. Verify the `trace.log` file to ensure that no errors are reported when you run an adapter operation.

Related concepts

Installing the dispatcher

If this is the first Security Directory Integrator-based adapter installation, you must install the RMI Dispatcher before you install the adapter. Install the RMI Dispatcher on the same Security Directory Integrator server where you want to install the adapter.

Restarting the adapter service

Various installation and configuration tasks might require the adapter to be restarted to apply the changes. For example, you must restart the adapter if there are changes in the adapter profile, connector, or assembly lines. To restart the adapter, restart the Dispatcher.

Service/Target form details

Complete the service/target form fields.

Installing the adapter language package

The adapters use a separate language package from IBM Security Verify Identity.

Related tasks

Installing the adapter binaries or connector

The connector might or might not be available with the base Security Directory Integrator or Security Directory Integrator product. The connector is required to establish communication between the adapter and the Dispatcher.

Installing 3rd party client libraries

Third party client libraries are libraries and/or configuration files that are provided by the target vendor. These 3rd party client libraries must be installed with the adapter. This is not required for all adapters. This topic is not applicable for this adapter.

Setting up the adapter environment

In addition to 3rd party client libraries, some adapter require file system and operating system configuration. This topic is not applicable for this adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

An adapter profile defines the types of resources that the Identity server can manage. It is packaged with the IBM Security Verify Adapter. Use the adapter profile to create an adapter service on Identity server and establish communication with the adapter.

Importing the adapter profile

You can import a profile definition file, which creates a profile in Identity server. Use this option for importing adapter profiles.

Importing attribute mapping file

After importing the adapter profile, you must import an attribute map from a profile mapping definition file.

Adding a connector

After you import the adapter profile on the Verify Governance Identity Manager server, add a connector so that Verify Governance Identity Manager server can communicate with the managed resource.

Enabling connectors

After you create a connector, by default it is in a disabled state. You must enable a connector to use it.

Reviewing and setting channel modes for each new connector

Use this procedure to set up the read-from and write-to channels and to set the synchronization schedule for each new connector.

Attribute Mapping

Attribute mapping is required to define which target attributes correspond to the Verify Governance Identity Manager account attributes.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Creating an adapter service/target

After you import the adapter profile on the Identity server, create a service/target so that Identity server can communicate with the managed resource.

Verifying that the adapter is working correctly

After you install and configure the adapter, verify that the installation and configuration are correct.

Chapter 5. Upgrading

Upgrading an IBM Security Directory Integrator-based adapter involves tasks such as upgrading the dispatcher, the connector, and the adapter profile. Depending on the adapter, some of these tasks might not be applicable. Other tasks might also be required to complete the upgrade.

To verify the required version of these adapter components, see the adapter release notes. For the installation steps, see [Chapter 4, “Installing,” on page 19](#).

Upgrading the dispatcher

Before you upgrade the dispatcher, verify the version of the dispatcher.

- If the dispatcher version mentioned in the release notes is later than the existing version on your workstation, install the dispatcher.
- If the dispatcher version mentioned in the release notes is the same or earlier than the existing version, do not install the dispatcher.

Note: Stop the dispatcher service before the upgrading the dispatcher and start it again after the upgrade is complete.

Related concepts

[Upgrading the adapter profile](#)

Read the adapter Release Notes for any specific instructions before you import a new adapter profile.

Upgrading the adapter profile

Read the adapter Release Notes for any specific instructions before you import a new adapter profile.

Note: Restart the Dispatcher service after importing the profile. Restarting the Dispatcher clears the assembly lines cache and ensures that the dispatcher runs the assembly lines from the updated adapter profile.

Related concepts

[Upgrading the dispatcher](#)

Before you upgrade the dispatcher, verify the version of the dispatcher.

Chapter 6. Configuring

After you install the adapter, configure it to function correctly. Configuration is based on your requirements or preference..

See the *IBM Security Dispatcher Installation and Configuration Guide* for more configuration options such as:

- JVM properties
- Dispatcher filtering
- Dispatcher properties
- Dispatcher port number
- Logging configurations
- Secure Sockets Layer (SSL) communication

Customizing the adapter profile

To customize the adapter profile, you must modify the IBM DB2 Adapter JAR file. You might customize the adapter profile to change the account form or the service form.

About this task

You can also use the Form Designer or the `CustomLabels.properties` file to change the labels on the forms. Each adapter has a `CustomLabels.properties` file for that adapter.

The JAR file is included in the IBM DB2 Adapter compressed file that you downloaded from the IBM website. The JAR file and the files that are contained in the JAR file vary depending on your operating system.

Note: You cannot modify the schema for this adapter. You cannot add or delete attributes from the schema.

The adapter JAR file includes the following files:

- `CustomLabels.properties`
- `erDB2Account.xml`
- `erDB2Service.xml`
- `schema.dsm1`
- `service.def`
- `DB2AddUserAL.xml`
- `DB2DeleteUserAL.xml`
- `DB2ModifyUserAL.xml`
- `DB2RestoreUserAL.xml`
- `DB2SearchUserAL.xml`
- `DB2SuspendUserAL.xml`
- `DB2TestAL.xml`

Procedure

- To edit the JAR file, take these steps:
 - a) Log on to the workstation where the IBM DB2 Adapter is installed.
 - b) On the **Start** menu, click **Programs** → **Accessories** → **Command Prompt**.

- c) Copy the JAR file into a temporary directory.
- d) Extract the contents of the JAR file into the temporary directory by running the following command. The following example applies to the IBM DB2 Adapter profile. Type the name of the JAR file for your operating system.

```
cd c:\temp cd /tmp
jar -xvf DB2AdapterProfile.jar
```

The **jar** command extracts the files into the DB2AdapterProfile directory.

- e) Edit the file that you want to change

After you edit the file, you must import the file into the Identity server for the changes to take effect.

- To import the file, take these steps:
 - a) Create a JAR file by using the files in the \temp /tmp directory. Run the following commands:

```
cd /tmp cd c:\temp
jar -cvf DB2AdapterProfile.jar DB2AdapterProfile
```

- b) Import the JAR file into the IBM Security Verify Identity IBM Security Verify Governance Identity Manager IBM Security Privileged Identity Manager application server.
- c) Stop and start the Identity server.
- d) Restart the adapter service.

Related tasks

[Editing adapter profiles on the UNIX or Linux operating system](#)

The adapter profile . jar file might contain ASCII files that are created by using the MS-DOS ASCII format.

Editing adapter profiles on the UNIX or Linux operating system

The adapter profile . jar file might contain ASCII files that are created by using the MS-DOS ASCII format.

About this task

If you edit an MS-DOS ASCII file on the UNIX operating system, you might see a character ^M at the end of each line. These characters indicate new lines of text in MS-DOS. The characters can interfere with the running of the file on UNIX or Linux® systems. You can use tools, such as **dos2unix**, to remove the ^M characters. You can also use text editors, such as the **vi** editor, to remove the characters manually.

Example

You can use the **vi** editor to remove the ^M characters. From the **vi** command mode, run the following command and press Enter:

```
:%s/^M//g
```

When you use this command, enter ^M or Ctrl-M by pressing **^v^M** or **Ctrl V Ctrl M** sequentially. The **^v** instructs the **vi** editor to use the next keystroke instead of issuing it as a command.

Related tasks

[Customizing the adapter profile](#)

To customize the adapter profile, you must modify the IBM DB2 Adapter JAR file. You might customize the adapter profile to change the account form or the service form.

Chapter 7. Troubleshooting

Troubleshooting is a systematic approach to solving a problem. The goal of troubleshooting is to determine why something does not work as expected and how to resolve the problem. This topic provides information and techniques for identifying and resolving problems that are related to the adapter, including troubleshooting errors that might occur during the adapter installation.

Techniques for troubleshooting problems

Certain common techniques can help with the task of troubleshooting. The first step in the troubleshooting process is to describe the problem completely.

Problem descriptions help you and the IBM technical-support representative find the cause of the problem. This step includes asking yourself basic questions:

- What are the symptoms of the problem?
- Where does the problem occur?
- When does the problem occur?
- Under which conditions does the problem occur?
- Can the problem be reproduced?

The answers to these questions typically lead to a good description of the problem, which can then lead you to a problem resolution.

What are the symptoms of the problem?

When you start to describe a problem, the most obvious question is "What is the problem?" This question might seem straightforward; however, you can break it down into several more-focused questions that create a more descriptive picture of the problem. These questions can include:

- Who, or what, is reporting the problem?
- What are the error codes and messages?
- How does the system fail? For example, is it a loop, hang, crash, performance degradation, or incorrect result?

Where does the problem occur?

Determining where the problem originates is not always easy, but it is one of the most important steps in resolving a problem. Many layers of technology can exist between the reporting and failing components. Networks, disks, and drivers are only a few of the components to consider when you are investigating problems.

The following questions help you to focus on where the problem occurs to isolate the problem layer:

- Is the problem specific to one operating system, or is it common across multiple operating systems?
- Is the current environment and configuration supported?
- Do all users have the problem?
- (For multi-site installations.) Do all sites have the problem?

If one layer reports the problem, the problem does not necessarily originate in that layer. Part of identifying where a problem originates is understanding the environment in which it exists. Take some time to completely describe the problem environment, including the operating system and version, all corresponding software and versions, and hardware information. Confirm that you are running within an environment that is a supported configuration. Many problems can be traced back to incompatible levels of software that are not intended to run together or are not fully tested together.

When does the problem occur?

Develop a detailed timeline of events that lead up to a failure, especially for those cases that are one-time occurrences. You can most easily develop a timeline by working backward: Start at the time an error was reported (as precisely as possible, even down to the millisecond), and work backward through the available logs and information. Typically, you use the first suspicious event that you find in a diagnostic log.

To develop a detailed timeline of events, answer these questions:

- Does the problem happen only at a certain time of day or night?
- How often does the problem happen?
- What sequence of events leads up to the time that the problem is reported?
- Does the problem happen after an environment change, such as upgrading or installing software or hardware?

Responding to these types of questions can give you a frame of reference in which to investigate the problem.

Under which conditions does the problem occur?

Knowing which systems and applications are running at the time that a problem occurs is an important part of troubleshooting. These questions about your environment can help you to identify the root cause of the problem:

- Does the problem always occur when the same task is being done?
- Is a certain sequence of events required for the problem to occur?
- Do any other applications fail at the same time?

Answering these types of questions can help you explain the environment in which the problem occurs and correlate any dependencies. Remember that just because multiple problems might occur around the same time, the problems are not necessarily related.

Can the problem be reproduced?

From a troubleshooting standpoint, the ideal problem is one that can be reproduced. Typically, when a problem can be reproduced you have a larger set of tools or procedures at your disposal to help you investigate. Problems that you can reproduce are often easier to debug and solve.

However, problems that you can reproduce can have a disadvantage: If the problem is of significant business impact, you do not want it to recur. If possible, re-create the problem in a test or development environment, which typically offers you more flexibility and control during your investigation.

- Can the problem be re-created on a test system?
- Do multiple users or applications have the same type of problem?
- Can the problem be re-created by running a single command, a set of commands, or a particular application?

Related concepts

[Error messages and problem solving](#)

A warning or error message might be displayed in the user interface to provide information about the adapter or when an error occurs.

Error messages and problem solving

A warning or error message might be displayed in the user interface to provide information about the adapter or when an error occurs.

A warning or error might be displayed in the user interface to provide information that you must know about the adapter or about an error. Table 9 on page 71 contains warnings or errors that might be displayed in the user interface if the IBM DB2 Adapter is installed on your system.

Message code	Warning or error message	Remedial action
CTGIMT001E	The following error occurred. Error: Either the IBM DB2 service name is incorrect or the service is not up.	Ensure that the IBM DB2 service name given on IBM Security Verify IdentityIBM Security Verify Governance Identity ManagerIBM Security Privileged Identity Manager service form is running.
CTGIMT001E	The following error occurred. Error: Either the IBM DB2 host or port is incorrect.	Verify that the host workstation name or the port for the IBM DB2 service is correctly specified.
CTGIMT002E	The login credential is missing or incorrect.	Verify that you provided correct login credential on service form.
CTGIMT001E	The following error occurred. Error: No suitable JDBC driver found.	Ensure that the correct version of the JDBC driver is copied onto the workstation where the adapter is installed. Ensure that the path for the driver is included in the system CLASSPATH variable.
CTGIMT600E	An error occurred while establishing communication with the IBM Security Directory Integrator server.	IBM Security Verify IdentityIBM Security Verify Governance Identity ManagerIBM Security Privileged Identity Manager cannot establish a connection with IBM Security Directory Integrator. To fix this problem, ensure that: <ul style="list-style-type: none"> • IBM Security Directory Integrator is running. • The URL specified on the service form for the IBM Security Directory Integrator is correct.
CTGIMT004E	The adapter does not have permission to add an account: <i>Account_Name</i> .	The administrator user that is provided on the IBM Security Directory Integrator service form does not have the required privileges to add a user account. Ensure that an administrator user with the required privileges is specified on service form. These privileges are the minimum that are required for the administrator user: <ul style="list-style-type: none"> • DBADM - database administrator authority • SECADM - security administrator authority
CTGIMT003E	The account already exists.	Use a different name for the user to be added.
CTGIMT015E	An error occurred while deleting the <i>Account_Name</i> account because the account does not exist.	The user you trying to delete does not exist. Ensure that you are deleting only an existing account.

Related conceptsTechniques for troubleshooting problems

Certain common techniques can help with the task of troubleshooting. The first step in the troubleshooting process is to describe the problem completely.

Chapter 8. Uninstalling

To remove an adapter from the Identity server for any reason, you must remove all the components that were added during installation. Uninstalling an IBM Security Directory Integrator based adapter mainly involves removing the connector file, and the adapter profile from the Identity server. Depending on the adapter, some of these tasks might not be applicable, or there can be other tasks.

Deleting the adapter profile

Remove the adapter service/target type from the Identity server. Before you delete the adapter profile, ensure that no objects exist on the Identity server that reference the adapter profile.

Objects on the Identity server that can reference the adapter profile:

- Adapter service instances
- Policies referencing an adapter instance or the profile
- Accounts

Note: The Dispatcher component must be installed on your system for adapters to function correctly in a Security Directory Integrator environment. When you delete the adapter profile, do not uninstall the Dispatcher.

For specific information about how to delete the adapter profile, see the IBM Security Verify Identity IBM Security Verify Governance Identity Manager IBM Security Privileged Identity Manager product documentation.

Chapter 9. Reference

Reference information is organized to help you locate particular facts quickly, such as adapter attributes, registry settings, and environment variables.

Adapter attributes and object classes

Adapter attributes and object classes are required for customization, creating provisioning rules, and understanding what service/target attributes are supported by the adapter. The Identity server communicates with the adapter by using attributes, which are included in transmission packets that are sent over a network. This topic is not applicable for this adapter.

The combination of attributes depends on the type of action that the Identity server requests from the adapter.

Table 10 on page 75 lists the account form attributes that the adapter uses.

Attribute	Directory server attribute	Description	Data format
Administration User Account	erRmiUDBAdminName	Specify the user ID that is used to connect to the IBM DB2. The value of this key must be the administrator user of the cataloged database. Administration User Account is the required field.	String
Administration User Password	erServicePwd1	Specify the password for the user ID that is used to connect to the IBM DB2. The value of this key must be the password of the administrator user of the cataloged database. Administration User Password is the required field.	String
IndexName	erRmiUDBIndexName	Specifies the name of the index.	String
PrivAlterinSchema	erRmiUDBPrivAlterinSchema	Specifies all schemas on which the privilege to alter objects in the schema is granted to the user. It is multivalued.	String

Table 10. Attributes, descriptions, and corresponding data types (continued)

Attribute	Directory server attribute	Description	Data format
PrivAlterinSchemaWGr	erRmiUDBPrivWGrAlterinSchema	Specifies all schemas on which the privilege to alter objects in the schema with grant option is granted to the user. It is multivalued.	String
PrivAlterTab	erRmiUDBPrivAlterTab	Specifies all tables on which the alter privilege is granted to the user. It is multivalued.	String
PrivControlIndex	erRmiUDBPrivIndexControl	Specifies all indexes on which the control privilege is granted to the user. It is multivalued.	String
PrivControlView	erRmiUDBPrivViewControl	Specifies all views on which the control privilege is granted to the user. It is multivalued.	String
PrivCreateinSchema	erRmiUDBPrivCreateinSchema	Specifies all schemas on which the privilege to create objects in the schema is granted to the user. It is multivalued.	String
PrivCreateinSchemaWGr	erRmiUDBPrivWGrCreateinSchema	Specifies all schemas on which the privilege to create objects in the schema with grant option is granted to the user. It is multivalued.	String
PrivDatabase	erRmiUDBPrivDatabase	Specifies the database authorities and privileges that are granted to the user. It is multivalued.	String
PrivDeleteTab	erRmiUDBPrivDeleteTab	Specifies all tables on which the delete privilege is granted to the user. It is multivalued.	String
PrivDeleteTabWGr	erRmiUDBPrivWGrDeleteTab	Specifies all tables on which the delete privilege with grant option is granted to the user. It is multivalued.	String

Table 10. Attributes, descriptions, and corresponding data types (continued)

Attribute	Directory server attribute	Description	Data format
PrivDeleteView	erRmiUDBPrivDeleteView	Specifies all views on which the delete privilege is granted to the user. It is multivalued.	String
PrivDeleteViewWGr	erRmiUDBPrivWGrVwDeleteView	Specifies all views on which the delete privilege with grant option is granted to the user. It is multivalued.	String
PrivDropinSchema	erRmiUDBPrivDropinSchema	Specifies all schemas on which the privilege to drop objects in the schema is granted to the user. It is multivalued.	String
PrivDropinSchemaWGr	erRmiUDBPrivWGrDropinSchema	Specifies all schemas on which the privilege to drop objects in the schema with grant option is granted to the user. It is multivalued.	String
PrivIndexTab	erRmiUDBPrivIndexTab	Specifies all tables on which the index privilege is granted to the user. It is multivalued.	String
PrivIndexTabWGr	erRmiUDBPrivWGrIndexTab	Specifies all tables on which the index privilege with grant option is granted to the user. It is multivalued.	String
PrivInsertTab	erRmiUDBPrivInsertTab	Specifies all tables on which the insert privilege is granted to the user. It is multivalued.	String
PrivInsertTabWGr	erRmiUDBPrivWGrInsertTab	Specifies all tables on which the insert privilege with grant option is granted to the user. It is multivalued.	String
PrivInsertView	erRmiUDBPrivInsertView	Specifies all views on which the insert privilege is granted to the user. It is multivalued.	String

Table 10. Attributes, descriptions, and corresponding data types (continued)

Attribute	Directory server attribute	Description	Data format
PrivInsertViewWGr	erRmiUDBPrivWGrVwInsertView	Specifies all views on which the insert privilege with grant option is granted to the user. It is multivalued.	String
PrivRefTab	erRmiUDBPrivRefTab	Specifies all tables on which the reference privilege is granted to the user. It is multivalued.	String
PrivRefTabWGr	erRmiUDBPrivWGrRefTab	Specifies all tables on which the reference privilege with grant option is granted to the user. It is multivalued.	String
PrivSelectTab	erRmiUDBPrivSelectTab	Specifies all tables on which the select privilege is granted to the user. It is multivalued.	String
PrivSelectTabWGr	erRmiUDBPrivWGrSelectTab	Specifies all tables on which the select privilege with grant option is granted to the user. It is multivalued.	String
PrivSelectView	erRmiUDBPrivSelectView	Specifies all views on which the select privilege is granted to the user. It is multivalued.	String
PrivSelectViewWGr	erRmiUDBPrivWGrVwSelectView	Specifies all views on which the select privilege with grant option is granted to the user. It is multivalued.	String
PrivUpdateTab	erRmiUDBPrivUpdateTab	Specifies all tables on which the update privilege is granted to the user. It is multivalued.	String
PrivUpdateTabWGr	erRmiUDBPrivWGrUpdateTab	Specifies all tables on which the update privilege with grant option is granted to the user. It is multivalued.	String

Table 10. Attributes, descriptions, and corresponding data types (continued)

Attribute	Directory server attribute	Description	Data format
PrivUpdateView	erRmiUDBPrivUpdateView	Specifies all views on which the update privilege is granted to the user. It is multivalued.	String
PrivUpdateViewWGr	erRmiUDBPrivWGrVwUpdateView	Specifies all views on which the update privilege with grant option is granted to the user. It is multivalued.	String
PrivUseTabSpace	erRmiUDBPrivUseTabSpace	Specifies all table spaces on which the use privilege is granted to the user. It is multivalued.	String
PrivUseTabSpaceWGr	erRmiUDBPrivWGrUseTabSpace	Specifies all table spaces on which the use privilege with grant option is granted to the user. It is multivalued.	String
SchemaName	erRmiUDBSchemaName	Specifies the name of the schema.	String
TableName	erRmiUDBTableName	Specifies the name of the table.	String
TabSpaceName	erRmiUDBTabSpaceName	Specifies the name of the table space.	String
UserName	erUid	Specifies the name of the user to be managed.	String
UserStatus	erAccountStatus	Specifies whether a user account is suspended.	String
ViewName	erRmiUDBViewName	Specifies the name of the view.	String
Roles	erRmiUDBPrivRole	Specifies the Role that is assigned to the user.	String

Adapter attributes by operations

Adapter attributes by operations refer to adapter actions by their functional transaction group. They are required for customization, creating provisioning rules, and understanding what service/target attributes are supported by the adapter.

Database login add

A database login add is a request to create a user account with the specified attributes.

Table 11. Add request attributes

Required attribute	Optional attribute	
erUid	erRmiUDBPrivWGrVwUpdateView erRmiUDBPrivCreateinSchema erRmiUDBPrivWGrCreateinSchema erRmiUDBPrivAlterinSchema erRmiUDBPrivWGrAlterinSchema erRmiUDBPrivDropinSchema erRmiUDBPrivWGrDropinSchema erRmiUDBPrivSelectTab erRmiUDBPrivWGrSelectTab erRmiUDBPrivDeleteTab erRmiUDBPrivRole erRmiUDBPrivWGrIndexTab erRmiUDBPrivRefTab erRmiUDBPrivWGrRefTab erRmiUDBPrivIndexControl erRmiUDBPrivSelectView	erRmiUDBPrivWGrVwSelectView erRmiUDBPrivInsertView erRmiUDBPrivWGrVwInsertView erRmiUDBPrivUpdateView erRmiUDBPrivInsertTab erRmiUDBPrivWGrInsertTab erRmiUDBPrivDatabase erRmiUDBPrivDeleteView erRmiUDBPrivWGrVwDeleteView erRmiUDBPrivViewControl erRmiUDBPrivUseTabSpace erRmiUDBPrivWGrUseTabSpace erRmiUDBPrivIndexTab erRmiUDBPrivAlterTab erRmiUDBPrivUpdateTab erRmiUDBPrivWGrUpdateTab erRmiUDBPrivWGrDeleteTab

Database login change

A database login change is a request to change one or more attributes for the specified users.

<i>Table 12. Change request attributes</i>	
Required attribute	Optional attribute
erUid	erRmiUDBPrivDatabase erRmiUDBPrivCreateinSchema erRmiUDBPrivWGrCreateinSchema erRmiUDBPrivAlterinSchema erRmiUDBPrivWGrAlterinSchema erRmiUDBPrivDropinSchema erRmiUDBPrivWGrDropinSchema erRmiUDBPrivSelectTab erRmiUDBPrivWGrSelectTab erRmiUDBPrivWGrVwUpdateView erRmiUDBPrivRole erRmiUDBPrivSelectView erRmiUDBPrivWGrVwSelectView erRmiUDBPrivDeleteView erRmiUDBPrivWGrVwDeleteView erRmiUDBPrivViewControl erRmiUDBPrivUseTabSpace erRmiUDBPrivInsertTab
	erRmiUDBPrivWGrInsertTab erRmiUDBPrivWGrUseTabSpace erRmiUDBPrivInsertView erRmiUDBPrivWGrVwInsertView erRmiUDBPrivUpdateTab erRmiUDBPrivWGrUpdateTab erRmiUDBPrivDeleteTab erRmiUDBPrivWGrDeleteTab erRmiUDBPrivAlterTab erRmiUDBPrivIndexTab erRmiUDBPrivWGrIndexTab erRmiUDBPrivRefTab erRmiUDBPrivWGrRefTab erRmiUDBPrivIndexControl erRmiUDBPrivUpdateView

Database login delete

A database login delete is a request to remove the specified user from the directory.

<i>Table 13. Delete request attributes</i>	
Required attribute	Optional attribute
erUid	None

Database login suspend

A database login suspend is a request to disable a user account.

The user is not removed. User attributes are not modified.

<i>Table 14. Suspend request attributes</i>	
Required attribute	Optional attribute
erUid erAccountStatus	None

Database login restore

A database login restore is a request to activate a user account that was previously suspended.

After an account is restored, the user can access the system by using the same attributes as the ones before the Suspend function was called.

<i>Table 15. Restore attributes</i>	
Required attribute	Optional attribute
erUid	None
erAccountStatus	

Ping

Use Ping to verify connection between the adapter and the Identity server. Ping does not require any variables.

<i>Table 16. Ping attributes</i>	
Required attribute	Optional attribute
None	None

Reconciliation

The reconciliation function synchronizes user account information between IBM Security Verify Identity IBM Security Verify Governance Identity Manager IBM Security Privileged Identity Manager and the adapter.

<i>Table 17. Reconciliation attributes</i>	
Attribute	
All supported attributes	

Special attributes

Certain attributes have special syntax and meaning that customers needs to be aware off. This information will be used to help the customer in how to supply the attribute value. This topic is not applicable for this adapter.

Index

A

adapter
 customization steps [67](#)
 features [1](#)
 installation
 verifying [60](#)
 installation worksheet [15](#)
 profile
 upgrading [65](#)
 supported configurations [2](#)
 uninstall [73](#)
 upgrading [65](#)
adapter installation
 troubleshooting errors [69](#)
 warnings [69](#)
adapter overview [1](#)
adapters
 removing profiles [73](#)
add request attributes [80](#)
attributes
 adapter action, by
 adding [80](#)
 changing [81](#)
 deleting [81](#)
 modifying [81](#)
 pinging [82](#)
 restoring [82](#)
 suspending [81](#)
 description [75](#)
 descriptions [75](#)
 reconciliation [82](#)

C

change request attributes [81](#)

D

delete request attributes [81](#)
dispatcher
 installation [19](#)
 upgrading [65](#)
download, software [14](#)

E

error messages [71](#)

I

installation
 adapter [19](#)
 adapter software [20](#)
 first steps [67](#)
 language pack [59](#)

installation (*continued*)
 planning roadmaps [5](#)
 uninstall [73](#)
 verification
 adapter [60](#)
 worksheet [15](#)

L

language pack
 installation [59](#)
 same for adapters and server [59](#)

M

messages
 error [71](#)
 warning [71](#)
MS-DOS ASCII characters [68](#)

O

operating system prerequisites [12](#)
overview [1](#)

P

ping request attributes [82](#)
profile
 editing on UNIX or Linux [68](#)

R

reconciliation attributes [82](#)
removing
 adapter profiles [73](#)
request attributes
 add [80](#)
 change [81](#)
 delete [81](#)
 ping [82](#)
 restore [82](#)
 suspend [81](#)
restore request attributes [82](#)
roadmaps
 planning [5](#)

S

service
 restart [25](#)
 start [25](#)
 stop [25](#)
software
 download [14](#)
 website [14](#)

- software requirements [12](#)
- supported configurations
 - adapter [2](#)
 - overview [2](#)
- suspend request attributes [81](#)

T

- troubleshooting
 - error messages [71](#)
 - identifying problems [69](#)
 - techniques for [69](#)
 - warning messages [71](#)
- troubleshooting and support
 - troubleshooting techniques [69](#)

U

- uninstallation [73](#)
- updating
 - adapter profile [67](#)
- upgrades
 - adapter [65](#)
 - adapter profiles [65](#)
 - dispatcher [65](#)

V

- verification
 - dispatcher installation [19](#)
 - installation [60](#)
 - operating system prerequisites [12](#)
 - operating system requirements [12](#)
 - software prerequisites [12](#)
 - software requirements [12](#)
- vi command [68](#)

W

- warning messages [71](#)

