CICS Migration for VSE/ESA CICS User Experience Pamela Lovely Skyline Corporation

CICS Migration for VSE/ESA 302

- ⇒ Migration from VSE 2.3 to VSE 2.4.
- ⇒ CICS 2.3 to TS 1.1.
- ⇒ Current Production Version 2.3.1.
- ⇒ New Test Version 2.4.1.
- ⇒ Ordered Product to begin the new install,- Mid Feb 2000.
- ⇒ Received product thru our 3rd party contact, end of Feb 2000.
- ⇒ Began the install, beginning of April 2000.

CICS Migration for VSE/ESA Road Blocks


- USE VSE
- Application software
- Development's testing and comfort level with changes with VSE 2.4.1
- CICS
- Outside Software, Product by Vendors
- ⇒ Prepare User's for new sign on

CICS Migration for VSE/ESA VSE Issues

- ⇒ Increase CICS partition size from 32meg to 50meg.
- ⇒ CICS migration of tables PCT, PPT, FCT.
- ⇒ Remove IBM supplied entries from CICS tables.
- CDS utility DFHCSDUP. Contains your system resources
- ⇒ Security Basic Security Manager BSM
- User Sign on process.
- ⇒ Again, Development comfort level.
- Turbo dispatch

CICS Migration for VSE/ESA Stubborn – no CICS 2.3 just TS.

- ⇒ Keep my VSE install as simplified as possible.
- ⇒ Not interested in using CICS 2.3.
- ⇒ Development can wait until outside software vendor are ready. Also, political reasons.
- ⇒ Coexistence-Startup another CICS partition for old CICS2.3, beginning of July.
- ⇒ With 2-CICS systems slower with turbo dispatch.



CICS Migration for VSE/ESA Security Issues

- Close The Security Server with JCL

 * PGM=DTRIATTN Close the Security Server Control File
 // EXEC DTRIATTN,PARM='MSG FB,DATA=CLOSECNTL'
 /*Comment Enter to Continue After MSG:BST233I. CLOSE SUCCESSFULLY
- **Restart Security Server Enter:** // EXE PROC=RESTASEC Pause FB, Enter this CMD to Start the Security Server in FB, Then Press enter.
- **Basic Security Manager BSM**Provides minimum sign-on security for CICS TS. The BSM is always active during the IPL of VSE/ESA.
 The Security Server runs in partition FB. VSE.Control.File. VSAM KSDS file.
- **Security Server Startup**Before VSE/Power starts, FB'S startup procedure begins to start the Security Server. FB 011 // Job SECSERV. PGM =BSTPSTS , START SECURITY SERVER.
- **Security Server Shutdown** A. After entering the PEND command, message from FB 0011 BST212I Stop command accepted. To end the SECSERV Enter: 11 /&

 B. Stopping the Security Server: // EXEC DTRIATTN,PARM='MSG FB,DATA=STOP'
 Pause, Review Message, then Press Enter to Continue after Response to: MSG: BST226W.
- Security Server Commands.

 Command: MSG FB Will display to you the possible security server commands that are available.

CICS Migration for VSE/ESA RD0

- Groups edit the PCT and PPT tables. Place the following statement in the table when you want to break on a new group. DFHPCT TYPE=GROUP,GROUP=TEST1 DFHPPT YPE=GROUP, GROUP=ACCT1 Then after Assemble and Lnkedt execute program DFHCSDUP, SIZE=DFHCSDUP MIGRATE TABLE(DFHPCTC5) TOGROUP(PCT01)
- LSR Pools

- ⇒ The old way assemble tables.
- The new way use CEDA, to define table entries. Remember, this always takes present, because they are loaded resident.
- To print the contents of your CSD file, execute program DFHCSDUP. Supply the LIST ALL parameter to the program.

CICS Migration for VSE/ESA References

- Migration to VSE/ESA 2.3 and CICS TS for VSE SG24-5595
- ⇒ CICS TS for VSE/ESA Operations and Utilities Guide SC33-1654
- CICS TS for VSE/ESA Resource Definition Guide SC33-1653
- Presentation: www.s390.IBM.com/products/VSE/library/ conf00/conf00.HTM

CICS Migration for VSE/ESA

Presentation Motivation - acronym for TS

- Trouble shooting

- Totally Sexy
- Tapping Synergy
 Tactic Systematic

- Tape Superiority
 Transportation Scan
- **Tool Session**