

IBM SPSS Collaboration and Deployment Services Scoring
Adapter for PMML
Version 8 Release 2

Installation Instructions



Note

Before using this information and the product it supports, read the information in "Notices" on page 23.

Product Information

This edition applies to version 8, release 2, modification 1 of IBM SPSS Collaboration and Deployment Services and to all subsequent releases and modifications until otherwise indicated in new editions.

© Copyright IBM Corporation 2000, 2019.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Chapter 1. Overview	1	Installing in console mode	15
Chapter 2. Installation requirements	3	Installing silently by using a response file	17
Chapter 3. Installation files	5	Chapter 6. Uninstalling IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML	19
Chapter 4. Getting started with Installation Manager	7	Uninstalling by using wizard mode	19
Repository preferences	8	Uninstalling by using console mode	20
Setting repository preferences in wizard mode	8	Chapter 7. Deprecated features	21
Setting repository preferences in console mode	9	Notices	23
Passport Advantage preferences	9	Privacy policy considerations	24
Setting Passport Advantage preferences in wizard mode	10	Trademarks	25
Setting Passport Advantage preferences in console mode.	10		
Chapter 5. Installing IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML	13		
Installing in wizard mode	13		

Chapter 1. Overview

IBM® SPSS® Collaboration and Deployment Services Scoring Adapter for PMML enables IBM SPSS Collaboration and Deployment Services to score models exported from IBM SPSS applications, such as SPSS Modeler and Statistics, as Predictive Model Markup Language (PMML) files.

IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML can be installed after IBM SPSS Collaboration and Deployment Services Repository is installed. It can also be installed together with IBM SPSS Collaboration and Deployment Services Repository if both packages are selected for installation in IBM Installation Manager.

To install IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML:

1. Verify that all requirements have been met.
2. Obtain the installation files.
3. Configure the Installation Manager repository preferences or the Passport Advantage® account preferences.
4. Install IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML using Installation Manager.
5. Verify that IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML is installed correctly.

Note: IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML is used only to generate scores for models saved as PMML files. If you will be generating scores for models in IBM SPSS Modeler streams, install the IBM SPSS Collaboration and Deployment Services Scoring Adapter for IBM SPSS Modeler.

Chapter 2. Installation requirements

Before you install IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML, set up the resources in your environment.

For current system requirements information, refer to the software product compatibility reports on the IBM Technical Support site at: <http://publib.boulder.ibm.com/infocenter/prodguid/v1r0/clarity/softwareReqsForProduct.html>

In addition, the following conditions must be satisfied:

- IBM SPSS Collaboration and Deployment Services Repository must either be already installed on the system, or IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML must be installed together with IBM SPSS Collaboration and Deployment Services Repository by selecting both for installation with IBM Installation Manager.
- You must use the same user credentials to install IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML and IBM SPSS Collaboration and Deployment Services Repository.
- For RedHat and SUSE Linux systems, the following libraries must be installed:
 - `libstdc++.so.6` (C++ Runtime Version 6.0)
 - `libgfortran.so.1` (LibGFortran Runtime library)
- Installation Manager must be installed on the system.

If Installation Manager is not already present on the system, it is automatically installed when you start the installation. If you have an older version of Installation Manager, you are required to update it as part of the installation.

If Installation Manager is not installed automatically, and it is not present on the system, install Installation Manager 1.8.9 from the IBM Corp. support site (<http://www.ibm.com/support>). For download location and user information, see the Installation Manager documentation: <http://www-01.ibm.com/support/knowledgecenter/SSDV2W/welcome>.

Chapter 3. Installation files

Before installing, you must obtain the installation files.

To obtain the installation files do one of the following:

- Download the files from the Passport Advantage site, and use local installation: Licensed customers with a Passport Advantage ID and password can download the necessary product repositories from the Passport Advantage site.
- Access the live repositories, and use web-based installation: If you have a Passport Advantage ID and password, you can use Installation Manager to install the product directly from IBM hosted repositories.

Chapter 4. Getting started with Installation Manager

Installing, updating, or uninstalling the product can be performed by using IBM Installation Manager in wizard, console, or silent mode. However, you must configure an IBM Installation Manager repository or Passport Advantage preferences before performing these tasks.

For complete information about Installation Manager, see the IBM Installation Manager documentation.

Wizard mode

In wizard mode, you run Installation Manager from a graphical user interface.

Most of the time, you start Installation Manager with the default shortcuts that are installed with your version of Installation Manager.

From the installation location of Installation Manager, you can run the IBMIM application file to start in wizard mode manually.

The default IBMIM location for the operating system varies depending on the installation type (administrator, nonadministrator, or group).

Table 1. Default installation locations for IBMIM

Operating system	Administrator	Nonadministrator	Group
Windows XP Professional	C:\Program Files\IBM\Installation Manager	C:\Documents and Settings\user\IBM\Installation Manager\eclipse	Not available.
Windows Vista, Windows 2008, Windows 7, Windows 8, and Windows 2012	C:\Program Files [(x86)]\IBM\Installation Manager\eclipse	C:\Users\user\IBM\Installation Manager\eclipse	
Linux and UNIX	/opt/IBM/InstallationManager/eclipse	/user_home_directory/IBM/InstallationManager/eclipse	/user_home_directory/IBM/InstallationManager_Group/eclipse

Console mode

Use console mode when you do not have a graphics display device available or when you want to run Installation Manager without the graphical user interface. Installation Manager supports installing in an ASCII text-based mode that is called the console mode. Console mode is interactive text-based user interface to Installation Manager. For example, use console mode for server-side deployments when no graphical user interface is present, or for running the installation from a remote host.

To start console mode:

1. Open a command line.
2. Go to the `tools` subdirectory.
3. Run the command that is appropriate for the operating system:
 - Windows: `imcl.exe -c`
 - Linux, UNIX, and z/OS®: `./imcl -c`

The default tools location varies depending on the operating system and installation type (administrator, nonadministrator, or group). For more information, see the Installation Manager documentation.

Table 2. Default installation locations for the tools subdirectory

Operating system	Administrator	Nonadministrator	Group
Windows XP Professional	C:\Program Files\IBM\Installation Manager\eclipse\tools	C:\Documents and Settings\user\IBM\Installation Manager\eclipse\tools	
Windows Vista, Windows 2003, Windows 2008, Windows 7, Windows 8, Windows 10, and Windows 2012	C:\Program Files [(x86)]\IBM\Installation Manager\eclipse\tools	C:\Users\user\IBM\Installation Manager\eclipse\tools	
Linux and UNIX	/opt/IBM/InstallationManager/eclipse/tools	/user_home_directory/IBM/InstallationManager/eclipse/tools	/user_home_directory/IBM/InstallationManager_Group/eclipse/tools

Silent mode

Use silent installations to deploy software to multiple systems, or to an enterprise. Silent installations are defined by a response file and started from the command line or a batch file. The response file is provided with the product distribution. For more information, see “Installing silently by using a response file” on page 17.

Repository preferences

An IBM Installation Manager repository is a location that stores data for installing, modifying, rolling back, or updating packages.

Before you install, modify, or update packages, obtain the installation repository location from your administrator or from IBM.

Note: To successfully access an installation repository, the repository location path must not contain an ampersand (&).

The following topics provide instructions for setting repository preferences in wizard and console mode.

Setting repository preferences in wizard mode

You can add, edit, or remove repositories and modify the repository order in the repository table using wizard mode.

About this task

You can clear credentials for a repository or test a connection to a repository. You might find both a `diskTag.inf` file and a `repository.config` file in the IBM product installation files. Use the `diskTag.inf` file when you select a repository location.

Procedure

To add, edit, or remove a repository location:

1. Start Installation Manager in wizard mode by using IBMIM. For more information, see Chapter 4, “Getting started with Installation Manager,” on page 7.

2. Click **File > Preferences > Repositories**. The Repositories page opens and shows available repositories, repository locations, and the connection status for the repositories.
3. Click **Add Repository**.
4. Enter the repository location or click **Browse**. When you browse, go to the repository location and select the `diskTag.inf` file, the `repository.config` file, the `.zip` file, or the `.jar` file as appropriate for your environment.
5. Click **OK**.
If you provided an HTTPS or restricted FTP repository location, you are prompted to enter a user ID and password. The new repository location is added to the list. If the repository is not connected, a red box shows in the **Connection** column.
6. Optional: Select **Search service repositories during installation and updates**. Installation Manager searches the service repositories at IBM.com for updates to installed packages.
7. Click **OK** to close the Preference page.

Setting repository preferences in console mode

You can use console mode to add, remove, open, move, or close repositories.

About this task

A selected option is indicated by an X in brackets: [X]. Options that are not selected are indicated by empty brackets: []. You can press **Enter** to select the default entry or select a different command. For example, [N] indicates that the default selection is N for the **Next** command.

Procedure

To add a repository:

1. Start Installation Manager in console mode by using `imcl -c`. For more information, see Chapter 4, “Getting started with Installation Manager,” on page 7.
2. Enter P: Preferences.
3. Enter 1: Repositories.
4. Enter D: Add repository.
5. Enter a repository location such as `C:\installation_files\repository.config`. If you add a repository that requires credentials, you are prompted to provide the required credentials.
Use the correct case when you enter the repository location. If the correct case is not used, the package is not shown in the list of available packages for installation.
 - a. Enter P: Provide credentials and connect.
 - b. Enter the *user_name* and press **Enter**.
 - c. Enter the *password* and press **Enter**.
 - d. Enter 1 to save the password.
 - e. Enter 0: Ok.
6. Enter A: Apply Changes and Return to Preferences Menu.
7. Enter R: Return to Main Menu.

Passport Advantage preferences

IBM Installation Manager can access installation packages from Passport Advantage. Passport Advantage is a centralized online location for the acquisition of IBM software offerings.

Before you install, modify, or update packages, obtain valid Passport Advantage credentials.

The following topics provide instructions for setting Passport Advantage preferences in wizard and console mode.

Setting Passport Advantage preferences in wizard mode

You can set the Installation Manager Passport Advantage preferences to connect to Passport Advantage using wizard mode.

About this task

Important: If you share an instance of Installation Manager with other users, see the Installation Manager documentation for information on installing as an administrator, nonadministrator, or group.

Procedure

To set Passport Advantage preferences:

1. Start Installation Manager in wizard mode by using IBMIM. For more information, see Chapter 4, "Getting started with Installation Manager," on page 7.
2. Click **File > Preferences > Passport Advantage**.
3. Select the **Connect to Passport Advantage** check box to connect to the Passport Advantage repository. The Password Required window opens.
4. Enter a user name and password for Passport Advantage.
5. Optional: Select **Save password** to save the user name and password credentials.
If you do not save the user name and password credentials, you are prompted for these credentials each time you access Passport Advantage.
6. Click **OK** to close the Password Required window.
7. Click **OK** to close the Preferences window.

What to do next

To delete saved user name and password credentials:

1. Click **File > Preferences > Passport Advantage**.
2. Click **Clear Credentials**.
3. Click **OK** in the Confirm Clear Credentials window.

Setting Passport Advantage preferences in console mode

You can set the Installation Manager Passport Advantage preference to connect to Passport Advantage in console mode.

Procedure

1. Start Installation Manager in console mode by using `imcl -c`. For more information, see Chapter 4, "Getting started with Installation Manager," on page 7.
2. Enter P: Preferences.
3. Enter 6: Passport Advantage.
4. Enter 1: Connect to Passport Advantage. A selected option is indicated by an X in brackets: [X].
5. Enter P: Provide credentials and connect.
6. Enter the user name for the Passport Advantage account.
7. Enter the password.
If you do not save the user name and password credentials, you are prompted for these credentials each time you access Passport Advantage.
 - a. Optional: If you entered a password, enter 1: Save password if valid.

8. Enter **O**: OK to save the credentials.

Chapter 5. Installing IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML

You can install IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML in wizard, console, or silent mode.

Important:

IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML can be installed after IBM SPSS Collaboration and Deployment Services Repository is installed. It can also be installed together with IBM SPSS Collaboration and Deployment Services Repository if both packages are selected for installation in IBM Installation Manager.

If you install IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML after IBM SPSS Collaboration and Deployment Services Repository:

- The IBM SPSS Collaboration and Deployment Services Repository database must be running.
- The application server running IBM SPSS Collaboration and Deployment Services Repository must be in the following state:
 - WebSphere: For a stand-alone server, the server must be stopped. For a managed server, the server must be stopped, while the Deployment Manager node must be running. For a cluster, all cluster members must be stopped with the Deployment Manager node running.
 - JBoss: Stopped.
- When installing IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML into a manually deployed IBM SPSS Collaboration and Deployment Services Repository, you must rerun the manual repository server deployment scripts following the adapter installation. For more information about manual deployment, see *IBM SPSS Collaboration and Deployment Services Repository Installation and Configuration Guide*.

Installing in wizard mode

You can install IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML by using IBM Installation Manager in wizard mode.

Before you begin

Before you can install, IBM Installation Manager must have access to the repository that contains the package.

- If you have an IBM Passport Advantage account, you can install packages from the Passport Advantage site. For more information about connecting to a Passport Advantage repository, see “Setting Passport Advantage preferences in wizard mode” on page 10.
- If you are installing from a repository that is not on the Passport Advantage site, you must specify the repository in the preferences before you install. For more information, see “Setting repository preferences in wizard mode” on page 8.

About this task

These steps apply only if you are not installing IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML together with IBM SPSS Collaboration and Deployment Services.

Procedure

1. Start Installation Manager in wizard mode by using IBMIM. For more information, see Chapter 4, “Getting started with Installation Manager,” on page 7.
2. In Installation Manager, click **Install**. Installation Manager searches the defined repositories for available packages. If no available packages are found, verify that you specified the repository correctly. See “Setting repository preferences in wizard mode” on page 8.
3. If a new version of Installation Manager is found, you might be prompted to confirm the installation. Click **Yes** to proceed. Installation Manager automatically installs the new version, restarts, and resumes.
4. The Install page of Installation Manager lists all the packages that were found in the repositories that Installation Manager searched. Only the most recent version of the package is shown. To show all versions of a package that Installation Manager finds, select **Show all versions**. Click a package version to show the package description in the **Details** pane. If more information about the package is available, a **More info** link is included at the end of the description text.

If you are running Installation Manager in group mode, you can install only packages that are enabled for installing in group mode. If the package is not enabled for installing in group mode, you receive an error and cannot continue with the package installation in group mode.

5. Select the IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML package. Click **Next**.
6. On the Licenses page, read the license agreements for the selected package. After you accept the license agreement, click **Next** to continue.
7. On the Location page, enter the path for the shared resources directory in the **Shared Resources Directory** field. The shared resources directory contains resources that can be shared by multiple package groups. Click **Next**.
8. On the Location page, either choose a package group into which to install the packages or create a package group. A package group is a directory that contains resources that packages share with other packages in the same group. The first time that you install a package, you must create a package group. If you select more than one package to install, verify that the packages can be installed in the same package group by checking the documentation for the packages. For packages that cannot be installed in the same package group, install one package in one package group. After the installation completes, install the second package in a different package group.

Option	Description
Use the existing package group	Select a package group into which to install the packages. If the packages being installed are not compatible with the selected group, an alert reports the conflict. If a group is not compatible, either select a different group or create a new group.
Create a new package group	Click Browse to specify the installation directory for the packages. If you are installing on a 64-bit operating system, select the architecture for the installation as either 32-bit or 64-bit.

Click **Next** to continue the installation.

9. On the Features page, select the package features to install.
 - a. Optional: To see the dependency relationships between features, select **Show Dependencies**.
 - b. Optional: Click a feature to view its brief description under **Details**.
 - c. Select or clear features in the packages. Installation Manager automatically enforces dependencies with other features and shows updated download size and disk space requirements for the installation. To restore the default features that are selected for the packages, click **Restore Default**.
10. Do one of the following:

- If you are installing IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML after IBM SPSS Collaboration and Deployment Services Repository is installed, proceed to the next step.
 - If you are installing IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML together with IBM SPSS Collaboration and Deployment Services Repository, proceed to Step 12.
11. On the Common Configuration - CDS Admin Credentials page, specify the credentials of IBM SPSS Collaboration and Deployment Services administrator. Click **Next**.

Parameter	Description
C&DS User Name	The user name of IBM SPSS Collaboration and Deployment Services Repository administrator.
C&DS Password	The password of IBM SPSS Collaboration and Deployment Services Repository administrator.

12. On the Summary page, review your choices before you install the packages.
On Windows, Installation Manager checks for running processes. If processes are blocking the installation, a list of these processes is shown in the **Blocking Processes** section. You must stop these processes before you continue the installation. Click **Stop All Blocking Processes**. If there are no processes that must be stopped, you do not see this list. The running processes lock files that must be accessed or modified by Installation Manager.
13. Click **Install**. When the installation process completes, you receive a confirmation message.

Results

IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML is installed in the specified directory.

What to do next

Verify that IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML is installed correctly.

Installing in console mode

You can install IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML by using IBM Installation Manager in console mode.

Before you begin

Before you can install, Installation Manager must have access to the repository that contains the package.

- If you have an IBM Passport Advantage account, you can install packages from the Passport Advantage site. For more information about connecting to a Passport Advantage repository, see “Setting Passport Advantage preferences in console mode” on page 10.
- If you are installing from a repository that is not on the Passport Advantage site, you must specify the repository in the preferences before you install. For more information, see “Setting repository preferences in console mode” on page 9.

About this task

A selected option is indicated by an X in brackets: [X]. Options that are not selected are indicated by empty brackets: []. You can press **Enter** to select the default entry or select a different command. For example, [N] indicates that the default selection is N for the **Next** command.

Some options may include a status prefix of **[Error]** or **[Incomplete]**. This status indicates that IBM Installation Manager does not currently have valid values for the parameters included in that option. You must select any options having this status and specify values for the parameters.

Procedure

To install in console mode:

1. Start Installation Manager in console mode by using `imcl -c`.
The default `imcl` location varies depending on the operating system and installation type (administrator, nonadministrator, or group). For more information, see Chapter 4, "Getting started with Installation Manager," on page 7.
2. Enter 1: Install - Install software packages. Packages that can be installed are listed.
If you have repositories that require credentials and you did not save the credentials, you are prompted to provide these credentials
3. Enter 1: [] *package_name*. To select a package, enter the number that is next to the package. This example selects the first package listed. If the selected package requires a later version of Installation Manager, you are prompted to install the later version.
4. On the Select screen, enter the number that is next to the package that you want to install.
 - 1: Choose version *package_version* for installation. This option shows when you chose a package that is not selected for installation.
The 1: Do NOT install version *package_version* option shows when you chose a package that is selected for installation.
 - 2: Show all available versions of the package.
5. Optional: Enter 0: Check for Other Versions, Fixes, and Extensions. Installation Manager searches available repositories for other versions, fixes, or extensions of the selected package.
 - For Installation Manager to search the default repository for the installed packages, the **Search service repositories during installation and updates** preference must be selected. This preference is selected by default. To access this preference, go to the Repositories preference page.
 - Typically, Internet access is required.
 - The **Check for Other Versions, Fixes, and Extensions** option indicates the number of other versions, fixes, or extensions found but does not list the found items. To see available versions, enter the number that is next to the package then enter 2: Show all available versions of the package.
6. Enter N: Next
7. Options for the Licenses screen:
 - 1: *product_name* - License Agreement. To view a license agreement, enter the number that is next to the product name. This example selects the first license agreement listed.
 - A: [] I accept the terms in the license agreement.
 - D: [] I do not accept the terms in the license agreement. If you decline the license agreement, the installation is stopped. To continue the installation, you must accept the license agreement.
 - a. Enter A to accept the license agreement.
 - b. Enter N: Next.
8. To enter a different value for the shared resources directory, enter M: Shared Resources Directory. To accept the default value for shared resources directory or to continue after you enter a different value, enter N: Next.

Important: You can specify the shared resources directory only the first time that you install a package. Select the drive with enough available space to ensure adequate space for the shared resources of future packages. You cannot change the location of the shared resources directory unless you uninstall all packages.

9. Optional: To enter a different value for the package group location, enter M: Change Location. To accept the default values or to continue after you enter a different value, enter N: Next.
A package group is a directory that contains resources that packages share with other packages in the same group. The first time that you install a package, you must create a package group. If you select more than one package to install, verify that the packages can be installed in the same package group by checking the documentation for the packages. For packages that cannot be installed in the same package group, install one package in one package group. After the installation completes, install the second package in a different package group.
10. Do one of the following:
 - If you are installing IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML after IBM SPSS Collaboration and Deployment Services Repository is installed, proceed to the next step.
 - If you are installing IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML together with IBM SPSS Collaboration and Deployment Services Repository, proceed to Step 17.
11. Options for the Common Configurations screen:
 - **1:** Proceed to the Admin Credentials screen.
 - **B:** Back, return to the previous screen.
 - **C:** Cancel, return to the main menu.
 - a. Enter 1 to proceed to the Admin Credentials screen.
12. On the Admin Credentials screen, enter 1 to proceed to the user name entry.
13. Enter the administrator user name.
14. On the Admin Credentials screen, enter 2 to proceed to the password entry.
15. Enter the administrator password.
16. Enter N: Next
17. On the Summary screen, review your selections before you install the package.
Optional: To generate a response file, enter G: Generate an installation response file. Enter the name of the response file and use .xml as the file extension. Response files are XML files. You can include a directory location when you enter the response file name to save the file to a different location.
18. Enter I: Install.
19. When the installation completes, enter F: Finish.

Results

IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML is installed in the specified directory.

What to do next

Verify that IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML is installed correctly.

Installing silently by using a response file

You can use a response file to install in silent mode.

Before you begin

Locate the SilentInstallOptions response file provided in the installation package.

Procedure

To install a package in silent mode:

Run the **imcl** command:

- Windows: `imcl.exe input response_file -log log_file`
- Linux and UNIX: `./imcl input response_file -log log_file`

The default **imcl** location will vary depending on the operating system and installation type (administrator, nonadministrator, or group). For more information, see Chapter 4, “Getting started with Installation Manager,” on page 7.

Results

When the installation is complete, a status of 0 is returned. If the installation cannot be completed, a non-zero number is returned.

A log file is available. For more information, see the Installation Manager documentation.

Example

Table 3. Install commands by operating system

Operating system	Command
Windows	<code>imcl.exe input c:\response_files\install.xml -log c:\mylog\install_log.xml -acceptLicense</code>
Linux, UNIX	<code>./imcl input /response_files/install.xml -log /mylog/install_log.xml -acceptLicense</code>

Enclose file paths that include spaces with double quotation marks.

Chapter 6. Uninstalling IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML

You can uninstall IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML in wizard or console mode.

You must log in with a user account that has the same privileges as the account that was used to install IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML.

Important: Certain files in the IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML program directory (for example, program data) cannot be deleted by IBM Installation Manager. You must manually delete the program directory to completely remove all IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML files from the system after you uninstall it.

Uninstalling IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML removes the adapter files from the host file system. However, the adapter remains deployed with IBM SPSS Collaboration and Deployment Services Repository in the application server.

Uninstalling by using wizard mode

You can use IBM Installation Manager in wizard mode to uninstall IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML.

Before you begin

You must log in with a user account that has the same privileges as the account that was used to install the packages that you want to uninstall.

Procedure

To uninstall IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML:

1. Close programs that you installed with Installation Manager.
2. Start Installation Manager in wizard mode by using IBMIM.
The default **IBMIM** location will vary depending on the operating system and installation type (administrator, nonadministrator, or group). For more information, see Chapter 4, “Getting started with Installation Manager,” on page 7.
3. In Installation Manager, click **Uninstall**.
4. In the Uninstall wizard, select the IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML package.
5. Click **Next**.
6. On the Summary page, review your selections. Click **Back** to change your selections. If you are satisfied with your choices, click **Uninstall**.

On Windows, Installation Manager checks for running processes. If processes are blocking the uninstall process, a list of these processes is shown in the Blocking Processes section. You must stop these processes before you continue the uninstall process. Click **Stop All Blocking Processes**. If there are no processes that must be stopped, you do not see this list. The running processes lock files that must be accessed or modified by Installation Manager.

7. When the uninstallation process finishes, the Complete page opens and confirms the uninstallation process.

Uninstalling by using console mode

You can use IBM Installation Manager in console mode to uninstall IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML.

Before you begin

You must log in with a user account that has the same privileges as the account that was used to install the packages.

About this task

A selected option is indicated by an X in brackets: [X]. Options that are not selected are indicated by empty brackets: []. You can press **Enter** to select the default entry or select a different command. For example, [N] indicates that the default selection is N for the **Next** command.

Procedure

To uninstall IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML:

1. Close programs that you installed with Installation Manager.
2. Start Installation Manager in console mode by using `imcl -c`.
The default `imcl` location will vary depending on the operating system and installation type (administrator, nonadministrator, or group). For more information, see Chapter 4, "Getting started with Installation Manager," on page 7.
3. Enter 5: Uninstall - Remove the installed software packages.
4. To select the IBM SPSS Collaboration and Deployment Services Scoring Adapter for PMML package group, enter the number that is next to the package group.
5. Enter N: Next to continue.
6. To select the package, enter the number that is next to the package.
Optional: To select all packages to uninstall, enter A: Select all packages. The A: Unselect all packages option shows when all packages are selected for uninstall.
7. In the Summary panel, review your selections before you uninstall. Enter U: Uninstall.
8. When the uninstall process completes, enter F: Finish.

Chapter 7. Deprecated features

If you are migrating from an earlier release of IBM SPSS Collaboration and Deployment Services, you should be aware of the various features that have been deprecated since the last version.

If a feature is deprecated, IBM Corp. might remove this capability in a subsequent release of the product. Future investment will be focused on the strategic function listed under the recommended migration action. Typically, a feature is not deprecated unless an equivalent alternative is provided.

No features have been deprecated in this release. For reference purposes, the following table indicates features that were deprecated in recent previous versions of the product. Where possible, the table also indicates the recommended migration action.

Table 4. Features deprecated in previous versions

Deprecation	Recommended migration action
Security Provider: Active Directory with local override, which supports extended groups and allowed users	Use the standard Active Directory security provider with any necessary groups added
IBM SPSS Collaboration and Deployment Services Enterprise View	Use the Analytic Data View feature
IBM SPSS Collaboration and Deployment Services Enterprise View Driver	Use the Analytic Data View feature
Scenario files	Scenario files (.scn) are no longer supported. Enterprise View source nodes cannot be modified in Deployment Manager. Old scenario files can be modified in IBM SPSS Modeler client and resaved as stream files. Also, scoring configurations that used a scenario file must be deleted and recreated based on a stream file.
Web Install for IBM SPSS Deployment Manager	Use the standalone installer
BIRT Report Designer for IBM SPSS	None
BIRT Report Designer for IBM SPSS viewer	None
IBM SPSS Collaboration and Deployment Services Portlet	Use the IBM SPSS Collaboration and Deployment Services Deployment Portal directly, or use the web services APIs
IBM SPSS Collaboration and Deployment Services Web Part	Use the IBM SPSS Collaboration and Deployment Services Deployment Portal directly, or use the web services APIs
Scoring Service V1 API	Scoring Service V2 API
Scheduling Server Service	None
Reporting Service	None
Authentication Service login operation	Authentication Service doLogin operation
Search Service search operation	Search Service search2.5 operation
SPSS AXIS/Castor web services client jar	Use the tools provided with the Java Runtime Environment, Integrated Development Environment, or Eclipse Web Tools Platform (WTP)
clemrt1_setLogFile() API function	None

Notices

This information was developed for products and services offered in the US. This material might be available from IBM in other languages. However, you may be required to own a copy of the product or product version in that language in order to access it.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Privacy policy considerations

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, See IBM's Privacy Policy at <http://www.ibm.com/privacy> and IBM's Online Privacy Statement at <http://www.ibm.com/privacy/details> the section entitled "Cookies, Web Beacons and Other Technologies" and the "IBM Software Products and Software-as-a-Service Privacy Statement" at <http://www.ibm.com/software/info/product-privacy>.

Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Intel, Intel logo, Intel Inside, Intel Inside logo, Intel Centrino, Intel Centrino logo, Celeron, Intel Xeon, Intel SpeedStep, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Other product and service names might be trademarks of IBM or other companies.



Printed in USA