



**Program Directory for  
DB2 Server for OS/390  
390 Enablement for Management Tools Package**

Version 05 Release 01, Modification Level 00

Program Number 5655-DB2

FMID JDB551D

for Use with  
OS/390

Document Date: September 1999

GI10-8195-01

**Note!**

Before using this information and the product it supports, be sure to read the general information under "Notices" on page iv.

A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 1999. All rights reserved.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

Notices	iv
Trademarks	v
<b>1.0 Introduction</b>	<b>1</b>
1.1 390 Enablement Description	2
1.2 390 Enablement FMID	2
<b>2.0 Program Materials</b>	<b>3</b>
2.1 Basic Machine-Readable Material	3
2.2 Optional Machine-Readable Material	4
2.3 Program Publications	4
2.3.1 Basic Program Publications	4
2.3.2 Optional Program Publications	4
2.4 Program Source Materials	4
2.5 Publications Useful During Installation	4
<b>3.0 Program Support</b>	<b>6</b>
3.1 Program Services	6
3.2 Preventive Service Planning	6
3.3 Statement of Support Procedures	6
<b>4.0 Program and Service Level Information</b>	<b>7</b>
4.1 Program Level Information	7
4.2 Service Level Information	7
4.3 Cumulative Service Tape	7
<b>5.0 Installation Requirements and Considerations</b>	<b>8</b>
5.1 Driving System Requirements	8
5.1.1 Machine Requirements	8
5.1.2 Programming Requirements	8
5.1.2.1 Required Toleration PTFs	9
5.2 Target System Requirements	9
5.2.1 Machine Requirements	9
5.2.2 Programming Requisites	9
5.2.2.1 Minimum Requisites	9
5.2.2.2 Functional Requisites	10
5.2.3 DASD Storage Requirements	11
5.3 FMIDs Deleted	13
5.4 Special Considerations	13
<b>6.0 Installation Instructions</b>	<b>14</b>
6.1 Installing 390 Enablement	14

6.1.1 SMP/E Considerations for Installing 390 Enablement	14
6.1.2 SMP/E Environment	14
6.1.3 SMP/E CALLLIBS Processing for 390 Enablement	15
6.1.4 SMP/E Options Subentry Values	15
6.1.5 Unload the Sample JCL from the Product Tape	15
6.1.6 Allocate SMP/E Target and Distribution Libraries	16
6.1.7 Create DDDEF Entries	16
6.1.8 Perform SMP/E RECEIVE	16
6.1.9 RECEIVE the Cumulative Service Tape	17
6.1.10 Perform SMP/E APPLY CHECK	17
6.1.11 Perform SMP/E APPLY	17
6.1.12 Perform SMP/E ACCEPT CHECK	18
6.1.13 Perform SMP/E ACCEPT	18
6.2 Activating 390 Enablement	18
6.2.1 Activate 390 Enablement Detail Steps	20
<b>Appendix A. 390 Enablement Install Logic</b>	<b>22</b>
A.1 SMP/E Modification Control Statements	22
A.2 SMP/E JCLIN	22
<b>Reader's Comments</b>	<b>23</b>

## Figures

1. Basic Material: Program Tape	3
2. Program Tape: File Content	3
3. Publications Useful During Installation	4
4. PSP Upgrade and Subset ID	6
5. Component IDs	6
6. Driving System Software Requirements	8
7. Minimum Requisites	9
8. Functional Requisites	10
9. Total DASD Space Required by 390 Enablement	11
10. Storage Requirements for SMP/E Work Data Sets	12
11. Storage Requirements for SMP/E Data Sets	12
12. Storage Requirements for 390 Enablement Target Libraries	13
13. Storage Requirements for 390 Enablement Distribution Libraries	13
14. FMIDs Deleted	13
15. SMP/E Options Subentry Values	15
16. Detail of 390 Enablement Activation Steps	20

---

## Notices

References in this document to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe on any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

International Business Machines Corporation  
IBM Director of Licensing  
North Castle Drive  
Armonk, New York 10504-1785  
USA

For online versions of this book, we authorize you to:

- Copy, modify, and print the documentation contained on the media, for use within your enterprise, provided you reproduce the copyright notice, all warning statements, and other required statements on each copy or partial copy.
- Transfer the original unaltered copy of the documentation when you transfer the related IBM product (which may be either machines you own, or programs, if the program's license terms permit a transfer). You must, at the same time, destroy all other copies of the documentation.

You are responsible for payment of any taxes, including personal property taxes, resulting from this authorization.

THERE ARE NO WARRANTIES, EXPRESS OR IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Some jurisdictions do not allow the exclusion of implied warranties, so the above exclusion may not apply to you.

Your failure to comply with the terms above terminates this authorization. Upon termination, you must destroy your machine readable documentation.

---

## Trademarks

CBPDO  
DATABASE 2  
Distributed Relational Database Architecture  
IBM  
MVS/ESA  
OS/390

CBIPO  
DB2  
DRDA  
IBMLink  
OS/2  
TCP/IP

---

## 1.0 Introduction

This program directory is intended for the system programmer responsible for program installation and maintenance. It contains information concerning the material and procedures associated with the installation of 390 Enablement for Management Tools Package. This publication refers to 390 Enablement for Management Tools Package as 390 Enablement. You should read all of this program directory before installing the program and then keep it for future reference.

The program directory contains the following sections:

- 2.0, "Program Materials" on page 3 identifies the basic and optional program materials and documentation for 390 Enablement.
- 3.0, "Program Support" on page 6 describes the IBM support available for 390 Enablement.
- 4.0, "Program and Service Level Information" on page 7 lists the APARs (program level) and PTFs (service level) incorporated into 390 Enablement.
- 5.0, "Installation Requirements and Considerations" on page 8 identifies the resources and considerations for installing and using 390 Enablement.
- 6.0, "Installation Instructions" on page 14 provides detailed installation instructions for 390 Enablement. It also describes the procedures for activating the functions of 390 Enablement, or refers to appropriate publications.
- Appendix A, "390 Enablement Install Logic" on page 22 provides the install logic for 390 Enablement.

Before installing 390 Enablement, read 3.2, "Preventive Service Planning" on page 6. This section tells you how to find any updates to the information and procedures in this program directory.

Do not use this program directory if you are installing 390 Enablement with an MVS Custom-Built Installation Process Offering (CBIPO), SystemPac, or ServerPac. When using these offerings, use the jobs and documentation supplied with the offering. This documentation may point you to specific sections of the program directory as required.

If you are installing 390 Enablement using the MVS Custom-Built Product Delivery Offering (CBPDO) (5751-CS3), use the softcopy program directory provided on the CBPDO tape. Your CBPDO contains a softcopy preventive service planning (PSP) upgrade for this product. All service and HOLDDATA for 390 Enablement are included on the CBPDO tape.

---

## 1.1 390 Enablement Description

IBM's DB2 Universal Database (UDB) Version 6 Control Center is being extended to support DB2 for OS/390. Users can now manage DB2 for OS/390 database objects using the same workstation-based GUI tool developed for UDB. This tool requires a set of enabling DB2 for OS/390 stored procedures that are shipped with this SMP/E installable package as 390 Enablement for Management Tools Package.

DB2 for OS/390 objects can now be displayed on the Control Center main window. The actions and utilities to manage these objects can be invoked by selecting the appropriate object on the navigation tree. For example, a user can list the table spaces of a particular database and perform the following actions on a selected table space: alter, drop, copy, runstats, etc.

---

## 1.2 390 Enablement FMID

390 Enablement consists of the following FMID:

JDB551D



## 2.0 Program Materials

An IBM program is identified by a program number and a feature number. The program number for 390 Enablement is 5655-DB2.

Basic Machine-Readable Materials are materials that are supplied under the base license and feature code, and are required for the use of the product. Optional Machine-Readable Materials are orderable under separate feature codes, and are not required for the product to function.

The program announcement material describes the features supported by 390 Enablement. Ask your IBM representative for this information if you have not already received a copy.

### 2.1 Basic Machine-Readable Material

The distribution medium for this program is 9-track magnetic tape (written at 6250 BPI), 3480 cartridge, or 4mm cartridge. The tape or cartridge contains all the programs and data needed for installation. It is installed using SMP/E, and is in SMP/E RELFILE format. See 6.0, "Installation Instructions" on page 14 for more information about how to install the program.

Figure 1 describes the tape or cartridge. Figure 2 describes the file content of the program tape or cartridge.

**Note:** If you are installing 390 Enablement using the MVS Custom-Built Product Delivery Offering (CBPDO) (5751-CS3), some of the information in these figures may not be valid. Consult the CBPDO documentation for actual values.

<i>Figure 1. Basic Material: Program Tape</i>				
Medium	Feature Number	Physical Volume	External Label Identification	VOLSER
6250 Tape	5801	1	390 Enablement	DB551D
		2	DB2 Connect Personal Edition V6	CDROM
3480 cart	5802	1	390 Enablement	DB551D
		2	DB2 Connect Personal Edition V6	CDROM
4mm cart	6112	1	390 Enablement	DB551D
		2	DB2 Connect Personal Edition V6	CDROM

<i>Figure 2 (Page 1 of 2). Program Tape: File Content</i>						
VOLSER	File	Name	Dist Library	RECFM	LRECL	BLK SIZE
DB551D	1	SMPMCS	n/a	FB	80	6400
	2	IBM.JDB551D.F1	ADSNBASE	FB	80	8800

Figure 2 (Page 2 of 2). Program Tape: File Content

<b>VOLSER</b>	<b>File</b>	<b>Name</b>	<b>Dist Library</b>	<b>RECFM</b>	<b>LRECL</b>	<b>BLK SIZE</b>
3	IBM.JDB551D.F2		ADSNMACS	FB	80	8800
4	IBM.JDB551D.F3		ADSNLOAD	U	0	6144

## 2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for 390 Enablement.

## 2.3 Program Publications

The following sections identify the basic and optional publications for 390 Enablement.

### 2.3.1 Basic Program Publications

No base publications are provided with 390 Enablement.

### 2.3.2 Optional Program Publications

No optional publications are provided for 390 Enablement.

## 2.4 Program Source Materials

No program source materials or viewable program listings are provided for 390 Enablement.

## 2.5 Publications Useful During Installation

Figure 3 (Page 1 of 2). Publications Useful During Installation

<b>Publication Title</b>	<b>Form Number</b>
<i>SMP/E User's Guide</i>	SC28-1302
<i>SMP/E Reference</i>	SC28-1107
<i>SMP/E Messages and Codes</i>	SC28-1108
<i>OS/390 SMP/E User's Guide</i>	SC28-1740
<i>OS/390 SMP/E Reference</i>	SC28-1806

*Figure 3 (Page 2 of 2). Publications Useful During Installation*

<b>Publication Title</b>	<b>Form Number</b>
<i>OS/390 SMP/E Messages and Codes</i>	SC28-1738

---

## 3.0 Program Support

This section describes the IBM support available for 390 Enablement.

---

### 3.1 Program Services

Contact your IBM representative for specific information about available program services.

---

### 3.2 Preventive Service Planning

Before installing 390 Enablement, you should review the current Preventive Service Planning (PSP) information. If you obtained 390 Enablement as part of a CBPDO, there is HOLDDATA and PSP information included on the CBPDO tape.

If you obtained 390 Enablement on a product tape, or if the CBPDO is more than two weeks old when you install it, you should contact the IBM Support Center or use S/390 SoftwareXcel to obtain the current PSP Bucket.

PSP Buckets are identified by UPGRADEs, which specify product levels, and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for 390 Enablement are:

*Figure 4. PSP Upgrade and Subset ID*

UPGRADE	SUBSET	Description
DB2510	JDB551D	390 Enablement

---

### 3.3 Statement of Support Procedures

Report any difficulties you have using this program to your IBM Support Center. If an APAR is required, the Support Center will provide the address to which any needed documentation can be sent.

Figure 5 identifies the component IDs (COMPID) for 390 Enablement.

*Figure 5. Component IDs*

FMID	COMPID	Component Name	RETAIN Release
JDB551D	5740XYR00	390 Enablement	51D

---

## **4.0 Program and Service Level Information**

This section identifies the program and any relevant service levels of 390 Enablement. The program level refers to the APAR fixes incorporated into the program. The service level refers to the PTFs integrated. Information about the cumulative service tape is also provided.

---

### **4.1 Program Level Information**

No APARs have been incorporated into 390 Enablement.

---

### **4.2 Service Level Information**

No PTFs against this release of 390 Enablement have been incorporated into the product tape.

---

### **4.3 Cumulative Service Tape**

A cumulative service tape, containing PTFs not incorporated into this release, might be included with this program. Installation instructions for cumulative service tapes can be found in the SMP/E publications.

If you received this product as part of a CBPDO or a ProductPac, PTFs not incorporated into this release are provided on the tape, and a separate cumulative service tape will not be provided.

---

## 5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating 390 Enablement. The following terminology is used:

- *Driving system*: the system used to install the program.
- *Target system*: the system on which the program is installed.

In many cases, the same system can be used as both a driving system and a target system. However, you may want to set up a clone of your system to use as a target system by making a separate IPL-able copy of the running system. The clone should include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Some cases where two systems should be used include the following:

- When installing a new level of a product that is already installed, the new product will delete the old one. By installing onto a separate target system, you can test the new product while still keeping the old one in production.
- When installing a product that shares libraries or load modules with other products, the installation can disrupt the other products. Installing onto a test system or clone will allow you to assess these impacts without disrupting your production system.

---

### 5.1 Driving System Requirements

This section describes the environment of the driving system required to install 390 Enablement.

#### 5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

#### 5.1.2 Programming Requirements

*Figure 6. Driving System Software Requirements*

<b>Program Number</b>	<b>Product Name and Minimum VRM/Service Level</b>
5655-001	OS/390 System Modification Program/Extended (SMP/E) Release 1

**5.1.2.1 Required Toleration PTFs:** Starting with OS/390 Version 2 Release 7, the DESCRIPTION operand on the ++FUNCTION statement of the System Modification Control Statements (SMPMCS) is introduced. 390 Enablement uses the new DESCRIPTION operand on the ++FUNCTION statement. In order to avoid syntax errors on the DESCRIPTION operand during installation of 390 Enablement, **you are required to install a toleration PTF**. Once installed, the toleration PTF allows previous releases of SMP/E to ignore the DESCRIPTION operand.

**Required Toleration PTFs For Earlier SMP/E Releases**

- OS/390 Version 1 Release 3 and Version 2 Release 4:
  - PTF UR50597
- OS/390 Version 2 Release 5 and Release 6:
  - PTF UR50598

## 5.2 Target System Requirements

This section describes the environment of the target system required to install and use 390 Enablement.

### 5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

### 5.2.2 Programming Requisites

**5.2.2.1 Minimum Requisites:** A minimum requisite is defined as one of the following:

1. *Installation Requisite:* A product that is required at installation time. i.e. this product **will not install** successfully unless this requisite is met. This includes products that are specified as REQs, PREs, or CALLLIBs.
2. *Run Time Requisite:* A product that is **not** required for the successful installation of this product, but **is** needed at run time in order for this product to work.

*Figure 7. Minimum Requisites*

Program Number	Product Name and Minimum VRM/Service Level	Install Req?
5655-001	OS/390 Version 1 Release 3	Yes

**5.2.2.2 Functional Requisites:** A functional requisite is defined as a product that is *not* required for the successful installation of this product or for the base function of the product, but *is* needed at run time for a specific function of this product to work. This includes products that are specified as IF REQs.

Before you can activate 390 Enablement as described in 6.2, “Activating 390 Enablement” on page 18, the functional requisites identified below must first be applied to DB2 Server for OS/390 V5:

*Figure 8. Functional Requisites*

Program Number	Product Name and Minimum VRM/Service Level	Function	Install Req?
5655-DB2	DB2 for OS/390 Version 5 with the following APARs:  PQ20558 - Enhance Display Database() Restrict PQ21716 - Storage Manager Component Overlay Problem PQ23162 - Add CALLLIBS for Modules Requiring LE/370 PQ24720 - Utilities as a Stored Procedure Enhancement PQ25091 - RUNSTATS Utility New Function	Database Server for OS/390	Yes

To enable all 390 functionality of Control Center, six DB2 stored procedures must be installed and configured as described in 6.2, “Activating 390 Enablement” on page 18. Four of these stored procedures are packaged with 390 Enablement: DSNACCMD, DSNACCQC, DSNACCMG, and DSNACCAV. Two of these stored procedures are packaged with DB2: DSNWZP, and DSNUTILS.

The 390 Enablement stored procedures and DSNWZP must be set to run in the DB2 stored procedures address space.

DSNUTILS must run in a WLM environment. See *DB2 for OS/390 Administration Guide, Volume 2* for information about setting up WLM to run a DB2 stored procedure. After APAR PQ24720 is installed, see member DSNUTSP of DB2 target data set SDSNMACS for DD statements that must be added to the JCL procedure to start a WLM-established address space for DSNUTILS.

Also, Resource Recovery Services (RRS) with associated system logger setup must be enabled to support DB2 RRSAF Attach as part of the DB2 WLM environment.

See IBM Redbook *Getting Started with DB2 Stored Procedures (SG24-4693)* for useful information to configure WLM and RSS to support DB2 stored procedures.



## 5.2.3 DASD Storage Requirements

390 Enablement libraries can reside on 3380 or 3390 DASD.

Figure 9 lists the total space required for each type of library.

<i>Figure 9. Total DASD Space Required by 390 Enablement</i>	
<b>Library Type</b>	<b>Total Space Required</b>
Target	10 blocks
Distribution	10 blocks

### Notes:

1. The data set sizes specified contain 15% extra space. You may wish to revise these numbers based on your plans for adding additional function or service.
2. IBM recommends use of system determined block sizes for efficient DASD utilization for all non-RECFM U data sets. For RECFM U data sets, IBM recommends a block size of 32760, which is the most efficient from a performance and DASD utilization perspective.

If you choose not to use system determined block sizes, use the block sizes and numbers of blocks specified to allocate the data sets. Data sets can be reblocked to a larger size. Please note that the maximum allowable block size will depend on the type of DASD on which the dataset will reside; for example, the block size of datasets on a 3350 DASD cannot exceed 19,069.

3. Abbreviations used for the data set type are:

- U** Unique data set used by only the FMIDs listed. In order to determine the correct storage needed for this data set, this table provides all required information; no other tables (or program directories) need to be referenced for the data set size.
- S** Shared data set used by more than the FMIDs listed. In order to determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old one and reclaim the space used by the old release and any service that had been installed. You can determine whether or not these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information on the names and sizes of the required data sets, please refer to 6.1.6, "Allocate SMP/E Target and Distribution Libraries" on page 16.

Figure 10. Storage Requirements for SMP/E Work Data Sets

Library DDNAME	T Y P E	D S R G	R E C F M	L R E C L	No. of Blks	BLK SIZE	No. of 3380/ Trks	No. of 3390 Trks	No. of DIR Blks
SMPWRK1	S	PO	FB	80	30	6160	3	2	150
SMPWRK2	S	PO	FB	80	30	6160	3	2	150
SMPWRK3	S	PO	FB	80	30	3200	3	2	150
SMPWRK4	S	PO	FB	80	30	3200	3	2	150
SMPWRK6	S	PO	FB	80	30	3200	3	2	150

The following table provides an estimate of the storage needed in the SMP/E data sets for 390 Enablement. The estimates must be added to those of any other programs and service being installed to determine the total additional storage requirements.

Figure 11. Storage Requirements for SMP/E Data Sets

Library DDNAME	T Y P E	D S R G	R E C F M	L R E C L	No. of Blks	BLK SIZE	No. of 3380/ Trks	No. of 3390 Trks	No. of DIR Blks
SMPLOG	S	PS	VB	260	6000	3200	508	435	–
SMPLOGA	S	PS	VB	260	6000	3200	508	435	–
SMPLTS	S	PO	U	0	100	6144	18	15	50
SMPMTS	S	PO	FB	80	60	3120	18	15	60
SMPPTS	S	PO	FB	80	400	3120	52	45	300
SMPSCDS	S	PO	FB	80	400	3120	52	45	300
SMPSTS	S	PO	FB	80	400	3120	52	45	150

The following figures list the target and distribution libraries (data sets) and their attributes required to install 390 Enablement. The storage requirements of 390 Enablement must be added to the storage required by other programs having data in the same data set (library).

Figure 12. Storage Requirements for 390 Enablement Target Libraries

Library DDNAME	T Y P E	D S R O G	R E C F M	L R E C L	No. of Blks	BLK SIZE	No. of 3380/ 9345 Trks	No. of 3390 Trks	No. of DIR Blks
SDSNBASE	U	PO	FB	80	10	8800	4	3	5

Figure 13. Storage Requirements for 390 Enablement Distribution Libraries

Library DDNAME	T Y P E	D S R O G	R E C F M	L R E C L	No. of Blks	BLK SIZE	No. of 3380/ 9345 Trks	No. of 3390 Trks	No. of DIR Blks
ADSNBASE	U	PO	FB	80	10	8800	4	3	5

### 5.3 FMIDs Deleted

This is a dependent function and does not explicitly delete previous levels. Previous levels of this dependent function will be implicitly deleted when their base function is deleted.

Installing 390 Enablement will result in the deletion of the following FMIDs:

Figure 14. FMIDs Deleted

Deleted FMID	Deleting FMID	Description
JDB55ZZ	JDB551D	390 Enablement Beta

### 5.4 Special Considerations

390 Enablement has no special considerations for the target system.

---

## 6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of 390 Enablement.

Please note the following:

- If you want to install 390 Enablement into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMPCSI and the SMP/E control data sets.
- Sample jobs have been provided to help perform some or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries required for SMP/E execution have been defined in the appropriate zones.
- The SMP/E dialogs may be used instead of the sample jobs to accomplish the SMP/E installation steps.

---

### 6.1 Installing 390 Enablement

#### 6.1.1 SMP/E Considerations for Installing 390 Enablement

This release of 390 Enablement is installed using the SMP/E RECEIVE, APPLY, and ACCEPT commands. The SMP/E dialogs may be used to accomplish the SMP/E installation steps.

#### 6.1.2 SMP/E Environment

All SMP/E installation jobs provided assume that all necessary DD statements for the execution of SMP/E are defined using DDDEFs.

Sample jobs are provided to assist you in installing 390 Enablement. After the RECEIVE step has been completed, the sample jobs can be found in SMPTLIB: **IBM.JDB551D.F1**. Make a copy of these jobs in your own library and modify them to use during the installation of 390 Enablement. The sample jobs are:

<b>DSNEALC</b>	Sample job to allocate target and distribution libraries
<b>DSNEDDEF</b>	Sample job to define SMP/E DDDEFs
<b>DSNRECV</b>	Sample RECEIVE job
<b>DSNAPPLC</b>	Sample APPLY CHECK job
<b>DSNAPPLY</b>	Sample APPLY job
<b>DSNACCPC</b>	Sample ACCEPT CHECK job
<b>DSNACCPT</b>	Sample ACCEPT job

In the sample SMP/E jobs provided, the name of the SMP/E CSI is SMPCSI.CSI. The global zone name in the SMP/E CSI is GLOBAL. The distribution zone name is #dzone. The target zone name is #tzone. The sample jobs should be updated to reflect the CSI and zone names used at your installation.

### 6.1.3 SMP/E CALLLIBS Processing for 390 Enablement

390 Enablement uses the CALLLIBS function provided in SMP/E Release 8 to resolve external references during installation. When 390 Enablement is installed, ensure the following:

- Verify that the SMP/E SMPLTS data set has been allocated. Refer to *SMP/E Reference* for information on allocating the SMPLTS data set.

**Note:** For 390 Enablement, 120 cylinders of 3380/3390 DASD space is adequate for the SMPLTS.

- Provide DDDEFs for the following library:
  - SCEELKED
  - CSSLIB

**Note:** The DDDEF above are used only to resolve the link-edit for 390 Enablement using CALLLIBS. This data set is not updated during the installation of 390 Enablement.

### 6.1.4 SMP/E Options Subentry Values

The recommended values for some SMP/E CSI subentries are shown in Figure 15. Use of values lower than these may result in failures in the installation process. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. Refer to the SMP/E manuals for instructions on updating the global zone.

<i>Figure 15. SMP/E Options Subentry Values</i>		
SUB-ENTRY	Value	Comment
DSSPACE	(200, 200, 500)	3390 DASD tracks
PEMAX	9999	The SMP/E default is larger than what can be specified here

### 6.1.5 Unload the Sample JCL from the Product Tape

Sample installation jobs are provided on the distribution tape to help you install 390 Enablement. The following sample JCL will copy the 390 Enablement jobs from the tape. Add a job card and modify the parameters in boldface to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=A
//IN DD DSN=IBM.JDB551D.F1,UNIT=tunit,VOL=SER=DB551D,
// LABEL=(2,SL),DISP=(OLD,KEEP)
//OUT DD DSNAME=DSN510.INSTALL,
// DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=dunit,
```

```
//          DCB=*.STEP1.IN,SPACE=(8800,(15,5,5))
//SYSUT3   DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN    DD *
          COPY INDD=IN,OUTDD=OUT
/*
```

where **tunit** is the unit value matching the product tape or cartridge, **DSN610.INSTALL** is the name of the data set where the sample jobs will reside, **dasdvol** is the volume serial of the DASD device where the data set will reside, and **dunit** is the DASD unit type of the volume.

You can also access the sample installation jobs by performing an SMP/E RECEIVE for FMID fmid, and then copying the jobs from dataset **hlq.IBM.JDB551D.F1** to a work dataset for editing and submission.

### 6.1.6 Allocate SMP/E Target and Distribution Libraries

Edit and submit sample job **DSNEALC** to allocate the SMP/E target and distribution libraries for 390 Enablement. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** This job should complete with a condition code of 0.

### 6.1.7 Create DDDEF Entries

Edit and submit sample job **DSNEDDEF** to create DDDEF entries for the SMP/E target and distribution libraries for 390 Enablement. Consult the instructions in the sample job for more information.

Before you run this job, comment out DDDEF statements for entries that are already defined on our system. In particular, SCEELKED and CSSLIB DDDEF entries may already be defined.

**Expected Return Codes and Messages:** This job should complete with a condition code of 0.

### 6.1.8 Perform SMP/E RECEIVE

Edit and submit sample job **DSNRECV** to perform the SMP/E RECEIVE for 390 Enablement. Consult the instructions in the sample job for more information.

NOTE: if you obtained 390 Enablement as part of a CBPDO, you can use the RCVPDO job found in the CBPDO RIMLIB data set to RECEIVE the 390 Enablement FMIDs as well as any service, HOLDDATA, or preventive service planning (PSP) information included on the CBPDO tape. For more information, refer to the documentation included with the CBPDO.

**Expected Return Codes and Messages:** This job should complete with a condition code of 4 or less.

**Note:** If you are running a lower level of OS/390 Version 2 Release 7, your DSNRECV job will end with a return code of 4. The following warning message will be issued: **GIM50050W**.

## 6.1.9 RECEIVE the Cumulative Service Tape

NOTE: This step is bypassed if receiving the product from a CBPDO.

**Expected Return Codes and Messages:**

## 6.1.10 Perform SMP/E APPLY CHECK

Edit and submit sample job **DSNAPPLC** to perform an SMP/E APPLY CHECK for 390 Enablement. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the following on the APPLY CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of **ERRORS** and not of **WARNINGS** (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

The GROUPEXTEND operand indicates that SMP/E apply all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

**Expected Return Codes and Messages:** This job should complete with a condition code of 4 or less.

**Note:** If you are running a lower level of OS/390 Version 2 Release 7, your DSNAPPLC job will end with a return code of 4. The following warning message will be issued: **GIM50050W**.

The following three modules are used in JCLIN. These modules are owned by DB2 for OS/390 Version 5 of which 390 Enablement is a feature.

- DSNA A
- DSNALI
- DSNTIAR

## 6.1.11 Perform SMP/E APPLY

Edit and submit sample job **DSNAPPLY** to perform an SMP/E APPLY for 390 Enablement. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** This job should complete with a condition code of 4 or less.

**Note:** If you are running a lower level of OS/390 Version 2 Release 7, your DSNAPPLY job will end with a return code of 4. The following warning message will be issued: **GIM50050W**.

The following three modules are used in JCLIN. These modules are owned by DB2 for OS/390 Version 5 of which 390 Enablement is a feature.

- DSNA A
- DSNALI
- DSNTIAR

## 6.1.12 Perform SMP/E ACCEPT CHECK

Edit and submit sample job **DSNACCPC** to perform an SMP/E ACCEPT CHECK for 390 Enablement. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the following on the ACCEPT CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of **ERRORS** and not of **WARNINGS** (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

The GROUPEXTEND operand indicates that SMP/E accept all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

**Expected Return Codes and Messages:** This job should complete with a condition code of 4 or less.

**Note:** If you are running a lower level of OS/390 Version 2 Release 7, your DSNACCCK job will end with a return code of 4. The following warning message will be issued: **GIM50050W**.

## 6.1.13 Perform SMP/E ACCEPT

Edit and submit sample job **DSNACCPT** to perform an SMP/E ACCEPT for 390 Enablement. Consult the instructions in the sample job for more information.

Before using SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. This will cause entries produced from JCLIN to be saved in the distribution zone whenever a SYSMOD containing inline JCLIN is ACCEPTed. For more information on the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E manuals.

**Expected Return Codes and Messages:** This job should complete with a condition code of 4 or less.

**Note:** If you are running a lower level of OS/390 Version 2 Release 7, your DSNACCPT job will end with a return code of 4. The following warning message will be issued: **GIM50050W**.

If PTFs containing replacement modules are being ACCEPTed, SMP/E ACCEPT processing will linkedit/bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder may issue messages documenting unresolved external references, resulting in a return code of 4 from the ACCEPT step. These messages can be ignored, because the distribution libraries are not executable and the unresolved external references will not affect the executable system libraries.

---

## 6.2 Activating 390 Enablement

Before you can activate 390 Enablement, the functional requisites identified in 5.2.2.2, "Functional Requisites" on page 10, must first be installed on your system.

IBM DB2 Workstation Control Center provides support to help you manage DB2 databases on an array of operating systems in your workplace (see Figure 8). A set of stored procedures must be installed at each



DB2 for OS/390 subsystem that you want to work with using Control Center. 390 Enablement provides these stored procedures in the form of an SMP/E installable package. The FMID for the 390 Enablement feature of DB2 for OS/390 is JDB551D.

IBM provides two sample jobs for you to use to define the stored procedures that are needed by the workstation Control Center: DSNTIJCC and DSNTIJSG. When SMP/E applies the 390 Enablement installation package, DSNTIJCC is added to the DB2 target data set SDSNSAMP. Sample job DSNTIJSG is not shipped with 390 Enablement. It is part of the base feature of DB2 for OS/390 and is also a member of data set SDSNSAMP.

Run sample job DSNTIJSG to register and bind DB2 stored procedures DSNUTILS and DSNWZP to the DB2 system. These sample procedures are required by Control Center.

After you have run job DSNTIJSG, modify sample procedure DSNTIJCC to add a job card for your OS/390 system. Also, tailor it for your environment by updating the following strings with values that are correct for your installation:

**SYSTEM(DSN)**

Replace DSN with the DB2 subsystem identifier.

**PLAN(DSNTIA!!)**

Replace DSNTIA!! with the DSNTIAD plan name that was bound during installation by job SDSNSAMP(DSNTIJTM).

**LIBRARY(DSN!!0.RUNLIB.LOAD)**

Replace DSN!!0 with the user-defined prefix that was used during installation by DSNTINST CLIST.

**LIBRARY(DSN!!0.SDSNDBRM)**

Replace DSN!!0 with the user-defined prefix that was used during installation by DSNTINST CLIST.

Refer to Figure 16 on page 20 for an overview of the steps to follow to activate 390 Enablement.

Finally, run sample procedure DSNTIJCC to register the 390 Enablement stored procedures to your DB2 subsystem and to bind the packages required by these stored procedures to DB2.

Consult the *DB2 for OS/390 Installation Guide*, GC26-8970, for more information about the jobs that were run when DB2 was installed.

To run the 390 Enablement installation job, you must have a user ID with authorization to bind the application packages and to update the SYSIBM.SYSROUTINES catalog table. A user ID with SYSADM authorization satisfies this requirement.

After you run sample job DSNTIJCC, you must refresh the DB2 stored procedures address space for the changes to take affect. Use the START and STOP PROCEDURE(\*) DB2 commands to refresh the stored procedures address space.

## 6.2.1 Activate 390 Enablement Detail Steps

Figure 16. Detail of 390 Enablement Activation Steps

STEP	DESCRIPTION	JOB or COMMAND
1	Edit and run job to define DB2 stored procedures DSNUTILS and DSNWZP. DSNUTILS runs in a WLM-managed address space. For information about WLM, consult <i>MVS/ESA: Workload Management</i> . For information about configuring and using WLM to run DB2 stored procedures, consult <i>DB2 for OS/390 V5 Administration Guide</i> .	DSNTIJSG
2	Stop the WLM-established stored procedure address space: VARY WLM,APPLENV=<name>,QUIESCE where <name> is the name of the WLM application environment.	MVS Console Command
3	Start the WLM-established stored procedure address space: VARY WLM,APPLENV=<name>,RESUME where <name> is the name of the WLM application environment.	MVS Console Command
4	Edit and run job to define 390 Enablement DB2 stored procedures DSNACCMD, DSNACCMG, DSNACCAV, and DSNACCQC in the DB2-established stored procedure address space.	DSNTIJCC
5	Stop the DB2-established stored procedure address space: -STOP PROCEDURE(*)	DB2 Command
6	Start the DB2-established stored procedure address space: -START PROCEDURE(*)	DB2 Command

Perform the following Control Center tasks to verify setup of the 390 stored procedure environment for Control Center:

- Select an MVS subsystem and double-click on the buffer pool object. A list of buffer pools for the subsystem should appear in the list pane. If a buffer pool object is not present under the MVS subsystem object, Control Center has determined that the 390 Enablement stored procedures are not known to DB2. In this case, 390 Enablement is not installed and activated.
- Select an MVS subsystem and click once on the right mouse button. Choose the 'Locate' choice. From the Locate window, specify object type 'Indexes' and object state filter of 'Runstats recommended.' Select OK. You should get back a list of indexes for which Runstats is recommended. Select Help for more information.

- Select an MVS subsystem. Use the right mouse button to select 'Display Subsystem Parameters.' You should get back a list of install panels and corresponding parameters and values.
- Select Catalog Tables object. Use right mouse button to select Query. Use the dropdown to select 'Without Stospace Information.' Select OK.
- Expand Databases object. Expand database DSNDB06. Select Table Spaces object. Choose any table space and use the right mouse button to select 'Report...'. A valid report summary should be returned.

---

## Appendix A. 390 Enablement Install Logic

---

### A.1 SMP/E Modification Control Statements

The SMP/E Modification Control Statements (SMPMCS) for 390 Enablement are contained in the SMPMCS file on the installation tape. The SMPMCS for each FMID in the product will be loaded to the SMPPTS dataset, with a member name matching the FMID, when the FMID is SMP/E RECEIVED. You may browse or print these members using TSO/E, ISPF, or IEBGENER (or IEBTPCH).

---

### A.2 SMP/E JCLIN

The JCLIN for 390 Enablement is contained in the RELFILES on the installation tape. These files will be loaded to disk by SMP/E when the product is SMP/E RECEIVED. You may browse or print these files using TSO/E, ISPF, or IEBGENER (or IEBTPCH).

The files containing JCLIN are:

FMID JDB551D: DSN510.JDB551D.F1(JDB551D)

**Note:** The high-level qualifier is the qualifier specified as the DSPREFIX in the SMP/E OPTIONS. **DSN510** can be replaced by the qualifier of your choice.

# Reader's Comments

## Program Directory for 390 Enablement for Management Tools Package Version 05 Release 01, Modification Level 00

You may use this form to comment about this document, its organization, or subject matter with the understanding that IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

For each of the topics below please indicate your satisfaction level by circling your choice from the rating scale. If a statement does not apply, please circle N.

RATING SCALE						
very satisfied	<=====>				very dissatisfied	not applicable
1	2	3	4	5	N	

	Satisfaction					
Ease of product installation	1	2	3	4	5	N
Contents of program directory	1	2	3	4	5	N
Installation Verification Programs	1	2	3	4	5	N
Time to install the product	1	2	3	4	5	N
Readability and organization of program directory tasks	1	2	3	4	5	N
Necessity of all installation tasks	1	2	3	4	5	N
Accuracy of the definition of the installation tasks	1	2	3	4	5	N
Technical level of the installation tasks	1	2	3	4	5	N
Ease of getting the system into production after installation	1	2	3	4	5	N

How did you order this product?

- CBIPO
- CBPDO
- CustomPac
- ServerPac
- Independent
- Other

Is this the first time your organization has installed this product?

- Yes
- No

Were the people who did the installation experienced with the installation of MVS products?

\_\_\_ Yes  
\_\_\_ No

If yes, how many years? \_\_\_

If you have any comments to make about your ratings above, or any other aspect of the product installation, please list them below:

---

---

---

---

---

---

---

---

---

---

---

Please provide the following contact information:

---

Name and Job Title

---

Organization

---

Address

---

Telephone

Thank you for your participation.

Please send the completed form to (or give to your IBM representative who will forward it to the 390 Enablement for Management Tools Package Development group):

IBM Corporation  
Department W24/H348  
P.O. Box 49023  
San Jose, CA 95161-9945





Program Number: 5655-DB2 5801  
5802  
6112

Printed in U.S.A.

G110-8195-01

