



IBM Software

# Getting Started with IBM Backup and Restore Manager for z/VM

VMSES/E Installation, SFS Setup, and Initial Configuration

Tracy Dean, IBM  
July 2008

## Important Disclaimer

THE INFORMATION CONTAINED IN THIS PRESENTATION IS PROVIDED FOR INFORMATIONAL PURPOSES ONLY.

WHILE EFFORTS WERE MADE TO VERIFY THE COMPLETENESS AND ACCURACY OF THE INFORMATION CONTAINED IN THIS PRESENTATION, IT IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED.

IN ADDITION, THIS INFORMATION IS BASED ON IBM'S CURRENT PRODUCT PLANS AND STRATEGY, WHICH ARE SUBJECT TO CHANGE BY IBM WITHOUT NOTICE.

IBM SHALL NOT BE RESPONSIBLE FOR ANY DAMAGES ARISING OUT OF THE USE OF, OR OTHERWISE RELATED TO, THIS PRESENTATION OR ANY OTHER DOCUMENTATION.

NOTHING CONTAINED IN THIS PRESENTATION IS INTENDED TO, OR SHALL HAVE THE EFFECT OF:

- CREATING ANY WARRANTY OR REPRESENTATION FROM IBM (OR ITS AFFILIATES OR ITS OR THEIR SUPPLIERS AND/OR LICENSORS); OR
- ALTERING THE TERMS AND CONDITIONS OF THE APPLICABLE LICENSE AGREEMENT GOVERNING THE USE OF IBM SOFTWARE.

## Agenda

- **Assumptions**
- **Preparing to install**
- **Installing using VMSES/E**
- **Configuring**
- **Verifying installation and configuration**

# Assumptions

- **DIRMAINT is installed for directory management**
  - MAINT is authorized to issue AMDISK commands
  - AUTOG is available for group USER for minidisk definitions
- **Shared File System is available**
- **Installation ID is 5697J06B**
  - No PPF overrides
- **3390 DASD**
- **REXX Library (5695-014) is installed and available**
  - Alternatively use free download of REXX Alternate Library at:  
<http://www.ibm.com/software/awdtools/rexx/rexxzseries/altlibrary.html>
- **Installing from tape (not an envelope file)**
- **Installing on minidisk (not SFS)**
- **Operations Manager is running on user ID OPMGRM1**
- **This is not the only way to perform the install**
  - Not all options are discussed
  - See product documentation for full details



IBM Software

## Preparing to Install

Create installation ID

Create an SFS server

Prepare system for VMSES/E installation

## Where do I Start ???



- In the Program Directory ??



- In the Installation Guide ??



- Because we require SFS, we recommend you start with this presentation



## Define the Installation ID: 5697J06B

- **From MAINT**

- Create a file called 5697J06B DIRECT

```
USER 5697J06B password 64M 256M BG
* 5697-J06 - SES install & admin for Backup Mgr V1.2
MACHINE ESA
IPL CMS
OPTION LNKNOPAS
CONSOLE 01F 3215
SPOOL 00C 2540 READER A
SPOOL 00D 2540 PUNCH A
SPOOL 00E 1403 A
LINK MAINT 190 190 RR
LINK MAINT 19D 19D R
LINK MAINT 19E 19E RR
LINK MAINT 51D 51D MR
LINK MAINT 5E5 5E5 RR
```

- Issue the command


```
DIRM ADD 5697J06B
```

## Define the Installation ID: 5697J06B

- **Add required minidisks**

- From MAINT, issue

```
DIRM FOR 5697J06B AMD 191 3390 AUTOG 10 USER MR
DIRM FOR 5697J06B AMD 198 3390 AUTOG 2 USER MR
DIRM FOR 5697J06B AMD 199 3390 AUTOG 5 USER MR
DIRM FOR 5697J06B AMD 2A2 3390 AUTOG 1 USER MR
DIRM FOR 5697J06B AMD 2B2 3390 AUTOG 5 USER MR
DIRM FOR 5697J06B AMD 2C2 3390 AUTOG 2 USER MR
DIRM FOR 5697J06B AMD 2D2 3390 AUTOG 10 USER MR
DIRM FOR 5697J06B AMD 2A6 3390 AUTOG 1 USER MR
DIRM FOR 5697J06B AMD 491 3390 AUTOG 5 USER MR
DIRM FOR 5697J06B AMD 492 3390 AUTOG 5 USER MR
DIRM FOR 5697J06B AMD 591 3390 AUTOG 5 USER MR
DIRM FOR 5697J06B AMD 592 3390 AUTOG 5 USER MR
DIRM FOR 5697J06B AMD 49D 3390 AUTOG 5 USER MR
```





## Format All Minidisks

- **From MAINT, issue**

```
link 5697J06B 191 333 MR
```


```
format 333 z
```

```
release z (det
```

- **Repeat for each 5697J06B disk**

# Create New SFS Server and File Pool

## ■ Background

- Backup catalog is stored in SFS
  - Separate file pool dedicated to Backup is recommended
    - Should not use VMSYS: or VMSYSU:
    - We'll use **BKRSFS:** here, with **BKRSVSFS** as the server
- Recommend starting with at least 3000 cylinders
  - Large sites will need more
  - Your mileage may vary 
- Need space for service machine work areas also
  - We'll use BKRSFS: for this also
- BKRSVSFS is a repository file pool server
  - Does not perform Coordinated Resource Recovery (CRR)
- Reference: “CMS File Pool Planning, Administration, and Operation” (SC24-6074)

# Create New SFS Server: BKRSVSFS

- From MAINT, create and add directory entry for BKRSVSFS, using most of the sample values
  - Same procedure used to create user ID 5679J06B
  - Do not format the disks after you've added them

## BKRSVSFS DIRECT

```
USER BKRSVSFS password 64M 64M BG
OPTION MAXCONN 2000 NOMDCF5 APPLMON QUICKDSP SVMSTAT
SHARE REL 1500
MACHINE XC
IUCV ALLOW
IUCV *IDENT RESANY GLOBAL
IPL CMS
CONSOLE 009 3215 T OPMGRM1
SPOOL 00C 2540 READER *
SPOOL 00D 2540 PUNCH A
SPOOL 00E 1403
LINK MAINT 190 190 RR
LINK MAINT 193 193 RR
LINK MAINT 19D 19D RR
```

Make Ops Mgr the secondary console

## BKRSVSFS Directory Entry (continued)

- From MAINT, issue

DIRM FOR BKRSVSFS AMD 191 3390 AUTOG 2 USER W	Work disk
DIRM FOR BKRSVSFS AMD 250 3390 AUTOG 30 USER R PW readpw writepw	Control disk
DIRM FOR BKRSVSFS MINIOPT 250 NOMDC	
DIRM FOR BKRSVSFS AMD 405 3390 AUTOG 10 USER R PW readpw writepw	Repository log disks
DIRM FOR BKRSVSFS AMD 406 3390 AUTOG 10 USER R PW readpw writepw	
DIRM FOR BKRSVSFS MINIOPT 405 NOMDC	
DIRM FOR BKRSVSFS MINIOPT 406 NOMDC	
DIRM FOR BKRSVSFS AMD 260 3390 AUTOG 10 USER R PW readpw writepw	Initial catalog disk
DIRM FOR BKRSVSFS AMD 310 3390 AUTOG 750 USER R PW readpw writepw	User data disks
DIRM FOR BKRSVSFS AMD 311 3390 AUTOG 750 USER R PW readpw writepw	
DIRM FOR BKRSVSFS AMD 312 3390 AUTOG 750 USER R PW readpw writepw	
DIRM FOR BKRSVSFS AMD 313 3390 AUTOG 750 USER R PW readpw writepw	

## Initial SFS Server Setup: BKRSVSFS

- **Format 191 disk**

- From BKRSVSFS, issue

- ```
format 191 a
```

- **Create a PROFILE EXEC on the 191 disk, containing**

```
/* */  
'ACCESS 193 C'  
'CP SET EMSG ON'  
Exit 0
```

- **Run the PROFILE**

- profile

## Define Startup Parameters for SFS Server: BKRSVSFS

- **On BKRSVSFS 191 disk, create a file called BKRSVSFS DMSPARMS**

```
ADMIN 5697J06B
ADMIN BKRADMIN
ADMIN BKRBKUP
ADMIN BKRWRK01
ADMIN BKRWRK02
ADMIN BKRWRK03
ADMIN BKRWRK04
NOBACKUP
FILEPOOLID BKRSFS
NOCRR
NOLUNAME
SAVESEGID CMSFILES
USERS 700
```

## Generate the File Pool BKRSFS

- **From BKRSVSFS, issue**  
fileserv generate
- **When prompted in \$\$TEMP \$POOLDEF, enter**

```
MAXUSERS=1000
MAXDISKS=500
DDNAME=CONTROL          VDEV=250
DDNAME=LOG1             VDEV=405
DDNAME=LOG2             VDEV=406
DDNAME=MDK00001         VDEV=260 GROUP=1 BLOCKS=0
DDNAME=MDK00002         VDEV=310 GROUP=2 BLOCKS=0
DDNAME=MDK00003         VDEV=311 GROUP=2 BLOCKS=0
DDNAME=MDK00004         VDEV=312 GROUP=2 BLOCKS=0
DDNAME=MDK00005         VDEV=313 GROUP=2 BLOCKS=0
```

- **Then** FILE

## Final SFS Server Tasks for BKRSVSFS

- **Start the server**
  - From BKRSVSFS, issue

```
fileserv start
#cp disc
```



## Authorize Users and Create Directories in SFS

- **Authorize administrators and service machines**

- From 5697J06B, issue

```
enroll user bkradmin bkrsfs (blocks 4000 storgroup 2
enroll user bkrbkup bkrsfs (blocks 4000 storgroup 2
enroll user bkrcatlg bkrsfs (blocks 500000 storgroup 2
enroll user bkrwrk01 bkrsfs (blocks 20000 storgroup 2
enroll user bkrwrk02 bkrsfs (blocks 20000 storgroup 2
enroll user bkrwrk03 bkrsfs (blocks 20000 storgroup 2
enroll user bkrwrk04 bkrsfs (blocks 20000 storgroup 2
```

- **Create required directory entries**

- From 5697J06B, issue

```
create directory bkrsfs:bkradmin.workarea
create directory bkrsfs:bkrcatlg.workarea
create directory bkrsfs:bkrbkup.workarea
create directory bkrsfs:bkrwrk01.workarea
create directory bkrsfs:bkrwrk02.workarea
create directory bkrsfs:bkrwrk03.workarea
create directory bkrsfs:bkrwrk04.workarea
```

## Authorize Users and Create Directories in SFS

- Create required directory entries for service machines

- From 5697J06B, issue

```
enroll user bkradmin bkrsfs (blocks 4000 storgroup 2
enroll user bkrbkup bkrsfs (blocks 4000 storgroup 2
enroll user bkrcatlg bkrsfs (blocks 4000 storgroup 2
enroll user bkrwrk01 bkrsfs (blocks 4000 storgroup 2
enroll user bkrwrk02 bkrsfs (blocks 4000 storgroup 2
enroll user bkrwrk03 bkrsfs (blocks 4000 storgroup 2
enroll user bkrwrk04 bkrsfs (blocks 20000 storgroup 2
create directory bkrsfs:bkrcatlg.workarea
create directory bkrsfs:bkrwrk01.workarea
create directory bkrsfs:bkrwrk02.workarea
create directory bkrsfs:bkrwrk03.workarea
create directory bkrsfs:bkrwrk04.workarea
```

It's okay if these user  
IDs don't actually  
exist yet

## Take a Breath – New SFS Server is Set Up

If you've never set up SFS before,  
this is the hardest part of the product install

## Prepare for VMSES/E Installation

- **From 5697J06B**

- Mount installation tape at virtual address 181

- Link and access MAINT disks

```
link MAINT 5e5 5e5 rr
```

```
access 5e5 b
```

```
link MAINT 51d 51d mr
```

```
access 51d d
```

- Load product control files

```
vmfins install info (nomemo
```

- Obtain planning info

```
vmfins install ppf 5697J06B BKUPMGR (plan nomemo
```

- Review for errors

```
vmfview install
```

## Create Directory Entries for All Required Users

- **Use directory entry samples in 5697J06B PLANINFO**
  - Located on 5697J06B 191 disk
- **Follow steps outlined earlier for creating 5697J06B user ID to create directory entries for**
  - BKRADMIN
  - BKRCATLG
  - BKRBKUP
  - BKRWRK01
  - BKRWRK02
  - BKRWRK03
  - BKRWRK04

## Format All Minidisks

- **From 5697J06B, issue**

```
link BKRADMIN 191 333 MR
```

```
format 333 z
```

```
release z (det
```

- **Repeat for each disk**



IBM Software

## Installing using VMSES/E

## Initial VMSES/E Install

- **From 5697J06B**

- Create and run a PROFILE EXEC

```
xedit profile exec a
===> input /**/
===> input 'access 5e5 b'
===> input 'access 51d d'
===> input 'CP SET PF12 RETRIEVE'
===> file
profile
```

- Mount product tape at virtual address 181

- If not already done

- Load the product code to disk and install

```
vmfins install ppf 5697J06B BKUPMGR (nomemo nolink
```



## Initial VMSES/E Install (continued)

- Review for errors

```
vmfview install
```

- Update Build Status Table

```
vmfins build ppf 5697J06B BKUPMGR (serviced nolink
```

- Review for errors

```
vmfview install
```

## Where Code is Installed for Configuration and Testing

| <b>Disk on<br/>5697J06B</b> | <b>Description</b>                                                                                                                  |
|-----------------------------|-------------------------------------------------------------------------------------------------------------------------------------|
| <b>2C2</b>                  | <b>Sample files</b>                                                                                                                 |
| <b>491</b>                  | <b>Service machine executables for</b> <ul style="list-style-type: none"><li>-BKRBKUP</li><li>-BKRCATLG</li><li>-BKRWRKxx</li></ul> |
| <b>492</b>                  | <b>End user and administrator executables</b>                                                                                       |
| <b>198</b>                  | <b>Configuration files</b>                                                                                                          |
| <b>199</b>                  | <b>Backup job templates</b>                                                                                                         |
| <b>49D</b>                  | <b>Help files for test system</b>                                                                                                   |

## VMSES/E Installation is Complete

- **All code is installed from tape**
- **Standard install commands used by most z/VM products**
- **This was the easy part**



IBM Software

# Configuring

## Verify System Access Privileges for Backup Servers

| <b>User ID</b>   | <b>Privileges Required and <i>Recommended</i></b>                                                                                                                                                                                                                                                                                                                                                                                |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>BKRAADMIN</b> | <ul style="list-style-type: none"> <li>➤ <b>OPTION LNKNOPAS</b> (or equivalent, such as <b>RACF OPERATIONS</b>)</li> <li>➤ <b>Privilege Class G</b></li> <li>➤ <i>Privilege Class B (for CP MSGNOH)</i></li> </ul>                                                                                                                                                                                                               |
| <b>BKRBACKUP</b> | <ul style="list-style-type: none"> <li>➤ <b>OPTION LNKNOPAS</b> (or equivalent, such as <b>RACF OPERATIONS</b>)</li> <li>➤ <b>Privilege Class G</b></li> <li>➤ <b>Privilege Class A</b> (for CP FORCE)</li> <li>➤ <b>Privilege Class B</b> (CP MSGNOH)</li> <li>➤ <b>Privilege Class D</b> (CP PURGE)</li> </ul>                                                                                                                 |
| <b>BKRCATLG</b>  | <ul style="list-style-type: none"> <li>➤ <b>Privilege Class G</b></li> <li>➤ <b>Privilege Class B</b> (CP MSGNOH)</li> <li>➤ <i><b>OPTION LNKNOPAS</b> (or equivalent, such as <b>RACF OPERATIONS</b>) if backing up to disk</i></li> </ul>                                                                                                                                                                                      |
| <b>BKRWRKxx</b>  | <ul style="list-style-type: none"> <li>➤ <b>OPTION LNKNOPAS</b> (or equivalent, such as <b>RACF OPERATIONS</b>)</li> <li>➤ <b>Privilege Class G</b></li> <li>➤ <b>Privilege Class B</b> (for CP MSGNOH)</li> <li>➤ <i><b>OPTION DEVINFO</b> (if you have minidisks defined with DEVNO or &amp;SYSRES options)</i></li> <li>➤ <i><b>OPTION LNKSTABL</b> (if you want to link disks in STABLE mode during a backup)</i></li> </ul> |

## Create PROFILE EXECs for Test Service Machines

- **PROFILE EXEC for BKRADMIN**

- From 5697J06B

```
link bkradmin 191 291 mr
acc 291 z
acc 2c2 e
copy admprof sampexec e profile exec z
xedit profile exec z
```

- **Change**

```
'ACCESS' SFS_Pool':BKRADMIN.CONFIGURATION B/B'
'ACCESS' SFS_Pool':BKRADMIN.RUNTIME C/C'
'ACCESS' SFS_Pool':BKRADMIN.JOBDEFS E'
```

- **To**

```
'ACCESS 198 B/B'
'CP LINK 5697J06B 491 491 RR'
'ACCESS 491 C/C'
'ACCESS 199 E'
```

- **Change**

```
SFS_Pool = 'ROCKSFS1'
```

- **To**

```
SFS_Pool = 'BKRSFS'
```

- **Add**

```
'ACCESS 592 F' /* Access end user and admin routines */
```

```
file
```

## Create PROFILE EXECs for Test Service Machines

- **PROFILE EXEC for BKRCATLG**

- From 5697J06B

```
link bkrcatlg 191 292 mr
acc 292 z
acc 2c2 e
copy catprof sampexec e profile exec z
xedit profile exec z
```

- **Change**

```
'ACCESS' SFS_Pool':BKRADMIN.CONFIGURATION B/B'
'ACCESS' SFS_Pool':BKRADMIN.RUNTIME C/C'
```

- **To**

```
'ACCESS 198 B/B'
'CP LINK 5697J06B 491 491 RR'
'ACCESS 491 C/C'
```

- **Change**

```
'ACCESS ROCKSFS2:RVBCATLG.WORKAREA D (FORCERW'
```

- **To**

```
'ACCESS .WORKAREA D (FORCERW'
```

- **Change**

```
SFS_Pool = 'ROCKSFS1'
```

- **To**

```
SFS_Pool = 'BKRSFS'
```

```
file
```

## Create PROFILE EXECs for Test Service Machines

- **PROFILE EXEC for BKRBKUP**

- From 5697J06B

```
link bkrbkup 191 293 mr
acc 293 z
acc 2c2 e
copy mastprof sampexec e profile exec z
xedit profile exec z
```

- **Change**

```
'ACCESS' SFS_Pool':BKRADMIN.CONFIGURATION B/B'
'ACCESS' SFS_Pool':BKRADMIN.RUNTIME C/C'
'ACCESS' SFS_Pool':BKRADMIN.JOBDEFS E/E'
```

- **To**

```
'ACCESS 198 B/B'
'CP LINK 5697J06B 491 491 RR'
'ACCESS 491 C/C'
'ACCESS 199 E/E'
```

- **Change**

```
SFS_Pool = 'ROCKSFS1'
```

- **To**

```
SFS_Pool = 'BKRSFS'
```

file



## Create PROFILE EXECs for Test Service Machines

- **PROFILE EXEC for BKRWRK01**

- From 5697J06B

```
link bkrwrk01 191 294 mr
acc 294 z
acc 2c2 e
copy wrkprof sampexec e profile exec z
xedit profile exec z
```

- **Change**

```
'ACCESS' SFS_Pool':BKRADMIN.CONFIGURATION B/B'
'ACCESS' SFS_Pool':BKRADMIN.RUNTIME C/C'
```

- **To**

```
'ACCESS 198 B/B'
'CP LINK 5697J06B 491 491 RR'
'ACCESS 491 C/C'
```

- **Change**

```
SFS_Pool = 'ROCKSFS1'
```

- **To**

```
SFS_Pool = 'BKRSFS'
```

File

- **Repeat for BKRWRK02, BKRWRK03, and BKRWRK04**

## Define Special Users to Backup Manager

- **From 5697J06B**

```
access 198 z
```

```
access 2c2 e
```

```
copy bkrusers namesamp e = names z
```

```
xedit bkrusers names z
```

- Add additional administrators:
  - BKRBKUP
  - Others as required by your site
- Use defaults for other fields
- Copy BKRUSER NAMES to a shared disk for user and server access
  - E.g. MAINT 19E (Y disk) or 5697J06B 492

## Update the Configuration File: BKRSYSTEM CONFIG

- **From 5697J06B**

```
access 198 z
```

```
access 2c2 e
```

```
copy bkrsystem confsamp e = config z
```

```
xedit bkrsystem config z
```

## Update the Configuration File: BKRSYSTEM CONFIG

- **Choose local options for**

```
Local_SVM_Contact = System Administrator - sysadmin@some.corp.com
```

- Contact name displayed on service machines
- Not used for automated e-mails or messages

```
Template_MDISK_Buffer_Pages = 512
```

- Increase this value if you have more than 30,000 minidisks on the system

```
BKR_Allow_EDF_Target_Format = 0
```

- Change to 1 if you want Backup Manager to format unformatted minidisks on restore

```
CatalogPool = RS54QA02
```

- Change to BKRSFS

- **Copy BKRSYSTEM CONFIG to a shared disk**

- E.g. MAINT 19E (Y disk) or 5697J06B 492

## Complete SFS Configuration and Authorization

- **Create backup catalog structure in SFS**

- From 5697J06B, issue

```
acc 591 c
```

```
setupcat
```

- Issue all SFS CREATE DIRECTORY commands displayed by SETUPCAT

- **Give all users access to the catalog for restore requests**

- User access is limited to catalog directories for their own data

- From 5697J06B, issue

```
enroll public bkrsfs:
```

## Create Backup Job to Test

- **Use a shipped sample template as a model**

- From 5697J06B, issue

```
access 2c2 e
```

```
access 199 z
```

```
copy sampfull tempsamp e testfull template z
```

```
xedit testfull template z
```

## Customize the Backup Job: TESTFULL

- **Choose local options for**

```
CONFIG BKR_JOB_WORKERS = 1
```

- Increase the number of workers based on the number of items to backup

```
CONFIG BKR_JOB_NAME = SAMPFULL
```

- Change to TESTFULL

```
CONSOLE * Sample full backup generated
```

- Change “Sample full” to indicate name of backup job TESTFULL

```
CP_QUIET SPOOL CONSOLE CLOSE NAME SAMPFULL $$SDATE$$
```

- Change SAMPFULL to TESTFULL

- **Many other options available**

- See job statements and comments in SAMPFULL TEMPSAMP

# Customize the Backup Job: TESTFULL

- **Update INCLUDE and EXCLUDE statements**

- Delete or replace the following entries for Linux guests

```
EXCLUDE MINIDISK MACK0* = *  
INCLUDE MINIDISK MACK0* = 019*  
EXCLUDE MINIDISK R54TUX* = *  
INCLUDE MINIDISK R54TUX* = 019*
```

- Delete the following entries

```
EXCLUDE MINIDISK MAINT = 0123  
EXCLUDE MINIDISK MAINT = 0124  
INCLUDE MINIDISK MAINT = 012*  
INCLUDE SFS VMDEVU: * *
```

- Change the following to reflect BKRSVSFS instead of SAMPSFS

```
EXCLUDE MINIDISK SAMPSFS* = *  
INCLUDE MINIDISK SAMPSFS* = 019*
```

- Modify the following to exclude large minidisks

```
EXCLUDE MINIDISK * = * * * = * = * > 3300
```

- **FILE to save changes**



## Configuration is Complete

- **Now let's see if it actually works!**





IBM Software

# Verifying

# Start Backup Manager Service Machines

- **Start required Backup Manager servers**
  - From MAINT, issue

```
cp xautolog bkrcatlg
cp xautolog bkrbkup
```
- **Starting workers is recommended when product is first installed to verify configuration**
  - From MAINT, issue

```
cp xautolog bkrwrk01
```
  - Repeat for other workers
- **Starting workers (BKRWRKxx) is not required in general**
  - BKRBKUP will start them when needed
- **Verify servers are up and running**
  - From MAINT, issue

```
cp msg bkrbkup status
cp msg bkrwrk01 status
```
  - Repeat for other workers
- **Workers automatically logged off when idle timeout expires**

## Submit a Backup Job

- **Submit a job for review**

- From BKRADMIN, issue

```
msg bkrbkup review testfull
```

- Review files returned to BKRADMIN's reader

- TESTFULL LINKFAIL

- All errors linking to disks included in backup job

- TESTFULn JOB

- One file for each backup worker assigned

- All configuration statements with (most) variables resolved

- All DUMPxxx statements for data that would be backed up

- > xxx = CKD, EDF, SFS, FBA

## Submit a Backup Job

- **Submit a job and perform real backup**
  - From BKRADMIN, issue  

```
msg bkrbkup submit testfull
```
  - Review files returned to BKRADMIN's reader
  - Review consoles of BKRWRKxx servers
    - From BKRADMIN, issue  

```
GOMCMD OPMGRM1 VIEWCON USER(BKRWRKxx)
```

# Backup and Restore Manager is Up and Running



- **Major task is SFS setup**
  - Especially if you aren't familiar with SFS
- **VMSES/E install is straightforward**
- **Configuration is quick for initial testing**
  - Use the defaults for most things
  - Give all options some thought before production use
- **Use your in-house procedures to move it to production**

## References and More Information

- **Backup and Restore Manager for z/VM Web site**
  - <http://www.ibm.com/software/stormgmt/zvm/backup>
    - Publications
    - Pre-requisites
    - Announcements
    - Support
- **e-mail: Tracy Dean, [tld1@us.ibm.com](mailto:tld1@us.ibm.com)**
- **Publications**
  - CMS File Pool Planning, Administration, and Operation (SC24-6074)
  - Directory Maintenance Facility Commands Reference (SC24-6133)
  - Backup and Restore Manager for z/VM Program Directory (GI10-8662)
  - Backup and Restore Manager for z/VM Administration Guide (SC18-9346)
  - Backup and Restore Manager for z/VM User Guide (SC18-9523)