MQSeries® for OS/390®

System Management Guide

Version 2 Release 1

SC34-5374-01

MQSeries® for OS/390®

System Management Guide

Version 2 Release 1

SC34-5374-01

Note!

Before using this information and the product it supports, be sure to read the general information under Appendix G, “Notices” on page 509.

Second edition (August 1999)

This edition applies to MQSeries for OS/390 Version 2 Release 1 and to all subsequent releases and modifications until otherwise indicated in new editions.

This book is based on the *System Management Guide* for MQSeries for OS/390 Version 2.1, SC34-5374-00.

© **Copyright International Business Machines Corporation 1993,1999. All rights reserved.**
US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About this book . . . xv
Who this book is for . . . xv
How to use this book . . . xv
Conventions used in this book . . . xv
What you need to know to understand this book . . . xvi

What is new for this version . . . xvii
Changes for this edition of the book . . . xvii
Changes for the previous edition of the book . . . xviii

Part 1. Introduction . . . 1

Chapter 1. Introduction to MQSeries for OS/390 . . . 3
MQSeries and message queuing . . . 3
Messages and queues . . . 4
Objects and commands . . . 7
An overview of storage management . . . 15
Logs and recovery . . . 17
Events . . . 18
Managing MQSeries with commands and utilities . . . 19
MQSeries and other products . . . 22
Making MQSeries available . . . 27
CSA storage requirement . . . 28

Part 2. Customizing MQSeries after installation . . . 31

Chapter 2. Preparing for customization . . . 33
Installable features . . . 33
Libraries that exist after installation . . . 34

Chapter 3. Customizing the queue managers . . . 37
Introducing the customization tasks . . . 37
Task 1: Choose which language you want to use . . . 39
Task 2: Choose the distributed queuing facility . . . 40
Task 3: Define the MQSeries subsystem to OS/390 . . . 41
Task 4: Update the OS/390 link list . . . 46
Task 5: APF authorize the MQSeries load libraries . . . 47
Task 6: Update the OS/390 program properties table . . . 48
Task 7: Create procedures for the MQSeries subsystem . . . 49
Task 8: Create procedures for the channel initiator . . . 50
Task 9: Implement your ESM security controls . . . 51
Task 10: Customize the initialization input data sets . . . 52
Task 11: Create the bootstrap and log data sets . . . 61
Task 12: Define your page sets . . . 63
Task 13: Tailor your system parameter module . . . 68
Task 14: Tailor the channel initiator parameter module . . . 86
Task 15: Set up Batch, TSO, and RRS adapters . . . 92
Task 16: Set up the operations and control panels . . . 93
Task 17: Include the MQSeries dump formatting member . . . 95

© Copyright IBM Corp. 1993,1999

Task 18: Suppress information messages 96

Chapter 4. Migrating from previous versions of MQSeries for MVS/ESA . 97
Migrating from Version 1.2 to Version 2.1 97
Migrating from Version 1.1.4 to Version 2.1 101
Migrating from Version 1.1.3 to Version 2.1 101
Migrating from Version 1.1.2 or earlier to Version 2.1 103
Coexistence with earlier versions of MQSeries for MVS/ESA 103

Chapter 5. Testing your queue manager 105
Basic function testing 105
Testing for C, C++, COBOL, PL/I, and CICS 108
Testing for distributed queuing 108

Part 3. MQSeries and CICS 113

Chapter 6. The MQSeries-CICS adapter 115
CICS adapter overview 115
Adapter components 117
Other adapter features 118
CICS adapter performance considerations 121
CICS adapter conventions 123
Setting up the CICS adapter 124
Customizing the CICS adapter 128

Chapter 7. Operating the CICS adapter 129
Invoking the adapter's control functions 129
Preparing to use the CICS adapter 131
Accessing the CICS adapter control panels 132
Starting a connection 133
Stopping a connection 136
Modifying a connection 138
Displaying details of connections and CICS tasks 141
Starting an instance of the task initiator CKTI 142
Stopping an instance of CKTI 144
Displaying the current instances of CKTI 146
Displaying CICS task information 147
Purging tasks that are using the CICS adapter 149
Shutting down a connection between MQSeries and the CICS adapter . . . 150

Chapter 8. The MQSeries-CICS bridge 153
Introduction to the CICS bridge 153
Customizing the CICS bridge 158
Starting the CICS bridge 160
Shutting down the CICS bridge 161

Part 4. MQSeries and IMS 163

Chapter 9. The MQSeries-IMS adapter 165
Introduction to the IMS adapter 165
Setting up the IMS adapter 167

Chapter 10. Operating the IMS adapter 175
Controlling IMS connections 175
Connecting from the IMS control region 176
Displaying in-doubt units of recovery 178
Controlling IMS dependent region connections 180
Disconnecting from IMS 182
Controlling the IMS trigger monitor 183

Chapter 11. The MQSeries-IMS bridge 185
Introduction to the IMS bridge 185
Customizing the IMS bridge 187
Controlling the IMS bridge 188
Security 191

Part 5. Operating and administering MQSeries 193

Chapter 12. Operating MQSeries for OS/390 195
Issuing commands 195
Starting and stopping MQSeries 197
Using the operations and control panels 203

Chapter 13. Writing programs to administer MQSeries 217
Before you begin 217
Understanding how it all works 218
Using the command server 219
Preparing queues for administration programs 220
Sending commands to the command server 222
Putting messages on the system-command input queue 223
Retrieving replies to your commands 224
Interpreting the replies 226
If you do not receive a reply 232
Passing commands using MGCR or MGCRE 232

Chapter 14. Using the MQSeries utilities 233
How to read syntax diagrams 234
MQSeries utility program (CSQUTIL) 235
Page set management functions 237
MQSeries command management functions 244
Queue management functions 251
The change log inventory utility (CSQJU003) 262
The print log map utility (CSQJU004) 271
The log print utility (CSQ1LOGP) 272

Part 6. Backup, recovery, and restart 275

Chapter 15. Introducing some recovery concepts 279
How changes are made to data 279
How consistency is maintained 281

Chapter 16. Understanding termination and restart 285
What happens during termination 285
Connections and threads 286

Contents

What happens during restart and recovery . . . 287
How in-doubt units of recovery are resolved . . . 289
Recovering CICS units of recovery manually . . . 292
Recovering IMS units of recovery manually . . . 294
Recovering RRS units of recovery manually . . . 296
What happens when the CICS adapter restarts . . . 297
What happens when the IMS adapter restarts . . . 299
Using the OS/390 Automatic Restart Manager (ARM) . . . 300

Chapter 17. Understanding the log and the bootstrap data set . . . 305
What logs are . . . 305
How the log is structured . . . 307
How the logs are written . . . 308
What the bootstrap data set is for . . . 311
Managing the logs and BSDS . . . 312

Chapter 18. Planning for backup and recovery . . . 313
Introduction . . . 313
General tips for backup and recovery . . . 313
Planning your logging environment . . . 315
Planning your archive storage . . . 316
Other recovery considerations . . . 317

Chapter 19. Managing the logs and the bootstrap data set . . . 321
Archiving logs with the ARCHIVE LOG command . . . 321
Discarding archive log data sets . . . 323
Printing log records . . . 325
Finding out what the BSDS contains . . . 325
Changing the BSDS . . . 327
BSDS recovery . . . 330
Recovering logs . . . 332

Chapter 20. Managing page sets . . . 333
Adding a page set to a queue manager . . . 333
When one of your page sets becomes full . . . 333
How to balance loads on page sets . . . 335
How to reduce a page set . . . 338
Backing up and recovering page sets . . . 339
Backing up and restoring queues using CSQUTIL . . . 343

Chapter 21. Example recovery scenarios . . . 345
Active log problems . . . 346
Archive log problems . . . 353
BSDS errors . . . 356
Page set problems . . . 361
Dealing with long running units of work . . . 363
IMS-related problems . . . 364
Hardware errors . . . 366
Restarting if you have lost your log data sets . . . 367
Performing a cold start of MQSeries . . . 368

Part 7. Monitoring performance and resource usage 369

Chapter 22. Monitoring performance and resource usage 371
Getting snapshots of MQSeries 372
Using CICS adapter statistics 372
Investigating performance problems 372
Using System Management Facility 374
Using other products with MQSeries 375
Using MQSeries trace 376
Using MQSeries events 378

Chapter 23. Interpreting MQSeries performance statistics 379
SMF type 115 record layout 379
Message manager statistics 382
Data manager statistics 383
Buffer manager statistics 384
Log manager statistics 389
Sample SMF statistics records 391

Chapter 24. Interpreting MQSeries accounting data 395
SMF type 116 record layout 395
Message manager accounting 398
Sample SMF accounting record 400

Part 8. Security 401

Chapter 25. Introduction to MQSeries security 403
Why you need to protect MQSeries resources 403
Implementing MQSeries security 404
Resources you can protect 405

Chapter 26. Using RACF classes and profiles 409
Using RACF security classes 410
RACF profiles 411
Switch profiles 411
Profiles used to protect MQSeries resources 414
Profiles for command security 431
Profiles for command resource security 432
Using the RESLEVEL security profile 435
User IDs for security checking 440
Auditing considerations 447

Chapter 27. MQSeries security implementation 449
Security implementation checklist 449
MQSeries security management 451
Customizing security 454
Security considerations for using MQSeries with CICS 455
Security considerations for using MQSeries with IMS 459
Security considerations for distributed queuing 463
Security considerations for cluster support 465
Security installation tasks 466
Example security scenario 468

Security problem determination 474

Part 9. Appendixes 477

Appendix A. Macros intended for customer use 479
General-use programming interface macros 479
General-use programming interface copy files 480
Product-sensitive programming interface macros 481
General-use programming interface include files 481

Appendix B. Using OTMA exits in IMS 483
Exit names 483
A sample scenario 483

Appendix C. Upgrading and applying service to TCP/IP, Language Environment, or OS/390 Callable Services 487
Running a REPORT CALLLIBS job 488

Appendix D. Enabling distributed queuing using CICS ISC 491
Defining MQSeries programs and data sets as CICS resources 491
Defining the channel definitions 492
Defining the CKMQ transient data queue 493
Defining MQSeries queues, triggers, and processes 493
Defining CICS resources used by distributed queuing 493
Defining access security 494
Setting up communications 494
Security considerations for distributed queuing (using CICS ISC) 494

Appendix E. Defining your queue manager environment parameters . . 497
Log data set definitions 497
Page set definitions 499
Buffer pool definitions 503

Appendix F. New messages and codes 505

Appendix G. Notices 509
Programming interface information 511
Trademarks 512

Part 10. Glossary and index 513

Glossary of terms and abbreviations 515

MQSeries publications 527
MQSeries information available on the Internet 530
Related publications 531

Index 533

Figures

1. Representation of an MQSeries message . . . 5
2. MQSeries for OS/390 overview . . . 9
3. Mapping queues to page sets through storage classes . . . 16
4. Buffers, buffer pools, and page sets . . . 18
5. Sample IEFSSNss statements for defining subsystems . . . 42
6. PPT additional entries needed for MQSeries . . . 48
7. Example job for migrating queue objects . . . 100
8. RACF commands for CSQ4IVP1 . . . 106
9. RACF commands for CSQ4IVPX . . . 110
10. Example output from CSQ4IVPX . . . 111
11. How CICS, the CICS adapter, and an MQSeries subsystem are related 117
12. JCL fragment for upgrading the CICS CSD . . . 125
13. Sample PLT for use with the CICS adapter . . . 126
14. Sample INITPARM statement to set the default connection values for CICS . . . 126
15. Linking to the adapter connect program, CSQCQCON, from a PLT program . . . 128
16. Padding adapter commands . . . 130
17. Starting a queue manager that is identified by the CPF '+cpf' . . . 131
18. The CICS adapter control initial panel . . . 132
19. Starting a connection . . . 133
20. Starting a connection from the command line . . . 134
21. Starting a connection from the command line specifying parameters . . 134
22. Specifying lowercase queue names . . . 134
23. Linking to the adapter connect program, CSQCQCON, from a CICS program . . . 135
24. Stopping a connection from the CKQC initial panel . . . 136
25. Stopping a connection from the command line—a quiesced shutdown 137
26. Stopping a connection from the command line—a forced shutdown . . 137
27. Stopping a connection from a CICS application program—a quiesced shutdown . . . 137
28. Stopping a connection from a CICS application program—a forced shutdown . . . 137
29. Modifying a connection . . . 138
30. Format of command to modify connection parameters from the command line . . . 139
31. Resetting connection statistics from the command line . . . 139
32. Changing the adapter's trace number and disabling the API-crossing exit from the command line . . . 139
33. Format of the MODIFY command issued from a CICS adapter application program . . . 140
34. Resetting connection statistics from a CICS program . . . 140
35. Linking to the adapter reset program, CSQCRST, from a CICS program 140
36. The display connection panel . . . 141
37. Starting an instance of CKTI . . . 142
38. Starting an instance of CKTI—for the default initiation queue . . . 143
39. Starting an instance of CKTI—for a specified initiation queue . . . 143
40. Linking to the adapter task-initiator program CSQCSSQ from CICS . . 143
41. Linking to the adapter task-initiator program CSQCSSQ from CICS . . 143
42. Stopping an instance of the task initiator CKTI . . . 144

Figures

43. Stopping an instance of CKTI from the command line—for the default initiation queue . . . 144
44. Stopping an instance of CKTI from the command line—for a specified initiation queue . . . 145
45. Stopping an instance of CKTI from a program—for the default initiation queue from CICS . . . 145
46. Stopping an instance of CKTI from a program—for a specified initiation queue from CICS . . . 145
47. The CKQC Display CKTI panel . . . 146
48. The CKQC Display Task panel . . . 147
49. Message showing the status of a connection . . . 148
50. Displaying the status of a connection . . . 148
51. Linking to the adapter program CSQCDSPL from a CICS program . . . 148
52. Components and data flow to run a CICS DPL program . . . 154
53. Components and data flow to run a CICS 3270 transaction . . . 156
54. Sample JCL to link-edit the dynamic call stub . . . 168
55. CSQQDEFX macro syntax . . . 171
56. Layout of a subsystem definition table . . . 172
57. Example CSQQTAPL transaction definition for CSQQTRMN . . . 173
58. Example CSQQTPSB PSB definition for CSQQTRMN . . . 173
59. The MQSeries-IMS bridge . . . 186
60. Issuing a DISPLAY command from the OS/390 console . . . 196
61. Starting the MQSeries subsystem from an OS/390 console . . . 198
62. MQSeries startup messages for subsystem CSQ1 . . . 199
63. Stopping MQSeries . . . 201
64. The MQSeries operations and control initial panel . . . 208
65. Listing queues . . . 209
66. Defining a local queue - first panel . . . 210
67. Defining a local queue - second panel . . . 211
68. Defining a local queue - trigger conditions . . . 211
69. Defining a local queue - event control . . . 212
70. Defining a local queue - backout reporting . . . 212
71. Specifying the queue manager that a utility is to work with . . . 235
72. Sample JCL for the FORMAT function of CSQUTIL . . . 238
73. Sample JCL showing the use of the COPYPAGE function . . . 240
74. Sample JCL showing the use of the RESETPAGE function . . . 242
75. Sample JCL for issuing MQSeries commands using CSQUTIL . . . 246
76. Sample JCL for using the MAKEDEF option of the COMMAND function 246
77. Sample JCL for using the MAKECLNT option of the COMMAND function 247
78. Sample JCL for the SDEFS function of CSQUTIL . . . 249
79. Sample JCL for the CSQUTIL COPY functions . . . 253
80. Sample JCL for the CSQUTIL SCOPY functions . . . 256
81. Sample JCL for the CSQUTIL EMPTY function . . . 258
82. Sample JCL for the CSQUTIL LOAD function . . . 260
83. Sample JCL to invoke the CSQJU003 utility . . . 262
84. Sample JCL to invoke the CSQJU004 utility . . . 271
85. Sample JCL to invoke the CSQ1LOGP utility using a BSDS . . . 272
86. Sample JCL to invoke the CSQ1LOGP utility using active log data sets 273
87. Sample JCL to invoke the CSQ1LOGP utility using archive logs . . . 273
88. A unit of recovery within an application program . . . 279
89. A unit of recovery showing back out . . . 280
90. The two-phase commit process . . . 282
91. Example restart messages . . . 298
92. Sample ARM policy . . . 301

93. The logging process 308
94. The off-loading process 309
95. Sample input statements for CSQJU003 320
96. Extract from a load balancing job 337
97. Part of an SMF record showing the header and self-defining sections . 380
98. SMF record 115, subtype 1 392
99. SMF record 115, subtype 2 393
100. Part of an SMF record showing the header and self-defining sections . 396
101. SMF record 116 400
102. Sample output from RACFRW showing RESLEVEL general audit records 448
103. Typical output from the MQSeries command DISPLAY SECURITY . . 454
104. Example security scenario 468
105. OTMA pre-routing exit assembler sample 484
106. Sample assembler DRU exit 486
| 107. Example SMP/E JOBCARD job step 489
| 108. Example SMP/E REPORT CALLLIBS job 489
109. Adding the distributed queuing definitions to the CICS CSD 492
110. Adding a DD statement to the CICS startup procedure 492

Tables

1. Summary of MQSeries administrator commands . . . 19
2. System control commands . . . 20
3. Suggested test and production definitions for JCL region sizes . . . 29
4. MQSeries libraries that exist after installation . . . 34
5. National language feature libraries . . . 39
6. Subsystem name to CPF associations . . . 42
7. Example of CPF subset and superset rules . . . 43
8. Valid character set for CPF strings . . . 43
9. Suggested test and production definitions for log and bootstrap data sets 62
10. Default values of CSQ6SYSP parameters . . . 69
11. Default values of CSQ6LOGP parameters . . . 76
12. Default values of CSQ6ARVP parameters . . . 79
13. Default values of CSQ6CHIP parameters . . . 87
14. TCP/IP settings . . . 90
15. Shutting down a CICS adapter connection . . . 150
16. SSM specifications options . . . 171
17. Valid operations and control panels actions for MQSeries objects . . . 205
18. A summary of MQSeries utilities . . . 233
19. How to read syntax diagrams . . . 234
20. Termination using QUIESCE, FORCE, and RESTART . . . 285
21. Example recovery scenarios . . . 345
22. SMF record header description . . . 379
23. Offsets to self-defining sections . . . 381
24. Structure of the message manager statistics record QMST . . . 382
25. Structure of the data manager statistics record QIST . . . 383
26. Structure of the buffer manager statistics record QPST . . . 384
27. Structure of the log manager statistics record QJST . . . 389
28. Problem symptoms that can be examined using log manager statistics 390
29. SMF record header description . . . 395
30. Offsets to self-defining sections . . . 397
31. Structure of the message manager accounting record QWHS . . . 398
32. Structure of the message manager accounting record QMAC . . . 398
33. Structure of the thread cross reference record for a CICS system . . . 399
34. Structure of the thread cross reference record for an IMS system . . . 400
35. RACF classes used by MQSeries . . . 410
36. Switch profiles . . . 412
37. Access levels for queue security . . . 416
38. Access levels for close options on permanent dynamic queues . . . 420
39. RACF authority to the dead-letter queue and its alias . . . 422
40. Access levels for process security . . . 424
41. Access levels for namelist security . . . 424
42. Access levels for alternate user security . . . 425
43. Access levels for context security . . . 427
44. MQOPEN, MQPUT1, and MQCLOSE options and the security authorization required . . . 429
45. Commands, profiles, and their access levels . . . 433
46. Checks made at different RACF access levels for the Batch/TSO adapter 438
47. Checks made at different RACF access levels for the CICS adapter . . . 438
48. Checks made at different RACF access levels for the IMS adapter . . . 439

49. Checks made at different RACF access levels for channel initiator connections . . . 439
50. User ID checking for Batch/TSO-type user IDs . . . 441
51. User ID checking for CICS-type user IDs . . . 442
52. User ID checking for IMS-type user IDs . . . 442
53. How the second user ID is determined for the IMS adapter . . . 442
54. User IDs checked for TCP/IP channels . . . 443
55. User IDs checked for LU 6.2 channels . . . 444
56. User IDs checked for LU 6.2 and TCP/IP server-connection channels . 445
57. CICS bridge monitor security . . . 457
58. CICS bridge task security . . . 458
59. RACF access to data sets associated with a queue manager . . . 467
60. RACF access to data sets associated with distributed queuing . . . 467
61. Security profiles for the example scenario . . . 470
62. Sample security profiles for the batch application on queue manager QM1 . . . 471
63. Sample security profiles for queue manager QM2 using TCP . . . 472
64. Sample security profiles for queue manager QM2 using LU 6.2 . . . 472
65. Sample security profiles for the CICS application on queue manager QM1 . . . 473
66. Service has been applied or the product has been upgraded to a new release . . . 487
67. One of the products has been updated to a new release in a new SMP/E environment and libraries . . . 487
68. Suggested test and production definitions for buffer pool settings . . . 503

Tables

About this book

MQSeries for OS/390 (referred to in this book as MQSeries) is part of the IBM MQSeries family of products. It provides application programming services that allow a new style of programming. This style enables you to code indirect program-to-program communication using *message queues*. MQSeries is an OS/390 *message-queue manager*.

MQSeries is an independent OS/390 subsystem using OS/390 cross-memory services, the CICS® task-related user exit product interface, and the IMS™ External Subsystem Attach Facility (ESAF). MQSeries supports application programs that can be run in:

- CICS
- MVS batch
- MVS/TSO
- IMS

Who this book is for

This book is intended for system programmers, system administrators, and system operators. It explains how to customize, operate, administer, and monitor MQSeries.

How to use this book

This book takes you through the steps required to make MQSeries available to application programmers. Read those sections that relate to your task, whether it be installing adapters, tuning, or communication.

The latter part of the book deals with termination, recovery, and restart. Read these sections when you need to perform such tasks.

Conventions used in this book

- Throughout this book, the term *object* refers to any MQSeries queue manager, queue, namelist, channel, storage class, or process.
- In the examples in this book, the string `+cpf` has been used to show the command prefix (CPF), and the commands are shown in UPPERCASE.
- CICS means both CICS Transaction Server for OS/390 and CICS for MVS/ESA unless otherwise stated. IMS means IMS/ESA® unless otherwise stated.
- Throughout this book, the default value `thlqual` is used to indicate the target library high-level qualifier for MQSeries data sets in your installation.
- Throughout this book, the term *distributed queuing* refers to the distributed queuing feature (also known as the “non-CICS mover”). The term *distributed queuing using CICS ISC* is used to refer to the optional CICS distributed queuing feature (also known as the “CICS mover”).

© Copyright IBM Corp. 1993,1999

What you need to know to understand this book

This book assumes you are familiar with the basic concepts of:

- CICS
- IMS
- OS/390 job control language (JCL)
- OS/390 Time Sharing Option (TSO)

If you want to write programs to administer MQSeries, this book assumes that you can write programs in one of the supported languages:

- COBOL
- C
- C++
- Assembler
- PL/I

You do not need to have written message-queuing programs previously.

What is new for this version

This is the second edition of this book for MQSeries for OS/390 Version 2.1.

Changes for this edition of the book

Some new functions have been added to MQSeries for OS/390 Version 2.1. If you want to use these functions you need to apply the APARs mentioned in this manual.

Changes for this edition of the book are marked with vertical bars in the left-hand margin. The following items have been changed:

- Information about restart and recovery scenarios has been added, and the existing information expanded (APAR PQ28083).
- Information about dealing with long-running units of work at restart has been added (APAR PQ27752).
- Information about messages issued to warn about long-running units of work has been added (APAR PQ28093).
- The RESETPAGE function of CSQUTIL has been changed (APAR PQ24994).
- Information about suggested settings for system parameters for both test and production systems has been added.
- Information about running a REPORT CALLLIBS job has been added.
- The STARTRBA parameter has been removed from the CRESTART function of CSQUTIL.
- The instructions for creating a point of recovery have been clarified.
- Information about a new method for adding a subsystem name has been added.
- Information about the KEYLIST TSO command has been added.
- Information about restarting with the OS/390 Automatic Restart Manager (ARM) when using TCP/IP has been added.
- Information about buffer pool statistics has been added.
- Information about the API-crossing exit has been clarified.
- Information about primary space allocation for DASD data sets has been clarified.
- The instructions for collecting SMF data have been clarified.
- Information about RACF profile names for the IMS bridge has been clarified.
- Some new error messages and codes have been included in this book.
- Minor editorial and organizational changes have been incorporated.

© Copyright IBM Corp. 1993,1999

Changes for the previous edition of the book

- The minimum levels for many of the items of software required to use MQSeries for OS/390 have changed. These are described in the *MQSeries Planning Guide*.
- There are several changes to the installation process, and some new libraries. These are described in the *MQSeries for OS/390 Program Directory*.
- The OS/390 Automatic Restart Manager (ARM) is now supported. This is described in "Using the OS/390 Automatic Restart Manager (ARM)" on page 300.
- MQSeries now supports clustering. This is described in the *MQSeries Queue Manager Clusters* manual.
- MQSeries now supports C++. This is described in the *MQSeries Using C++* manual.
- MQSeries Batch and TSO applications can now participate in 2-phase commit protocols with other RRS-enabled products, coordinated by OS/390 Resource Recovery Services (RRS). This is described in "Task 15: Set up Batch, TSO, and RRS adapters" on page 92.
- There are new system parameters in CSQZPARM (EXITLIM, EXITTCB, and WLMTIME) and channel initiator parameters in CSQXPARM (TCPTYPE, LU62ARM, and LSTRTMR). If you do not use the supplied default parameter modules, consider whether you need to use these new parameters, and change and link-edit your parameter modules again accordingly.
- If you are using TCP/IP for distributed queuing, you can now use the OpenEdition® sockets interface. This is described "Task 2: Choose the distributed queuing facility" on page 40.
- The CICS bridge is now incorporated into MQSeries for OS/390. This is described in "Introduction to the CICS bridge" on page 153.
- MQSeries can now be used in conjunction with the OS/390 Workload Manager. This is described in "MQSeries, the Workload Manager, and Workflow" on page 26.
- The operations and control panels have been extended and reorganized to accommodate the new clustering function. The panels can now also be used for the security commands. A number of actions have been consolidated into a new PERFORM action. This is described in "Using the operations and control panels" on page 203.
- The supplied default for storage class SYSTEM has been changed to page set 01, so that messages are not put on page set 00. This is described in "Migrating from Version 1.2 to Version 2.1" on page 97.
- The supplied sample input initialization data sets have been reorganized and renamed. This is described in "Task 10: Customize the initialization input data sets" on page 52.
- New code pages are supported for data conversion, including those with the Euro currency symbol. These are described in the *MQSeries Application Programming Reference* manual.

Part 1. Introduction

Chapter 1. Introduction to MQSeries for OS/390 . . . 3
MQSeries and message queuing . . . 3
Time-independent applications . . . 3
Event-driven processing . . . 4
Data integrity and resource protection . . . 4
Application environments . . . 4
Messages and queues . . . 4
What messages are . . . 4
What queues are . . . 5
Objects and commands . . . 7
Object names . . . 7
MQSeries queue managers . . . 8
MQSeries queues . . . 9
Specific local queues used by MQSeries . . . 10
Namelists . . . 13
Channels . . . 13
Process definitions . . . 14
Storage classes . . . 14
An overview of storage management . . . 15
Page sets . . . 15
Storage classes - mapping queues to page sets . . . 15
Page set zero . . . 16
Buffers and buffer pools . . . 17
Logs and recovery . . . 17
Bootstrap data set (BSDS) . . . 18
Events . . . 18
Managing MQSeries with commands and utilities . . . 19
Issuing commands . . . 19
Administrator commands . . . 19
System control commands . . . 20
Utilities . . . 21
Operations and control panels . . . 22
MQSeries and other products . . . 22
Address spaces . . . 22
MQSeries and OS/390 Batch and TSO . . . 22
MQSeries and CICS . . . 24
MQSeries and IMS . . . 25
MQSeries and security . . . 26
MQSeries and SMS . . . 26
MQSeries and ARM . . . 26
MQSeries, the Workload Manager, and Workflow . . . 26
Making MQSeries available . . . 27
Customizing MQSeries and its adapters . . . 27
Operating MQSeries . . . 27
Administering MQSeries . . . 28
Tuning MQSeries . . . 28
Preparing for recovery . . . 28
CSA storage requirement . . . 28
Private region storage usage . . . 29

© Copyright IBM Corp. 1993,1999

Chapter 1. Introduction to MQSeries for OS/390

This chapter introduces IBM MQSeries for OS/390[1] from an administrator's perspective and describes:

- The basic concepts of MQSeries and messaging.
- The system-specific things you need to know.
- An outline of the facilities MQSeries for OS/390 provides for system management and administration.
- The relationship between MQSeries and other products.

It contains these sections:

- "MQSeries and message queuing"
- "Messages and queues" on page 4
- "Objects and commands" on page 7
- "An overview of storage management" on page 15
- "Logs and recovery" on page 17
- "Events" on page 18
- "Managing MQSeries with commands and utilities" on page 19
- "MQSeries and other products" on page 22
- "Making MQSeries available" on page 27
- "CSA storage requirement" on page 28

MQSeries and message queuing

MQSeries for OS/390 lets OS/390 applications use message queuing to participate in message-driven processing. With message-driven processing, applications can communicate across different platforms by using the appropriate message queuing software products. For example, OS/390 and OS/400® applications can communicate through MQSeries for OS/390 and MQSeries for AS/400 respectively.

MQSeries products implement a common application programming interface (Message Queue Interface or MQI) whatever platform the applications run on. The calls made by the applications and the messages they exchange are common.

Time-independent applications

With message queuing, the exchange of messages between the sending and receiving programs is time independent. This means that the sending and receiving applications are decoupled so that the sender can continue processing without having to wait for the receiver to acknowledge the receipt of the message.

[1] In the rest of this book, where the context allows, this is referred to simply as MQSeries.

© Copyright IBM Corp. 1993,1999

Event-driven processing

Applications can be started by messages arriving on a queue and, if necessary, terminated when the message or messages have been processed.

Data integrity and resource protection

MQSeries applications can transfer data with an extremely high degree of confidence. Message delivery can involve a *syncpoint* mechanism. This allows for the recovery of important data—using MQSeries logs—if the system fails.

All MQSeries resources, including MQSeries commands, messages, and queues, can be protected using an external security manager such as Resource Access Control Facility (RACF®) (also known as the OS/390 Security Server).

Application environments

With MQSeries for OS/390 you can create applications in these environments:

- An OS/390 Batch and TSO environment
- A CICS transaction environment
- An IMS transaction environment

Applications (or transactions) connect to MQSeries through an *adapter*. There are three types of adapter; one for each of these environments.

Messages and queues

Messages and queues are the basic components of any queuing system.

What messages are

A *message* is a string of bytes that has meaning to the applications that use the message. Messages are used for transferring information from one application to another (or different parts of the same application). The applications can be running in the same environment, or in a different environment. They can be running on the same platform, or on a different platform.

In MQSeries, messages have two parts; the *application data* and a *message descriptor*. The content and structure of the application data is defined by the application programs that use them. The message descriptor identifies the message and contains other control information, such as the message length, the type of message, and the priority assigned to the message by the sending application.

The format of the message descriptor is defined by MQSeries. For a complete description of the message descriptor, see the *MQSeries Application Programming Reference* manual. Figure 1 on page 5 represents an MQSeries message that is logically divided into message descriptor and application data.



Figure 1. Representation of an MQSeries message. The message descriptor and application data are shown as separate parts. Information that is specific to the application, such as the Account name in this example, is in the application data part of the message.

All applications that participate in message queuing use messages that conform to this common specification. In MQSeries, there are four types of message:

Datagram A simple message for which no reply is expected.

Request A message for which a reply is expected.

Reply A reply to a request message.

Report A message that describes an event, such as the occurrence of an error.

The message type is part of the message descriptor. For more information, see the *MQSeries Application Programming Reference* manual.

Message lengths

In MQSeries for OS/390, the maximum message length is 4 MB (megabytes). In practice, the message length might be limited by:

- The maximum message length defined for the receiving queue.
- The maximum message length defined for the queue manager.
- The maximum message length defined by the applications, when one of the applications is operating in a non-OS/390 platform.
- The amount of storage available for the message.

It might take several messages to send all the information that an application requires.

What queues are

A queue is a data structure that is used to store messages until they are retrieved by an application.

In MQSeries there are three types of queues that hold messages, as defined by the DEFTYPE attribute in the queue definition. These are:

- Predefined
- Permanent dynamic
- Temporary dynamic

Predefined queues are created by the MQSeries command DEFINE QLOCAL. Dynamic queues are created by applications making an **MQOPEN** call against a model queue. (Model queues are described “Using queue objects” on page 10.) Permanent queues, that is, predefined queues and permanent dynamic queues, exist independently of the applications that use them and survive MQSeries

restarts. Temporary dynamic queues are deleted when the application that created them is stopped, or if MQSeries is stopped.

Queues can exist in main storage, but might be paged out to DASD depending on the usage of that queue. If a queue must be kept for recovery purposes, it is written to DASD. This means that if it needs to be recovered it can be retrieved from DASD.

Each queue belongs to a *queue manager*, which is responsible for maintaining it. The queue manager puts the messages it receives on the appropriate queues.

Applications send and receive messages using MQI calls. For example, to put a message on a queue, the queue is opened for 'puts' by the sending application making an **MQOPEN** call. Then, the application issues an **MQPUT** call to put the message onto that queue. The receiving application must open the same queue for 'gets'. It then issues an **MQGET** to retrieve a message from the queue.

In MQSeries, messages can be retrieved from a queue by suitably authorized applications according to these retrieval algorithms:

- First-in-first-out (FIFO).
- Message priority, as defined in the message descriptor. Messages having the same priority are retrieved on a FIFO basis.
- A program request for a specific message.

Queues can be local or remote. MQSeries for OS/390 can send your messages to queues on another queue manager using its distributed queuing facility. Distributed queuing involves communications links called channels between the queue manager systems; communications can be handled by any of the following:

- TCP/IP
- APPC/MVS (LU 6.2)
- CICS
- SNS/TCPaccess

You can group queue managers in a cluster. Queue managers within the cluster can make the queues that they host available to the whole cluster. Using clusters enables you to:

- Simplify your system administration
- Increase the availability of your queues
- Distribute workload among your queue managers

This is described in the *MQSeries Queue Manager Clusters* manual.

Objects and commands

Many of the tasks described in this book involve manipulating MQSeries *objects*. These objects are common across the different platforms, although some implementations might support a subset of the types listed here.

In MQSeries for OS/390, there are six different types of object:

1. Channels

   (Note that if you are using CICS for distributed queuing, channels are not objects, and cannot be manipulated using MQSeries commands.)

2. Queues, subdivided into:

   - Local queues
   - Remote queues
   - Alias queues
   - Model queues
   - Cluster queues

3. Queue managers
4. Namelists
5. Process definitions
6. Storage classes

These objects can be manipulated by the MQSeries commands described in the *MQSeries Command Reference* manual. For example, the MQSeries command DEFINE QLOCAL, with the appropriate attributes, defines a local queue object. This means that if you issue this command, and the command is successful, you create a new queue. Depending on the attributes provided on the queue definition, applications can then open this queue for putting and getting messages.

Object names

Each queue manager is identified by a unique subsystem name. This name is associated with a *command prefix* string (CPF). See “Using command prefix strings” on page 42. Depending on the task you are performing, a queue manager might be identified by its subsystem name or by its CPF. (For example, you use the CPF if you are entering commands at the OS/390 console, and you use the subsystem name when you are using the operations and control panels.)

For the other types of objects, each object has a name associated with it and can be referenced in MQSeries commands by that name. In general, names must be unique within each of these object types. For example, you can have a queue and a process with the same name, but you cannot have two queues with the same name. This means that you cannot have a local queue with the same name as a model queue, a remote queue, or an alias queue. There are a few exceptions to this rule; these are described where they arise.

MQSeries queue managers

Each MQSeries instance is a queue manager. It is the queue manager that provides queuing services to applications that are connected to it through an adapter. For example, the application can be a CICS transaction, which is connected to the MQSeries queue manager by the CICS adapter.

Figure 2 on page 9 shows two queue managers with applications connected through adapters. The queue manager manages the queues that are local to it, and ensures that outgoing messages are routed correctly. *Distributed queuing* is the part of MQSeries that handles communications with other queue managers. (MQSeries applications can also access CICS and IMS applications directly through bridges; these are introduced in "MQSeries and other products" on page 22.)

A queue is a *local queue* if it is managed by the same queue manager that is connected to the application. If the queue is managed by a different queue manager, it is called a *remote queue*. In Figure 2 on page 9 queues A1 and A2 are local queues for applications 1, 2, and 3. However, for applications 4, 5, and 6, they are remote queues.

Queue manager objects

A queue manager provides queuing services to applications and commands to administrators, but it is also an MQSeries object in its own right. Because it is an object, a queue manager can be used in both MQI calls and MQSeries commands.

MQI calls: A queue manager object can be used in some MQI calls. For example, you can inquire about the attributes of the queue manager object using the MQI call **MQINQ**. However, you cannot put messages on a queue manager object using an **MQPUT** call. Messages are always put to queue objects, not to queue manager objects. See the *MQSeries Application Programming Reference* manual for further details of the MQI calls that can be used with a queue manager object.

MQSeries commands: The queue manager object has attributes, which can be displayed using the MQSeries command DISPLAY QMGR. Some of these attributes can be changed using the ALTER QMGR command. However, unlike the other MQSeries objects, there are no commands to define or delete the queue manager object. Once a queue manager is installed and customized, it is always in existence.

For more information, see Chapter 3, "Customizing the queue managers" on page 37 and "Managing MQSeries with commands and utilities" on page 19.



Figure 2. MQSeries for OS/390 overview

MQSeries queues

Queues are defined to MQSeries using the appropriate DEFINE commands for queues. For example, you use the DEFINE QLOCAL command to define a local queue. These commands specify the attributes of the queue being defined. For example, a local queue object has attributes that specify what happens when applications reference that queue in MQI calls. Some of the things that the attributes of a queue determine are:

- Whether applications can retrieve messages from the queue (get enabled).
- Whether applications can put messages on the queue (put enabled).
- Whether access to the queue is exclusive to one application or shared between applications.
- The maximum number of messages that can be stored on the queue at the same time (maximum queue depth).
- The maximum length of messages that can be put on the queue.

This list is only a subset; for full details about queue attributes and the commands for defining and manipulating queue objects, see the *MQSeries Command Reference* manual.

Using queue objects

In MQSeries, there are five types of queue object. Each type of object can be manipulated by MQSeries commands and is associated with real queues in different ways:

1. A *local queue* object identifies a local queue belonging to the queue manager to which the application is connected. Messages always end up on a queue that is a local queue on the destination queue manager.
2. A *remote queue* object identifies a queue belonging to another queue manager. This queue, therefore, must be defined as a local queue to the remote queue manager. The information you specify when you define a remote queue object allows the queue manager to find the remote queue manager, so that any messages destined for the remote queue go to the correct queue manager.
3. An *alias queue* object lets applications access a queue by referring to it indirectly in MQI calls. When an alias queue name is used in an MQI call, the name is resolved to the name of either a local or a remote queue at run time. This lets you to change the queues that applications use without changing the application in any way—you merely change the alias queue definition to reflect the name of the new queue that the alias resolves to.
4. A *model queue* object defines a set of queue attributes that are used as a template for creating a dynamic queue. Dynamic queues are created by the queue manager when an application makes an **MQOPEN** request specifying a queue name that is the name of a model queue. The dynamic queue that is created in this way is a local queue whose attributes are taken from the model queue definition. The dynamic queue name can be specified by the application or, if the application does not specify one, the queue manager generates a unique name, starting "CSQ." and returns it to the application.

   Dynamic queues defined in this way can be *temporary queues*, which do not survive MQSeries restarts, or *permanent queues*, which do.
5. A *cluster queue* object represents a queue, defined on this queue manager or elsewhere in the network, that is in a cluster. MQSeries clusters are described in the *MQSeries Queue Manager Clusters* manual.

Use the appropriate DEFINE command to create one of these types of queue objects. These commands are described in the *MQSeries Command Reference* manual. You can also use the default queue objects supplied with MQSeries as the basis of your definitions. These defaults are described in "CSQ4INSG system object sample" on page 55.

Specific local queues used by MQSeries

MQSeries uses some local queues for specific purposes related to its operation. These queues must be defined before MQSeries can use them.

The MQSeries administrator is responsible for defining and maintaining all queues using the information in this book and the *MQSeries Command Reference* manual.

Initiation queues

An *initiation queue* receives *trigger messages*; these show that trigger events have occurred. Typically, a trigger event occurs when a message is put on a queue so that the trigger conditions for that queue are met. For example, the trigger conditions could be that a trigger event occurs when the number of messages on the queue reaches a predefined depth. The trigger event causes the queue manager to put a trigger message onto the initiation queue for that queue. This trigger message is retrieved from the initiation queue by a trigger monitor application. The trigger monitor then starts up the application program that was specified in the trigger message.

If a queue manager is to use triggering, at least one initiation queue must be defined for that queue manager.

Transmission queues

A *transmission queue* temporarily stores messages that are destined for a remote queue manager. You must define at least one transmission queue for each remote queue manager to which the local queue manager is to send messages directly, unless you are using queue manager clusters. In this case, you only need to define one transmission queue to handle messages for all destinations. For details about the use of transmission queues in distributed queuing, see the *MQSeries Intercommunication* manual.

Channel queues

Channels are objects used in distributed queuing to define how communication between queue managers takes place. The following local queues are required to support channels for distributed queuing:

- A *channel initiation queue* is needed to send commands to channels. This queue must be called `SYSTEM.CHANNEL.INITQ`.
- A *channel synchronization queue* is used for sequential message numbering for handling unit of work information when MQSeries subsystems are communicating. Each queue manager needs the channel synchronization queue if it is to receive or send messages to another queue manager (regardless of the number of other queue managers involved). This queue must be called `SYSTEM.CHANNEL.SYNCQ`.
- A *channel reply information queue* is needed to handle replies from channel commands. This queue must be called `SYSTEM.CHANNEL.REPLY.INFO`.

Different local queues are required if you are using CICS ISC for distributed queuing. These are described in Appendix D, “Enabling distributed queuing using CICS ISC” on page 491.

Cluster support queues

The following local queues are required to support clustering:

- A local queue is needed to hold a persistent copy of the repository. (The repository is a collection of information about the queue managers that are members of the cluster, held on some of the queue managers in the cluster and replicated on the other queue managers.) This queue is called `SYSTEM.CLUSTER.REPOSITORY.QUEUE`.
- A local queue is needed to communicate repository changes between queue managers. This queue is used for information about updates to the repository

data to be applied to the local repository, or requests for repository data. This queue is called SYSTEM.CLUSTER.COMMAND.QUEUE.

- A local queue is needed as the transmission queue for all destinations in the cluster. This queue is called SYSTEM.CLUSTER.TRANSMIT.QUEUE.

For information about MQSeries clusters, see the *MQSeries Queue Manager Clusters* manual.

Dead-letter queue

A *dead-letter queue* receives messages that cannot be routed to their correct destinations. This occurs when, for example:

- The destination queue is full
- Message puts have been inhibited on the destination queue
- The sender is not authorized to use the destination queue
- The destination queue does not exist

For distributed queuing, it is strongly recommended that you define a dead-letter queue for each queue manager involved. If you do not do this, a channel will close if MQSeries is unable to deliver a message, and distributed queuing will stop.

System-command input queue

The *system-command input queue* (SYSTEM.COMMAND.INPUT) is a local queue to which suitably authorized applications can send MQSeries commands. These commands are then retrieved by an MQSeries component called the command server. The command server validates the commands and passes the valid ones on for processing by the MQSeries command processor. See also “Using the command server” on page 219.

A system-command input queue must be defined for each queue manager.

The supplied default model queue SYSTEM.COMMAND.REPLY.MODEL is used by the CSQUTIL utility, the distributed queuing features, and the MQSeries operations and control panels. The operations and control panels use dynamic queues generated from this model queue to receive replies to MQSeries commands. These replies can then be viewed by users from the operations and control panels. The dynamic queue names are of the form SYSTEM.CSQUTIL.*, SYSTEM.CSQXCMD.*, and SYSTEM.CSQOREXX.* respectively.

Event queues

An *event queue* is a local or remote queue used to hold event messages. Event messages are generated by the queue manager to help you monitor your system.

The following event queues are required:

- SYSTEM.ADMIN.QMGR to hold messages about queue manager events
- SYSTEM.ADMIN.PERFM.EVENT to hold messages about performance events
- SYSTEM.ADMIN.CHANNEL.EVENT to hold messages about channel events

For information about MQSeries events, see “Events” on page 18.

System default queues

The *system default queues* are a set of queue definitions supplied with MQSeries. You can copy and rename any of these queue definitions for use in applications at your installation.

For example, to define a local queue, you can copy the supplied default SYSTEM.DEFAULT.LOCAL.QUEUE, change its name, and then alter any of its other attributes, as required.

Namelists

A *namelist* is an MQSeries object that contains a list of other MQSeries objects. Namelists are maintained independently of applications, that is, they can be updated without stopping any of the applications that use them.

Use the DEFINE NAMELIST command to create a new namelist. You can also use the default namelist object, SYSTEM.DEFAULT.NAMELIST (supplied with MQSeries) as the basis of your own definitions. System default objects are described in "CSQ4INSG system object sample" on page 55.

Channels

A channel provides a communication path. There are two types of channel, message channels and MQI channels.

A *message channel* provides a communication path between two queue managers. The message channel is used for the transmission of messages from one queue manager to another, and shields the application programs from the complexities of the underlying networking protocols.

A message channel can transmit messages in one direction only. If two-way communication is required between two queue managers, two message channels are required.

In order to set up a channel, you usually define one channel definition for each end of the channel. There are six types of message channel: Sender, Server, Receiver, Requester, Cluster-sender and Cluster-receiver.

An *MQI channel* connects an MQSeries client to a queue manager on a server machine. It is for the transfer of MQI calls and responses only and is bidirectional. A channel definition exists for each end of the link. There are two types of MQI channel: Server-connection and Client-connection.

For distributed queuing (without CICS ISC), channels are MQSeries objects. Use the DEFINE CHANNEL command to create a new channel. You can also use the default channel objects (supplied with MQSeries for OS/390) as the basis of your own definitions. This is described in "CSQ4INSX system object sample" on page 56. If you are using clustering, most channels are created automatically.

For distributed queuing using CICS ISC, channels are maintained by a CICS transaction called CKMC.

Process definitions

A *process definition object* defines an application that is to be started in response to a trigger event on an MQSeries queue manager. In MQSeries, an application retrieves messages from one or more specified queues and processes them. An application can be any of the following types:

- CICS transactions
- IMS transactions
- TSO or batch programs

This definition includes the application ID, the application type, and data specific to the application.

Use the DEFINE PROCESS command to create a process definition. You can also use the default process definition object, `SYSTEM.DEFAULT.PROCESS` (supplied with MQSeries) as the basis of your own definitions. System default objects are described in "CSQ4INSG system object sample" on page 55.

Trigger monitors and task initiators

A *trigger monitor* is an application that monitors an initiation queue associated with a queue manager (see "Initiation queues" on page 11). When a trigger message arrives on the initiation queue, it is retrieved by the trigger monitor. Typically, the trigger monitor then starts an application that is specified in the message on the initiation queue.

MQSeries supplies trigger monitors for use in the following environments:

CICS This is referred to in this book as the CICS *task initiator* transaction, CKTI. See "Task initiator" on page 119 for a description of this transaction and Chapter 7, "Operating the CICS adapter" on page 129 for how to use it.

IMS This is referred to in this book as the IMS transaction CSQQTRMN. See "The IMS trigger monitor" on page 166 for a description of this transaction and Chapter 10, "Operating the IMS adapter" on page 175 for how to use it.

Storage classes

See "Storage classes - mapping queues to page sets" on page 15 for information about storage classes.

An overview of storage management

In MQSeries for OS/390, storage management involves using these entities:

- Page sets
- Storage classes
- Buffer pools

Page sets

A *page set* is a linear VSAM data set that has been specially formatted to be used in MQSeries. Page sets are used to store messages and object definitions. Each page set is identified by a page set identifier (PSID), an integer in the range 00 through 99. MQSeries uses page set zero (PSID=00) to store object definitions and other important information relevant to the queue manager subsystem.

Each queue manager must have its own page sets including a page set zero.

Page sets must be formatted and so MQSeries provides a FORMAT utility for this, see “Formatting page sets (FORMAT)” on page 237. Page sets must also be defined to the MQSeries subsystem, see “Task 12: Define your page sets” on page 63.

If you define secondary extents for your page sets, MQSeries for OS/390 expands a page set dynamically if it becomes full. MQSeries continues to expand the page set if required until 123 logical extents exist, provided that there is sufficient disk storage space available.

Note: You cannot use page sets from one MQSeries subsystem on a different MQSeries subsystem, or change the subsystem name. If you want to transfer the data from one subsystem to another, you must unload all the objects and messages from the first subsystem and reload them onto another.

Storage classes - mapping queues to page sets

Storage classes allow you to control where message data is stored for administrative, data set space and load management, or application isolation purposes.

A *storage class* maps one or more queues to a page set. This means that messages for that queue are stored (subject to buffering) on that page set. This is how it works:

- You define a storage class, using the DEFINE STGCLASS command, specifying a page set identifier (PSID).
- When you define a queue, you can specify a storage class in the STGCLASS attribute.

In the following example, the local queue QE5 is mapped to page set 21 through storage class ARC2.

```
DEFINE STGCLASS(ARC2) PSID(21)
DEFINE QLOCAL(QE5) STGCLASS(ARC2)
```

This means that messages that are put on the queue QE5 are stored on page set 21 (if they stay on the queue long enough to be written to DASD).



Figure 3. Mapping queues to page sets through storage classes

More than one queue can use the same storage class and you can define as many storage classes as you like. For example, you can extend the previous example to include more storage class and queue definitions, as follows:

```
DEFINE STGCLASS(ARC1) PSID(05)
DEFINE STGCLASS(ARC2) PSID(21)
DEFINE STGCLASS(MAXI) PSID(05)
DEFINE QLOCAL(QE1) STGCLASS(ARC1) ...
DEFINE QLOCAL(QE2) STGCLASS(ARC1) ...
DEFINE QLOCAL(QE3) STGCLASS(MAXI) ...
DEFINE QLOCAL(QE4) STGCLASS(ARC2) ...
DEFINE QLOCAL(QE5) STGCLASS(ARC2) ...
```

In Figure 3, both storage classes ARC1 and MAXI are associated with page set 05. Therefore, the queues QE1, QE2, and QE3 are mapped to page set 05. Similarly, storage class ARC2 associates queues QE4 and QE5 with page set 21.

If you define a queue without specifying a storage class, MQSeries uses the default storage class.

Page set zero

Page set zero is used to store all the object definitions required by the queue manager. For normal operation of MQSeries, it is essential that page set zero does not become full. For performance reasons, it is best not to have object definitions and messages on the same page set. Therefore, we recommend that you do not define storage classes that map to page set zero. If you do, you run the risk of filling page set zero if too many messages accumulate there. This would mean that any MQSeries facility that uses the system-command input queue, for example, the operations and control panels, would fail. Also, applications would be unable to create permanent dynamic queues.

Buffers and buffer pools

For efficiency, MQSeries uses a form of caching whereby messages (and object definitions) are stored temporarily in buffers before being stored in page sets on DASD. Short-lived messages, that is, messages that are retrieved from a queue shortly after they are received, might only ever be stored in the buffers. However, this is all transparent to the user because the buffers are controlled by a buffer manager, which is a component of MQSeries.

The buffers are organized into *buffer pools*. You can define up to four buffer pools (0 through 3) for each MQSeries subsystem; you are recommended to use four buffer pools. Each buffer is 4 KB long. The maximum number of buffers is determined by the amount of storage available in the MQSeries address space, although you should not use more than about 70% of the space for buffers. Usually, the more buffers you have, the more efficient the buffering and the better the performance of the MQSeries subsystem.

Figure 4 on page 18 shows the relationship between messages, buffers, buffer pools, and page sets. A buffer pool is associated with one or more page sets; each page set is associated with a single buffer pool.

You specify the number of buffers in a pool with the DEFINE BUFFPOOL command. For details of this command, see the *MQSeries Command Reference* manual.

For performance reasons, messages and object definitions should not be in the same buffer pool. You are recommended therefore to use one buffer pool (say number zero) exclusively for page set zero, where the object definitions are kept, and for the page set containing performance critical system message queues such as SYSTEM.CHANNEL.SYNCQ and SYSTEM.CLUSTER.* queues. No other message queues should map to this page set.

Similarly, short-lived messages and long-lived messages should be kept in different buffer pools and therefore on different page sets, and in different queues.

For more information about setting up buffer pools, see Appendix E, “Defining your queue manager environment parameters” on page 497.

Logs and recovery

MQSeries records all persistent messages, object definitions, and significant events as they occur in one of a cycle of log data sets. When this *active log* is full, MQSeries switches the active log to the next data set, and copies the contents of the full log to an *archive log*, which can be a data set on a direct access storage device (DASD) or magnetic tape. If there is a subsystem problem, MQSeries uses these log entries to restore itself to a consistent state. In particular, persistent messages can be recovered over MQSeries subsystem restarts. For greater assurance against, for example, DASD failure, MQSeries supports dual logging for both the active and the archive logs.

For a complete description of logs, their contents, and archiving, see Chapter 17, “Understanding the log and the bootstrap data set” on page 305.



Figure 4. Buffers, buffer pools, and page sets

Bootstrap data set (BSDS)

The *bootstrap data set* (BSDS) is a VSAM key-sequenced data set (KSDS) that holds information required by MQSeries for recovery. It contains an inventory of all active and archived log data sets known to MQSeries and a *wrap-around inventory* of all recent MQSeries activity, which is needed if MQSeries has to be restarted. MQSeries also supports dual BSDSs.

For a complete description of the functions and uses of the BSDS, see “What the bootstrap data set is for” on page 311.

Events

MQSeries events provide information about errors, warnings, and other significant occurrences in a queue manager. By incorporating these events into your own system management application, you can monitor the activities across many queue managers, for multiple MQSeries applications. In particular, you can monitor all the queue managers in your system from a single queue manager.

Events can be reported through a user-written reporting mechanism to an administration application that supports the presentation of the events to an operator. Events also enable applications acting as agents for other administration networks, for example NetView®, to monitor reports and create the appropriate alerts.

For more information about using events, see the *MQSeries Programmable System Management* manual.

Managing MQSeries with commands and utilities

MQSeries provides a set of commands and a set of utilities to help you to manage MQSeries at your installation.

This section gives an overview of the following:

- Issuing commands
- Administrator commands
- System control commands
- Utilities
- Operations and control panels

For more information on all MQSeries commands, including the command syntax, see the *MQSeries Command Reference* manual.

Issuing commands

The commands can be issued from:

- The initialization input data sets (see page 52)
- The OS/390 console (see page 196)
- The system-command input queue (see page 217)
- The COMMAND function of the CSQUTIL utility (see page 235)
- The operations and control panels (see page 203)

For more information, see “Issuing commands” on page 195.

Administrator commands

You use the administrator commands to manage these MQSeries objects:

- Channels (for distributed queuing without CICS ISC)
- Namelists
- Processes
- Queues
- Queue managers
- Storage classes

For each of these types of objects you can use these types of commands:

Command type	***Purpose***
ALTER	Changes an existing object definition
DEFINE	Defines the attributes of an object and creates the object (not the queue manager)
DISPLAY	Displays the attributes of an object
DELETE	Deletes an object definition (not the queue manager)

Table 1 shows the administrator commands that are available.

Table 1 (Page 1 of 2). Summary of MQSeries administrator commands

	ALTER	**DEFINE**	**DISPLAY**	**DELETE**
CHANNEL	√	√	√	√
NAMELIST	√	√	√	√
PROCESS	√	√	√	√

Table 1 (Page 2 of 2). Summary of MQSeries administrator commands				
	ALTER	**DEFINE**	**DISPLAY**	**DELETE**
QALIAS	√	√	√	√
QCLUSTER			√	
QLOCAL	√	√	√	√
QMGR	√		√	
QMODEL	√	√	√	√
QREMOTE	√	√	√	√
QUEUE			√	
STGCLASS	√	√	√	√

System control commands

You can use the system control commands to manage entities specific to MQSeries for OS/390, such as page sets and buffer pools. Table 2 summarizes the MQSeries system control commands.

Table 2 (Page 1 of 2). System control commands		
This command...	**Deals with...**	**For these tasks...**
ARCHIVE LOG	Logs	Copying the current active log to an archive log.
DEFINE BUFFPOOL	Buffer pools	Defining a buffer pool and the number of 4 KB buffers it contains.
DEFINE MAXSMSGS DISPLAY MAXSMSGS	Messages	Defining the maximum number of messages that a task can get or put within a single unit of recovery.
DEFINE PSID	Page sets	Defining a page set and an associated buffer pool.
DISPLAY THREAD	Threads	Displaying information about a thread.
DISPLAY USAGE	Page sets	Displaying the current state of a page set.
RECOVER BSDS	BSDS	Re-establishing a dual bootstrap data set that had a data set error.
REFRESH SECURITY RVERIFY SECURITY ALTER SECURITY DISPLAY SECURITY	Security	Performing tasks associated with security, for example, refresh security if you change security profiles; changing and displaying security options.
RESOLVE INDOUBT	Threads	Resolving in-doubt threads.
START CMDSERV STOP CMDSERV DISPLAY CMDSERV	Command server	Starting or stopping the command server, displaying command server attributes.
START TRACE STOP TRACE ALTER TRACE DISPLAY TRACE	Traces	Starting or stopping MQSeries traces, changing and displaying trace parameters.

Table 2 (Page 2 of 2). System control commands

This command...	Deals with...	For these tasks...
START QMGR STOP QMGR SUSPEND QMGR RESUME QMGR	Queue managers	Starting and stopping queue managers, joining and leaving clusters.
START CHANNEL STOP CHANNEL PING CHANNEL RESET CHANNEL RESOLVE CHANNEL DISPLAY CHSTATUS	Channels	Starting and stopping channels, testing a channel, resetting channel sequence numbers, resolving in-doubt messages, and displaying channel status.
START CHINIT STOP CHINIT DISPLAY DQM	Channel initiators	Starting and stopping channel initiators, display information about channel initiators.
START LISTENER STOP LISTENER	Channel listeners	Starting and stopping channel listeners.
RESET TPIPE	IMS transaction pipes (Tpipe)	Resetting sequence numbers for an IMS Tpipe.
DISPLAY CLUSQMGR	Queue managers	Displaying cluster information about queue managers in a cluster.
REFRESH CLUSTER RESET CLUSTER	Clusters	Refreshing locally-held cluster information, performing special cluster operations.

Utilities

MQSeries also provides the following utilities to help you perform other administrative and management tasks:

- MQSeries utility program, CSQUTIL; you can use this utility for:
  - Managing page sets
  - Issuing system administrator and system control commands from an OS/390 batch program
  - Managing queues
- Data conversion exit utility program, CSQUCVX
- Change log inventory program, CSQJU003, for modifying the bootstrap data set
- Print log map utility, CSQJU004, for listing information about the log
- Log print utility, CSQ1LOGP, for printing the log

The MQSeries utilities are described in Chapter 14, “Using the MQSeries utilities” on page 233.

Operations and control panels

MQSeries provides a set of operations and control panels that enable you to manage MQSeries objects interactively. The panels use the Interactive System Productivity Facility (ISPF).

The operations and control panels are available in the following national languages:

- US English (mixed case)
- US English (uppercase)
- Japanese
- Simplified Chinese

depending on which language feature you have installed.

Both the Time Sharing Option/Extensions (TSO/E) and the Interactive Systems Productivity Facility (ISPF) are required if you want to use the operations and control panels supplied with MQSeries.

For more details about the operations and control panels and how they are used, see “Using the operations and control panels” on page 203.

MQSeries and other products

This section describes some of the other products you can use with MQSeries and how these products are used.

MQSeries operates as a formal subsystem of OS/390. MQSeries connects to the application environments through *adapters*. Adapters are provided for each of these environments:

- Batch and TSO
- CICS
- IMS

Address spaces

There is one MQSeries address space and there are *allied address spaces* for each environment in which the applications run.

Each TSO user, each batch program, and each IMS program has its own allied address space. For the CICS adapter, there is one CICS address space and that is for the CICS region (not for individual CICS programs).

MQSeries and OS/390 Batch and TSO

The Batch/TSO adapters are the interface between OS/390 application programs running under JES, TSO, or OS/390 OpenEdition and an MQSeries subsystem. They enable OS/390 application programs to use the MQI.

The adapters provide access to MQSeries resources for programs running in:

- Task (TCB) mode
- Problem or supervisor state
- Non-cross-memory mode
- Non-access register mode

Connections between application programs and MQSeries are at the task level. The adapters provide a connection thread from an application task control block (TCB) to MQSeries.

The Batch/TSO adapter supports a single-phase commit protocol for changes made to resources owned by MQSeries. It does not support multi-phase commit protocols. The RRS adapter enables MQSeries applications to participate in two-phase commit protocols with other RRS-enabled products, coordinated by OS/390 Resource Recovery Services (RRS).

The adapters use the OS/390 STIMERM service to schedule an asynchronous event every second. This event runs an interrupt request block (IRB) that does not involve any waiting by the batch application's task. This IRB checks to see if the MQSeries termination ECB has been posted. If the termination ECB has been posted, the IRB posts any application ECBs that are waiting on an event in the MQSeries subsystem (for example, a signal or a wait).

The MQSeries-Batch/TSO adapter

The MQSeries Batch/TSO adapter provides MQSeries support for OS/390 Batch and TSO applications. All application programs that run under OS/390 Batch or TSO must have the stub CSQBSTUB link-edited with them. The stub provides the application with access to all MQI calls. You use single-phase commit and backout for applications by issuing the MQI calls **MQCMIT** and **MQBACK**.

For information about building application programs that use the Batch/TSO adapter, see the *MQSeries Application Programming Reference* manual.

The MQSeries-Batch/TSO RRS adapter

Resource Recovery Services (RRS) is a subcomponent of OS/390 that provides a system-wide service for coordinating two-phase commit across OS/390 products. The MQSeries Batch/TSO RRS adapter (the RRS adapter) provides MQSeries support for OS/390 Batch and TSO applications that want to use these services. The RRS adapter enables MQSeries to become a full participant in RRS coordination. Applications can participate in two-phase commit processing with other products that support RRS (for example, DB2®).

The RRS adapter provides two stubs; application programs that want to use RRS must be link-edited with one of these stubs.

- CSQBRSTB allows you to use two-phase commit and backout for applications by using the RRS callable resource recovery services instead of the MQI calls **MQCMIT** and **MQBACK**. The callable resource recovery services of RRS are described in the *MVS Programming: Callable Services for High Level Languages* manual. You must also link-edit module ATRSCSS from library SYS1.CSSLIB with your application. If you use the MQI calls **MQCMIT** and **MQBACK**, you will receive return code `MQRC_ENVIRONMENT_ERROR`.
- CSQBRSSI allows you to use MQI calls **MQCMIT** and **MQBACK**; MQSeries actually implements these calls as the **SRRCMIT** and **SRRBACK** RRS calls.

For information about building application programs that use the RRS adapter, see the *MQSeries Application Programming Reference* manual.

MQSeries and CICS

The MQSeries-supplied CICS adapter gives you access to MQSeries from CICS. You can start and stop CICS and MQSeries independently, and you can establish or terminate a connection between them at any time. You can also allow CICS to connect to MQSeries automatically.

The CICS adapters use the CICS task-related user exit (TRUE) facility. This facility is described in the *CICS Customization Guide*.

In a CICS multiregion operation or intersystem communication (ISC) environment, each CICS address space can have its own attachment to the queue manager subsystem. A single CICS address space can be connected to only one queue manager at a time. However, multiple CICS address spaces can connect to the same MQSeries subsystem.

The CICS adapter also lets you use distributed queuing to send messages to and receive messages from other queue managers using CICS communication facilities. For more information, see the *MQSeries Intercommunication* manual.

The CICS adapter provides CICS applications with access to MQSeries data while operating in the CICS environment. Therefore, CICS applications connected to MQSeries can access both MQSeries data and CICS data.

Usually, if CICS or MQSeries terminate or if the application terminates, CICS coordinates the recovery of both MQSeries data and CICS data. However, if messages are being sent from one queue manager to another using distributed queuing, recovery is coordinated by the sender Message Channel Agent (MCA). For more information about distributed queuing, see the *MQSeries Intercommunication* manual.

You can use MQSeries with the CICS Extended Recovery Facility (XRF) to aid recovery from a CICS error. For more information about XRF, see “Using Extended Recovery Facility” on page 318 and the *CICS/ESA Version 3.3 XRF Guide*.

The CICS adapter uses standard CICS command-level services where required, for example, EXEC CICS WAIT and EXEC CICS ABEND. A portion of the CICS adapter runs under the control of the transaction issuing the messaging requests. Therefore, these calls for CICS services appear to be issued by the transaction. For more information, see Chapter 6, “The MQSeries-CICS adapter” on page 115.

Application programming with CICS

The CICS adapter provides MQSeries support for CICS applications. All application programs that run under CICS must have the stub CSQCSTUB link-edited with them if they are to access MQSeries, unless the program is using dynamic calls. (For information about calling the CICS stub dynamically, see the *MQSeries Application Programming Guide*.) This stub provides the application with access to all MQI calls. For two-phase commit and backout, applications must use the appropriate EXEC CICS commands.

For information about building application programs that use the CICS adapter, see the *MQSeries Application Programming Guide*.

System administration and operation with CICS

An authorized CICS terminal operator can issue CICS commands to control and monitor the CICS adapter. However, the CICS terminal operator has no control over the MQSeries address space. For example, the operator cannot shut down MQSeries from the CICS address space.

The MQSeries-CICS bridge

The MQSeries-CICS bridge enables an application, not running in a CICS environment, to run a *program* or *transaction* on CICS and get a response back. This non-CICS application can be run from any environment that has access to an MQSeries network that encompasses MQSeries for OS/390.

A *program* is a CICS program that can be invoked using the EXEC CICS LINK command. It must conform to the DPL subset of the CICS API, that is, it must not use CICS terminal or syncpoint facilities. A *transaction* is a CICS transaction designed to run on a 3270 terminal. This transaction can use BMS or TC commands. It can be conversational or part of a pseudoconversation. It is permitted to issue syncpoints.

For more information, see “Introduction to the CICS bridge” on page 153.

MQSeries and IMS

The IMS adapter provided with MQSeries gives access to MQSeries from IMS. The IMS adapter receives and interprets requests for access to MQSeries using the External Subsystem Attach Facility (ESAF) provided by IMS. This facility is described in the *IMS Customization Guide*. Usually, IMS connects to MQSeries automatically without operator intervention. (For more information see Chapter 9, “The MQSeries-IMS adapter” on page 165.)

You can use MQSeries with the IMS Extended Recovery Facility (XRF) to aid recovery from a IMS error. For more information about XRF, see “Using Extended Recovery Facility” on page 318, and the *IMS Administration Guide: System* manual.

Application programming with IMS

With the IMS adapter, MQSeries provides message queuing services for IMS-dependent regions. All application programs that run under IMS must have the stub CSQQSTUB and the IMS language interface module link-edited with them if they need to access MQSeries. This stub provides the application with access to all MQI calls. To use two-phase commit and backout, your application should use the appropriate IMS calls. Batch DL/I programs must use the batch adapter stub, CSQBSTUB (see “The MQSeries-Batch/TSO adapter” on page 23).

For information about building application programs that use the IMS adapter, see the *MQSeries Application Programming Guide*.

The MQSeries-IMS bridge

The MQSeries-IMS bridge is the component of MQSeries for OS/390 that allows direct access from MQSeries applications to applications on your IMS system. The bridge enables implicit MQSeries API support. This means that you can re-engineer legacy applications that were controlled by 3270-connected terminals to be controlled by MQSeries messages, without having to rewrite, recompile, or re-link them.

The bridge is an IMS *Open Transaction Manager Access* (OTMA) client. For more information, see “Introduction to the IMS bridge” on page 185.

System administration and operation with IMS

An authorized IMS terminal operator can issue IMS commands to control and monitor the connection to MQSeries. However, the IMS terminal operator has no control over the MQSeries address space. For example, the operator cannot shut down MQSeries from an IMS address space.

MQSeries and security

MQSeries uses the OS/390 System Authorization Facility (SAF) to route authorization requests to an external security manager, for example, the Resource Access Control Facility (RACF). MQSeries does no security verification of its own.

For details of how security is carried out in MQSeries, see Part 8, “Security” on page 401.

MQSeries and SMS

MQSeries parameters enable you to specify Storage Management Subsystem (MVS/DFP™ SMS) storage classes when dynamically allocating MQSeries archive data sets. MQSeries initiates the archiving of log data sets, but SMS can be used to perform allocation of the archive data set.

MQSeries and ARM

The OS/390 Automatic Restart Manager (ARM) is an OS/390 recovery function. You can use it to improve the availability of your MQSeries subsystems.

When a job or task fails, or the system on which it is running fails, ARM can restart the job or task without operator intervention. This means that, for MQSeries, you do not have to wait for operations staff to notice that a queue manager has failed, and to take corrective action. Instead, OS/390 notices if either a queue manager or a channel initiator has failed, or if an OS/390 system has failed. This results in a faster resumption of productive work, and hence in improved system availability.

Using ARM with MQSeries is described in “Using the OS/390 Automatic Restart Manager (ARM)” on page 300.

MQSeries, the Workload Manager, and Workflow

The OS/390 *Workload Manager* (WLM) provides a solution for managing workload distribution, workload balancing, and distributing resources to competing workloads. You can set service classes for each different type of work performed by your system, and then set service goals for each class of service. The WLM allocates system resources to achieve these goals.

To use the queuing services of the workload manager with MQSeries, you need to use *Workflow*. You need to set up OS/390 WLM class qualifiers for MQSeries, and use the WLM to define different classes of service for your MQSeries messages. When you have done this, if you put messages on a special queue called a *WLM-managed queue*, Workflow passes information taken from the message descriptor and a work information header in the message to the WLM, and so determine which class of service to use for the message.

For a general explanation of the basic concepts of MQSeries Workflow, see the *MQSeries Workflow: Concepts and Architecture* manual, and for information about planning to use it on OS/390, see the *MQSeries Workflow for OS/390: Customization and Administration* manual. For information about the Workload Manager, see the *MVS Planning: Workload Management* manual.

Making MQSeries available

Installing MQSeries consists of three stages: receiving, applying, and accepting. See the *MQSeries for OS/390 Program Directory* for instructions on how to do this.

After installation, there are five main tasks to perform to make MQSeries available to application programmers developing MQSeries applications and to applications in production:

- Customizing MQSeries and its adapters
- Operating MQSeries
- Administering MQSeries
- Tuning MQSeries
- Preparing for recovery

Customizing MQSeries and its adapters

When you have installed MQSeries, you must customize it to suit the requirements of your installation. To find out more about customization, read the following chapters:

- Chapter 2, “Preparing for customization” on page 33
- Chapter 3, “Customizing the queue managers” on page 37
- Chapter 5, “Testing your queue manager” on page 105
- Appendix E, “Defining your queue manager environment parameters” on page 497

If you are migrating from a previous version of MQSeries, read Chapter 4, “Migrating from previous versions of MQSeries for MVS/ESA” on page 97. This chapter discusses which customization tasks you need to perform again.

Operating MQSeries

Operating MQSeries involves starting and stopping MQSeries, connecting and disconnecting CICS and IMS regions, using MQSeries commands to manage message queues, and using the MQSeries utilities.

You can find details of these and related tasks in Part 5, “Operating and administering MQSeries” on page 193. Some of these tasks overlap with those of the administrator, so you might also find this Chapter 13, “Writing programs to administer MQSeries” on page 217 useful.

The commands are described in the *MQSeries Command Reference* manual. For details of the MQSeries utilities, see Chapter 14, “Using the MQSeries utilities” on page 233.

Administering MQSeries

MQSeries administration can be performed by a system administrator, system programmer, or computer operator. You can find details of these tasks in Chapter 13, “Writing programs to administer MQSeries” on page 217. The person who undertakes this task has to define and manage resources, and be responsible for managing security and monitoring performance.

Tuning MQSeries

The tuning of MQSeries can be performed by a system programmer or capacity planner. The person who undertakes this task must be able to monitor the operation of MQSeries, and then use the statistics produced to improve its performance.

You can find details of these tasks in Chapter 22, “Monitoring performance and resource usage” on page 371. For information about dealing with performance problems, see the *MQSeries for OS/390 Problem Determination Guide*

Preparing for recovery

Preparing for recovery underlies all other tasks, and is performed by system programmers. To understand the background to MQSeries recovery, read these chapters:

- Chapter 16, “Understanding termination and restart” on page 285
- Chapter 17, “Understanding the log and the bootstrap data set” on page 305

If you plan the data that must be recovered after an error and how the recovery can be done, you can handle any type of error efficiently. For details on preparing recovery plans and help on recovering from specific failures, see these chapters:

- Chapter 18, “Planning for backup and recovery” on page 313
- Chapter 21, “Example recovery scenarios” on page 345

CSA storage requirement

Each MQSeries for OS/390 subsystem (including the channel initiator) has the following storage requirements:

CSA 4 KB
ECSA 5 MB

In addition, each concurrent MQSeries task requires about 1500 bytes of ECSA. When a task ends, this storage can be reused by other MQSeries tasks. MQSeries does not release the storage until the queue manager is shut down, so the maximum amount of ECSA required can be calculated by multiplying the maximum number of concurrent tasks by 1500 bytes.

Concurrent tasks consist of the following:

- The number of Batch, TSO, or IMS regions that have connected to MQSeries, but not disconnected
- The number of CICS transactions that have issued an MQSeries request, but have not terminated

The trace table also resides in the ECSA; you should use the TRACTBL parameter of the CSQ6SYSP macro to determine the size of the resident trace table. This macro is described in “Using CSQ6SYSP” on page 69.

Private region storage usage

Every channel uses the following private region virtual storage below the 16 MB line in the channel initiator address space:

- 1200 bytes if LE/370 APAR PQ03507 has been applied
- None if LE/370 APAR PQ06157 has also been applied
- 8 KB otherwise

Every channel uses approximately 160 KB of extended private region in the channel initiator address space. Storage is increased if messages larger than 32 KB are transmitted. This increased storage is freed when:

- A sending or client channel requires less than half the current buffer size for 10 consecutive sends
- A heartbeat is sent or received

The storage is freed for re-use within the LE environment but is not seen as free by the OS/390 virtual storage manager.

This means that the upper limit for the number of channels is dependent on message size and arrival patterns as well as individual user system limitations on extended private region size. The limit is likely to be approximately 9000 channels on many systems.

Region sizes

The following table shows suggested values for region sizes. Two sets of values are given; one set is suitable for a test system, the other for a production system or a system that will become a production system eventually.

Table 3. Suggested test and production definitions for JCL region sizes

Definition setting	Test system	Production system
Queue manager	REGION=7168K (default)	REGION=0M
Channel initiator	REGION=7168K (default)	REGION=0M

The default region sizes used in the test system (REGION=7168K for both the queue manager region and channel initiator region) allow the queue manager and channel initiator to allocate 7 MB of private virtual storage below the 16 MB line (PVT) and up to 32 MB of extended private virtual storage above the 16 MB line (extended PVT).

These defaults are insufficient for a production system with large buffer pools and many active channels. The production region sizes chosen (REGION=0M) allow all available private storage above and below the 16 MB line to be used, although MQSeries uses very little storage below the 16 MB line.

Note: MVS exit IEFLIMIT can override the region limits below the 16 MB line; MVS exit IEFUSI can override the region limits above and below the 16 MB line.

CSA storage

Part 2. Customizing MQSeries after installation

Chapter 2. Preparing for customization . . . 33
Installable features . . . 33
Libraries that exist after installation . . . 34

Chapter 3. Customizing the queue managers . . . 37
Introducing the customization tasks . . . 37
Task 1: Choose which language you want to use . . . 39
Task 2: Choose the distributed queuing facility . . . 40
Task 3: Define the MQSeries subsystem to OS/390 . . . 41
Updating the subsystem name table . . . 41
Using command prefix strings . . . 42
Running in a sysplex environment . . . 44
Reviewing the number of system LXs . . . 45
Task 4: Update the OS/390 link list . . . 46
Task 5: APF authorize the MQSeries load libraries . . . 47
Task 6: Update the OS/390 program properties table . . . 48
Task 7: Create procedures for the MQSeries subsystem . . . 49
Task 8: Create procedures for the channel initiator . . . 50
Task 9: Implement your ESM security controls . . . 51
Task 10: Customize the initialization input data sets . . . 52
Initialization commands . . . 52
Initialization data set formats . . . 53
Initialization data set samples . . . 54
Using the CSQINP1 sample . . . 54
Using the CSQINP2 samples . . . 55
Using the other samples . . . 59
Task 11: Create the bootstrap and log data sets . . . 61
Task 12: Define your page sets . . . 63
Calculating the storage requirement for messages . . . 64
Enabling dynamic page set expansion . . . 66
Task 13: Tailor your system parameter module . . . 68
Creating your own system parameter module . . . 68
Fine tuning a system parameter module . . . 69
Using CSQ6SYSP . . . 69
Using CSQ6LOGP . . . 76
Using CSQ6ARVP . . . 79
Task 14: Tailor the channel initiator parameter module . . . 86
Creating your own channel initiator parameter module . . . 86
Using CSQ6CHIP . . . 87
Task 15: Set up Batch, TSO, and RRS adapters . . . 92
Task 16: Set up the operations and control panels . . . 93
Setting up the libraries . . . 93
Updating the ISPF menu . . . 94
Updating the function keys and command settings . . . 94
Task 17: Include the MQSeries dump formatting member . . . 95
Task 18: Suppress information messages . . . 96

Chapter 4. Migrating from previous versions of MQSeries for MVS/ESA . 97
Migrating from Version 1.2 to Version 2.1 . . . 97
Migrating from Version 1.1.4 to Version 2.1 . . . 101

© Copyright IBM Corp. 1993,1999

Migrating from Version 1.1.3 to Version 2.1 101
Migrating from Version 1.1.2 or earlier to Version 2.1 103
Coexistence with earlier versions of MQSeries for MVS/ESA 103
Multiple queue manager versions 103
Operations and control panels 104
Application stubs 104

Chapter 5. Testing your queue manager 105
Basic function testing 105
Running the installation verification program CSQ4IVP1 105
Checking the results of CSQ4IVP1 107
Testing for C, C++, COBOL, PL/I, and CICS 108
Testing for distributed queuing 108
Overview of CSQ4IVPX job 108
Preparing to run CSQ4IVPX 108
Running CSQ4IVPX 110
Checking the results of CSQ4IVPX 110

Chapter 2. Preparing for customization

The *MQSeries for OS/390 Program Directory* lists the contents of the MQSeries installation tape, the program and service level information for MQSeries, and describes how to install MQSeries under OS/390 using the System Modification Program Extended (SMP/E).

When you have installed MQSeries, you must carry out a number of tasks before you can make it available to users. Refer to the following chapters for a description of these tasks:

- Chapter 3, “Customizing the queue managers” on page 37
- Chapter 5, “Testing your queue manager” on page 105
- Part 8, “Security” on page 401
- Appendix E, “Defining your queue manager environment parameters” on page 497

If you have migrated from a previous version of MQSeries for OS/390, you don’t need to perform most of the customization tasks. Refer to Chapter 4, “Migrating from previous versions of MQSeries for MVS/ESA” on page 97 for information about the tasks you have to perform.

Installable features

MQSeries for OS/390 comprises the following features:

Base

This is required; it comprises all the main functions, and includes the MQSeries-CICS bridge and the distributed queuing facility (supporting both TCP/IP and APPC communications).

Note: This distributed queuing facility is known as the “non-CICS mover” because you do not need to have CICS installed to use it.

National language features

These contain error messages and panels in all the supported national languages. Each language has a language letter associated with it. The languages and letters are:

C Simplified Chinese
E U.S. English (mixed case)
K Japanese
U U.S. English (uppercase)

You must install at least one of these (you can install more than one).

Distributed queuing with CICS feature

This is optional; it is required only if you are using CICS ISC for distributed queuing.

Note: This feature is known as the “CICS mover.”

Client attachment feature

This is optional; it is only required if you are going to attach clients to your MQSeries for OS/390 subsystem. When you have installed this feature, there are no configuration parameters to set before you can attach clients to

© Copyright IBM Corp. 1993,1999

MQSeries for OS/390. Administration for clients is available even if you don't install this feature.

Internet Gateway feature
This is optional; it is only required if you want to use the MQSeries Internet Gateway. This is described in the *MQSeries Internet Gateway User's Guide*. (This online book is supplied with the Internet Gateway.)

Libraries that exist after installation

MQSeries is supplied with a number of separate load libraries. Table 4 shows the libraries that might exist after you have installed MQSeries.

thlqual

Throughout this book, the default value `thlqual` is used to indicate the target library high-level qualifier for MQSeries data sets in your installation.

For more information, see the *MQSeries for OS/390 Program Directory*.

Table 4 (Page 1 of 3). MQSeries libraries that exist after installation

Name	Description
thlqual.SCSQANLC	Contains the load modules for the Simplified Chinese version of MQSeries.
thlqual.SCSQANLE	Contains the load modules for the U.S. English (mixed case) version of MQSeries.
thlqual.SCSQANLK	Contains the load modules for the Japanese version of MQSeries.
thlqual.SCSQANLU	Contains the load modules for the U.S. English (uppercase) version of MQSeries.
thlqual.SCSQASMS	Contains source for assembler sample programs.
thlqual.SCSQAUTH	The main repository for all MQSeries product load modules; it also contains the default parameter modules, CSQZPARM and CSQXPARM. This library must be APF-authorized.
thlqual.SCSQCICS	Contains the load modules that must be included in the CICS DFHRPL concatenation. These are separated from the main MQSeries load library so that the number of modules in the concatenation search is kept to a minimum to improve performance and to avoid the need for APF authorization.
thlqual.SCSQCLST	Contains CLISTs used by the mail manager sample program.
thlqual.SCSQCOBC	Contains COBOL copybooks, including copybooks required for the sample programs.
thlqual.SCSQCOBS	Contains source for COBOL sample programs.
thlqual.SCSQCPPS	Contains C source for C++.
thlqual.SCSQC37S	Contains source for C/370™ sample programs.
thlqual.SCSQC370	Contains C/370 headers, including headers required for the sample programs.
thlqual.SCSQDEFS	Contains side definitions for C++.

Table 4 (Page 2 of 3). MQSeries libraries that exist after installation

Name	Description
thlqual.SCSQEXEC	Contains REXX execs to be included in the SYSEXEC or SYSPROC concatenation if you are using the MQSeries operations and control panels.
thlqual.SCSQHPPS	Contains header files for C++.
thlqual.SCSQINST	Contains JCL for installation jobs.
thlqual.SCSQLINK	Early code library. Contains the load modules that must be in the link list because they are loaded at system initial program load (IPL). The library must be APF-authorized and must be in the link list.
thlqual.SCSQLOAD	Load library. Contains load modules for non-APF code, user exits, utilities, samples, installation verification programs, and adapter stubs. The library does not need to be APF-authorized and does not need to be in the link list.
thlqual.SCSQMACS	Contains Assembler macros including: sample macros, product macros, and system parameter macros.
thlqual.SCSQMAPS	Contains CICS mapsets used by sample programs.
thlqual.SCSQMSGC	Contains ISPF messages to be included in the ISPMLIB concatenation if you are using the Simplified Chinese language feature for the MQSeries operations and control panels.
thlqual.SCSQMSGE	Contains ISPF messages to be included in the ISPMLIB concatenation if you are using the U.S. English (mixed case) language feature for the MQSeries operations and control panels.
thlqual.SCSQMSGK	Contains ISPF messages to be included in the ISPMLIB concatenation if you are using the Japanese language feature for the MQSeries operations and control panels.
thlqual.SCSQMSGU	Contains ISPF messages to be included in the ISPMLIB concatenation if you are using the U.S. English (uppercase) language feature for the MQSeries operations and control panels.
thlqual.SCSQMVR1	Contains the load modules for distributed queuing when using TCP/IP with the OpenEdition sockets or IUCV interface, or LU 6.2. This library must be APF-authorized.
thlqual.SCSQMVR2	Contains the load modules for distributed queuing when using TCP/IP with the TCPaccess interface, or LU 6.2. This library must be APF-authorized.
thlqual.SCSQPLIC	Contains PL/I headers.
thlqual.SCSQPLIS	Contains source for PL/I sample programs.
thlqual.SCSQPNLA	Contains IPCS panels, for the dump formatter, to be included in the ISPPLIB concatenation. Also contains panels for MQSeries sample programs.
thlqual.SCSQPNLC	Contains ISPF panels to be included in the ISPPLIB concatenation if you are using the Simplified Chinese language feature for the MQSeries operations and control panels.
thlqual.SCSQPNLE	Contains ISPF panels to be included in the ISPPLIB concatenation if you are using the U.S. English (mixed case) language feature for the MQSeries operations and control panels.

Table 4 (Page 3 of 3). MQSeries libraries that exist after installation

Name	Description
thlqual.SCSQPNLK	Contains ISPF panels to be included in the ISPPLIB concatenation if you are using the Japanese language feature for the MQSeries operations and control panels.
thlqual.SCSQPNLU	Contains ISPF panels to be included in the ISPPLIB concatenation if you are using the U.S. English (uppercase) language feature for the MQSeries operations and control panels.
thlqual.SCSQPROC	Contains sample JCL and default system initialization data sets.
thlqual.SCSQSKL	Contains ISPF skeletons to be included in the ISPSLIB concatenation if you are using the MQSeries operations and control panels.
thlqual.SCSQSNLC	Contains the load modules for the Simplified Chinese versions of the MQSeries modules that are required for special purpose function (for example the early code).
thlqual.SCSQSNLE	Contains the load modules for the U.S. English (mixed case) versions of the modules that are required for special purpose function (for example the early code).
thlqual.SCSQSNLK	Contains the load modules for the Japanese versions of the MQSeries modules that are required for special purpose function (for example the early code).
thlqual.SCSQSNLU	Contains the load modules for the U.S. English (uppercase) versions of the MQSeries modules that are required for special purpose function (for example the early code).
thlqual.SCSQTBLC	Contains ISPF tables to be included in the ISPTLIB concatenation if you are using the Simplified Chinese language feature for the MQSeries operations and control panels.
thlqual.SCSQTBLE	Contains ISPF tables to be included in the ISPTLIB concatenation if you are using the U.S. English (mixed case) language feature for the MQSeries operations and control panels.
thlqual.SCSQTBLK	Contains ISPF tables to be included in the ISPTLIB concatenation if you are using the Japanese language feature for the MQSeries operations and control panels.
thlqual.SCSQTBLU	Contains ISPF tables to be included in the ISPTLIB concatenation if you are using the U.S. English (uppercase) language feature for the MQSeries operations and control panels.
Attention: Do *not* modify or customize any of these libraries. If you want to make changes, copy the libraries, and make your changes to the copies.	

Chapter 3. Customizing the queue managers

This chapter leads you through the various stages of customizing MQSeries after you have successfully installed it. The installation process is described in the *MQSeries for OS/390 Program Directory*.

Important

Before you perform the customization tasks in this chapter, there are a number of configuration options that you should consider because they will affect the performance of your MQSeries for OS/390 installation. These options are discussed in Appendix E, "Defining your queue manager environment parameters" on page 497.

If you are migrating from a previous version of MQSeries for OS/390, you might not need to perform these tasks. See Chapter 4, "Migrating from previous versions of MQSeries for MVS/ESA" on page 97 for information about what you need to do.

Note: The sample data set members supplied with MQSeries have names beginning with the four characters CSQ4 and are in the library thlqual.SCSQPROC.

Introducing the customization tasks

To customize MQSeries for your installation, you must perform the tasks listed here. However, before you begin customization, read this notice:

Read this notice before you do anything

For each task you must consider:

1. ***Whether the task must be repeated for each MQSeries subsystem.***

   Some of these tasks you need only do once, regardless of the number of MQSeries subsystems, while others must be repeated for each MQSeries subsystem. Each task description tells you which category that task belongs to.

2. ***Whether the task requires an IPL.***

   Some tasks might only take effect following an OS/390 system initial program load (IPL). For example, an IPL might be required by:

   - Any task that changes certain OS/390 system parameters
   - Task 7, when you change certain tables used by an external security manager, such as RACF

   Therefore, make sure you have completed **all** the necessary tasks before you IPL the system. Each task description tells you whether an IPL is required. In general, an IPL is needed when you install and customize MQSeries, but not when you add a new MQSeries subsystem.

© Copyright IBM Corp. 1993,1999

Customizing queue managers

Work through the following tasks, checking each one off as you complete it:

- ☐ Task 1: Choose which language you want to use
- ☐ Task 2: Choose the distributed queuing facility
- ☐ Task 3: Define the MQSeries subsystem to OS/390
- ☐ Task 4: Update the OS/390 link list
- ☐ Task 5: APF authorize the MQSeries load libraries
- ☐ Task 6: Update the OS/390 program properties table
- ☐ Task 7: Create procedures for the MQSeries subsystem
- ☐ Task 8: Create procedures for the channel initiator
- ☐ Task 9: Implement your ESM security controls
- ☐ Task 10: Customize the initialization input data sets
- ☐ Task 11: Create the bootstrap and log data sets
- ☐ Task 12: Define your page sets
- ☐ Task 13: Tailor your system parameter module
- ☐ Task 14: Tailor the channel initiator parameter module
- ☐ Task 15: Set up Batch, TSO, and RRS adapters
- ☐ Task 16: Set up the operations and control panels
- ☐ Task 17: Include the MQSeries dump formatting member
- ☐ Task 18: Suppress information messages

Tasks 3 through 6 involve updating the OS/390 system parameters. You need to know which ones were specified when the system IPL was performed. SYS1.PARMLIB(IEASYSpp) contains a list of parameters that point to other members of SYS1.PARMLIB (where pp represents the OS/390 system parameter list that was used to IPL the system).

The entries you need to find are:

For Task 3:

SSN=ss Points to the defined subsystem list (member IEFSSNss)

NSYSLX=nn
The number of linkage indexes reserved for system LXs (member IEASYSxx)

For Task 4:

LNK=kk Points to the link list (member LNKLSTkk)

For Task 5:

PROG=xx or APF=aa
Points to the Authorized Program Facility (APF) authorized library list (member PROGxx or IEFAPFaa)

For Task 6:

SCH=xx Points to the Program Properties Table (PPT) (member SCHEDxx)

When you have completed all the customization tasks required, refer to Part 3, “MQSeries and CICS” on page 113 if you are using CICS, and Part 4, “MQSeries and IMS” on page 163 if you are using IMS.

Task 1: Choose which language you want to use

- *Repeat this task for each MQSeries subsystem.*

You can choose one of the following national languages for the MQSeries operator messages and the MQSeries operations and control panels (including the character sets used). Each language is identified by a language letter:

C Simplified Chinese
E U.S. English (mixed case)
K Japanese
U U.S. English (uppercase)

The samples, MQSeries commands, and utility control statements are available only in mixed case U.S. English.

You must specify the appropriate libraries in the JCL that you will use for running MQSeries (as described in the following sections). Table 5 shows the names of the libraries for the language features; the language letter is the last letter of the library names.

Table 5. National language feature libraries

Description	Japanese	Simplified Chinese	U.S. English (mixed case)	U.S. English (uppercase)
Load modules	thlqual.SCSQANLK	thlqual.SCSQANLC	thlqual.SCSQANLE	thlqual.SCSQANLU
ISPF messages	thlqual.SCSQMSGK	thlqual.SCSQMSGC	thlqual.SCSQMSGE	thlqual.SCSQMSGU
ISPF panels	thlqual.SCSQPNLK	thlqual.SCSQPNLC	thlqual.SCSQPNLE	thlqual.SCSQPNLU
Special purpose function (for example, early code)	thlqual.SCSQSNLK	thlqual.SCSQSNLC	thlqual.SCSQSNLE	thlqual.SCSQSNLU
ISPF tables	thlqual.SCSQTBLK	thlqual.SCSQTBLC	thlqual.SCSQTBLE	thlqual.SCSQTBLU

More details are given in the following sections.

Task 2: Choose the distributed queuing facility

- *Repeat this task for each MQSeries subsystem.*

The distributed queuing facility provided with the base product feature of MQSeries uses native OS/390 communications (APPC or TCP/IP). It can either use APPC (LU 6.2), TCP/IP from IBM, or TCPaccess from Interlink Computer Sciences, Inc. This facility is also known as the *non-CICS mover* because it does not use CICS intersystem communication (ISC) for communications, and so you do not need to have CICS installed to use it. (However, even if you do use CICS, you can still use this mover.) You are recommended to use the non-CICS mover.

Alternatively, you can use CICS ISC for distributed queuing; this facility is also known as the *CICS mover*. You must have installed the CICS mover feature to use this.

You can enable both facilities and use them simultaneously on the same MQSeries instance. However, the two types will have no knowledge of each other or each other's channels, and you must ensure that the channel names they use are distinct.

If you want to use clustering, you must use the non-CICS mover. See the *MQSeries Queue Manager Clusters* manual for information about using clusters. If you want to use clients, you must also use the non-CICS mover; the client attachment feature is needed as well (but you can administer clients without it).

Whichever mover you choose, you must perform the following three tasks to enable distributed queuing:

- Customize the distributed queuing facility and define the MQSeries objects required.
- Define access security; this is described in "Security considerations for distributed queuing" on page 463.
- Set up your communications; this is described in the *MQSeries Intercommunication* manual. Amongst other things, you must set up your TCPIP.DATA data set if you are using TCP/IP, LU names and side information if you are using APPC, and CICS definitions if you are using CICS.

If you choose the non-CICS mover, customization instructions are described in this chapter. You also need to choose which communications interface to use. This can be:

- APPC (LU 6.2)
- IBM TCP/IP IUCV (OS/390 Version 2.4 only)
- IBM TCP/IP OpenEdition sockets
- TCPaccess (native)
- TCPaccess IUCV
- TCPaccess OpenEdition sockets

Note: OpenEdition is also known as UNIX System Services.

If you choose the CICS mover, customization instructions are described in Appendix D, "Enabling distributed queuing using CICS ISC" on page 491.

Task 3: Define the MQSeries subsystem to OS/390

- *Repeat this task for each MQSeries subsystem.*
- *You might need to IPL the system before these changes take effect.*

Updating the subsystem name table

The subsystem name table of OS/390, which is taken initially from the SYS1.PARMLIB member IEFSSNss, contains the definitions of formally defined OS/390 subsystems. To define each MQSeries subsystem, you must add an entry to this table, either by changing the IEFSSNss member of SYS1.PARMLIB, or by using the `SETSSI` OS/390 command if it is available.

If you use the `SETSSI` command, the change takes effect immediately, otherwise you must IPL your system. Even if you use the `SETSSI` OS/390 command so that changes take effect immediately, you should add the entries to the IEFSSNss member of SYS1.PARMLIB as well, so that they will remain in effect after subsequent IPLs.

There are two methods of doing this:

- The keyword parameter form of the MQSeries subsystem definition in IEFSSNss. This is the recommended method.

```
SUBSYS SUBNAME(ssid) INITRTN(CSQ3INI) INITPARM('CSQ3EPX,cpf,scope')
```

- The positional parameter form of the MQSeries subsystem definition.

```
ssid,CSQ3INI,'CSQ3EPX,cpf,scope'
```

Do not mix the two forms in one IEFSSNss member. If different forms are required, use a separate IEFSSNss member for each type, adding the SSN operand of the new member to the IEASYSxx SYS1.PARMLIB member. To specify more than one SSN, use SSN=(aa,bb,...) in IEASYSxx.

The corresponding SETSSI command to dynamically define an MQSeries subsystem is:

```
SETSSI ADD,S=ssid,I=CSQ3INI,P='CSQ3EPX,cpf,scope'
```

In the examples above,

`ssid` The subsystem identifier.

`cpf` The command prefix string (see “Using command prefix strings” on page 42 for information about the rules for defining CPFs).

`scope` The system scope, used if you are running in an OS/390 sysplex (see "Defining the scope for sysplex operation" on page 44). If you are not running in a sysplex, use M for this value.

Figure 5 shows several examples.

```
CSQ1,CSQ3INI,'CSQ3EPX,+mqs1cpf,M'
CSQ2,CSQ3INI,'CSQ3EPX,+mqs2cpf,M'
CSQ3,CSQ3INI,'CSQ3EPX,++,M'
```

Figure 5. Sample IEFSSNss statements for defining subsystems

Note: Once you have created objects in a subsystem, you cannot change the subsystem name or use the page sets from one subsystem in another subsystem. To do either of these, you must unload all the objects and messages from one subsystem and reload them into another.

Table 6 gives a number of examples showing the associations of subsystem names and CPFs, as defined by the statements in Figure 5.

Table 6. Subsystem name to CPF associations

MQSeries subsystem name	CPF
CSQ1	+mqs1cpf
CSQ2	+mqs2cpf
CSQ3	++

Note: The `ACTIVATE` and `DEACTIVATE` functions of the `SETSSI` OS/390 command are not supported by MQSeries.

Using command prefix strings

Each instance of MQSeries that you install must have its own *command prefix* string (CPF). You use the CPF to identify the OS/390 subsystem that commands are intended for. It also identifies the OS/390 subsystem from which messages sent to the console originate.

You can issue all MQSeries commands from an authorized console by inserting the CPF before the command. If you enter commands via the system command input queue (for example, using CSQUTIL), or use the MQSeries operations and control panels, you do not use the CPF.

To start a subsystem called CSQ1 whose CPF is '`+cpf`', issue the command `+cpf START QMGR` from the operator console (the space between the CPF and the command is optional).

The CPF also identifies the subsystem that is returning operator messages. The following example shows `+cpf` as the CPF between the message number and the message text.

```
CSQ9022I +cpf CSQNCDSP ' DISPLAY CMDSERV' NORMAL COMPLETION
```

Defining command prefix strings

You should adopt a system-wide convention for your CPFs for all subsystems to avoid conflicts. You should adhere to the following guidelines:

- Define a CPF as a one- to eight-character string.
- Do not use a CPF that is already in use by any other subsystem, and avoid using the JES backspace character defined on your system as the first character of your string.
- Define your CPF using characters from the set of valid characters listed in Table 8.
- Do not use a CPF that is an abbreviation for an already defined process or that might be confused with command syntax. For example, a CPF such as 'D' conflicts with OS/390 commands such as DISPLAY. To avoid this happening, you should use one of the special characters (shown in Table 8) as the first or only character in your CPF string.
- Do not define a CPF that is either a subset or a superset of an existing CPF. For an example, see Table 7:

Table 7. Example of CPF subset and superset rules

Subsystem name	CPF defined	Commands routed to...
MQA	!A	MQA
MQB	!B	MQB
MQC1	!C1	MQC1
MQC2	!C2	MQC2
MQB1	!B1	**MQB**

Commands intended for subsystem MQB1 (using CPF !B1) are routed to subsystem MQB because the CPF for this subsystem is !B, a subset of !B1. For example, if you entered the command `!B1 START QMGR`, subsystem MQB will receive the command `1 START QMGR` (which, in this case, it will be unable to deal with).

You can see which prefixes already exist by issuing the OS/390 command DISPLAY OPDATA.

If you are running in a sysplex, OS/390 will diagnose any conflicts of this type at the time of CPF registration (see "Running in a sysplex environment" on page 44 for information about CPF registration).

Table 8 shows the characters that you can use when defining your command prefix (CPF) strings:

Table 8 (Page 1 of 2). Valid character set for CPF strings

Character set	Contents	
Alphanumeric	Alphabetic Numeric	Uppercase A through Z, lowercase a through z, 0 through 9

Table 8 (Page 2 of 2). Valid character set for CPF strings

Character set	Contents	
National (see note)	"At" sign Dollar sign Pound sign	@ $ # (Characters that can be represented as hexadecimal values X'7C', X'5B', and X'7B')
Special	period slash left parenthesis right parenthesis asterisk ampersand plus sign hyphen equal sign cent sign less than sign vertical bar exclamation point semi-colon percent sign underscore question mark colon	. / ( ) * & + - = ¢ < | ! ; % _ ? :

Note: The system recognizes the following hexadecimal representations of the national characters: @ as X'7C', $ as X'5B', and # as X'7B'. In countries other than the U.S., the U.S. national characters represented on terminal keyboards might generate a different hexadecimal representation and cause an error. For example, in some countries the $ character might generate an X'4A'.

Running in a sysplex environment

If you are in a sysplex environment, MQSeries registers your CPFs to enable you to enter a command from any console in the sysplex and route that command to the appropriate system for execution. The command responses are returned to the originating console.

Defining the scope for sysplex operation

Scope is used to determine the type of CPF registration performed by the MQSeries subsystem when you are running MQSeries in a sysplex environment.

Possible values for scope are as follows:

M System scope.

The CPF is registered with OS/390 at system IPL time by MQSeries and remains registered for the entire time that the OS/390 system is active.

MQSeries operator commands must be entered at a console connected to the OS/390 image running the target subsystem, or you must use ROUTE commands to direct the command to that image.

You should use this option if you are not running in a sysplex.

X Sysplex IPL scope.

The CPF is registered with OS/390 at system IPL time by MQSeries and remains registered for the entire time that the OS/390 system is active.

MQSeries operator commands can be entered at any console connected to the sysplex, and are routed to the image that is executing the target system automatically.

S Sysplex started scope.

The CPF is registered with OS/390 at the time the MQSeries subsystem is started and remains active until the MQSeries subsystem terminates.

You must use ROUTE commands to direct the original START MQSeries command to the target system, but all further MQSeries operator commands can be entered at any console connected to the sysplex, and are routed to the target system automatically.

After MQSeries termination, you must use the ROUTE commands to direct subsequent START commands to the target MQSeries subsystem.

An MQSeries subsystem with a CPF with scope of X can only be defined on one OS/390 image within a sysplex. If you use this option, you must define a unique subsystem name table for each OS/390 image requiring MQSeries subsystems with CPFs of scope X.

An MQSeries subsystem with a CPF with scope of S can be defined on one or more OS/390 images within a sysplex, so these images can share a single subsystem name table. However you must ensure that the initial START command is issued on (or routed to) the OS/390 image on which you want the MQSeries subsystem to run. If you use this option, you can stop the MQSeries subsystem and restart it on a different OS/390 image within the sysplex without having to change the subsystem name table or re-IPL an OS/390 system.

If you want to use ARM to restart queue managers in different OS/390 images automatically, every queue manager must be defined in each OS/390 image on which that queue manager might be restarted, with a sysplex-wide, unique 4-character subsystem name with a CPF scope of S. See “Using the OS/390 Automatic Restart Manager (ARM)” on page 300 for more information about automatic restart.

Reviewing the number of system LXs

Each MQSeries subsystem defined in the subsystem name table reserves one system linkage index at IPL time. This system linkage index is reused if the MQSeries subsystem is stopped and restarted. The NSYSLX parameter in IEASYSxx defines the number of linkage indexes (in addition to those in the system function table) to be reserved as system linkages. The default number is 55.

If your environment has a number of subsystems defined that use system linkage indexes (for example, DB2, IRLM, and IMS V5), you might need to increase the value of NSYSLX when you define MQSeries subsystems. Each MQSeries subsystem reserves one system linkage index, and each instance of the distributed queuing feature reserves one non-system linkage index.

You must IPL your system before changes to NSYSLX take effect.

Task 4: Update the OS/390 link list

- *You need only perform this task once.*
- *You must IPL the system before these changes take effect.*

You must add the MQSeries early code library, thlqual.SCSQLINK, to the link list, SYS1.PARMLIB(LNKLSTkk), and put thlqual.SCSQLINK in the master catalog.

If you want to minimize the number of libraries in the link list, copy the load modules from thlqual.SCSQLINK into an existing library that is in the link list and in the master catalog. The library you copy the members into must also be APF-authorized. However, if you do this, the installation program (SMP/E) cannot apply service to these modules, so you must recopy the load modules if service is to be applied to them.

You also need the associated early error message module, CSQ3ECMX. Either add the library containing the language you want to the link list, or copy this module from that library to an existing library in the link list. The libraries are called thlqual.SCSQSNLx, where x is the language letter.

The distributed queuing facility, CICS bridge, and Internet Gateway need access to the LE run-time library SCEERUN. You might want to include it in the link list. (This is not required for the CICS mover.)

Task 5: APF authorize the MQSeries load libraries

- *You need only perform this task once.*
- *You might need to IPL the system before these changes take effect.*

The MQSeries load libraries thlqual.SCSQAUTH and thlqual.SCSQLINK must be APF-authorized. You must also APF-authorize the libraries for your national language feature (thlqual.SCSQANLx and thlqual.SCSQSNLx) and for the non-CICS mover (thlqual.SCSQMVR1 or thlqual.SCSQMVR2).

All members of the link list are APF-authorized if the SYS1.PARMLIB member IEASYSpp contains the statement:

```
LNKAUTH=LNKLST
```

LNKAUTH=LNKLST is the default if LNKAUTH is not specified.

Because thlqual.SCSQLINK must be included in the link list, if IEASYSpp contains this LNKAUTH statement or if you allow it to default, you do not need to put thlqual.SCSQLINK in the APF list as well.

Note: You must APF-authorize all the libraries that you include in the MQSeries STEPLIB. If you put a library that is not APF-authorized in the STEPLIB, the whole library concatenation loses its APF authorization.

The APF lists are in the SYS1.PARMLIB member PROGxx or IEAAPFaa. The lists contain the names of APF authorized OS/390 libraries. The order of the entries in the lists is not significant. See the *MVS Initialization and Tuning Reference* manual for information about APF lists.

If you use PROGxx members with dynamic format, you need only issue the `SET PROG=` OS/390 command for the changes to take effect. Otherwise, if you use static format or IEAAPFaa members, you must IPL your system.

Task 6: Update the OS/390 program properties table

- *You need only perform this task once.*
- *You must IPL the system before these changes take effect.*

You must add the following entry to the program properties table (PPT) which you can find in SYS1.PARMLIB(SCHEDxx).

```
PPT     PGMNAME(CSQYASCP) /* CSQ - THIS IS REQUIRED FOR MQSERIES  */
        CANCEL            /* CAN BE CANCELED                     */
        KEY(7)            /* STORAGE PROTECTION KEY              */
        SWAP              /* PROGRAM IS SWAPPABLE                */
        NOPRIV            /* NOT PRIVILEGED                      */
        DSI               /* REQUIRES DATA SET INTEGRITY         */
        PASS              /* NOT ALLOWED TO BYPASS PASS PROT     */
        SYST              /* SYSTEM TASK SO NOT TIMED            */
        AFF(NONE)         /* NO PROCESSOR AFFINITY               */
        NOPREF            /* NO PREFERRED STORAGE FRAMES         */
```

Figure 6. PPT additional entries needed for MQSeries

Task 7: Create procedures for the MQSeries subsystem

- *Repeat this task for each MQSeries subsystem.*

For each MQSeries subsystem defined in the subsystem name table, create a cataloged procedure in a procedure library. The IBM-supplied procedure library is called SYS1.PROCLIB, but your installation might use its own naming convention.

The name of the MQSeries started task procedure is formed by concatenating the subsystem name with the characters MSTR. For example, subsystem CSQ1 has the procedure name CSQ1MSTR. You need one procedure for each of the subsystems you define.

We recommend that a subsystem called CSQ1MSTR is created initially for installation verification and testing purposes.

Copy the sample started task procedure thlqual.SCSQPROC(CSQ4MSTR) to member CSQ1MSTR (or a name of your choice) of your SYS1.PROCLIB or, if you are not using SYS1.PROCLIB, your procedure library. Copy CSQ4MSTR to a member in your procedure library for each of the MQSeries subsystems that you define.

When you have copied the members, you can tailor them to the requirements of each subsystem, using the instructions in member CSQ4MSTR. You can also use symbolic parameters in the JCL to allow the procedure to be modified when it is started. See “Start options” on page 200 for an example of this.

You must concatenate thlqual.SCSQANLx (where x is the language letter for your national language) before thlqual.SCSQAUTH in the STEPLIB DD statement.

Before you start MQSeries, you should set up MQSeries data set and system security by:

- Authorizing the queue manager started task procedure to run under your external security manager.
- Authorizing access to the queue manager data sets.

For details about how to do this, see “Security installation tasks” on page 466.

The exit library (CSQXLIB) can be added to this procedure later if you want to use queue manager exits. In this case, you also need access to the LE run-time library SCEERUN; if it is not in your link list (SYS1.PARMLIB(LNKLSTkk)), concatenate it in the STEPLIB DD statement. You need to stop and restart your queue manager to do this.

Task 8: Create procedures for the channel initiator

- *Repeat this task for each MQSeries subsystem.*
- *Omit this task if you are using the CICS mover.*

You need to create a channel-initiator started task procedure for each MQSeries subsystem that is going to use distributed queuing. To do this, you need to:

1. Copy the sample started task procedure thlqual.SCSQPROC(CSQ4CHIN) to your procedure library. Name the procedure *xxxx*CHIN, where *xxxx* is the name of your MQSeries subsystem (for example, CSQ1CHIN would be the channel initiator started task procedure for queue manager CSQ1).
2. Make a copy for each MQSeries subsystem that you are going to use.
3. Tailor the procedures to your requirements using the instructions in the sample procedure CSQ4CHIN. You can also use symbolic parameters in the JCL to allow the procedure to be modified when it is started. See “Start options” on page 200 for an example of this.

   Concatenate the library containing your national language feature (thlqual.SCSQANLx where x is the letter for your language) before thlqual.SCSQAUTH in the STEPLIB DD statement.

   Choose the appropriate distributed queuing library: thlqual.SCSQMVR1 if you are using the OpenEdition sockets or IUCV TCP/IP interface, or thlqual.SCSQMVR2 if you are using the TCPaccess interface. For LU 6.2 you can use either library.

   Access to the LE run-time library SCEERUN is required; if it is not in your link list (SYS1.PARMLIB(LNKLSTkk)), concatenate it in the STEPLIB DD statement.
4. Authorize the procedures to run under your external security manager.

The exit library (CSQXLIB) can be added to this procedure later if you want to use channel exits. You will need to stop and restart your channel initiator to do this.

If you are using TCP/IP, the channel initiator address space must be able to access the TCPIP.DATA data set that contains TCP/IP system parameters. There are various ways that this has to be set up, depending on which TCP/IP product and interface you are using. They include:

- Environment variable, RESOLVER_CONFIG
- HFS file, /etc/resolv.conf
- //SYSTCPD DD statement
- //SYSTCPDD DD statement
- *jobname/userid*.TCPIP.DATA
- SYS1.TCPPARMS(TCPDATA)
- *zapname*.TCPIP.DATA

Some of these will affect your started-task procedure JCL. For more information, see the following:

- *TCP/IP OpenEdition: Planning and Release Guide*
- *OS/390 OpenEdition: Planning*
- Your TCPaccess documentation

Task 9: Implement your ESM security controls

- *Repeat this task for each MQSeries subsystem.*
- *You might have to IPL the system before these changes take effect.*

You must now consider how you are going to implement any security controls for MQSeries.

If you use RACF as your external security manager, see Part 8, “Security” on page 401, which describes how to implement these security controls. If you are using RACF, you might need to IPL the system if you change the started-task procedures table, depending on how you choose to associate user IDs with the started tasks.

If you are using the non-CICS mover, you must also do the following tasks:

1. If your subsystem has connection security active, define a connection security profile ssid.CHIN to your external security manager (see “Connection security profiles for distributed queuing” on page 415 for information about this).
2. If you are using a sockets interface, ensure that the user ID under whose authority the channel initiator is running is configured to use OpenEdition, as described in the *OS/390 OpenEdition Planning* manual.

Task 10: Customize the initialization input data sets

- *Repeat this task for each MQSeries subsystem.*

Each MQSeries instance gets its initial definitions from a series of commands contained in the MQSeries *initialization input data sets*. These data sets are referenced by the DDnames CSQINP1 and CSQINP2 defined in the MQSeries subsystem started task procedure.

Responses to these commands are written to the initialization output data sets referenced by the DDnames CSQOUT1 and CSQOUT2.

Initialization commands

Commands in the initialization input data sets are processed when MQSeries is initialized on MQSeries startup. Three types of command can be issued from the initialization input data sets:

- Commands to define MQSeries entities that cannot be recovered. For example:

  ```
  DEFINE BUFFPOOL
  DEFINE PSID
  ```

  Note: This set of DEFINE commands specifically excludes MQSeries objects.

  These commands must reside in the data set identified by the DDname CSQINP1. They are processed before the restart phase of initialization. They cannot be issued through the console, operations and control panels, or an application program. The responses to these commands are written to the sequential data set that you refer to in the CSQOUT1 statement of the started task procedure.

- Commands to define MQSeries objects that are recoverable after restart. These objects are listed in “Objects and commands” on page 7. These definitions must be specified in the data set identified by the DDname CSQINP2. They are stored in page set zero. CSQINP2 is processed after the restart phase of initialization. The responses to these commands are written to the sequential data set that you refer to in the CSQOUT2 statement of the started task procedure.

- Commands to manipulate MQSeries objects. These commands must also be specified in the data set identified by the DDname CSQINP2. For example, the MQSeries-supplied data set CSQ4INP2 contains an ALTER QMGR command to specify a dead-letter queue for the subsystem. The response to these commands is written to the CSQOUT2 output data set.

Commands are restricted to a maximum of 32 762 characters.

If MQSeries objects are defined in CSQINP2, MQSeries attempts to redefine them each time the MQSeries subsystem is started. If the queues already exist, the attempt to define them fails. You can avoid this problem by using the REPLACE parameter of the DEFINE commands as described in the *MQSeries Command Reference* manual.

Initialization commands for distributed queuing

You can also use the CSQINP2 initialization data set for the START CHINIT command, and follow it with a series of other commands to define your distributed queuing environment (for example, defining your channels). If you stop and restart the channel initiator however, CSQINP2 is not reprocessed, so MQSeries provides a third initialization input data set, called CSQINPX, that you can choose to process as part of the channel initiator started task procedure.

The MQSC commands contained in the data set are executed at the end of channel initiator initialization, and output is written to the data set specified by the CSQOUTX DD statement. The output is similar to that produced by the COMMAND function of the MQSeries utility program (CSQUTIL). See “MQSeries utility program (CSQUTIL)” on page 235 for information about the MQSeries utility program.

You can specify any of the MQSC commands that can be issued from CSQUTIL, not only the channel commands. You can enter commands from other sources while CSQINPX is being processed. All commands are issued in sequence, regardless of the success of the previous command.

To specify a command response time, you can use the pseudo-command COMMAND as the first command in the data set. This takes a single optional keyword RESPTIME(*nnn*), where *nnn* is the time, in seconds, to wait for a response to each of the commands. This is in the range 5 through 999; the default is 30. If MQSeries detects that the responses to four commands have taken too long, processing of CSQINPX is stopped and no further commands are issued. The channel initiator is not stopped, but message CSQU052E is written to the CSQOUTX data set, and message CSQU013E is sent to the console. When MQSeries has completed processing of CSQINPX successfully, message CSQU012I is sent to the console.

Initialization data set formats

The initialization input data sets can be partitioned data set (PDS) members or sequential data sets. They can be a concatenated series of data sets. Define them with a record length of 80 bytes, where:

- Only columns 1 through 72 are significant. Columns 73 through 80 are ignored.
- Records with an asterisk (*) in column 1 are interpreted as comments and are ignored.
- Blank records are ignored.
- Each command must start on a new record.
- A trailing - means continue from column 1 of the next record.
- A trailing + means continue from the first non-blank column of the next record.
- The maximum number of characters permitted in a command is 32762.

If you use a sequential data set for CSQINP1 or CSQINP2, the data set remains allocated to the queue manager started task while the queue manager is active. During this time, it is not available for editing; if you want to change the data set, you must first stop the queue manager. The same applies to CSQINPX for the duration of the channel initiator started task.

The initialization output data sets are sequential data sets, with a record length of 125, a record format of VBA, and a block size of 629.

Initialization data set samples

The following sample initialization data set members are supplied with MQSeries:

For CSQINP1

thlqual.SCSQPROC(CSQ4INP1)

For CSQINP2

thlqual.SCSQPROC(CSQ4INSG)
thlqual.SCSQPROC(CSQ4INSX)
thlqual.SCSQPROC(CSQ4INYG)
thlqual.SCSQPROC(CSQ4INYD)
thlqual.SCSQPROC(CSQ4INYC)

Other

thlqual.SCSQPROC(CSQ4DISP)
thlqual.SCSQPROC(CSQ4DISQ)
thlqual.SCSQPROC(CSQ4IVP)
thlqual.SCSQPROC(CSQ4INPX)

To preserve the originals, you should make working copies of each sample. Then you can tailor the commands in these working copies to suit your system requirements.

If you intend to define more than one MQSeries subsystem, you are recommended to include the subsystem name in the high-level qualifier of the initialization input data set name. This allows you to identify more easily the MQSeries subsystem associated with each data set.

Using the CSQINP1 sample

The sample CSQINP1 data set thlqual.SCSQPROC(CSQ4INP1) contains definitions of buffer pools, page set to buffer pool associations, MAXSMSGS, and an ALTER SECURITY command. The sample should be included in the CSQINP1 concatenation of your MQSeries started task procedure.

Notes:

1. MQSeries supports up to four buffer pools (0 through 3). The DEFINE BUFFPOOL command can only be issued from a CSQINP1 initialization data set. The definitions in the sample specify four buffer pools.
2. Each page set used by the subsystem must be defined in the CSQINP1 initialization data set by using the DEFINE PSID command. The page set definition associates a buffer pool ID with a page set. If no buffer pool is specified, buffer pool 0 is used by default.

   Page set zero (00) must be defined. It contains all the object definitions. You can define up to 100 page sets for each MQSeries subsystem.
3. The DEFINE MAXSMSGS command defines the maximum number of **MQGET** and **MQPUT** calls that can be made within an MQSeries unit of recovery. In CSQ4INP1, the default value for MAXSMSGS is defined as 10000.

4. The ALTER SECURITY command can be used to alter the security attributes TIMEOUT and INTERVAL. In CSQ4INP1, the default values are defined as 54 and 12 respectively.

See “An overview of storage management” on page 15 for information about organizing buffer pools and page sets.

Using the CSQINP2 samples

CSQ4INSG and CSQ4INSX contain system object definitions that can be included in the CSQINP2 concatenation of your MQSeries started task procedure. CSQ4INYG, CSQ4INYD, and CSQ4INYC contain some definitions that you can customize for your own objects.

CSQ4INSG system object sample

The sample CSQINP2 data set thlqual.SCSQPROC(CSQ4INSG) contains definitions for system objects for general use, which comprise:

- System default objects
- System command objects
- Event reporting objects

You must define the objects in this sample, but you need to do it only once when the subsystem is first started. Including the definitions in the CSQINP2 data set is the best way to do this. They are maintained across MQSeries subsystem shutdown and restart. You must not change the object names, but you can change their attributes if required.

If you attempt to define objects that already exist, you get messages similar to the following:

```
CSQM095I +cpf CSQMMSGP QLOCAL(SYSTEM.DEFAULT.LOCAL.QUEUE) ALREADY EXISTS
CSQM090E +cpf CSQMMSGP FAILURE REASON CODE X'00D44003'
CSQ9023E +cpf CSQMMSGP ' DEFINE QLOCAL' ABNORMAL COMPLETION
```

The objects are not damaged by this failure. If you want to leave the SYSTEM definitions data set in the CSQINP2 concatenation, you can avoid the failure messages by specifying the REPLACE attribute against each object.

System default objects: The names of the default system object definitions begin with the characters “SYSTEM.DEFAULT” or “SYSTEM.DEF”. For example, the system default local queue is named:

```
SYSTEM.DEFAULT.LOCAL.QUEUE
```

The sample describes how you can tailor these objects. These objects define the system defaults for the attributes of these MQSeries objects:

- Local queues
- Model queues
- Alias queues
- Remote queues
- Processes
- Namelists
- Channels (for distributed queuing without CICS)
- Storage classes

These default objects are used by DEFINE commands if no LIKE attribute is specified.

System command objects: The names of the system command objects begin with the characters SYSTEM.COMMAND.

There are two system-command objects:

1. The system-command input queue is a local queue on which commands are put before they are processed by the MQSeries command processor. It must be called SYSTEM.COMMAND.INPUT, and for normal operation it must have these attributes:
   - MAXSMSGL(32 762)
   - USAGE(NORMAL)
   - DEFSOPT(EXCL)
   - NOTRIGGER

   You can specify any of the other local queue attributes as required.
2. SYSTEM.COMMAND.REPLY.MODEL is a model queue that defines the system-command reply-to queue.

You must define these objects before the MQSeries operations and control panels can be used to issue commands to an MQSeries subsystem.

Commands are normally sent using nonpersistent messages so both the system-command objects should have the DEFPSIST(NO) attribute. However, in case you wish an application to use persistent messages for commands, you should set the DEFTYPE(PERMDYN) attribute for the reply-to queue.

Event reporting objects: The names of the event reporting objects begin with the characters SYSTEM.ADMIN.

There are three system-administration objects:

- The SYSTEM.ADMIN.QMGR.EVENT queue
- The SYSTEM.ADMIN.PERFM.EVENT queue
- The SYSTEM.ADMIN.CHANNEL.EVENT queue

These queues are used for event messages; for more information about using MQSeries events, see the *MQSeries Programmable System Management* manual.

CSQ4INSX system object sample

Additional system queues must be defined in order to use non-CICS distributed queuing and clustering. The member CSQ4INSX in the thlqual.SCSQPROC library contains the queue definitions required. You can include this member in the CSQINP2 DD concatenation of the MQSeries startup procedure, or you can use the COMMAND function in CSQUTIL utility to issue the required DEFINE commands.

There are two types of object definitions:

- SYSTEM.CHANNEL.xx, needed for any distributed queuing
- SYSTEM.CLUSTER.xx, needed for clustering

Channel queues: Distributed queuing requires queues for use with sequence numbers and logical units of work identifiers (LUWID). You must ensure that a queue is available with the name SYSTEM.CHANNEL.SYNCQ. To improve

channel performance, you should define this queue with an index type of MSGID (as shown in the supplied sample queue definitions). Queue indexes are described in the *MQSeries Command Reference*.

You need to ensure that channel command queues exist for your system with the names SYSTEM.CHANNEL.INITQ and SYSTEM.CHANNEL.REPLY.INFO. You also need to ensure that the channel initiator has access to the SYSTEM.COMMAND.INPUT queue (both to get and put messages).

Cluster queues: To use MQSeries clusters, you need to define the following objects:

- A local queue called the SYSTEM.CLUSTER.COMMAND.QUEUE, which is used to communicate repository changes between queue managers. Messages written to this queue contain updates to the repository data to be applied to the local copy of the repository, or requests for repository data.
- A local queue called SYSTEM.CLUSTER.REPOSITORY.QUEUE, which is used to hold a persistent copy of the repository.
- A local queue called SYSTEM.CLUSTER.TRANSMIT.QUEUE, which is the transmission queue for all destinations in the cluster. For performance reasons you should define this queue with an index type of CORRELID (as shown in the sample queue definitions).

These queues typically contain large numbers of messages.

Cluster queue managers and repositories are described in the *MQSeries Queue Manager Clusters* manual.

CSQ4INYG object sample

The member CSQ4INYG in the thlqual.SCSQPROC library contains sample definitions that you can use for customizing your own objects for general use. It comprises:

- Storage classes
- Recommended queues
- CICS adapter objects

You cannot use this sample as is, you must customize it before use. Then you can include this member in the CSQINP2 DD concatenation of the MQSeries startup procedure, or you can use the COMMAND function of the CSQUTIL utility to issue the required DEFINE commands.

In addition to the sample definitions here, you can use the system object definitions as the basis for your own resource definitions. For example, you could make a working copy of SYSTEM.DEFAULT.LOCAL.QUEUE and name it MY.DEFAULT.LOCAL.QUEUE. You can then change any of the parameters in this copy as required. You could then issue a DEFINE command by whichever method you choose, provided you have the authority to create resources of that type.

Storage classes: Four storage classes (SYSTEM, REMOTE, DEFAULT, and NODEFINE) are required because they are used by other object definitions. Modify their attributes and add other storage classes as required.

Notes:

1. A storage class can only be changed when:
   - All queues that use this storage class are empty, and have no uncommitted activity.
   - All queues that use this storage class are closed.
2. If a message is put on a queue that names a non-existent storage class, the calling program will receive error MQRC_STORAGE_CLASS_ERROR. Alter the queue definition to give it an existing storage class name, or create the storage class named by the queue.
3. If a queue is defined and no storage class is explicitly assigned, the DEFAULT storage class is assigned automatically by MQSeries.

Recommended queues: You are recommended to have two special purpose queues of your own; a default transmission queue and a dead-letter queue. The default transmission queue is used when sending messages to another queue manager and no other suitable transmission queue is available.

The dead-letter queue is used if the message destination is not valid. The queue manager puts such messages on a local queue called the dead-letter queue. Although having a dead-letter queue is not mandatory, it should be regarded as essential, especially if you are using either distributed queuing or one of the MQSeries bridges.

In addition to defining these queues you also need to tell the queue manager their names. To do this use the ALTER QMGR command, as shown in the sample.

CICS adapter objects: The sample defines an initiation queue named CICS01.INITQ. This queue is used by the MQSeries-supplied CKTI transaction. You can change the name of this queue; however it must match the name specified in the CICS system initialization table (SIT) or SYSIN override in the INITPARM statement:

```
INITPARM=(CSQCPARM='IQ=CICS01.INITQ,...')
```

This example shows you how to define the initiation queue name in INITPARM. For more details, see the sample INITPARM in Figure 14 on page 126 and the accompanying notes.

CSQ4INYD object sample

If you are using distributed queuing (non-CICS) and not clustering, you need to set up your own queues, processes, and channels. The member CSQ4INYD in the thlqual.SCSQPROC library contains sample definitions that you can use for customizing your distributed queuing objects. It comprises:

- A set of definitions for the sending end
- A set of definitions for the receiving end
- A set of definitions for using clients

You cannot use this sample as is; you must customize it before use. Then you can include this member in the CSQINP2 DD concatenation of the MQSeries startup procedure, or you can use the COMMAND function of the CSQUTIL utility to issue the required DEFINE commands.

CSQ4INYC object sample

If you are using clustering, definitions equivalent to the channel definitions and remote queue definitions of distributed queuing are created automatically, when needed. However, some manual channel definitions are needed – a cluster-receiver channel for the cluster, and a cluster-sender definition to at least one cluster repository queue manager.

The member CSQ4INYC in the thlqual.SCSQPROC library contains sample definitions that you can use for customizing your clustering objects. It comprises:

- Definitions for the queue manager
- Definitions for the receiving channel
- Definitions for the sending channel
- Definitions for cluster queues
- Definitions for lists of clusters

You cannot use this sample as is; you must customize it before use. Then you can include this member in the CSQINP2 DD concatenation of the MQSeries startup procedure, or you can use the COMMAND function of the CSQUTIL utility to issue the required DEFINE commands.

Using the other samples

This section describes the other sample definitions that are supplied.

CSQ4DISP display sample

The sample thlqual.SCSQPROC(CSQ4DISP) contains a set of generic DISPLAY commands that display all the defined resources on your MQSeries subsystem. This includes the definitions for all MQSeries objects and definitions such as storage classes and trace. These commands can generate a large amount of output. This sample can be used in the CSQINP2 data set or as input to the COMMAND function of the CSQUTIL utility.

CSQ4DISQ distributed queuing using CICS sample

The sample thlqual.SCSQPROC(CSQ4DISQ) contains a set of commands that are required to implement distributed queuing using CICS ISC. For more information see Appendix D, “Enabling distributed queuing using CICS ISC” on page 491.

You can include this member in the CSQINP2 DD concatenation of the MQSeries startup procedure, or you can use the COMMAND function of the CSQUTIL utility to issue the required DEFINE commands.

CSQ4IVP sample

The sample thlqual.SCSQPROC(CSQ4IVP) contains a set of DEFINE commands that are required to run the installation verification program (IVP). For more information, see “Running the installation verification program CSQ4IVP1” on page 105.

You can include this sample in the CSQINP2 data set. Once you have successfully run the IVP, you do not need to run it each time MQSeries is restarted. Therefore, you do not need to keep CSQ4IVP permanently in the CSQINP2 concatenation.

CSQ4INPX sample

The sample thlqual.SCSQPROC(CSQ4INPX) contains a set of commands that you might want to execute each time the channel initiator starts. You must customize this sample before use; you can then include it in the CSQINPX data set for the channel initiator.

Task 11: Create the bootstrap and log data sets

- *Repeat this task for each MQSeries subsystem.*

Use the supplied program CSQJU003 to prepare the bootstrap data sets (BSDSs) and log data sets. You must run this job once for each subsystem you want to define. The sample JCL and Access Method Services (AMS) control statements to run CSQJU003 to create a single or dual logging environment are held in thlqual.SCSQPROC(CSQ4BSDS). Customize and run this job to create your BSDSs and logs.

The startup procedure, CSQ4MSTR, described in "Task 7: Create procedures for the MQSeries subsystem" on page 49, refers to BSDSs in statements of the form:

```
//BSDS1     DD DSN=++HLQ++.BSDS01,DISP=SHR
//BSDS2     DD DSN=++HLQ++.BSDS02,DISP=SHR
```

The log data sets are referred to by the BSDSs.

Notes:

1. The BLKSIZE must be specified on the SYSPRINT DD statement in the CSQTLOG step. The BLKSIZE must be 629.
2. To help identify bootstrap data sets and log data sets from different MQSeries subsystems, include the subsystem name in the high level qualifier of these data sets.
3. A typical size for each BSDS might be 500 KB.
4. The number of records to specify in the cluster for each log data set is:

   ```
   Number of records = (a * log switch interval required in seconds) / 4096

     where
           a = (Number of MQPUTs/sec * (Average message size + 440))
              + (Number of MQGETs/sec * 72)
              + (Number of units of recovery started  * 100)
              + (Number of syncpoints per second * 196)

     and
           log switch interval = time period between successive
                                 log switches
   ```

   Each log data set should have the same number of records specified and should not have secondary extents. Other than for a very small number of records, AMS rounds up the number of records so that a whole number of cylinders is allocated. The number or records actually allocated is:

   ```
   c = (INT (number of log records / b) + 1) * b

   Where b is the number of 4096-byte blocks per cylinder (180 for a
   3390 device) and INT means round down to an integer
   ```

5. You are recommended to have at least three log data sets, and to use dual logging and log archiving. The following table shows suggested values for log and bootstrap data set definitions that affect the performance of queue

manager operation, recovery, and restart. Two sets of values are given; one set is suitable for a test system, the other for a production system or a system that will become a production system.

Table 9. Suggested test and production definitions for log and bootstrap data sets

Definition setting	Test system	Production system
Log data set size[1,2]	10 000 records (40 MB approx.) Access Method Services rounds to nearest cylinder and allocates 10 080 records.	180 000 records (700 MB or 1 000 cylinders of 3390)
Number of active logs[1,3]	3	6
BSDS size	60 records (240 KB approx.)	120 records (480 KB approx.) A primary extent of this size should be sufficient for the maximum number of archive logs that can be recorded in the BSDS (1 000).

Notes:

1. The optimum value for this definition is dependent on the characteristics of the individual system. The values given are intended as a guideline only and might not be appropriate for your system.
2. For more information about the recommended size for log data sets, refer to "How large should the active logs be?" on page 498.
3. For more information about the recommended number of active log data sets, refer to "How many active log data sets do you need?" on page 498.

Chapter 17, "Understanding the log and the bootstrap data set" on page 305 also gives more information about log and bootstrap data sets.

Task 12: Define your page sets

- *Repeat this task for each MQSeries subsystem.*

You must define separate page sets for each MQSeries subsystem. thlqual.SCSQPROC(CSQ4PAGE) contains JCL and AMS control statements to define and format four page sets. The JCL runs the supplied utility program CSQUTIL.

The startup procedure CSQ4MSTR described in "Task 7: Create procedures for the MQSeries subsystem" on page 49 refers to the page sets, in a statement of the form:

```
//CSQP00nn  DD DISP=OLD,DSN=xxxxxxxxx
```

where *nn* is the page set number between 00 and 99, and *xxxxxxxxx* is the data set that you define.

Notes:

1. Each MQSeries subsystem must have a page set 00. This is where all the object definitions used by the queue manager are kept. You should avoid putting messages on page set 00 for the reasons discussed in "Page set zero" on page 16.
2. Each MQSeries subsystem can have a maximum of 100 page sets.
3. If you intend to allow the FORCE option to be used with the FORMAT function of the utility program CSQUTIL, you must add the REUSE attribute on the AMS DEFINE CLUSTER statement. See page 237 for details.
4. If you intend to use the dynamic page set expansion feature, ensure that secondary extents are defined for each page set. thlqual.SCSQPROC(CSQ4PAGE) shows how to do this.
5. To help identify page sets from different MQSeries subsystems, include the subsystem name in the high level qualifier of the data set associated with each page set.
6. MQSeries attempts to keep data in virtual storage buffer pools for as long as it can (subject to demands for buffer pool storage). This means that the page set storage required is that to hold the maximum amount of data held in the system. If the system is closed down (using the STOP command), all the data held in the buffer pools is flushed out to DASD.

   For queue manager object definitions (for example, queues and processes), it is simple to calculate the storage requirement because these objects are of fixed size and are permanent. For messages however, the calculation is more complex for the following reasons:

   - Messages vary in size.
   - Messages are transitory.
   - Space occupied by messages that have been retrieved is reclaimed periodically by an asynchronous process.

"Calculating the storage requirement for messages" on page 64 describes how to calculate the space requirement for messages.

7. For page set zero, the storage required is:

```
   (maximum number of local queue definitions x 1010)
+  (maximum number of model queue definitions x 746)
+  (maximum number of alias queue definitions x 338)
+  (maximum number of remote queue definitions x 434)
+  (maximum number of permanent dynamic queue definitions x 1010)
+  (maximum number of process definitions x 674)
+  (maximum number of namelist definitions x 12320)
+  (maximum number of message channel definitions x 1010)
+  (maximum number of client-connection channel definitions x 1714)
+  (maximum number of server-connection channel definitions x 1010)
+  (maximum number of cluster-receiver channel definitions x 1010)
+  (maximum number of cluster-sender channel definitions x 1010)
+  (maximum number of storage class definitions x 266)
```

   Divide this value by 4096 to determine the number of records to specify in the cluster for the page set data set.

8. The total number of objects that can be created is limited by the capacity of page set zero. There is an implementation limit on the number of local queues that can be defined, which is 524 287.

9. For page sets 01 to 99, the storage required for each page set is determined by the number and size of the messages stored on that page set.

   "Calculating the storage requirement for messages" describes how to calculate the space requirement for messages. Divide this value by 4096 to determine the number of records to specify in the cluster for the page set data set.

Additional guidance on setting up your page sets is given in Appendix E, "Defining your queue manager environment parameters" on page 497.

Calculating the storage requirement for messages

This section describes how messages are stored on pages. Understanding this will help you calculate how much page set storage you need to define for your messages. To calculate the approximate space required for all messages on a page set you must consider maximum queue depth of all the queues that map to the page set and the average size of messages on those queues.

You must allow for the possibility that message "gets" might be delayed for reasons outside the control of MQSeries (for example, because of a problem with your communications protocol). In this case, the "put" rate of messages might far exceed the "get" rate. This could lead to a large increase in the number of messages stored in the page sets and a consequent increase in the storage size demanded.

Each page in the page set is 4096 bytes long. Allowing for fixed header information, each page has 4057 bytes of space available for storing messages.

When calculating the space required for each message, the first thing you need to consider is whether the message will fit on one page (a *short message*) or whether it needs to be split over two or more pages (a *long message*). When messages are split in this way, you need to allow for additional control information in your space calculations.

For the purposes of space calculation, a message can be represented like this:



The message header section contains the message descriptor (352 bytes) and other control information, the size of which varies depending on the size of the message. The message data section contains all the actual message data, and any other headers (for example, the transmission header or the IMS bridge header).

A minimum of two pages are required for page set control information. This is typically less than 1% of the total space required for messages.

Short messages

A short message is defined as a message that will fit on one page.

For a short message the control information is 20 bytes long. When this is added to the length of the message header, the usable space remaining on the page is 3685 bytes. If the size of the message data is 3685 bytes or less, MQSeries stores the messages in the next available space on the page, or if there is not enough space available, on the next page, as shown below:



If there is enough space remaining on the page, the next message is also stored on this page, if not, the remaining space on the page is left unused.

Long messages

If the size of the message data is greater than 3685 bytes, the message is classed as a long message. When presented with a long message, MQSeries stores the message on a series of pages, and stores control information that points to these pages in the same way that it would store a short message.



Each segment of the long message is preceded by 8 bytes of control information, and the first segment also includes the message header portion of 352 bytes. This means that the first page contains 3697 bytes of the message data. The remaining message data is placed on subsequent pages, in 4049-byte segments. If this does not fill an exact number of pages, the remaining space in the last page is left unused.

The number of pages (n) used for a long message is calculated as follows:

```
     message data length + 352
n = -------------------------
                4049

rounded up to the nearest page
```

In addition to this, you need to allow space for the control information that points to the pages. The length of this (c) depends on the length of the message, and is calculated as follows:

```
c = 20 + (3n) bytes

(where n is the number of pages calculated above)
```

This means that the total page set space required for a long message is:

```
(n * 4096) + c bytes
```

Each page has 4057 bytes available for short messages and other control information, and so c must be less than 4057 bytes.

Enabling dynamic page set expansion

Page sets can be extended dynamically while MQSeries is running. A page set can have up to 123 extents, which can exist on multiple disk volumes.

Note: The maximum number of extents for a page set cataloged in an ICF catalog is between 119 and 123, depending upon the number of extents (1-5) allocated by direct access storage data management (DADSM) per allocate/extend request.

In order to use this facility, your page sets must be allocated with secondary extent values defined. If you have existing page set definitions, they cannot be altered to

add secondary extent definitions. You will have to re-allocate each of your page sets with secondary extents, and then use the COPYPAGE function of CSQUTIL to copy the old versions of the page sets to the new ones.

thlqual.SCSQPROC(CSQ4PAGE) shows how to define the secondary extents, and Chapter 14, “Using the MQSeries utilities” on page 233 gives information about using CSQUTIL.

How to determine an appropriate secondary extent value

You might decide the secondary extent value by considering how many times the page set should exceed its original value. For instance, if your page set primary allocation is 1000 units (records/pages, tracks, cylinders, kilobytes, megabytes), and you want it to grow to be at most four times that size, then determine the secondary extent size from:

$$\frac{(\text{maximum size} - \text{original size})}{119}$$

In this case, $\frac{4000 - 1000}{119} = \frac{3000}{119} = 25 \text{ or } 26$

However, see “Number of extents available” for a description of why you might not be able to use this much disk space.

Note: If you define the size of your extent in records, IDCAMS rounds this up to map onto a physical boundary. The queue manager uses all this space for the secondary extent.

Multivolume data sets

If the definition of a page set allows it to utilize multiple volumes, the primary space is wholly contained on the first volume, and secondary extents are first allocated on the same volume, while space is available, and thereafter the next volume is used, while space is available, and so on. The process stops when you have used all the secondary extents, or no more disk space is available.

Note: This behavior differs if the page set is a data set managed by Storage Management Subsystem (SMS), and you use a storage class that uses the **GUARANTEED SPACE** attribute. Then the multivolume processing differs in that a primary extent is allocated on each volume when the page set is defined. Thereafter, secondary extents are allocated, as before, except that when the services of a new volume are required, the pre-allocated secondary extent is used.

Number of extents available

Note that the Data Facility Product (DFP) uses up to five non-contiguous areas of disk to satisfy the total space requirements of a primary or secondary extent. This means, in the worst case of badly fragmented disk space, that you might only get around 22 times the secondary space allocated before you reach the maximum extent limit.

Task 13: Tailor your system parameter module

- *Repeat this task for each MQSeries subsystem, as required.*

The MQSeries system parameter module controls the logging, archiving, tracing, and connection environments that MQSeries uses in its operation. The system parameter module has three macros as follows:

Macro name	Purpose
CSQ6SYSP	Specifies the connection and tracing parameters, see page 69
CSQ6LOGP	Controls log initialization, see page 76
CSQ6ARVP	Controls archive initialization, see page 79

MQSeries supplies a default system parameter module, CSQZPARM, which is invoked automatically if you issue the START QMGR command (without a PARM parameter) to start an instance of MQSeries. CSQZPARM is in the APF-authorized library thlqual.SCSQAUTH also supplied with MQSeries. The values of these parameters are displayed as a series of messages when you start MQSeries.

See the *MQSeries Command Reference* manual for more information about the START command and “Starting MQSeries” on page 198 for more information about how this command is used.

Creating your own system parameter module

If CSQZPARM does not contain the system parameters you want, you can create your own system parameter module using the sample JCL provided in thlqual.SCSQPROC(CSQ4ZPRM).

To create your own system parameter module:

1. Make a working copy of the JCL sample.
2. Edit the parameters for each macro in the copy as required. If you remove any parameters from the macro calls, the default values are automatically picked up at run time.
3. Replace the placeholder `++NAME++` with the name that the load module is to take (this can be CSQZPARM).
4. If your assembler is not high level assembler, change the JCL as required by your assembler.
5. Run the JCL to assemble and link-edit the tailored versions of the system parameter macros to produce a load module. This is the new system parameter module with the name that you have specified.
6. Put the load module produced in an APF-authorized user library.
7. Include this library in the MQSeries started task procedure STEPLIB. This library name must come before the library thlqual.SCSQAUTH in STEPLIB.

8. Invoke the new system parameter module when you start MQSeries. For example, if the new module is named NEWMODS, issue the command:

   ```
   START QMGR PARM(NEWMODS)
   ```

Note: If you choose to name your module CSQZPARM, you do not need to specify the PARM parameter on the START QMGR command.

Fine tuning a system parameter module

MQSeries also supplies a set of three assembler source modules, which can be used to fine tune an existing system parameter module. These modules are in library thlqual.SCSQASMS. Typically, you use these modules in a test environment to change the default parameters in the system parameter macros. Each source module calls a different system parameter macro:

This assembler source module...	Calls this macro...
CSQFSYSP	CSQ6SYSP (connection and tracing parameters)
CSQJLOGP	CSQ6LOGP (log initialization)
CSQJARVP	CSQ6ARVP (archive initialization)

This is how you use these modules:

1. Make working copies of each assembler source module in a user assembler library.
2. Edit your copies by adding or altering the values of any parameters as required.
3. Assemble your copies of any edited modules to create object modules in a user object library.
4. Link-edit these object code modules with an existing system parameter module to produce a load module that is the new system parameter module.
5. Ensure that new system parameter module is a member of a user authorized library.
6. Include this library in the MQSeries started task procedure STEPLIB. This library must come before the library thlqual.SCSQAUTH in STEPLIB.
7. Invoke the new system parameter module by issuing a START QMGR command, specifying the new module name in the PARM parameter, as before.

Using CSQ6SYSP

Use CSQ6SYSP to set system parameters.

The default parameters for CSQ6SYSP are shown in Table 10. If you want to change any of these values, refer to the detailed descriptions of the parameters.

Table 10 (Page 1 of 2). Default values of CSQ6SYSP parameters

Parameter	Description	Default value
CMDUSER	The default user ID for command security checks.	CSQOPR

Table 10 (Page 2 of 2). Default values of CSQ6SYSP parameters

Parameter	Description	Default value
CTHREAD	Maximum number of connections from batch, CICS, IMS, and TSO tasks to a single instance of MQSeries.	300
EXITLIM	Time (in seconds) for which queue-manager exits can execute during each invocation.	30
EXITTCB	How many started server tasks to use to run queue manager exits.	8
IDBACK	Maximum number of connections to a single instance of MQSeries from batch or TSO background tasks.	20
IDFORE	Maximum number of connections to a single instance of MQSeries from TSO foreground tasks.	100
LOGLOAD	Number of log records written by MQSeries between the start of one checkpoint and the next.	10 000
OTMACON	OTMA connection parameters.	See below
QMCCSID	Coded character set identifier for the queue manager.	0
ROUTCDE	Message routing code assigned to messages not solicited from a specific console.	1
SMFACCT	Specifies whether SMF accounting data is to be collected when MQSeries is started.	NO
SMFSTAT	Specifies whether SMF statistics are to be collected when MQSeries is started.	NO
STATIME	Default time (in minutes) between each gathering of statistics.	30
TRACSTR	Specifies whether tracing is to be started automatically.	NO
TRACTBL	Size of trace table, in 4 KB blocks, to be used by the global trace facility.	99 (396 KB)
WLMTIME	Time (in minutes) between scanning the queue index for WLM-managed queues.	30

CMDUSER

Specifies the default user ID used for command security checks. This user ID must be defined to the ESM (for example, RACF). Specify a name of 1 through 8 alphanumeric characters. The first character must be alphabetic.

The default is CSQOPR.

CTHREAD

Specifies the maximum number of connections from batch, CICS, IMS, TSO, and the channel initiator to a single instance of MQSeries.

CICS connections are not limited in the same way as TSO and batch connections. During the connection of the main CICS TCB to MQSeries, the adapter attempts to attach up to eight OS/390 subtasks (TCBs) to be used by this CICS system. This means each CICS system connected takes up nine of the connections specified on CTHREAD, so you must increase CTHREAD by

nine for each CICS system connected. You must also increase the value of CTHREAD by one for each instance of the task initiator CKTI.

For IMS connections, the number of connections required is one for the control region, and one for each dependant region connected to MQSeries. For each IMS MPP or IFP region that is defined to permit MQSeries connections through either a specific SSM= EXEC parameter or through the control region default, a thread is created when the first application is scheduled in that region, regardless of whether that application invokes any MQSeries calls. The value you set for CTHREAD should take account of this.

For distributed queuing (without CICS), the number of connections required by the channel initiator address space depends on the number of adapter subtasks and dispatchers there will be; see “Using CSQ6CHIP” on page 87.

When the number of connections reaches the limit set by CTHREAD, any further requests for a connection are suspended until a spare slot becomes available. For example, an **MQDISC** call releases that connection. For planning purposes, the value of CTHREAD must be greater than the maximum of IDBACK, IDFORE, and the number of potential connections from the CICS, IMS, and channel initiator address spaces.

Specify a number in the range 1 through 32 767.

The default is 300.

Note that this controls the number of *connections*; a connection might involve more than one thread. See “Connections and threads” on page 286 for more information.

EXITLIM

Specifies the time, in seconds, allowed for each invocation of the queue manager exits. (This parameter has no effect on channel exits.)

Specify a value in the range 5 through 9999.

The default is 30. The queue manager polls exits that are running every 30 seconds. On each poll, any that have been running for more than the time specified by EXITLIM are forcibly terminated.

EXITTCB

Specifies the number of started server tasks to use to run exits in the queue manager. (This parameter has no effect on channel exits.)

Specify a value in the range 0 through 99. A value of 0 means that no exits can be run.

The default is 8.

IDBACK

Specifies the maximum number of background batch and TSO connections to a single instance of MQSeries. The value of IDBACK is related to those of IDFORE and CTHREAD. See the description of the CTHREAD parameter for more information.

Specify a number in the range 1 through 32 767.

The default is 20.

IDFORE
Specifies the maximum number of TSO foreground connections to MQSeries.

The value of IDFORE is related to those of IDBACK and CTHREAD. See the description of the CTHREAD parameter for more information.

The number of TSO connections might be greater than the number of concurrent TSO users if, for example, users split their ISPF screens.

Specify a number in the range 0 through 32 767.

The default is 100.

LOGLOAD
Specifies the number of log records that MQSeries writes between the start of one checkpoint and the next. MQSeries starts a new checkpoint after the number of records that you specify has been written.

Specify a value in the range 200 through 16 000 000.

The default is 10 000.

The greater the value, the better the performance of MQSeries; however, restart takes longer if the parameter is set to a large value.

Suggested settings:

Test system 10 000 (default)

Production system 500 000

In a production system, the supplied default value might result in a checkpoint frequency that is too high.

The value of LOGLOAD determines the frequency of queue manager checkpoints. Too large a value means that a large amount of data is written to the log between checkpoints, resulting in an increased queue manager forward recovery restart time following a failure. Too small a value causes checkpoints to occur too frequently during peak load, adversely affecting response times and CPU usage.

An initial value of 500 000 is suggested for LOGLOAD. (For example, this adds approximately 90 seconds to the restart time after a failure if using RAMAC® Virtual Array 2 Turbo 82 (RVA2-T82) DASD.) For a 1 KB persistent message rate of 100 messages per second (that is, 100 **MQPUT**s with commit and 100 **MQGET**s with commit) the interval between checkpoints will be approximately 5 minutes.

Note: This is intended as a guideline only and the optimum value for this parameter is dependent on the characteristics of the individual system.

OTMACON
OTMA parameters. This keyword takes five positional parameters, as shown below:

OTMACON = (`Group,Member,Druexit,Age,TpipePrefix`**)**

Group
This is the name of the XCF group to which this particular instance of MQSeries belongs.

It can be 1 through 8 characters long and must be entered in uppercase characters.

The default is blanks, which indicates that MQSeries should not attempt to join an XCF group.

Member
This is the member name of this particular instance of MQSeries within the XCF group.

It can be 1 through 16 characters long and must be entered in uppercase characters.

The default is the 4-character queue manager name.

Druexit
This specifies the name of the OTMA destination resolution user exit to be run by IMS.

It can be 1 through 8 characters long.

The default is DFSYDRU0.

This parameter is optional; it is required if MQSeries is to receive messages from an IMS application that was not started by MQSeries. The name should correspond to the destination resolution user exit coded in the IMS system. For more information see Appendix B, “Using OTMA exits in IMS” on page 483.

Age
This represents the length of time, in seconds, that a user ID from MQSeries is considered previously verified by IMS.

It can be in the range 0 through 2 147 483 647.

The default is 2 147 483 647.

TpipePrefix
This represents the prefix to be used for Tpipe names.

It comprises three characters; the first character is in the range A through Z, subsequent characters are A through Z or 0 through 9. The default is CSQ.

This is used each time MQSeries creates a Tpipe; the rest of the name is assigned by MQSeries. You cannot set the full Tpipe name for any Tpipe created by MQSeries.

QMCCSID
Specifies the default coded character set identifier that the queue manager (and therefore distributed queuing) is to use.

Specify a value in the range 0 through 65 535. 0 means use the CCSID currently set or, if none is set, use CCSID 500.

The default is 0.

ROUTCDE
Specifies the default OS/390 message routing code assigned to messages that are not sent in direct response to an MQSeries command.

Specify one of:

1. A value in the range 1 through 16, inclusive.

2. A list of values, separated by a comma and enclosed in parentheses. Each value must be in the range 1 through 16, inclusive.

The default is 1.

For more information about OS/390 routing codes, see the *MVS Routing and Descriptor Codes* manual.

SMFACCT
Specifies whether MQSeries sends accounting data to SMF automatically when MQSeries starts.

Specify one of:

NO Do not start gathering accounting data automatically.
YES Start gathering accounting data automatically for the default class 1.

The default is NO.

SMFSTAT
Specifies whether to gather SMF statistics automatically when MQSeries starts.

Specify one of:

NO Do not start gathering statistics automatically.
YES Start gathering statistics automatically for the default class 1.

The default is NO.

STATIME
Specifies the default time, in minutes, between each gathering of statistics.

Specify a number in the range 1 through 1440.

The default is 30.

TRACSTR
Specifies whether global tracing is to start automatically.

Specify one of:

NO Do not start global tracing automatically.

YES Start global tracing automatically for the default class, class 1.

integers A list of classes for which global tracing is to be started automatically in the range 1 through 4.

* Start global trace automatically for all classes.

The default is NO if you do not specify the keyword in the macro.

Note: The supplied default system parameter load module (CSQZPARM) has TRACSTR=YES (set in the assembler module CSQFSYSP). If you do not want to start tracing automatically, you can change this after you have successfully started your MQSeries subsystem. Refer to "Fine tuning a system parameter module" on page 69 for information about how do this.

For details about the START TRACE command, see the *MQSeries Command Reference* manual.

TRACTBL
Specifies the default size, in 4 KB blocks, of trace table where the global trace facility stores MQSeries trace records.

Specify a value in the range 1 through 999.

The default is 99. This is equivalent to 396 KB.

Note: Storage for the trace table is allocated in the ECSA. Therefore, you must select this value with care.

WLMTIME
Specifies the time (in minutes) between each scan of the indexes for WLM-managed queues.

Specify a value in the range 1 through 9999.

The default is 30.

Using CSQ6LOGP

Use CSQ6LOGP to establish your logging options.

The default parameters for CSQ6LOGP are shown in Table 11. If you need to change any of these values, refer to the detailed descriptions of the parameters.

Table 11. Default values of CSQ6LOGP parameters

Parameter	Description	Default value
INBUFF	Active and archive logs input buffer size.	28 KB
MAXALLC	Maximum number of archive log volumes that can be allocated.	3
MAXARCH	Maximum number of archive log volumes that can be recorded.	500
OFFLOAD	Archiving on or off.	YES (ON)
OUTBUFF	Size of output buffer storage for active and archive log data sets.	400 KB
TWOACTV	Single or dual active logging.	YES (dual)
TWOARCH	Single or dual archive logging.	YES (dual)
TWOBSDS	Single or dual BSDS.	YES (dual BSDS)
WRTHRSH	Number of output buffers to be filled before they are written to the active log data sets.	20

INBUFF

Specifies the size, in kilobytes, of the input buffer for reading the active and archive logs during recovery. Use a decimal number in the range 28 through 60. The value specified is rounded up to a multiple of 4.

The default is 28 KB.

Suggested settings:

Test system 28 KB (default)

Production system 60 KB

Set this to the maximum for best log read performance.

MAXALLC

Specifies the maximum number of archive log volumes that can be allocated concurrently for input mode. Archive log data sets are read when required for recovery, system restart, or dynamic backout. Use a decimal number in the range 1 through 99.

The default is 3.

For information about the logs, see Chapter 17, “Understanding the log and the bootstrap data set” on page 305.

MAXARCH

Specifies the maximum number of archive log volumes that can be recorded in the BSDS. When this number is exceeded, recording begins again at the start of the BSDS.

Use a decimal number in the range 10 through 1000.

The default is 500.

Suggested settings:

Test system 500 (default)

Production system 1 000

Set this to the maximum so that the BSDS can record as many logs as possible.

For information about the logs and BSDS, see Chapter 17, “Understanding the log and the bootstrap data set” on page 305.

OFFLOAD

Specifies whether archiving is on or off.

Specify either:

YES Archiving is on
NO Archiving is off

The parameter cannot be blank.

The default is YES.

Attention: Do **not** switch archiving off unless you are working in a test environment. If you do switch it off, you cannot guarantee that data will be recovered in the event of a system or transaction failure. See the note about archiving in “What logs are” on page 305.

OUTBUFF

Specifies the total size, in kilobytes, of the storage to be used by MQSeries for output buffers for writing the active and archive log data sets. Each output buffer is 4 KB.

The parameter cannot be blank, and must be in the range 40 through 4000. The value specified is rounded up to a multiple of 4.

The default is 400 KB.

Suggested settings:

Test system 400 KB (default)

Production system 4 000 KB

Set this value to the maximum to avoid running out of log output buffers.

TWOACTV

Specifies single or dual active logging.

Specify either:

NO Single active logs
YES Dual active logs

The parameter cannot be blank.

The default is YES.

For more information about the use of single and dual logging, refer to “Should your installation use single or dual logging?” on page 498.

TWOARCH
Specifies the number of archive logs that MQSeries produces when the active log is off-loaded.

Specify either:

NO Single archive logs
YES Dual archive logs

This parameter cannot be blank even if the OFFLOAD parameter is specified as NO.

The default is YES.

Suggested settings:

Test system NO

Production system YES (default)

For more information about the use of single and dual logging, refer to “Should your installation use single or dual logging?” on page 498.

TWOBSDS
Specifies the number of bootstrap data sets.

Specify either:

NO Single BSDS
YES Dual BSDS

This parameter cannot be left blank.

The default is YES.

For more information about the use of single and dual logging, refer to “Should your installation use single or dual logging?” on page 498.

WRTHRSH
Specifies the number of 4 KB output buffers to be filled before they are written to the active log data sets.

The larger the number of buffers, the less often the write takes place, and this improves the performance of MQSeries. The buffers might be written before this number is reached if significant events, such as a commit point, occur.

Specify the number of buffers in the range 1 through 256.

The default is 20.

Suggested settings:

Test system 15

Production system 15

This is the *optimum* value. It corresponds to the maximum number of buffers written in a single log I/O.

Using CSQ6ARVP

Use CSQ6ARVP to establish your archiving environment.

The default parameters for CSQ6ARVP are shown in Table 12. If you need to change any of these values, refer to the detailed descriptions of the parameters. See “Planning your archive storage” on page 316 for more information.

Table 12. Default values of CSQ6ARVP parameters

Parameter	Description	Default value
ALCUNIT	Units in which primary and secondary space allocations are made.	BLK (blocks)
ARCPFX1	Prefix for first archive log data set name.	CSQARC1
ARCPFX2	Prefix for second archive log data set name.	CSQARC2
ARCRETN	The retention period of the archive log data set in days.	9999
ARCWRTC	List of route codes for messages to the operator about archive log data sets.	1,3,4
ARCWTOR	Whether to send message to operator and wait for reply before trying to mount an archive log data set.	YES
BLKSIZE	Block size of archive log data set.	20480
CATALOG	Whether archive log data sets are cataloged in the ICF.	NO
COMPACT	Whether archive log data sets should be compacted.	NO
PRIQTY	Primary space allocation for DASD data sets.	4320
PROTECT	Whether archive log data sets are protected by ESM profiles when the data sets are created.	NO
QUIESCE	Maximum time, in seconds, allowed for quiesce when ARCHIVE LOG with MODE(QUIESCE) specified.	5
SECQTY	Secondary space allocation for DASD data sets. See the ALCUNIT parameter for the units to be used.	540
TSTAMP	Whether the archive data set name should include a time stamp.	NO
UNIT	Device type or unit name on which archive log data sets are stored.	TAPE

ALCUNIT

Specifies the unit in which primary and secondary space allocations are made.

Specify one of:

CYL Cylinders
TRK Tracks
BLK Blocks

You are recommended to use BLK because it is independent of the device type.

The default is BLK.

If free space on the archive DASD volumes is likely to be fragmented, you are recommended to specify a smaller primary extent and allow expansion into secondary extents. For more information about space allocation for active logs, refer to “How large should the active logs be?” on page 498.

ARCPFX1
Specifies the prefix for the first archive log data set name.

See the TSTAMP parameter for a description of how the data sets will be named and for restrictions on the length of ARCPFX1.

This parameter cannot be left blank.

The default is CSQARC1.

You might need to authorize the MQSeries subsystem to create archive logs with this prefix.

ARCPFX2
Specifies the prefix for the second archive log data set name.

See the TSTAMP parameter for a description of how the data sets will be named and for restrictions on the length of ARCPFX2.

This parameter cannot be blank even if the TWOARCH parameter is specified as NO.

The default is CSQARC2.

You might need to authorize the MQSeries subsystem to create archive logs with this prefix.

ARCRETN
Specifies the retention period, in days, to be used when the archive log data set is created.

The parameter must be in the range 0 through 9999.

The default is 9999.

Suggested settings:

Test system 3

In a test system, archive logs will probably not be required over long periods.

Production system 9999 (default)

Set this value high to effectively switch automatic archive log deletion off.

For more information, see “Automatic archive log data set deletion” on page 323.

ARCWRTC
Specifies the list of OS/390 routing codes for messages about the archive log data sets to the operator. This field is ignored if ARCWTOR is set to NO.

Specify up to 14 routing codes, each with a value in the range 1 through 16. You must specify at least one code. Separate codes in the list by commas, not by blanks.

The default is the list of values: 1,3,4.

For more information about OS/390 routing codes, see the *MVS Routing and Descriptor Codes* manual.

ARCWTOR
Specifies whether a message is to be sent to the operator and a reply is received before attempting to mount an archive log data set.

Other MQSeries users might be forced to wait until the data set is mounted, but they are not affected while MQSeries is waiting for the reply to the message.

Specify either:

YES The device needs a long time to mount archive log data sets. For example, a tape drive.

NO The device does not have long delays. For example, DASD.

The default is YES.

Suggested settings:

Test system NO

Production system YES (default)

This is dependent on operational procedures. If tape robots are used, NO might be more appropriate.

BLKSIZE
Specifies the block size of the archive log data set. The block size you specify must be compatible with the device type you specify in the UNIT parameter.

The parameter must be in the range 4 097 through 28 672. The value you specify is rounded up to a multiple of 4 096.

The default is 20 480.

This parameter is ignored for data sets that are managed by the storage management subsystem (SMS).

If the archive log data set is written to DASD, you are recommended to choose the maximum block size that will allow 2 blocks per track. For example, for a 3390 device, you should use a block size of 24 576.

If the archive log data set is written to tape, specifying the largest possible block size improves the speed of reading the archive log.

Suggested settings:

Test system 24 576 (6 log records per block)

This is the optimum block size for 3390 DASD.

Production system 28 672 (the maximum allowed; 7 log records per block)

Use the highest possible block size for optimum tape I/O efficiency.

CSQ6ARVP

CATALOG
Specifies whether archive log data sets are cataloged in the primary integrated catalog facility (ICF) catalog.

Specify either:

NO Archive log data sets are not cataloged
YES Archive log data sets are cataloged

This parameter cannot be blank.

The default is NO.

All archive log data sets allocated on DASD must be cataloged. If you archive to DASD with the CATALOG parameter set to NO, message CSQJ072E is displayed each time an archive log data set is allocated, and MQSeries catalogs the data set.

Suggested settings:

Test system YES

Production system NO (default)

COMPACT
Specifies whether data written to archive logs is to be compacted. This option applies only to a 3480 or 3490 device that has the improved data recording capability (IDRC) feature. When this feature is turned on, hardware in the tape control unit writes data at a much higher density than normal, allowing for more data on each volume. Specify NO if you do not use a 3480 device with the IDRC feature or a 3490 base model, with the exception of the 3490E. Specify YES if you want the data to be compacted.

Specify either:

NO Do not compact the data sets
YES Compact the data sets

The default is NO.

Specifying YES adversely affects performance. Also be aware that data compressed to tape can be read only using a device that supports the IDRC feature. This might be a concern if you have to send archive tapes to another site for remote recovery.

Suggested settings:

Test system Not applicable

Production system NO (default)

This applies to 3480 and 3490 IDR compression only. Setting this to YES might degrade archive log read performance during recovery and restart; however, it does not affect writing to tape.

PRIQTY
Specifies the primary space allocation for DASD data sets in ALCUNITs.

The value must be greater than zero.

The default is 4320.

This value must be sufficient for a copy of either the log data set or its corresponding BSDS, whichever is the larger. To determine the necessary value, follow this procedure:

1. Determine the number of active log records actually allocated (c) as explained in "Task 11: Create the bootstrap and log data sets" on page 61.
2. Determine the number of 4096-byte blocks in each archive log block:

   ```
   d = BLKSIZE / 4096

   Where BLKSIZE is the rounded up value
   ```

3. If ALCUNIT=BLK:

   ```
   PRIQTY = INT(c / d) + 1

   where INT means round down to an integer
   ```

   If ALCUNIT=TRK:

   ```
   PRIQTY = INT(c / (d * INT(e/BLKSIZE))) + 1

   where e is the number of bytes per track (56664 for a 3390 device)
   and INT means round down to an integer
   ```

   If ALCUNIT=CYL:

   ```
   PRIQTY = INT(c / (d * INT(e/BLKSIZE) * f)) + 1

   where f is the number of tracks per cylinder (5 for a 3390 device)
   and INT means round down to an integer
   ```

For information about how large to make your log and archive data sets, see "Task 11: Create the bootstrap and log data sets" on page 61 and "Task 12: Define your page sets" on page 63.

Suggested settings:

Test system 1680

Sufficient to hold the entire active log, that is:

```
10080 / 6 = 1 680 blocks
```

Production system Not applicable when archiving to tape.

If free space on the archive DASD volumes is likely to be fragmented, you are recommended to specify a smaller primary extent and allow expansion into secondary extents. For more information about space allocation for active logs, refer to "How large should the active logs be?" on page 498.

PROTECT

Specifies whether archive log data sets are to be protected by discrete ESM (external security manager) profiles when the data sets are created.

Specify either:

NO Profiles are not created.

YES Discrete data set profiles are created when logs are offloaded. If you specify YES:

- ESM protection must be active for MQSeries.

- The user ID associated with the MQSeries address space must have authority to create these profiles.
- The TAPEVOL class must be active if you are archiving to tape.

Otherwise, offloads will fail.

The default is NO.

QUIESCE
Specifies the maximum time in seconds allowed for the quiesce when an +cpf ARCHIVE LOG command is issued with MODE QUIESCE specified.

The parameter must be in the range 1 through 999.

The default is 5.

SECQTY
Specifies the secondary space allocation for DASD data sets in ALCUNITs.

The parameter must be greater than 0.

The default is 540.

TSTAMP
Specifies whether the archive log data set name has a time stamp in it.

Specify either:

NO Names do not include a time stamp. The archive log data sets will be named:

arcpfxi.A*nnnnnnn*

Where *arcpfxi* is the data set name prefix specified by ARCPFX1 or ARCPFX2. *arcpfxi* can have up to 35 characters.

YES Names include a time stamp. The archive log data sets will be named:

arcpfxi.cyyddd.T*hhmmsst*.A*nnnnnnn*

where *c* is 'D' for the years up to and including 1999 or 'E' for the year 2000 and later, and *arcpfxi* is the data set name prefix specified by ARCPFX1 or ARCPFX2. *arcpfxi* can have up to 19 characters.

EXT Names include a time stamp. The archive log data sets will be named:

arcpfxi.D*yyyyddd*.T*hhmmsst*.A*nnnnnnn*

Where *arcpfxi* is the data set name prefix specified by ARCPFX1 or ARCPFX2. *arcpfxi* can have up to 17 characters.

The default is NO.

UNIT
Specifies the device type or unit name of the device that is used to store archive log data sets.

Specify a device type or unit name of 1 through 8 alphanumeric characters. The first character must be alphabetic.

This parameter cannot be blank.

The default is TAPE.

If you archive to DASD, you can specify a generic device type with a limited volume range.

If you archive to DASD:

- Make sure that the primary space allocation is large enough to contain all the data from the active log data sets.
- Make sure that the archive log data set catalog option (CATALOG) is set to YES.
- The archive log data sets cannot extend to another volume.

If you archive to TAPE, MQSeries can extend to a maximum of 20 volumes.

Suggested settings:

Test system DASD

Production system TAPE

For more information about choosing a location for archive logs, refer to "Should your archive logs reside on tape or DASD?" on page 497.

Task 14: Tailor the channel initiator parameter module

- *Repeat this task for each MQSeries subsystem, as required.*
- *Omit this task if you are using the CICS mover.*

This process is analogous to tailoring the system parameter module (see “Task 13: Tailor your system parameter module” on page 68).

The channel initiator parameter module controls how distributed queuing operates. It has the single macro, CSQ6CHIP.

MQSeries supplies a default parameter module, CSQXPARM, which is invoked automatically if you issue the START CHINIT command (without a PARM parameter) to start a channel initiator. “Using CSQ6CHIP” on page 87 lists the default values for the supplied CSQXPARM. CSQXPARM is in the APF-authorized library thlqual.SCSQAUTH, also supplied with MQSeries.

The values of these parameters are displayed as a series of messages each time you start the channel initiator.

Creating your own channel initiator parameter module

In most cases you will need to create your own parameter module. If you are using LU 6.2 communications, you will have to do this because you will at least need to set the outbound LU name to be used. If you are using TCP/IP, you will probably need to set TCPTYPE and TCPNAME.

To create your own parameter module, use the sample JCL provided in thlqual.SCSQPROC(CSQ4XPRM):

1. Make a working copy of the JCL sample.
2. Edit the parameters in the copy as required. See “Using CSQ6CHIP” on page 87 for more information about each parameter. If you remove any parameters from the macro call, the default values are automatically picked up at run time.
3. Replace the placeholder `++NAME++` with the name that the load module is to take. (This can be CSQXPARM.)
4. If your assembler is not high-level assembler, change the JCL as required by your assembler.
5. Run the JCL to assemble and link-edit the tailored versions of the channel initiator parameter macros to produce a load module. This is the new channel initiator parameter module with the name that you have specified.
6. Put the load module produced in an APF-authorized user library.
7. Include this library in the channel initiator started task procedure STEPLIB. This library name must come before the library thlqual.SCSQAUTH in STEPLIB.

8. Invoke the new channel initiator parameter module when you start the channel initiator. For example, if the new module is named NEWMODS, issue the command:

   ```
   START CHINIT PARM(NEWMODS)
   ```

Note: If you choose to name your module CSQXPARM, you do not need to specify the PARM parameter on the START CHINIT command.

Using CSQ6CHIP

Use CSQ6CHIP to set channel initiator parameters.

The default parameters for CSQ6CHIP are shown in Table 13. If you want to change any of these values, refer to the detailed descriptions of the parameters.

Table 13. Default values of CSQ6CHIP parameters

Parameter	Description	Default value
ACTCHL	The maximum number of channels that can be active.	CURRCHL
ADAPS	The number of adapter subtasks to use for processing MQI calls.	8
CURRCHL	The maximum number of channels that can be current.	200
DISPS	The number of dispatchers to use.	5
LSTRTMR	The interval, in seconds, between listener restart attempts.	60
LUNAME	The name of the LU to use for outbound transmissions.	Blank
LU62ARM	APPCPMxx SYS1.PARMLIB member name suffix.	Blank
LU62CHL	The maximum number of channels that can be current and use the LU 6.2 transmission protocol.	CURRCHL
TCPCHL	The maximum number of channels that can be current and use the TCP/IP transmission protocol.	CURRCHL
TCPKEEP	Whether the TCP KEEPALIVE facility is to be used or not.	NO
TCPNAME	The name of the TCP/IP address space or system that will be used.	TCPIP
TCPTYPE	TCP/IP interface method.	OESOCKET
TRAXSTR	Whether trace should start automatically or not.	YES
TRAXTBL	The size of the trace data space in MB.	2

ACTCHL

Specifies the maximum number of channels that can be active.

Specify a value in the range 1 through 9999.

The default value is CURRCHL.

CSQ6CHIP

ADAPS
Specifies the number of adapter subtasks to use for processing MQI calls. As a guideline, the ratio of adapters to dispatchers (the DISPS parameter) should be about 8 to 5. However, if you have only a small number of channels, you do not have to decrease the value of this parameter from the default value.

Specify a value in the range 0 through 9999.

The default value is 8.

Suggested settings:

Test system 8 (default)

Production system 20

Ideally, you should have 20 adapters, which gives greater parallelism of MQI calls. This is particularly important for persistent messages. Fewer adapters might be better for nonpersistent messages.

CURRCHL
Specifies the maximum number of channels that can be current (including server-connection channels with connected clients).

Specify a value in the range 1 through 9999.

The default value is 200.

Suggested settings:

Test system 200 (default)

Production system 1 000

DISPS
Specifies the number of dispatchers to use for the channel initiator. As a guideline, allow one dispatcher for each 50 current channels. However, if you have only a small number of channels, you do not have to decrease the value of this parameter from the default value.

If you are using TCP/IP, the greatest number of dispatchers that will be used for TCP/IP channels is 100, even if you specify a larger value here.

Specify a value in the range 1 through 9999.

The default value is 5.

Suggested settings:

Test system 5 (default)

Production system 20

You are recommended to have 20 dispatchers to handle up to 1 000 active channels.

LSTRTMR
Specifies the time interval (in seconds) between attempts by MQSeries to restart the listener if there has been an APPC or TCP/IP failure.

Specify a value in the range 5 through 9999.

The default value is 60.

Note: This parameter is ignored if you are using the IUCV or TCPAccess interfaces to TCP/IP.

LUNAME
Specifies the name of the LU to use for outbound LU 6.2 transmissions. This must be set to the same LU that will be used for inbound transmissions by the listener.

Specify the LU name.

The default is blank, which means that the APPC/MVS default LU should be used; this is variable, so LUNAME should always be set if you are using LU 6.2.

LU62ARM
Specifies the suffix of the SYS1.PARMLIB member APPCPMxx, that nominates the LUADD for this channel initiator. The channel initiator issues the OS/390 command `SET APPC=xx` when it starts.

Specify the two-character suffix.

The default is blank which means that no `SET APPC=xx` is issued.

LU62CHL
Specifies the maximum number of channels that can be current or clients that can be connected, that use the LU 6.2 transmission protocol. If 0, the LU 6.2 transmission protocol is not used.

Specify a value in the range 0 through 9999.

The default value is CURRCHL.

TCPCHL
Specifies the maximum number of channels that can be current or clients that can be connected, that use the TCP/IP transmission protocol. If 0, the TCP/IP transmission protocol is not used.

The maximum number of TCP/IP sockets used is TCPCHL+DISPS. The OpenEdition MAXFILEPROC parameter (specified in the BPXPRMxx member of SYS1.PARMLIB) controls how many sockets each task is allowed, and thus how many channels each dispatcher is allowed. The number of channels using TCP/IP in this case is limited to MAXFILEPROC*DISPS.

Specify a value in the range 0 through 9999.

Note: TCP/IP might not support as many as 9999 channels.

The default value is CURRCHL.

TCPKEEP
Specifies whether the TCP KEEPALIVE facility, as specified by the KEEPALIVEOPTIONS statement in the TCP profile configuration data set, is to be used or not.

Specify YES or NO.

The default is NO.

TCPNAME
Specify the name of the TCP/IP system that you are using. This depends on the type of TCP/IP interface that you are using:

IUCV
The name of the TCP/IP address space.

OpenEdition Sockets
The name of the OpenEdition stack for TCP/IP, as specified in the SUBFILESYSTYPE NAME parameter in the BPXPRMxx member of SYS1.PARMLIB.

TCPaccess
The name of the TCPaccess subsystem.

The default is TCPIP.

TCPTYPE
Specifies the type of TCP/IP interface to be used.

Specify one of the following:

IUCV	IUCV interface
OESOCKET	OpenEdition sockets interface
SNSTCPACCESS	TCPaccess native interface

The default is OESOCKET.

See "Task 2: Choose the distributed queuing facility" on page 40 for information about these interfaces, and Table 14 for a summary of the settings.

TRAXSTR
Specifies whether trace should start automatically or not.

Specify YES or NO.

The default is YES.

TRAXTBL
Specifies the size of the trace data space (in MB).

Specify a value in the range 0 through 2048.

The default value is 2.

Note: Whenever you use large OS/390 data spaces, you should ensure that sufficient auxiliary storage is available on your system to support any related OS/390 paging activity. You might also need to increase the size of your SYS1.DUMP data sets.

Notes:

1. The channel initiator makes a number of connections to the queue manager that must be allowed for when setting the CTHREAD system parameter (see "Using CSQ6SYSP" on page 69). The number of connections is up to 6 plus the value of ADAPS plus the value of DISPS.
2. Each dispatcher and each adapter subtask uses a separate OS/390 task. As a guideline, keep the total number of dispatchers and adapter subtasks below 20.

Table 14 (Page 1 of 2). TCP/IP settings

Product	Interface	Library	TCPTYPE	TCPNAME
IBM TCP/IP	OpenEdition sockets	SCSQMVR1	OESOCKET	OpenEdition TCP/IP stack name
IBM TCP/IP	IUCV	SCSQMVR1	IUCV	TCP/IP address space name

Table 14 (Page 2 of 2). TCP/IP settings

Product	Interface	Library	TCPTYPE	TCPNAME
Interlink TCPaccess	OpenEdition sockets	SCSQMVR1	OESOCKET	OpenEdition TCP/IP stack name
Interlink TCPaccess	IUCV	SCSQMVR1	IUCV	TCP/IP address space name
Interlink TCPaccess	Native TCPaccess	SCSQMVR2	SNSTCPACCESS	TCPaccess subsystem name

Task 15: Set up Batch, TSO, and RRS adapters

- *Repeat this task for each MQSeries subsystem as required.*

The Batch/TSO and RRS adapters are the interface between OS/390 application programs running under JES, TSO, or OS/390 OpenEdition and an MQSeries subsystem. They enable OS/390 application programs to use the MQI. They are generally referred to in this book as the batch adapter and the RRS adapter. "MQSeries and OS/390 Batch and TSO" on page 22 describes these adapters.

To make the adapters available to batch and TSO applications, add the following MQSeries libraries to the STEPLIB concatenation for your batch application or TSO logon procedure:

- thlqual.SCSQANL*x*
- thlqual.SCSQAUTH

where *x* is the language letter for your national language.

Note: If the adapter detects an unexpected MQSeries subsystem error, it issues an OS/390 SNAP dump to DDname CSQSNAP, and issues reason code `MQRC_UNEXPECTED_ERROR` to the application.

If this occurs, rerun the job with a CSQSNAP DD statement included in the JCL, and contact your IBM support center.

The supplied program CSQBDEFV improves the portability of your application programs. In CSQBDEFV, you can specify the name of a subsystem to be connected to rather than specifying it in the **MQCONN** call in an application program. You can create a new version of CSQBDEFV for each subsystem. To do this, follow these steps:

1. Copy the MQSeries assembler program CSQBDEFV from thlqual.SCSQASMS to a user library.
2. The supplied program contains the default subsystem name CSQ1. You can retain this name for testing and installation verification. For production subsystems, you can change the NAME=CSQ1 to your one- to four-character subsystem name, or use CSQ1.
3. Assemble and link-edit the program to produce the CSQBDEFV load module. For the assembly, include the library thlqual.SCSQMACS in your SYSLIB concatenation; use the link-edit parameters `RENT,AMODE=31,RMODE=ANY`. This is shown in the sample JCL in thlqual.SCSQPROC(CSQ4DEFV). Then include the load library in the OS/390 Batch or the TSO JOBLIB or STEPLIB.

Task 16: Set up the operations and control panels

- *You need only perform this task once.*

To set up the operations and control panels you must first set up the libraries that contain the required panels, EXECs, messages, and tables. To do this, you must take into account which national language feature is to be used for the panels. When you have done this, you can optionally:

- Update the main ISPF menu for MQSeries operations and control panels
- Change the function key settings

Setting up the libraries

Follow these steps to install the MQSeries operations and control panels:

1. Include the library thlqual.SCSQEXEC in your SYSEXEC or SYSPROC concatenation. This library, which is allocated with a fixed-block 80 record format during installation, contains the required EXECs.

   Notes:

   a. You should put these EXECs into your SYSEXEC concatenation. However, if you want to put them in SYSPROC, it must have a record length of 80 bytes. If you move the EXECs from SYSPROC to SYSEXEC and your system searches SYSPROC before SYSEXEC, you must ensure that the EXECs are deleted from SYSPROC.

   b. Ensure that all the libraries contained in your concatenations are either in the same format (F, FB, V, VB) and have the same block size, or in the order of decreasing block sizes. Otherwise, you might have problems trying to use these panels.

2. Add SCSQAUTH to the TSO logon procedure STEPLIB if it is not in LINKLIB.

3. You can either install the MQSeries panel libraries permanently in your ISPF library setup, or allow them to be set up dynamically when the panels are used. For the former choice, you need to do the following:

   a. Include the name of the library containing the operations and control panel definitions in your ISPPLIB concatenation. The name is thlqual.SCSQPNLx, where x is the language letter for your national language.

   b. Install the required tables in your ISPTLIB concatenation. The name is thlqual.SCSQTBLx, where x is the language letter for your national language.

   c. Install the required messages in your ISPMLIB concatenation. The name is thlqual.SCSQMSGx, where x is the language letter for your national language.

   d. Include the library thlqual.SCSQSKL in your ISPSLIB concatenation. This library contains the required skeletons for data set tailoring.

   e. Install the required load modules in your ISPLLIB concatenation. These modules are in the thlqual.SCSQAUTH library with names beginning CSQOX.

4. Test that you can access the MQSeries panels from the TSO Command Processor panel. This is usually option 6 on the ISPF/PDF Primary Options Menu. The name of the EXEC that you run is CSQOREXX. There are no parameters to specify if you have installed the MQSeries libraries permanently in your ISPF setup as in step 3 on page 93. If you have not, use the following:

   ```
   CSQOREXX thlqual langletter
   ```

   where `langletter` is a letter identifying the national language to be used:

   C Simplified Chinese
   E U.S. English (mixed case)
   K Japanese
   U U.S. English (uppercase)

Updating the ISPF menu

You can update the ISPF main menu to allow access to the MQSeries operations and control panels from ISPF. The required setting for &ZSEL is:

```
CMD(%CSQOREXX thlqual langletter) NEWAPPL(CSQO) PASSLIB
```

For information about `thlqual` and `langletter`, see Step 4.

For more details, see the *ISPF Dialog Developer's Guide and Reference* manual.

Updating the function keys and command settings

You can use the normal ISPF procedures for changing the function keys and command settings used by the panels. The application identifier is CSQO.

However, this is *not* recommended because the help information is not updated to reflect any changes that you have made.

Task 17: Include the MQSeries dump formatting member

- *You need only perform this task once.*

To be able to format MQSeries dumps using the Interactive Problem Control System (IPCS), copy the data set thlqual.SCSQPROC(CSQ7IPCS) to SYS1.PARMLIB. You should not need to edit this data set.

Edit SYS1.PARMLIB member BLSCECTX and add this statement at the end of the member:

```
IMBED MEMBER(CSQ7IPCS) ENVIRONMENT(ALL)
```

(This member is described in the *MVS Initialization and Tuning Reference* manual.)

If you have customized the TSO procedure for IPCS, thlqual.SCSQPROC(CSQ7IPCS) can be copied into any library in the IPCSPARM definition. See the *MVS IPCS Customization* manual for details on IPCSPARM.

You must also include the library thlqual.SCSQPNLA in your ISPPLIB concatenation.

To make the dump formatting programs available to your TSO session or IPCS job, you must also include the library thlqual.SCSQAUTH in your STEPLIB concatenation. (Alternatively SCSQAUTH can be included in the OS/390 LINKLIST concatenation.)

Task 18: Suppress information messages

- *You need only perform this task once.*

If your MQSeries system is heavily used, with many channels stopping and starting, a large number of information messages are sent to the OS/390 console. The MQSeries-IMS bridge and buffer manager can also produce a large number of information messages.

If required, you can suppress some of these messages by using the OS/390 message processing facility list, specified by the MPFLSTxx members of SYS1.PARMLIB. The messages you specify still appear on the hard-copy log, but not on the console.

Sample thlqual.SCSQPROC(CSQ4MPFL) shows suggested settings for MPFLSTxx. See the *MVS Initialization and Tuning Reference* manual for more information about MPFLSTxx.

Chapter 4. Migrating from previous versions of MQSeries for MVS/ESA

This chapter describes the things that you must consider if you are migrating from a previous version of MQSeries for MVS/ESA. The following topics are discussed:

- "Migrating from Version 1.2 to Version 2.1"
- "Migrating from Version 1.1.4 to Version 2.1" on page 101
- "Migrating from Version 1.1.3 to Version 2.1" on page 101
- "Migrating from Version 1.1.2 or earlier to Version 2.1" on page 103
- "Coexistence with earlier versions of MQSeries for MVS/ESA" on page 103

You can continue to use your existing subsystems along with their page sets, log data sets, object definitions, and initialization input data sets with the new version. After installing the new version, you must IPL the system so that the new MQSeries early code is brought into use. **Once you have used the new version, it will not be possible to revert to a previous version.**

Migrating from Version 1.2 to Version 2.1

Software levels

The minimum levels for many of the items of software required to use MQSeries for OS/390 have changed (OS/390, CICS, and IMS in particular). Check that you have the correct levels for your prerequisite and corequisite software from the list in the *MQSeries Planning Guide*.

System parameter module

Relink your system parameter module if you are not using the supplied default CSQZPARM (see "Task 13: Tailor your system parameter module" on page 68).

There are new system parameters (EXITLIM, EXITTCB, and WLMTIME) and channel initiator parameters (TCPTYPE, LU62ARM, and LSTRTMR). Consider whether you need to use these new parameters, and change your parameter modules again accordingly. See "Task 13: Tailor your system parameter module" on page 68 and "Task 14: Tailor the channel initiator parameter module" on page 86 for more information.

Installation process

There are several changes to the installation process, and some new libraries. The two distributed queuing features for the non-CICS mover have been incorporated into the base product, and the CICS mover has been made an optional feature. The CICS bridge has also been incorporated into the base product.

These are described in the *MQSeries for OS/390 Program Directory*.

Automatic Restart Manager (ARM)

The OS/390 Automatic Restart Manager (ARM) is now supported. This support coexists on the same OS/390 image with earlier releases that do not support ARM. The queue managers and channel initiators in the earlier releases do not register with ARM and so can not be restarted automatically.

If you do not want to use ARM with your Version 2.1 queue managers and channel initiators, specify RESTART_ATTEMPTS(0) for the MQSeries

© Copyright IBM Corp. 1993,1999

element in your ARM policy. Note that if you do not specify MQSeries elements in your ARM policy, default ARM policies are used for MQSeries.

OS/390 ARM support is described in "Using the OS/390 Automatic Restart Manager (ARM)" on page 300.

Clusters

MQSeries now supports clustering. Before you use clustering you must review all of your applications to determine whether each one can operate in a clustering environment. You might have to modify your applications to remove or manage inter-message affinity. Applications that attempt to open non-existent queues might experience delays, or might even successfully open a queue somewhere in the cluster.

You also need to create the new system objects required for clustering. This is described in "CSQ4INSX system object sample" on page 56.

There is a cluster workload user exit; if you use this you need to add a CSQXLIB DD statement to your queue manager started task procedure, *xxxx*MSTR, and ensure that you have access to the LE run-time library SCEERUN.

Cluster support is described in the *MQSeries Queue Manager Clusters* manual.

Storage classes

The supplied default for storage class SYSTEM (which was used by many of the SYSTEM queues) has been changed to page set 01, so that messages are not put on page set 00.

If you currently use the defaults supplied, this change will probably have no effect, even if you use the DEFINE REPLACE option for your storage class definitions in your initialization input data set. This is because some of the queues using that storage class (like the SYSTEM.CHANNEL.SYNCQ for example) have messages on them permanently. If you want to move the queues to another page set, follow the procedure given in "Load balancing by moving queues" on page 336.

Initialization data sets

The sample input initialization data sets supplied with MQSeries have been reorganized and renamed. This is described in "Task 10: Customize the initialization input data sets" on page 52.

Resource Recovery Services (RRS)

You can migrate your existing batch/TSO MQSeries applications to exploit RRS coordination with little or no application program change. If you link-edit your MQSeries application with the CSQBRRSI adapter, **MQCMIT** and **MQBACK** will synchronize your unit of work across MQSeries and all other RRS-enabled resource managers. If you link-edit your MQSeries application with the CSQBRSTB adapter, you must change **MQCMIT** and **MQBACK** to **SRRCMIT** and **SRRBACK**.

Version 2.1 continues to support the non-RRS managed batch adapter in addition to supporting the RRS managed adapter. Thus different versions of MQSeries queue managers can coexist on the same OS/390 image.

OpenEdition sockets

OpenEdition sockets are now available for use as an alternative to IUCV. If you are using OS/390 Version 2.5 or later, and are using IBM TCP/IP for distributed queuing, IUCV is not available. You must set the TCPTYPE

channel initiator parameter to OESOCKETS (as described in Table 13 on page 87). Using OpenEdition sockets, you do not need to restart the channel initiator if TCP/IP has to be restarted.

Channel initiator security
Channel initiator user ID checking has been changed and some new facilities added. See "User IDs used by the channel initiator" on page 443 for details, and review your channel definitions to ensure that you are getting the security control you want.

Channel initiator snap dumps
The channel initiator can now record error information in a data set instead of taking a dump. Add the CSQSNAP DD statement to your channel initiator started task procedure to support this.

IMS language interface module
The IMS language interface module CSQ2LI00 is no longer supported. All IMS applications should use the IMS supplied DFSLI000 module.

Euro currency symbol
Support for the new euro currency symbol has been added to MQSeries. If you need to modify your applications to use this symbol, ensure that they use one of the coded character sets that include it. These are described in the *MQSeries Application Programming Reference* manual. If you need to change the coded character set used by your queue manager, use the CCSID parameter of the system parameter module. This is described in "Using CSQ6SYSP" on page 69.

Queue object size
The size of queue objects has increased for Version 2.1 to allow for the new cluster attributes. MQSeries automatically updates each of these queue objects the first time that it is changed. This happens whether you are using clustering or not. However, due to the nature of space reclamation in MQSeries, the space used on page set zero might increase dramatically until all these queue objects have been updated.

To avoid this, you should run a job similar to that in Figure 7 on page 100 that changes all of your queue objects, enabling MQSeries to update them all at the same time.

If you do not run a job like this, applications attempting to open queues might receive return code MQRC_OBJECT_IN_USE. This includes attempts by the channel initiator to open transmission queues.

Operations and control panels
The operations and control panels have been extended and reorganized to accommodate the new clustering function. The panels can now also be used for the security commands. A number of actions have been consolidated into a new PERFORM action. This is described in "Using the operations and control panels" on page 203.

```
//STEP1    EXEC  PGM=CSQUTIL,PARM='CSQ1'
//STEPLIB  DD    DISP=SHR,DSN=thlqual.SCSQANLE
//         DD    DISP=SHR,DSN=thlqual.SCSQAUTH
//OUTPUT1  DD    DISP=OLD,DSN=MY.MQSERIES.COMMANDS(DEFS)
//SYSPRINT DD    SYSOUT=*
//SYSIN    DD    *
COMMAND DDNAME(CMDINP) MAKEDEF(OUTPUT1)
/*
//CMDINP   DD *
DISPLAY QUEUE(*) TYPE(QLOCAL) ALL
DISPLAY QUEUE(*) TYPE(QMODEL) ALL
/*
//*   STEP2
//*********************************************************************
//* PERFORM A GLOBAL CHANGE ON THE OUTPUT DATA SET FROM STEP 1, THAT    *
//* IS: MY.MQSERIES.COMMANDS(DEFS).  CHANGE 'NOREPLACE'  TO 'REPLACE'   *
//* THE CHANGED MY.MQSERIES.COMMANDS(DEFS) WILL BE THE INPUT FOR STEP3. *
//*********************************************************************
//*
//STEP3    EXEC  PGM=CSQUTIL,PARM='CSQ1'
//STEPLIB  DD    DISP=SHR,DSN=thlqual.SCSQANLE
//         DD    DISP=SHR,DSN=thlqual.SCSQAUTH
//SYSPRINT DD    SYSOUT=*
//SYSIN    DD    *
COMMAND DDNAME(DEFINES)
/*
//DEFINES  DD DISP=SHR,DSN=MY.MQSERIES.COMMANDS(DEFS)
```

Figure 7. Example job for migrating queue objects

Migrating from Version 1.1.4 to Version 2.1

If you intend to migrate from Version 1.1.4 to Version 2.1, you need to note the following when you customize your new version in addition to the tasks in the previous section (you don't need to install and customize the intervening versions):

Index queues

There is a new queue attribute, INDXTYPE, that allows the queue manager to expedite **MQGET** operations on the queue. To improve channel performance, you should set INDXTYPE to MSGID for the SYSTEM.CHANNEL.SYNCQ queue. In general, you will then need to restart the queue manager to have this take effect. See the *MQSeries Command Reference* manual for more information.

Channel attributes

There is a new channel attribute, NPMSPEED, that specifies a class of service for nonpersistent messages on the channel. **The class applied to existing channel definitions is FAST, which means that nonpersistent messages might be lost if there is a channel error.** If this is not acceptable, you must alter your channel definitions to have NPMSPEED(NORMAL).

There are also two other new channel attributes, HBINT and BATCHINT. See the *MQSeries Command Reference* manual for more information.

Distributed queuing

There are new libraries for distributed queuing: `thlqual.SCSQMVR1` if you are using the OpenEdition sockets or IUCV interface and `thlqual.SCSQMVR2` if you are using the TCPaccess interface. Add the appropriate library to the STEPLIB DD statement of the JCL used for your channel initiator started task procedures (xxxxCHIN) and data conversion utility (CSQUCVX).

C/370

Use of the C/370 library product by MQSeries is no longer supported (although MQSeries applications can still use it). You must now use LE instead. Change your channel initiator started-task procedures (xxxxCHIN) and data conversion utility (CSQUCVX) JCL accordingly.

TCP/IP Version 2

TCP/IP Version 2 is no longer supported.

Migrating from Version 1.1.3 to Version 2.1

If you intend to migrate from Version 1.1.3 to Version 2.1, you need to do the following when you customize Version 2.1, in addition to the tasks in the previous sections (you don't need to install and customize the intervening versions).

Note: This information is included for your convenience, although this version of MQSeries for MVS/ESA is no longer supported.

Long connection names

The connection names for channels can be up to 48 characters long. The data format in SYSTEM.CHANNEL.SYNCQ will be updated to accommodate this change automatically. Create new system channel objects SYSTEM.DEF.SVRCONN and SYSTEM.DEF.CLNTCONN as described in "Task 10: Customize the initialization input data sets" on page 52.

Initialization data set

Ensure that your CSQINP2 initialization input data set has DEFINE commands for the storage classes SYSTEMST, DEFAULT, REMOTE, SYSTEM and NODEFINE, as in the supplied samples thlqual.SCSQPROC(CSQ4INSG) and thlqual.SCSQPROC(CSQ4INYG); if not, you might get MQI calls failing with MQRC_STORAGE_CLASS_ERROR. Any storage classes that were being used by your queues will have non-empty storage class objects automatically created for them.

The NODEFINE storage class is no longer allocated automatically. It must be defined explicitly, as in the supplied sample thlqual.SCSQPROC(CSQ4INYG).

New library organization

Change the STEPLIB DD statements in all JCL used for started task procedures and utility jobs to reflect the new library organization. The MQSeries libraries required are now as follows:

Authorized	Distributed queuing	Non-authorized	CICS
SCSQANLx	SCSQANLx SCSQMVRy	SCSQANLx	SCSQANLx
SCSQAUTH	SCSQAUTH	SCSQLOAD	SCSQCICS

Where x is the language letter of your national language, and y is 1 if you are using the OpenEdition sockets or IUCV interface or 2 if you are using the TCPaccess interface.

System parameters

There are new system parameters in CSQZPARM (QMCCSID, OTMACON) and CSQXPARM (ACTCHL, TCPKEEP). If you do not use the supplied default parameter modules, consider whether you need to use these new parameters, and change and link-edit your parameter modules again accordingly.

Default transmission queue

There is a new queue manager attribute, DEFXMITQ, which you might wish to use.

CICS adapter

For the CICS adapter, additional programs need to be defined to CICS/ESA®; update the CSD using the supplied sample data set thlqual.SCSQPROC(CSQ4B100).

CSQSYNA data set

The channel initiator no longer uses the CSQSYNA data set; this can be deleted and removed from the channel initiator started task procedure.

Channel initiator initialization data set

The channel initiator can now have an initialization input data set, CSQINPX (see “Initialization commands for distributed queuing” on page 53) and the channel initiator started task procedure can now have symbolic parameters.

Migrating from Version 1.1.2 or earlier to Version 2.1

If you intend to migrate from Version 1.1.2 to Version 2.1, you need to do the following when you customize Version 2.1, in addition to the tasks in the previous sections (you don't need to install and customize the intervening versions).

Note: This information is included for your convenience, although this version of MQSeries for MVS/ESA is no longer supported.

System objects
Create new system objects and queue attributes (see "Task 10: Customize the initialization input data sets" on page 52).

Dynamic page set expansion
If you want to use the dynamic page set expansion feature, re-allocate each of your page sets with secondary extents, and then use the COPYPAGE function of CSQUTIL to copy the old versions of the page sets to the new ones. (You can define up to 123 secondary extents for a page set, provided that there is sufficient disk storage space available.)

The supplied sample thlqual.SCSQPROC(CSQ4PAGE) shows how to define the secondary extents, and Chapter 14, "Using the MQSeries utilities" on page 233 gives information about using CSQUTIL.

Command prefix strings
If you want to use both command prefix strings (CPFs) and subsystem recognition characters (SRCs) check the coexistence rules given under "Coexistence with earlier versions of MQSeries for MVS/ESA."

System-command input queue
If you have programs that send commands to the SYSTEM.COMMAND.INPUT queue, note that command replies can be sent in several batches. (See "Interpreting the replies" on page 226 for more information.)

Coexistence with earlier versions of MQSeries for MVS/ESA

This topic discusses coexistence issues for the following:

- "Multiple queue manager versions"
- "Operations and control panels" on page 104
- "Application stubs" on page 104

Multiple queue manager versions

There can be several MQSeries subsystems in an OS/390 image, and they can use different versions of MQSeries, provided the MQSeries early code modules are of the latest version being used. (These modules are loaded at OS/390 IPL time and are shared among all the MQSeries subsystems in the OS/390 image.) This means that you can run one queue manager with Version 2.1 and another in the same image with Version 1.2, provided that the early code is that of Version 2.1.

As explained in "Migrating from Version 1.2 to Version 2.1" on page 97, ARM support and RRS support allow such coexistence.

Operations and control panels

When using the operations and control panels, the MQSeries libraries you use in ISPF must match those of the queue manager you are working with. That is, the panels at the Version 2.1 level will work only with a Version 2.1 queue manager, and Version 1.1.4 panels will work only with a Version 1.1.4 queue manager, and so on.

Application stubs

The stub modules that are link-edited with applications and exits (CSQASTUB, CSQBRSSI, CSQBRSTB, CSQBSTUB, CSQCSTUB, CSQQSTUB, and CSQXSTUB) might not work with earlier versions of the queue manager. For example, stubs supplied with Version 1.2 can be used by applications running on a Version 1.2 or 2.1 queue manager; however, if the application is run on a Version 1.1.4 queue manager, it might not work, or might end abnormally.

Chapter 5. Testing your queue manager

When you have customized or migrated your queue manager, you can test it by running some of the sample applications shipped with MQSeries.

You can then compile and link-edit whichever of the other samples are appropriate to your installation using the sample JCL supplied.

This chapter tells you about:

- Basic function testing using an Assembler MQSeries application program in the OS/390 batch environment
- “Testing for C, C++, COBOL, PL/I, and CICS” on page 108
- “Testing for distributed queuing” on page 108

Basic function testing

Use the Batch Assembler installation verification program (IVP) to verify the base MQSeries without using C, COBOL, or CICS samples.

The Batch Assembler IVP is link-edited by SMP/E and the load modules are shipped in library thlqual.SCSQLOAD.

After you have completed both the SMP/E APPLY step and the customization steps, run the Batch Assembler IVP.

Running the installation verification program CSQ4IVP1

After you have installed and customized MQSeries, you can use the supplied installation verification program, CSQ4IVP1, to confirm that MQSeries is operational.

Overview of the CSQ4IVP1 job

CSQ4IVP1 is a batch job that connects to your MQSeries subsystem and performs these basic functions:

- Issues MQI calls
- Communicates with the command server
- Verifies triggering is active
- Generates and deletes a dynamic queue

Preparing to run CSQ4IVP1

Before you run CSQ4IVP1:

1. Check that the IVP entries are in the CSQINP2 data set concatenation in the MQSeries startup program. The IVP entries are supplied in member thlqual.SCSQPROC(CSQ4IVP). If not, add the definitions supplied in thlqual.SCSQPROC(CSQ4IVP) to your CSQINP2 concatenation. If MQSeries is currently running, you will need to restart it so that these definitions can take effect.
2. The sample JCL, CSQ4IVPR, required to run the installation verification program (CSQ4IVP1) is in library thlqual.SCSQPROC.

© Copyright IBM Corp. 1993,1999

Customize the CSQ4IVPR JCL with the high-level qualifier for the MQSeries libraries, the national language you want to use, the four-character MQSeries subsystem name, and the destination for the job output.

3. Update RACF to allow CSQ4IVP1 to access its resources if MQSeries security is active.

   To run CSQ4IVP1 when MQSeries security is enabled, you need a RACF user ID with authority to access the objects. For details of defining resources to RACF, see Part 8, “Security” on page 401. The user ID that runs the IVP must have:

   - READ access to ssid.DISPLAY.PROCESS in class MQCMDS
   - UPDATE access to ssid.SYSTEM.COMMAND.INPUT in class MQQUEUE
   - UPDATE access ssid.SYSTEM.COMMAND.REPLY.MODEL in class MQQUEUE
   - UPDATE access to ssid.CSQ4IVP1.** in MQQUEUE
   - READ access to ssid.BATCH in MQCONN

   These requirements assume that all MQSeries security is active. The RACF commands to activate MQSeries security are shown in Figure 8. This example assumes that the MQSeries subsystem name is CSQ1 and that the user ID of the person running sample CSQ4IVP1 is TS101.

```
RDEFINE MQCMDS CSQ1.DISPLAY.PROCESS
PERMIT CSQ1.DISPLAY.PROCESS CLASS(MQCMDS) ID(TS101) ACCESS(READ)

RDEFINE MQQUEUE CSQ1.SYSTEM.COMMAND.INPUT
PERMIT CSQ1.SYSTEM.COMMAND.INPUT CLASS(MQQUEUE) ID(TS101) ACCESS(UPDATE)

RDEFINE MQQUEUE CSQ1.SYSTEM.COMMAND.REPLY.MODEL
PERMIT CSQ1.SYSTEM.COMMAND.REPLY.MODEL CLASS(MQQUEUE) ID(TS101) ACCESS(UPDATE)

RDEFINE MQQUEUE CSQ1.CSQ4IVP1.**
PERMIT CSQ1.CSQ4IVP1.** CLASS(MQQUEUE) ID(TS101) ACCESS(UPDATE)

RDEFINE MQCONN CSQ1.BATCH
PERMIT CSQ1.BATCH CLASS(MQCONN) ID(TS101) ACCESS(READ)
```

Figure 8. RACF commands for CSQ4IVP1

Running CSQ4IVP1

When you have completed these steps, start your MQSeries subsystem. If MQSeries is already running and you have made changes to CSQINP2, you must stop MQSeries and restart it.

The IVP runs as a batch job. Customize the job card to meet the submission requirements of your installation.

Checking the results of CSQ4IVP1

The IVP is split into eight stages; each stage must complete with a zero completion code before the next stage is run. The IVP generates a report, listing:

- The name of queue manager that is being connected to.
- A one-line message showing the completion code and the reason code returned from each stage.

For an explanation of the completion and reason codes, see the *MQSeries for OS/390 Messages and Codes* manual.

Some stages have more than one MQI call and, in the event of failure, a message is issued indicating the specific MQI call that returned the failure. Also, for some stages the IVP puts explanatory and diagnostic information into a comment field.

The IVP job requests exclusive control of certain queue manager objects and therefore should be single threaded through the system. However, there is no limit to the number of times the IVP can be run against your MQSeries subsystem.

The functions performed by each stage are:

Stage 1 Connect to the queue manager by issuing **MQCONN**.

Stage 2 Determine the name of the system-command input queue used by the command server to retrieve request messages. This queue receives display requests from Stage 5.

To do this, the sequence of calls is:

1. Issue an **MQOPEN**, specifying the queue manager name, to open the queue manager object.
2. Issue an **MQINQ** to find out the name of the system-command input queue.
3. Issue an **MQCLOSE** to close the queue manager object.

On successful completion of this stage, the name of the system-command input queue is displayed in the comment field.

Stage 3 Open an initiation queue using **MQOPEN**.

This queue is opened at this stage in anticipation of a trigger message, which arrives as a result of the command server replying to the request from Stage 5. The queue must be opened for input to meet the triggering criteria.

Stage 4 Create a permanent dynamic queue using the CSQ4IVP1.MODEL queue as a model. The dynamic queue has the same attributes as the model from which it was created. This means that when the replies from the command server request in Stage 5 are written to this queue, a trigger message is written to the initiation queue opened in Stage 3.

Upon successful completion of this stage, the name of the permanent dynamic queue is indicated in the comment field.

Stage 5 Issue an **MQPUT1** request to the command server command queue.

A message of MQMT_REQUEST is written to the system-command input queue requesting a display of process CSQ4IVP1. The message descriptor for the message specifies the permanent dynamic queue

created in Stage 4 as the reply-to queue for the command server's response.

Stage 6 Issue an **MQGET** request from the initiation queue. At this stage, a GET WAIT with an interval of one minute is issued against the initiation queue opened in Stage 3. The message returned is expected to be the trigger message generated by the command server's response messages being written to the reply-to queue.

Stage 7 Delete the permanent dynamic queue created in Stage 4. As the queue still has messages on it, the MQCO_PURGE_DELETE option is used.

Stage 8 Disconnect from the queue manager using **MQDISC**.

After running the IVP, you can delete any objects that you no longer require.

If the IVP does not run successfully, try each step manually to find out which function is failing.

Testing for C, C++, COBOL, PL/I, and CICS

You can test for C, C++, COBOL, PL/I, or CICS, using the sample applications supplied with MQSeries. Although the IVP (CSQ4IVP1) is supplied as a load module, the samples are supplied as source modules.

For more information about sample applications, see the *MQSeries Application Programming Reference* and *MQSeries Using C++* manuals.

Testing for distributed queuing

You can use the supplied installation verification program, CSQ4IVPX, to confirm that distributed queuing (without CICS) is operational.

Overview of CSQ4IVPX job

CSQ4IVPX is a batch job that starts the channel initiator and issues the DISPLAY DQM MQSC command. This verifies that all major aspects of distributed queuing are operational, while avoiding the need to set up channel and network definitions.

Preparing to run CSQ4IVPX

Before you run CSQ4IVPX:

1. The sample JCL, CSQ4IVPX, required to run the installation verification program is in library thlqual.SCSQPROC.

   Customize the CSQ4IVPX JCL with the high-level qualifier for the MQSeries libraries, the national language you want to use, the four-character MQSeries subsystem name, and the destination for the job output. If you have a customized channel initiator parameter module, replace CSQXPARM with the name of your module.

2. Update RACF to allow CSQ4IVPX to access its resources if MQSeries security is active. To run CSQ4IVPX when MQSeries security is enabled, you need a RACF user ID with authority to access the objects. For details of defining resources to RACF, see Part 8, “Security” on page 401. The user ID that runs the IVP must have:
   - READ access to ssid.DISPLAY.DQM in class MQCMDS
   - CONTROL access to ssid.START.CHINIT and STOP.CHINIT in class MQCMDS
   - UPDATE access to ssid.SYSTEM.COMMAND.INPUT in class MQQUEUE
   - UPDATE access to ssid.SYSTEM.CSQUTIL.* in MQQUEUE
   - READ access to ssid.BATCH in MQCONN

   These requirements assume that the connection security profile ssid.CHIN has been defined (as shown in “Connection security profiles for distributed queuing” on page 415), and that all MQSeries security is active. The RACF commands to do this are shown in Figure 9 on page 110. This example assumes that:
   - The MQSeries subsystem name is CSQ1
   - The user ID of the person running sample CSQ4IVPX is TS101
   - The channel initiator address space is running under the user ID CSQ1MSTR
3. Update RACF to allow the channel initiator address space the following RACF access:
   - READ access to ssid.CHIN in class MQCONN
   - UPDATE access to ssid.SYSTEM.COMMAND.INPUT in class MQQUEUE
   - UPDATE access to ssid.SYSTEM.CHANNEL.INITQ in class MQQUEUE
   - UPDATE access to ssid.SYSTEM.CHANNEL.SYNCQ in class MQQUEUE
   - ALTER access to ssid.SYSTEM.CLUSTER.COMMAND.QUEUE in class MQQUEUE
   - UPDATE access to ssid.SYSTEM.CLUSTER.TRANSMIT.QUEUE in class MQQUEUE
   - ALTER access to ssid.SYSTEM.CLUSTER.REPOSITORY.QUEUE in class MQQUEUE
   - CONTROL access to ssid.CONTEXT in class MQADMIN

   The RACF commands to do this are also shown in Figure 9 on page 110.

```
RDEFINE MQCMDS CSQ1.DISPLAY.DQM
PERMIT CSQ1.DISPLAY.DQM CLASS(MQCMDS) ID(TS101) ACCESS(READ)

RDEFINE MQCMDS CSQ1.START.CHINIT
PERMIT CSQ1.START.CHINIT CLASS(MQCMDS) ID(TS101) ACCESS(CONTROL)

RDEFINE MQCMDS CSQ1.STOP.CHINIT
PERMIT CSQ1.STOP.CHINIT CLASS(MQCMDS) ID(TS101) ACCESS(CONTROL)

RDEFINE MQQUEUE CSQ1.SYSTEM.COMMAND.INPUT
PERMIT CSQ1.SYSTEM.COMMAND.INPUT CLASS(MQQUEUE) ID(TS101,CSQ1MSTR) ACCESS(UPDATE)

RDEFINE MQQUEUE CSQ1.SYSTEM.CSQUTIL.*
PERMIT CSQ1.SYSTEM.CSQUTIL.* CLASS(MQQUEUE) ID(TS101) ACCESS(UPDATE)

RDEFINE MQCONN CSQ1.BATCH
PERMIT CSQ1.BATCH CLASS(MQCONN) ID(TS101) ACCESS(READ)

RDEFINE MQCONN CSQ1.CHIN
PERMIT CSQ1.CHIN CLASS(MQCONN) ID(CSQ1MSTR) ACCESS(READ)

RDEFINE MQQUEUE CSQ1.SYSTEM.CHANNEL.SYNCQ
PERMIT CSQ1.SYSTEM.CHANNEL.SYNCQ CLASS(MQQUEUE) ID(CSQ1MSTR) ACCESS(UPDATE)

RDEFINE MQQUEUE CSQ1.SYSTEM.CLUSTER.COMMAND.QUEUE
PERMIT CSQ1.SYSTEM.CLUSTER.COMMAND.QUEUE CLASS(MQQUEUE) ID(CSQ1MSTR) ACCESS(ALTER)

RDEFINE MQQUEUE CSQ1.SYSTEM.CLUSTER.TRANSMIT.QUEUE
PERMIT CSQ1.SYSTEM.CLUSTER.TRANSMIT.QUEUE CLASS(MQQUEUE) ID(CSQ1MSTR) ACCESS(UPDATE)

RDEFINE MQQUEUE CSQ1.SYSTEM.CLUSTER.REPOSITORY.QUEUE
PERMIT CSQ1.SYSTEM.CLUSTER.REPOSITORY.QUEUE CLASS(MQQUEUE) ID(CSQ1MSTR) ACCESS(ALTER)

RDEFINE MQQUEUE CSQ1.SYSTEM.CHANNEL.INITQ
PERMIT CSQ1.SYSTEM.CHANNEL.INITQ CLASS(MQQUEUE) ID(CSQ1MSTR) ACCESS(UPDATE)

RDEFINE MQADMIN CSQ1.CONTEXT
PERMIT CSQ1.CONTEXT CLASS(MQADMIN) ID(CSQ1MSTR) ACCESS(CONTROL)
```

Figure 9. RACF commands for CSQ4IVPX

Running CSQ4IVPX

When you have completed these steps, start your MQSeries subsystem.

The IVP runs as a batch job. Customize the job card to meet the submission requirements of your installation.

Checking the results of CSQ4IVPX

CSQ4IVPX runs the CSQUTIL MQSeries utility to issue three MQSC commands. The SYSPRINT output data set should look like Figure 10 on page 111, although details might differ depending on your channel initiator parameters.

- You should see the commands **(1)** each followed by several messages.

- The last message from each command should be “CSQ9022I ... NORMAL COMPLETION” **(2)**. The job as a whole should complete with return code 0 **(3)**.

```
 CSQU000I CSQUTIL IBM MQSeries for OS/390 - V2.1
 CSQU001I CSQUTIL Queue Manager Utility - 1999-01-31 09:06:48
 COMMAND
 CSQU127I CSQUTIL Executing COMMAND using input from CSQUCMD data set
 CSQU055I CSQUTIL Target queue manager is CSQ1
 CSQU120I CSQUTIL Connecting to queue manager CSQ1
 CSQU121I CSQUTIL Connected to queue manager CSQ1
  START CHINIT PARM(CSQXPARM)
(1)
CSQN205I   COUNT=       2, RETURN=00000000, REASON=00000004
CSQM138I +cpf CSQMSCHI CHANNEL INITIATOR STARTING
CSQN205I   COUNT=       2, RETURN=00000000, REASON=00000000
CSQ9022I +cpf CSQXCRPS ' START CHINIT' NORMAL COMPLETION
(2)
  DISPLAY DQM
(1)
CSQN205I   COUNT=       2, RETURN=00000000, REASON=00000004
CSQM137I +cpf CSQMDDQM  DISPLAY DQM COMMAND ACCEPTED
CSQN205I   COUNT=      12, RETURN=00000000, REASON=00000000
CSQX830I +cpf CSQXRDQM Channel initiator active
CSQX845I +cpf CSQXRDQM TCP/IP address space name is TCPIP
CSQX848I +cpf CSQXRDQM TCP/IP listener not started
CSQX849I +cpf CSQXRDQM LU6.2 listener not started
CSQX832I +cpf CSQXRDQM 5 dispatchers started, 5 requested
CSQX831I +cpf CSQXRDQM 8 adapter subtasks started, 8 requested
CSQX840I +cpf CSQXRDQM 0 channel connections current, maximum 200
CSQX841I +cpf CSQXRDQM 0 channel connections active, maximum 200
CSQX842I +cpf CSQXRDQM 0 channel connections starting,
0 stopped, 0 retrying
CSQ9022I +cpf CSQXCRPS ' DISPLAY DQM' NORMAL COMPLETION
(2)
  STOP  CHINIT
(1)
CSQN205I   COUNT=       2, RETURN=00000000, REASON=00000004
CSQM137I +cpf CSQMTCHI  STOP CHINIT COMMAND ACCEPTED
CSQN205I   COUNT=       2, RETURN=00000000, REASON=00000000
CSQ9022I +cpf CSQXCRPS ' STOP CHINIT' NORMAL COMPLETION
(2)
 CSQU057I CSQUCMDS 3 commands read
 CSQU058I CSQUCMDS 3 commands issued and responses received
 CSQU143I CSQUTIL 1 COMMAND statements attempted
 CSQU144I CSQUTIL 1 COMMAND statements executed successfully
 CSQU148I CSQUTIL Utility completed, return code=0
(3)
```

Figure 10. Example output from CSQ4IVPX

Testing distributed queuing

Part 3. MQSeries and CICS

Chapter 6. The MQSeries-CICS adapter 115
CICS adapter overview 115
Control functions 115
MQI support 116
Adapter components 117
Other adapter features 118
Alert monitor 118
Auto-reconnect 119
Task initiator 119
Multi-tasking 120
The API-crossing exit 120
CICS adapter performance considerations 121
CICS adapter conventions 123
Temporary storage queue names 123
MQGET 123
ENQUEUE names 123
Setting up the CICS adapter 124
Resource definition 124
System definition 126
Completing the connection from CICS 127
Controlling CICS application connections 128
Customizing the CICS adapter 128
Writing a PLTPI program to start the connection 128

Chapter 7. Operating the CICS adapter 129
Invoking the adapter's control functions 129
From the CICS adapter control panels 129
From the CICS command line 129
From CICS application programs 130
Preparing to use the CICS adapter 131
Accessing the CICS adapter control panels 132
Starting a connection 133
Starting a connection from the CICS adapter control panels 133
Starting a connection from the CICS command line 134
Starting a connection from a CICS application program 135
Stopping a connection 136
Stopping a connection from the CICS adapter control panels 136
Stopping a connection from the CICS command line 137
Stopping a connection from a CICS application program 137
Modifying a connection 138
Modifying a connection from the CICS adapter control panels 138
Modifying a connection from the CICS command line 139
Modifying a connection from a CICS application program 140
Displaying details of connections and CICS tasks 141
Displaying details of a connection from the CICS adapter control panels . 141
Starting an instance of the task initiator CKTI 142
Starting CKTI from the CICS adapter control panels 142
Starting CKTI from the CICS command line 143
Starting CKTI from a CICS application program 143
Stopping an instance of CKTI 144

© Copyright IBM Corp. 1993,1999

Stopping an instance of CKTI from the CICS adapter control panels . . . 144
Stopping an instance of CKTI from the command line 144
Stopping an instance of CKTI from an application program 145
Displaying the current instances of CKTI 146
Displaying the current instances of CKTI from the CICS adapter control panels 146
Displaying CICS task information 147
Displaying CICS tasks from the CICS adapter control panels 147
Displaying connection status and in-flight tasks 148
Purging tasks that are using the CICS adapter 149
Shutting down a connection between MQSeries and the CICS adapter . . . 150
Orderly shutdown 151
Forced shutdown 151

Chapter 8. The MQSeries-CICS bridge 153
Introduction to the CICS bridge 153
When to use the CICS bridge 153
Running CICS DPL programs 154
Running CICS 3270 transactions 155
Customizing the CICS bridge 158
Starting the CICS bridge 160
Tuning considerations 160
Shutting down the CICS bridge 161

Chapter 6. The MQSeries-CICS adapter

This chapter describes the MQSeries-CICS adapter (generally referred to as the CICS adapter or, where the context permits, simply as the adapter). It contains these sections:

- "CICS adapter overview"
- "Adapter components" on page 117
- "Other adapter features" on page 118
- "CICS adapter performance considerations" on page 121
- "CICS adapter conventions" on page 123
- "Setting up the CICS adapter" on page 124
- "Customizing the CICS adapter" on page 128

CICS adapter overview

The CICS adapter connects a CICS subsystem to an MQSeries subsystem, enabling CICS application programs to use the MQI.

The CICS adapter provides two main facilities:

- A set of control functions for use by system programmers and administrators to manage the adapter.
- MQI support for CICS applications.

The CICS adapter is supplied with MQSeries as the CICS transaction CKQC. Through this transaction, you can control the MQSeries-supplied task initiator transaction CKTI[2], which is described on page 119.

Control functions

The CICS adapter's control functions let you manage the connections between CICS and MQSeries dynamically. These functions can be invoked using the CICS adapter panels, from the command line, or from a CICS application. You can use the adapter's control function to:

- Start a connection to a queue manager.
- Stop the connection.
- Modify the current connection. For example, you can reset the connection statistics, change the adapter's trace ID number, and enable or disable the API-crossing exit.
- Display the current status of a connection and the statistics associated with that connection.
- Start an instance of the task initiator transaction, CKTI.
- Stop an instance of CKTI.
- Display details of the current instances of CKTI.

[2] This is CICS terminology. In MQSeries terminology, this is a trigger monitor process. It must have its own process definition—generated by issuing the MQSeries command, DEFINE PROCESS.

© Copyright IBM Corp. 1993,1999

- Display details of the CICS tasks currently using the adapter.

These functions and the different methods of invoking them are described in Chapter 7, “Operating the CICS adapter” on page 129.

MQI support

The CICS adapter implements the MQI for use by CICS application programs. The MQI calls, and how they are used, are described in the *MQSeries Application Programming Guide*. The adapter also supports an *API-crossing exit*, see “The API-crossing exit” on page 120, and a trace facility.

For performance, the CICS adapter can handle up to eight MQI calls concurrently. For transaction integrity, the adapter fully supports syncpointing under the control of the CICS syncpoint manager, so that units of work can be committed or backed out as required. The adapter also supports security checking of MQSeries resources when used with an appropriate security management product, such as RACF. The adapter provides high availability with automatic reconnection after an MQSeries termination, and automatic resource resynchronization after a restart. It also features an alert monitor that responds to unscheduled events such as a shut down of the MQSeries subsystem.

Note: If the CICS adapter detects an unexpected MQSeries subsystem error, it issues an OS/390 SNAP dump to DDname CSQSNAP, and issues reason code `MQRC_UNEXPECTED_ERROR` to the application.

If this occurs, rerun the application with a CSQSNAP DD statement included in the CICS JCL, and contact your IBM support center.

Adapter components

Figure 11 shows the relationship between CICS, the CICS adapter, and an MQSeries subsystem. CICS and the adapter share the same address space; the MQSeries for OS/390 is a separate OS/390 subsystem, executing in its own address space.

Part of the adapter is a CICS task-related user exit that communicates with the MQSeries message manager. CICS management modules call the exit directly; application programs call it through a supplied *API stub program* called CSQCSTUB. Task-related user exits and stub programs are described in the *CICS Customization Guide*.

Each CKTI transaction is normally in an **MQGET WAIT** state, ready to respond to any trigger messages that are placed on its initiation queue.

The adapter management interface provides the operation and control functions described in Chapter 7, “Operating the CICS adapter” on page 129.



Figure 11. How CICS, the CICS adapter, and an MQSeries subsystem are related

Other adapter features

The CICS adapter incorporates several other features that you should be aware of:

- Alert monitor
- Auto-reconnect
- Task initiator
- Multi-tasking
- API-crossing exit

Alert monitor

The *alert monitor* transaction, CKAM, handles unscheduled events—known as *pending events*—that occur as a result of connect requests to instances of MQSeries. The alert monitor generates messages that are sent to the system console.

There are two kinds of pending events:

1. Deferred connection
If CICS tries to connect to MQSeries before MQSeries is started, a *pending event* called a *deferred connection* is activated. When MQSeries is started, a connection request is issued by the CICS adapter, a connection is made, and the pending event is canceled.

There can be multiple deferred connections, one of which will be connected when MQSeries is started. If there is more than one instance of MQSeries, which deferred connection is made to which instance of MQSeries is unpredictable.

2. Termination notification
When a connection is successfully made to MQSeries, a pending event called *termination notification* is created. This pending event expires when:

- MQSeries shuts down normally with MODE(QUIESCE). The alert monitor issues a quiesce request on the connection.
- MQSeries shuts down with MODE(FORCE) or terminates abnormally. After an abnormal termination, the CICS adapter waits for ten seconds and then tries a connect call. This enables the CICS system to be automatically reconnected to the queue manager when the latter is restarted.
- The connection is shut down from the CKQC transaction.

The maximum number of pending events that can be handled is 99. If this limit is reached, no more events can be created until at least one current event expires.

The alert monitor terminates itself when all pending events have expired. It is subsequently restarted automatically by any new connect request.

If the alert monitor has been inadvertently force-purged (this is not recommended) you must first disable the task-related user exit before attempting to start a new connection. The command to do this is:

```
CECI DISABLE PROGRAM(CSQCTRUE) ENTRYNAME(MQM) EXITALL STOP
```

Auto-reconnect

When CICS is connected to MQSeries and MQSeries terminates, the CICS adapter tries to issue a connect request ten seconds after the stoppage has been detected. This request uses the same connect parameters that were used in the previous connect request. If MQSeries has not been restarted within the ten seconds, the connect request is deferred until MQSeries is restarted later.

Task initiator

CKTI is an MQSeries-supplied CICS transaction that starts a CICS transaction when an MQSeries event occurs, for example when a message is put onto a specific queue.

How it works:

When a message is put onto a message queue, a trigger is generated if the trigger conditions are met. The queue manager then writes a message, containing user-defined data, known as a *trigger message*, to the initiation queue that has been specified for that message queue. In a CICS environment, an instance of CKTI can be set up to monitor an initiation queue and to retrieve the trigger messages from it as they arrive. CKTI starts another CICS transaction, (specified using the DEFINE PROCESS command), which typically reads the message from the message queue and then processes it. The process must be associated with the application queue, not the initiation queue.

Each copy of CKTI services a single initiation queue. To start or stop a copy of CKTI, you must supply the name of the queue that this CKTI is to serve, or is serving. You cannot start more than one instance of CKTI against the same initiation queue from a single CICS subsystem.

At CICS system initialization or at connect time, you can define a default initiation queue. This is described in “System definition” on page 126 and “Starting a connection” on page 133. If you issue a STARTCKTI or a STOPCKTI without specifying an initiation queue, these commands are automatically interpreted as referring to the default initiation queue.

Notes:

1. If you are using version 4.1 of CICS, any transaction entries processed by CKTI, for example EXEC CICS START, are locked by the CKTI task until it terminates. Any attempt to CEDA INSTALL such entries after altering them will fail: CEDA rejects the install request because the transaction entry is being used by another task.

   In this situation, you must stop the CKTI task using the CICS adapter, see “Stopping an instance of CKTI” on page 144, and restart it after the CEDA install, see “Starting an instance of the task initiator CKTI” on page 142.
2. This restriction also applies to intersystem connection (ISC) and multi-region operation (MRO) links. For example, if CKTI has started a remote transaction, a connection cannot be reinstalled until CKTI has been stopped.

Multi-tasking

The CICS adapter optimizes the performance of a CICS to MQSeries connection by exploiting multi-processors and by removing work from the main CICS task control block (TCB), allowing multiple MQI calls to be handled concurrently.

The adapter enables some MQI calls to be executed under subtasks, rather than under the main CICS TCB that runs the application code. All the CICS adapter administration code, including connection and disconnection from MQSeries, runs under the main CICS TCB.

The adapter tries to attach up to eight OS/390 subtasks (TCBs) to be used by this CICS system. *You cannot modify this number*. Each subtask makes a connect call to MQSeries. Each CICS system connected takes up nine of the connections specified on CTHREAD. This means that you must increase the value specified for CTHREAD in CSQ6SYSP by nine for each CICS system connected. For more details, see “Using CSQ6SYSP” on page 69. MQI calls can flow over those connections. When the main connection is terminated, the subtasks are disconnected and terminated automatically.

The API-crossing exit

MQSeries provides an API-crossing exit for use with the CICS adapter; it runs in the CICS address space. You can use this exit to intercept MQI calls as they are being run, for monitoring, testing, maintenance, or security purposes.

The sample API-crossing exit is supplied in source form only. For more information about writing API-crossing exit programs, see the *MQSeries Application Programming Guide*.

Note: Using the API-crossing exit degrades MQSeries performance. You should plan your use of it carefully.

Defining the exit program

Before the API-crossing exit can be used, an exit program load module must be available when the CICS adapter connects to MQSeries. The exit program is a CICS program that must be named CSQCAPX and reside in a library in the DFHRPL concatenation. CSQCAPX must be defined in the CICS system definition file (CSD) and must be enabled.

When CSQCAPX is loaded a confirmation message is written to the CICS adapter control panel, CKQC, or the console. If it cannot be loaded, a diagnostic message is displayed, but otherwise the application program runs normally.

CICS adapter performance considerations

This section describes how the CICS adapter optimizes the performance of a CICS to MQSeries connection, and how you can monitor the connection.

There are a number of factors to be taken into consideration when performance is critical:

First MQI call

In general, the first MQI call of a task takes longer to perform than subsequent calls. This is because the environment must be set up. For example, the adapter must acquire storage and security information, and control blocks must be allocated and formatted.

MQGET and the SIGNAL option

Using the SIGNAL option with an **MQGET** call imposes an additional overhead. This is because the SIGNAL option can produce a CICS GETMAIN in the adapter, which is used to record the address of the ECB so that it can be posted if the queue manager abends.

API-crossing exit

Using the API-crossing exit also imposes a host processor overhead on each MQI call. The overhead in handling the exit parameter block and the invocations are minimal, but the exit can be invoked twice for each MQI call through EXEC CICS LINK.

CICS tracing

CICS tracing in the adapter also increases the pathlength of an MQI call. A large number of trace entries can be generated depending on how busy the system is. There is no control over the granularity of the trace entries produced in the adapter. Therefore, tracing should only be switched on if necessary.

MQGET and the WAIT option

Using **MQGET** with the WAIT option is less efficient if the task has been put into a wait until a message arrives. The adapter implements the wait as a form of CICS wait. When a message arrives, the adapter effectively re-issues the **MQGET** call for the application.

Therefore, use the WAIT option with care and only when the queue is known to be not very busy.

MQCLOSE

Issuing an **MQCLOSE** call is not always necessary because MQSeries automatically closes any unclosed handles when the task ends.

MQPUT1

If there is only one **MQPUT**, it is more efficient than an **MQOPEN**-**MQPUT**-**MQCLOSE** sequence because only one flow is generated between the MQSeries and the adapter, instead of three.

If there are multiple messages to be put, **MQOPEN**-**MQPUT**...**MQPUT**-**MQCLOSE** should be used.

EXEC CICS RETURN

Implicit syncpointing generated by EXEC CICS RETURN is more efficient than issuing the explicit syncpoint call EXEC CICS SYNCPOINT followed by EXEC CICS RETURN.

The EXEC CICS RETURN call accommodates all the work needed for syncpointing and task termination into one flow to MQSeries instead of the two separate flows used when explicit syncpointing is used.

Two-phase commit

A two-phase commit consumes more resources than a single-phase commit, both in host processor cost and response time. This is because a two-phase commit involves one more flow to MQSeries and more physical logging. If an application is restricted to recoverable updates in MQSeries and no other resource managers, CICS invokes the adapter for a single-phase commit.

Syncpoint bypassing

The adapter does not use the read-only commit feature in CICS. When a transaction is restricted to non-recoverable or non-destructive work in MQSeries, syncpointing is bypassed because it is not necessary. The clean-up process is performed when the task ends.

Statistics collection

Statistics collection by connection and by task is done on a per MQI call basis and cannot be switched off. This overhead is negligible.

You can use the CKQC transaction to display statistics for the current connection. See “Displaying details of connections and CICS tasks” on page 141.

CICS adapter conventions

There are a number of conventions that must be observed in applications using the adapter.

Temporary storage queue names

The CICS adapter display function uses two temporary storage queues (MAIN) per invoking task to store the output data for browsing. The names of the queues are **ttttCKRT** and **ttttCKDP**, where **tttt** is the terminal identifier of the terminal from which the display function is requested.

Do not try to access these queues.

MQGET

When the CICS adapter puts a task on a CICS wait because the WAIT option was used with the **MQGET** call and there was no message available, the RESOURCE NAME used is GETWAIT and the RESOURCE_TYPE is MQSeries.

When the CICS adapter puts a task on a CICS wait because of a need to perform task switching the RESOURCE NAME used is TASKSWCH and the RESOURCE_TYPE is MQSeries.

ENQUEUE names

The CICS adapter uses the name:

```
CSQ.genericapplid(8).QMGR
```

to issue CICS ENQ and CICS DEQ calls during processing, for example, starting and stopping the connection.

Attempts to use similar names for CICS ENQ or DEQ purposes should be avoided.

Setting up the CICS adapter

This section tells you how to make the MQSeries-CICS adapter (generally referred to in this book as the CICS adapter) available to your CICS subsystem. If you are not familiar with defining resources to CICS, refer to:

- The *CICS System Definition Guide* for general information on setting up a CICS subsystem.
- The *CICS Resource Definition Guide*, for background information on defining resources to CICS, details of and the command syntax of the CEDA transaction, and the MIGRATE command.
- The *CICS Operations and Utilities Guide* and the *CICS Resource Definition Guide* for details of the CSD utility program (DFHCSDUP).

Resource definition

This section takes you through the steps you must perform to define the resources for the CICS adapter.

Updating the CSD

This section describes the updates required for the CICS system definition (CSD) data set for the CICS adapter. It also describes the CSD updates required for the distributed queuing facility (if you want to use the "CICS mover") and the CICS sample application programs. However, it does not contain all the information required to complete these tasks. If you are implementing distributed queuing, see Appendix D, "Enabling distributed queuing using CICS ISC" on page 491. If you intend to use the CICS sample application programs, see the *MQSeries Application Programming Guide*.

You must use resource definition online (RDO) to add new groups to the CSD data set. The new groups must contain definitions of:

- The supplied adapter programs
- The supplied adapter management transactions
- The supplied sets of BMS maps, required for the adapter panels

To update the CSD, run the CICS offline utility program, DFHCSDUP, with the supplied sample input data sets:

- thlqual.SCSQPROC(CSQ4B100)
- thlqual.SCSQPROC(CSQ4D100)
- thlqual.SCSQPROC(CSQ4S100)

Where:

This data set...	Provides the definitions required for...
CSQ4B100	CICS adapter
CSQ4D100	Distributed queuing using CICS ISC (this is optional)
CSQ4S100	Supplied samples

Each of these data sets contains sample CICS definitions that must be tailored. To preserve the originals, copy these data sets into a user JCL library whose name

contains the MQSeries subsystem name, for example, MQS.CSQ1.USERJCL, and tailor them there.

Note: With some versions of CICS, you might receive warning messages about obsolete keywords; you can ignore these.

Ensure that any user-written CICS applications that issue MQI calls, and the resources they use, are also defined to the CSD. You can edit the input data set, to include definitions of user-programs and their resources.

You can add this fragment of JCL to your CSD upgrade (DFHCSDUP) job to define the MQSeries supplied groups to the CICS CSD:

```
//SYSIN  DD DSN=thlqual.SCSQPROC(CSQ4B100),DISP=SHR
//       DD DSN=thlqual.SCSQPROC(CSQ4D100),DISP=SHR
//       DD DSN=thlqual.SCSQPROC(CSQ4S100),DISP=SHR
//       DD *
  ADD GROUP(CSQCAT1) LIST(yourlist)
  ADD GROUP(CSQKDQ1) LIST(yourlist)
  ADD GROUP(CSQ4SAMP) LIST(yourlist)
/*
```

Figure 12. JCL fragment for upgrading the CICS CSD

Here, `yourlist` is the name of a CICS list that contains a list of groups to be installed by CICS during a cold start of the system. This is specified in the GRPLIST parameter of your CICS system initialization table (SIT). For details of CICS SIT parameters, see the *CICS System Definition Guide*.

Include the new resource groups in the CICS startup group list. For information about resource groups, installing them in CICS, the CICS CSD, and DFHCSDUP, see the *CICS Resource Definition Guide*.

Note: If you use the CEDA transaction to install redefined adapter resources in an active CICS system, you must first shut down the adapter and wait until the alert monitor has finished its work.

Starting a connection automatically during CICS initialization

If you want the adapter to connect to MQSeries automatically during CICS initialization, the CSQCCODF program should be included in a CICS PLTPI program. CSQCCODF must execute during the third stage of CICS initialization and must therefore be added after the entry for DFHDELIM. If there is no entry for DFHDELIM in your current PLTPI, you must add one.

Alternatively, if your version of CICS supports it, you can use the MQCONN SIT parameter to connect to MQSeries automatically. See the *CICS System Definition Guide* for information about this parameter.

Instead of using CSQCCODF, you can write your own program; see “Writing a PLTPI program to start the connection” on page 128.

1. Use the CICS DFHPLT macro to add your program to the list of programs executed by CICS during the third stage initialization. Figure 13 on page 126 shows how to code the entry for CSQCCODF in a CICS PLT program called DFHPLT41. For information about coding PLT entries, see the *CICS Resource Definition Guide*.

```
DFHPLT41 DFHPLT TYPE=INITIAL,SUFFIX=41
         DFHPLT TYPE=ENTRY,PROGRAM=DFHDELIM
         DFHPLT TYPE=ENTRY,PROGRAM=CSQCCODF
         DFHPLT TYPE=FINAL
         END
```

Figure 13. Sample PLT for use with the CICS adapter. This sample assumes that you are using the supplied PLTPI program, CSQCCODF, to start the adapter.

2. Specify the particular list of programs to be run at initialization by naming the suffix of your PLT on the PLTPI system initialization parameter. In Figure 13, the PLT suffix is 41.

Note: You can use the CICS adapter in a CICS system that has interregion communication (IRC) to remote CICS systems. If you are using IRC, you should ensure that the IRC facility is OPEN before you start the adapter. This is essential if the IRC access method is defined as cross memory, that is, ACCESSMETHOD(XM).

System definition

Use the INITPARM parameter in the CICS system initialization table (SIT), or the SYSIN override, to set the default connection parameters. Figure 14 shows you how to do this.

```
INITPARM=(CSQCPARM='SN=CSQ1,TN=001,IQ=CICS01.INITQ')
```

Figure 14. Sample INITPARM statement to set the default connection values for CICS

Where:

SN The subsystem name.

TN The trace number to identify the adapter in CICS trace entries. This must be in the range 0 through 199.

IQ The name of the default initiation queue. If this is blank, and you do not specify an initiation queue name by any other method, an instance of CKTI is not started when the CICS adapter connects to the queue manager.

The INITPARM statement does not accept a parameter string longer than 60 characters. If you specify a 4-character subsystem name and a 3-character trace number, the maximum allowable length of the initiation queue name is 42 characters. If you need a queue name longer than 42 characters, you cannot use the INITPARM statement to specify the default initiation queue.

At connect time, you must override the INITPARM setting, either by using the CKQC transaction, or in a PLTPI program.

1. If you are using a PLTPI program to start the adapter, code the suffix of your PLT on the PLTPI system initialization parameter. See Figure 13 for an example of this.
2. Add the sample DCT entries (CSQ4DCT1 and CSQ4DCT2) to those of the existing CICS DCT and then reassemble the DCT.

3. Add the following MQSeries libraries to the STEPLIB concatenation in your CICS procedure in this order:
   - thlqual.SCSQANLx
   - thlqual.SCSQAUTH

   Where x is the language letter for your national language.
4. Add the following MQSeries libraries to the DFHRPL concatenation in your CICS procedure in this order:
   - thlqual.SCSQANLx
   - thlqual.SCSQCICS
   - thlqual.SCSQAUTH

   Where x is the language letter for your national language.

   If you are using any CICS programs that dynamically call the MQSeries CICS stub, CSQCSTUB, also add thlqual.SCSQLOAD to the DFHRPL concatenation.

   If you are using the API-crossing exit (CSQCAPX), also add the name of the library that contains the load module for the program.
5. Update CSQINP2. You can use the sample CSQ4INYG, but you might need to change the initiation queue name to match your system definition.

For more information about:

- The CICS initiation queue, see "Task initiator" on page 119.
- The CKQC transaction, see "Starting a connection" on page 133.
- PLTPI programs, see "Writing a PLTPI program to start the connection" on page 128.
- Coding CICS system initialization parameters, see the *CICS System Definition Guide*.

Completing the connection from CICS

The connection is completed when the CICS adapter completes these steps:

1. Enable the CICS adapter and initialize the control blocks.
2. Attach the OS/390 subtasks and identify CICS generic *applid* (as specified in the CICS system initialization parameters as the connection ID) to MQSeries. This is described in the *CICS System Definition Guide*.

These two steps are done for you automatically if you use the INITPARM parameter or the CKQC transaction (see Chapter 7, "Operating the CICS adapter" on page 129). You can also use a PLTPI program to do this; see "Writing a PLTPI program to start the connection" on page 128.

When the connection is complete, a pending event called a *termination notification* is activated. This pending event remains active until MQSeries terminates in either an orderly or a forced way. When the pending event expires (or matures), it causes a FORCE shutdown request to be issued to the CICS adapter, and the pending event is canceled.

Controlling CICS application connections

Every CICS transaction that issues calls to MQSeries is assigned a unique thread ID to service the requests and keep track of changes made to MQSeries resources. The thread ID is created the first time a transaction issues an MQSeries request, and accompanies all subsequent MQSeries requests made by that transaction.

While executing work under the CICS main task TCB, the CICS adapter queues MQSeries requests for processing by any of the eight subtask TCBs. These subtask TCBs are attached by the adapter when the connection to MQSeries is established.

Customizing the CICS adapter

You can customize the CICS adapter by:

- Writing a user version of CSQCCODF that can be included in a CICS PLTPI program. See “Writing a PLTPI program to start the connection” for more information.
- Writing an API-crossing exit program. See “The API-crossing exit” on page 120 for more information.

Writing a PLTPI program to start the connection

You can write your own PLTPI program, based on the supplied assembler sample thlqual.SCSQASMS(CSQCSPLT).

Although this sample is written in assembler, you can write your own program in any language supported by CICS. A typical use of PLTPI programs is for overriding the INITPARM settings if your CICS adapter initiation queue name is too long. (You cannot use more than 42 characters for an initiation queue name in an INITPARM statement.) If your PLTPI program gets its input parameters from a data set, you do not need an INITPARM statement.

Your PLTPI program must link to the adapter connect program, thlqual.SCSQCICS(CSQCQCON), and pass a parameter list that specifies the connection values to be used. The parameter list is described in “Starting a connection from a CICS application program” on page 135. Figure 15 shows the LINK command that your PLTPI program must issue. In this example, the parameter list is named CONNPL. Because no terminals are available at this stage of CICS start up, you must use the COMMAREA option to pass the parameter list.

```
EXEC CICS LINK PROGRAM('CSQCQCON')
          COMMAREA(CONNPL) LENGTH(length of CONNPL)
```

Figure 15. Linking to the adapter connect program, CSQCQCON, from a PLT program. The COMMAREA option is used, because no terminals are currently available.

For more information about writing CICS PLTPI programs, see the *CICS Customization Guide*.

Chapter 7. Operating the CICS adapter

This chapter describes how you can use the CICS adapter control functions to initiate and manage connections between MQSeries and CICS. It describes these tasks:

- "Invoking the adapter's control functions"
- "Preparing to use the CICS adapter" on page 131
- "Accessing the CICS adapter control panels" on page 132
- "Starting a connection" on page 133
- "Stopping a connection" on page 136
- "Modifying a connection" on page 138
- "Displaying details of connections and CICS tasks" on page 141
- "Starting an instance of the task initiator CKTI" on page 142
- "Stopping an instance of CKTI" on page 144
- "Displaying the current instances of CKTI" on page 146
- "Displaying CICS task information" on page 147
- "Purging tasks that are using the CICS adapter" on page 149
- "Shutting down a connection between MQSeries and the CICS adapter" on page 150

In this chapter, the MQSeries CICS adapter control panels are referred to as the CICS adapter control panels.

Invoking the adapter's control functions

You can invoke the control functions of the CICS adapter in three different ways:

1. From the CICS adapter control panels.
2. From the CICS command line.
3. From an application program.

From the CICS adapter control panels

You can use these CICS adapter controls panels to monitor and control connections between MQSeries and CICS.

From the initial panel, you first select an item from the menu bar at the top of the panel, and then select an action from one of the pull-down menus. In the displayed panel or secondary window, you can then type new values in the fields, as required.

From the CICS command line

You can take a "fast-path" approach and bypass the CICS adapter control panels, by specifying command line parameters on the CKQC transaction. The syntax of these command parameters, and examples of them, are given for each of the tasks described later in this chapter.

Note: You can also issue these commands from the console using OS/390 commands.

Commands take this form:

```
MODIFY CICS-job-name CKQC command-line-command
```

© Copyright IBM Corp. 1993,1999

From CICS application programs

You can use the EXEC CICS LINK command to invoke most adapter control functions from CICS application programs. The syntax of the EXEC CICS LINK commands you need, and examples, are given for each of the tasks described later in this chapter.

Command syntax in application programs

Some commands issued in this way must be padded with trailing spaces to make the length of the command 10 characters. When an argument follows the command, an extra space character must be added as a separator. See Figure 16. The commands affected by this restriction and the number of trailing spaces required for each command are:

Command	*Number of trailing spaces (not including the separator)*
START	5
MODIFY	4
STARTCKTI	1
STOPCKTI	2

With all other commands the padding is optional.

```
EXEC CICS LINK PROGRAM('CSQCRST ')
          INPUTMSG('CKQC MODIFY     Y')
                          ↑           ↑
                          ............
                          1           12
```

Figure 16. Padding adapter commands. The MODIFY command must be padded with 4 trailing spaces plus another space as a separator. Starting at the 'M' in MODIFY, the argument 'Y' is the twelfth character.

Note: This restriction applies only to commands issued from an application program; it does not apply to commands issued from the command line.

Passing parameters from a CICS transaction

Use the following rules to determine how to pass the parameters:

- The CICS transaction must be running on an attached terminal. If it is not, all MQSeries commands are ignored.
- If a CICS application program on an attached terminal is connected to MQSeries, you must use the INPUTMSG option with EXEC CICS LINK to pass parameters, except at PLTPI time.
- If you connect to MQSeries at PLTPI time, you must use the COMMAREA option to pass parameters. If you use the INPUTMSG option, the command is ignored.

  However, the adapter STOP commands:

  ```
  CKQC STOP
  CKQC STOP FORCE
  ```

  cannot be run at PLTPI time, regardless of whether you use the INPUTMSG option or the COMMAREA option.

EXEC CICS LINK interface messages

If you invoke the adapter operation functions START and STOP from an application program using EXEC CICS LINK, the resultant messages are written to both the system console and a transient data queue (TDQ) named CKQQ. When the application program returns from the LINK, it can read back the messages by repeating EXEC CICS READQ TD QUEUE(CKQQ) until the queue is empty. The following restrictions apply:

- The TDQ queue name is CKQQ and cannot be changed. A sample TDQ definition is provided (in CSQ4DCT2), which defines CKQQ as an intra-partition TDQ.
- The queue is not cleared before it is written to.
- The messages are not time-stamped.
- If you have more than one application writing to the TDQ, the messages are not serialized. It is the responsibility of the invoking programs to serialize themselves.
- The same set of messages also appear on the system console.
- The server subtask messages are not written to CKQQ.

Preparing to use the CICS adapter

Before you can use the CICS adapter for messaging, you must start the MQSeries subsystem, if you have not already done so. To do this, use the START command with the appropriate command prefix string (CPF). Figure 17 shows the start command you issue from the operator console if the CPF is '`+cpf`'.

```
+cpf START QMGR
```

Figure 17. Starting a queue manager that is identified by the CPF '+cpf'

For more information about CPFs, see "Using command prefix strings" on page 42.

Accessing the CICS adapter control panels

To access the adapter control panels, use the CICS transaction CKQC:

1. Type CKQC and press Enter.

   The CICS adapter control initial panel, shown in Figure 18, is displayed.

2. In the menu bar at the top of the screen, use the TAB key to move between the three options **Connection**, **CKTI**, and **Task**.
3. Press Enter to select your choice.
4. Select the required option from one of the pull-down menus by typing the number of your choice and then pressing Enter to confirm or function key F12 to cancel.
5. Press function key F1 to get help on any panel or window.



Figure 18. The CICS adapter control initial panel

Note: You can access the adapter control panels *without* starting the MQSeries subsystem. You can also start a connection but it will not be active until MQSeries is started.

Starting a connection

You can start a connection from:

- The CICS adapter control panels
- The CICS command line
- A CICS application program
- A PLTPI program
- The CICS MQCONN SIT parameter

Starting a connection from the CICS adapter control panels

To start a connection from the CICS adapter control initial panel:

1. Select **Connection** from the menu bar.
2. Select the **Start** action from the pull-down menu. See Figure 19.
3. Modify the connection values displayed in the **Start a Connection** secondary parameter window. Alternatively, use the defaults derived from the INITPARM settings, if defined.
4. Press Enter to confirm.

Messages indicating the success or failure of the attempt to start the connection are displayed on the CICS adapter messages panel, CKQCM1.



Figure 19. Starting a connection

Starting a connection from the CICS command line

The example shown in Figure 20 starts a connection, using the default connection values set at system initialization.

```
CKQC START
```

Figure 20. Starting a connection from the command line

The command shown in Figure 21 starts a connection, using the explicitly defined connection parameter values. The parameters are positional—every field must be entered to its maximum length if you want to override the default.

```
CKQC START Y|N <subsystem ID> <trace number> <initiation queue name>
```

Figure 21. Starting a connection from the command line specifying parameters

Where:

Y|N
Specify either:

'Y' Use the default values, that is, substitute default values for any blank arguments.
'N' Do not use the default values.

<subsystem ID>
OS/390 subsystem name of the target queue manager.

<trace number>
The trace number. It must be in the range 0 through 199.

<initiation queue name>
The name of the default initiation queue.

Specifying lowercase queue names

By default, CICS translates lowercase input, for both keywords and parameters, to uppercase. Therefore, by default, these commands are equivalent:

```
CKQC START Y CSQ1 199 CICS01.INITQ
ckqc start y csq1 199 cics01.initq
```

Figure 22. Specifying lowercase queue names

If you want to use lowercase queue names, you must:

1. Specify UCTRAN(TRANID) on the TYPETERM definition of terminals that start adapter control functions.
2. Specify UCTRAN(NO) on the transaction profile used by all “CKxx” transactions.

Thereafter, the adapter translates all lowercase arguments, *except queue names*, to uppercase.

For details of TYPETERM and PROFILE definitions, see the *CICS Resource Definition Guide*.

Starting a connection from a CICS application program

You can start a connection by linking the adapter connect program, CSQCQCON, from a CICS application program. Your program, which can be written in C/370, COBOL, PL/I, or assembler language, must pass a parameter list that specifies the connection values to be used. The parameter list is:

CKQC 4-character transaction ID—must be `'CKQC'`.

DISPMODE 1-byte field—must contain a blank.

CONNREQ 10-character field—must contain `'START '`.

DELIM1 1-byte delimiter field—must contain a blank.

INITP 1-character field that specifies whether this connection is to use the default parameters set by INITPARM. The possible values are:

- `'Y'` Use the default values, that is, substitute default values for any blank arguments.
- `'N'` Do not use the default values. If you code `'N'`, you must supply all the new connection values, to override the INITPARM settings, in the CONNSSN, CONNTN, and CONNIQ fields.
- `' '` Equivalent to `'Y'`.

DELIM2 1-byte delimiter field—must contain a blank.

CONNSSN 4-character field used to specify the OS/390 subsystem name of the target queue manager.

DELIM3 1-byte delimiter field—must contain a blank.

CONNTN 3-character trace number. If supplied, it must be in the range 0 through 199.

DELIM4 1-byte delimiter field—must contain a blank.

CONNIQ 48-character field that specifies the name of the default initiation queue.

Figure 23 shows the LINK command that your CICS program must issue.

```
EXEC CICS LINK PROGRAM('CSQCQCON')
          INPUTMSG(CONNPL) INPUTMSGLEN(length of CONNPL)
```

Figure 23. Linking to the adapter connect program, CSQCQCON, from a CICS program. In this example, the name of the parameter list is CONNPL.

Output messages from CSQCQCON are displayed on the system console.

Stopping a connection

You can stop a connection from:

- The CICS adapter control panels
- The CICS command line
- A CICS application program

Stopping a connection from the CICS adapter control panels

From the initial panel:

1. Select **Connection** from the menu bar.
2. Select the **Stop** action from the pull-down menu.
3. Use the **Stop Connection** secondary parameter window to select the type of shutdown that you require. Methods of shutting down the CICS adapter are summarized in Table 15 on page 150.



Figure 24. Stopping a connection from the CKQC initial panel

The messages associated with stopping a connection are displayed on the system console.

Stopping a connection from the CICS command line

The command shown in Figure 25 initiates a *quiesced* shutdown. The connection shuts down only after the last task has completed its work.

```
CKQC STOP
```

Figure 25. Stopping a connection from the command line—a quiesced shutdown

The command shown in Figure 26 initiates a *forced* shutdown. The connection shuts down immediately, regardless of the state of any in-flight tasks.

```
CKQC STOP FORCE
```

Figure 26. Stopping a connection from the command line—a forced shutdown

Stopping a connection from a CICS application program

To stop a connection from a CICS program, the program must link to the adapter shutdown program, CSQCDSC. Figures 27 and 28 show examples of LINK commands initiating quiesced and forced shutdowns. When you do an EXEC CICS LINK to CSQCDSC, the program requires a terminal associated task.

```
EXEC CICS LINK PROGRAM('CSQCDSC ')
          INPUTMSG('CKQC STOP')
```

Figure 27. Stopping a connection from a CICS application program—a quiesced shutdown. The QUIESCE parameter is optional.

```
EXEC CICS LINK PROGRAM('CSQCDSC ')
          INPUTMSG('CKQC STOP FORCE')
```

Figure 28. Stopping a connection from a CICS application program—a forced shutdown

Output messages from CSQCDSC are displayed on the system console.

Modifying a connection

You can modify a connection to reset the connection statistics, enable or disable the API-crossing exit, or change the adapter's trace number. You can do this from:

- The CICS adapter control panels
- The CICS command line
- A CICS application program

Modifying a connection from the CICS adapter control panels

From the initial panel:

1. Select **Connection** from the menu bar.
2. Select the **Modify** action from the pull-down menu.
3. Use the **Modification Options** secondary parameter window to specify the option you require.

   To change the trace number:

   - Enter 4 in the options selection field
   - Enter a number, in the range 0 through 199, in the trace number field. Do not change the 4 in the options selection field before you press Enter. If you do, the trace number will not be changed.
4. Press Enter to confirm your choice.
5. Repeat steps 1 through 4, as required.



Figure 29. Modifying a connection

Modifying a connection from the CICS command line

You can use the CKQC MODIFY command to modify a connection.

```
CKQC MODIFY Y|N E|D <trace-number>
```

Figure 30. Format of command to modify connection parameters from the command line

The command syntax is shown in Figure 30, where:

Y|N Specify one of:

Y Reset connection statistics.
N Do not reset connection statistics.

This parameter is required.

E|D Specify one of:

E Enable the API-crossing exit.
D Disable the API-crossing exit.

This parameter is optional, the default is to disable the API-crossing exit.

<trace number>
Specify a valid trace number in the range 0 through 199. This parameter is optional. If it is not specified, the trace number is not changed.

The command shown in Figure 31 resets the connection statistics only. The command shown in Figure 32 disables the API-crossing exit and changes the trace number to 121.

```
CKQC MODIFY Y
```

Figure 31. Resetting connection statistics from the command line

```
CKQC MODIFY N D 121
```

Figure 32. Changing the adapter's trace number and disabling the API-crossing exit from the command line

Modifying a connection from a CICS application program

To modify a connection from a CICS program, the program must link to the adapter reset program, CSQCRST.

Figure 33 shows the format of the LINK command. It has the same effect as the command-line requests described in “Modifying a connection from the CICS command line” on page 139.

```
EXEC CICS LINK PROGRAM('CSQCRST ')
          INPUTMSG('CKQC MODIFY     Y E <trace-number>')
```

Figure 33. Format of the MODIFY command issued from a CICS adapter application program

The command shown in Figure 34 resets the connection statistics only.

```
EXEC CICS LINK PROGRAM('CSQCRST ')
          INPUTMSG('CKQC MODIFY     Y')
```

Figure 34. Resetting connection statistics from a CICS program

The command shown in Figure 35 disables the API-crossing exit and changes the trace number to 121.

```
EXEC CICS LINK PROGRAM('CSQCRST ')
          INPUTMSG('CKQC MODIFY     N D 121')
```

Figure 35. Linking to the adapter reset program, CSQCRST, from a CICS program

Note: The MODIFY command must be padded to 10 characters, see “Command syntax in application programs” on page 130.

Displaying details of connections and CICS tasks

You can use the CICS adapter control panels to display details of the current connection. The equivalent functionality is not available from the CICS command line or from a CICS application program. However, you can obtain some status information using the CKQC DISPLAY command, see “Displaying connection status and in-flight tasks” on page 148.

Displaying details of a connection from the CICS adapter control panels

From the initial panel:

1. Select **Connection** from the menu bar.
2. Select the **Display** action from the pull-down menu.

Figure 36 shows the details provided:

```
CKQCM2                    Display Connection panel

Read connection information. Then press F12 to cancel.

  CICS Applid =  VICIC14   Connection Status = Connected       Qmgrname = VCA
  Trace No.   =  124       Tracing           = On              API Exit = Off
  Initiation Queue Name = VICIC14.INITIATION.QUEUE
--------------------------- S T A T I S T I C S ----------------------------
Number of in-flight tasks =   1           Total No. of API calls =      43912
Number of running CKTI    =   1
         APIs and flows analysis              Syncpoint          Recovery
----------------------------------------  -------------------  ---------------
Run OK        43874  MQINQ          6806  Tasks            26  Indoubt       0
Futile            0  MQSET             0  Backout           0  UnResol       0
MQOPEN         6833  ------ Flows ------  Commit           10  Commit        0
MQCLOSE        6823  Calls         43952   S-Phase         10  Backout       0
MQGET         10032  SyncComp      43922   2-Phase          0
 GETWAIT       3399  SuspReqd          0  ------------------------------------
MQPUT         13399  MsgWait           7  InitTCBs  8 StrtTCBs  8 BusyTCBs  0
MQPUT1            5  Switched      43940


F1=Help  F12=Cancel  Enter=Refresh
```

Figure 36. The display connection panel

The display is organized into three areas:

- Top: parameters used for the connection, and current status.
- Middle: connection statistics. These are totals for the current connection, since statistics were last reset.
- Bottom: statistics produced by the adapter.

For an explanation of specific fields on this screen, view the online help panels by pressing function key F1.

Starting an instance of the task initiator CKTI

CKTI is the MQSeries-supplied task initiator[3] used in a CICS environment to start a transaction when the trigger conditions on any of its associated MQSeries queues are met. For more information, see “Task initiator” on page 119.

You can start a CKTI instance from:

- The CICS adapter control panels
- The CICS command line
- A CICS application program
- From emulated terminals (see “Automating starting of CKTI” on page 456)

Starting CKTI from the CICS adapter control panels

From the initial panel:

1. Select **CKTI** from the menu bar.
2. Select the **Start** action from the pull-down menu.
3. In the **Start Task Initiator** secondary window, use the **Initiation Queue Name** field to specify the name of the initiation queue to be serviced by this CKTI instance. If you leave this field blank, the default initiation queue is used, if defined.



Figure 37. Starting an instance of CKTI

[3] Trigger monitor in MQSeries terminology.

Starting CKTI from the CICS command line

The command shown in Figure 38 starts an instance of CKTI to serve the default initiation queue, if defined.

```
CKQC STARTCKTI
```

Figure 38. Starting an instance of CKTI—for the default initiation queue

The command shown in Figure 39 starts an instance of CKTI to serve a specified initiation queue.

```
CKQC STARTCKTI CICS01.INITIATION.QUEUE2
```

Figure 39. Starting an instance of CKTI—for a specified initiation queue

Starting CKTI from a CICS application program

To start an instance of CKTI from a CICS program, the program must link to the adapter task initiation program, CSQCSSQ. Figures 40 through 41 show suitable LINK commands. When you do an EXEC CICS LINK to CSQCSSQ, the program requires a terminal associated task.

```
EXEC CICS LINK PROGRAM('CSQCSSQ ')
          INPUTMSG('CKQC STARTCKTI ')
```

Figure 40. Linking to the adapter task-initiator program CSQCSSQ from CICS. This starts a CKTI that uses the default initiation queue.

```
EXEC CICS LINK PROGRAM('CSQCSSQ ')
          INPUTMSG('CKQC STARTCKTI  CICS01.INITIATION.QUEUE2')
```

Figure 41. Linking to the adapter task-initiator program CSQCSSQ from CICS. This starts a CKTI that uses a named initiation queue.

Output messages from CSQCSSQ are displayed on the system console.

Note: The STARTCKTI command must be padded to 10 characters; see “Command syntax in application programs” on page 130.

Stopping an instance of CKTI

You can stop an instance of CKTI by using:

- The CICS adapter control panels
- The CICS command line
- A CICS application program

Stopping an instance of CKTI from the CICS adapter control panels

From the initial panel:

1. Select **CKTI** from the menu bar.
2. Select the **Stop** action from the pull-down menu.
3. Use the **Stop Task Initiator** secondary window to specify the name of the initiation queue serviced by this instance of CKTI. If you leave the name blank, the default initiation queue, if defined, is used.



Figure 42. Stopping an instance of the task initiator CKTI

Stopping an instance of CKTI from the command line

The command shown in Figure 43 stops an instance of CKTI that is serving the default initiation queue, if there is one.

```
CKQC STOPCKTI
```

Figure 43. Stopping an instance of CKTI from the command line—for the default initiation queue

The command shown in Figure 44 stops the instance of CKTI that is serving a specified initiation queue.

```
CKQC STOPCKTI CICS01.INITIATION.QUEUE2
```

Figure 44. Stopping an instance of CKTI from the command line—for a specified initiation queue

Stopping an instance of CKTI from an application program

You can stop an instance of CKTI by linking to the adapter task-initiator program, CSQCSSQ. Figures 45 through 46 show alternative LINK commands to stop an instance of CKTI from a CICS program. The first command stops the CKTI that is serving the default initiation queue; the second stops the CKTI serving a specified initiation queue.

```
EXEC CICS LINK PROGRAM('CSQCSSQ ')
          INPUTMSG('CKQC STOPCKTI  ')
```

Figure 45. Stopping an instance of CKTI from a program—for the default initiation queue from CICS

```
EXEC CICS LINK PROGRAM('CSQCSSQ ')
          INPUTMSG('CKQC STOPCKTI   CICS01.INITIATION.QUEUE2')
```

Figure 46. Stopping an instance of CKTI from a program—for a specified initiation queue from CICS

Note: The STOPCKTI command must be padded to 10 characters; see “Command syntax in application programs” on page 130.

Displaying the current instances of CKTI

You can use the CICS adapter control panels to display details of the current instances of CKTI. The equivalent functionality is not available from the CICS command line or from a CICS application program.

Displaying the current instances of CKTI from the CICS adapter control panels

From the initial panel:

1. Select **CKTI** from the menu bar
2. Select the **Display** action from the pull-down menu

Figure 47 shows the details provided for each instance of CKTI:

- CICS task number
- Task status
- Thread status
- Number of API calls it has issued
- Most recent API call it has issued
- Name of the initiation queue it is serving

Press function key F1 to display help information about each of the fields in this panel.

```
CKQCM4                        Display CKTI panel

Read CKTI status information. Then press F12 to cancel.

CKTI   1 to   1 of   1

 Task No.    Task Status    Thread Status    No-of-APIs    Last API
----------  -------------  ---------------  ------------  ----------
 0000123       Normal         Msg Wait                2     MQGET
   Initiation Queue Name: CICS01.INITIATION.QUEUE1









F1=Help  F7=Backward  F8=Forward  F12=Cancel  Enter=Refresh
```

Figure 47. The CKQC Display CKTI panel

Displaying CICS task information

You can use the CICS adapter control panels to display information about CICS tasks using MQI calls. The equivalent functionality is not available from the CICS command line or from a CICS application program. However, you can obtain some status information using the CKQC DISPLAY command, see “Displaying connection status and in-flight tasks” on page 148.

Displaying CICS tasks from the CICS adapter control panels

You can display information about the CICS tasks that are currently using MQI calls. From the initial panel:

1. Select **Task** from the menu bar.
2. Select an action from the pull-down menu.

   Select option 1, **List all tasks** to obtain information about all tasks that are currently active. To limit the scope of the display, select option 2, **List from task**, to specify the starting number of the first task to be displayed.

```
CKQCM3                        Display Task panel

Read task status information. Then press F12 to cancel.

Tasks   1 to   3 of   3

Txn    User    Task    Task    Thread     Total    Res  In     Last     Thread
Id      Id      No.    Status  Status      APIs    Sec API-X  MQ-Call     ID
---- -------- ----- -------- --------  ---------- ---  --- ---------- --------
PUTQ CICSUSER 00065  Normal  InQueue          102 No   No    MQPUT1   00012420
GETQ CICSUSER 00067  Normal  BtnCalls          22 No   No    MQOPEN   00012620
CKTI CICSUSER 00123  Normal  Msg Wait           2 No   No    MQGET    00012C20









F1=Help  F7=Backward  F8=Forward  F12=Cancel  Enter=Refresh
```

Figure 48. The CKQC Display Task panel

Figure 48 shows the details provided for each CICS task:

- Transaction ID (name)
- User ID
- CICS task number
- Task status
- Thread status
- Total number of API calls issued by this task
- Whether resource security checking is active for this task
- Whether this task is currently in the API-crossing exit
- Most recent API call issued by this task
- Thread ID used by MQSeries

Displaying connection status and in-flight tasks

You can use the CKQC DISPLAY command, from both the CICS command line or from a CICS application program to display limited information about the current connection and CICS tasks. The information from this command is returned in a message CSQC453I, see Figure 49. This message contains:

- The name of the MQSeries subsystem.
- The status of the connection.
- The number of in-flight tasks that are still using the connection.

```
CSQC453I VICY06 CSQCDSPL Status of connection to JAC2 is Connected. 2
tasks are in-flight
```

Figure 49. Message showing the status of a connection

To obtain more detailed information, use the CICS adapter control panels. See “Displaying details of a connection from the CICS adapter control panels” on page 141 and “Displaying CICS tasks from the CICS adapter control panels” on page 147, respectively.

From the CICS command line

You can use the CKQC DISPLAY command, shown in Figure 50, from the CICS command line.

```
CKQC DISPLAY
```

Figure 50. Displaying the status of a connection

Figure 49 shows a typical response to this command. The response messages are sent to your CICS terminal.

From a CICS application program

Figure 51 shows the LINK command for displaying the status of a connection from a CICS application program.

```
EXEC CICS LINK PROGRAM('CSQCDSPL') INPUTMSG('CKQC DISPLAY')
```

Figure 51. Linking to the adapter program CSQCDSPL from a CICS program

Figure 49 shows a typical output from this command. The response messages are sent to the CKQQ queue (the transient data queue).

The COMMAREA option can be used instead of INPUTMSG but only when the program is run at PLT time.

Purging tasks that are using the CICS adapter

You can use the CICS CEMT transaction to purge user tasks that are using the CICS adapter. Tasks that are waiting on the adapter respond only to CEMT SET TASK FORCEPURGE commands—CEMT SET TASK PURGE commands are ignored. The way the adapter handles a FORCEPURGE command depends on the kind of wait state that the task is in:

- If a task is waiting for a message to arrive, for example, the application has issued an **MQGET WAIT** call, the task is abended with code AEXY immediately.
- If the task is waiting for an MQI request to be completed by MQSeries, message CSQC413I is displayed on the system console.

  The adapter waits for the request to complete, and then checks whether it is suitable to abend the task:

  – If the task is in a critical state, the CICS adapter lets the task continue and ignores the attempt to purge it. This is done to preserve data and system integrity. Message CSQC415I is displayed.

    A task is in a critical state is when, for example, it is in the process of completing phase 2 of a two-phase commit sequence.

  – If the task is not in a critical state, the adapter abends it with code AEXY. Message CSQC414I is displayed.

For information about CEMT commands, see the *CICS-Supplied Transactions* manual.

Shutting down a connection between MQSeries and the CICS adapter

You can shut down a connection between MQSeries and the CICS adapter by using the CKQC transaction or an application program. There are two types of shutdown:

- Forced
- Quiesced

Other forms of connection shutdown result from a termination of CICS or MQSeries. Table 15 summarizes how the adapter handles different forms of connection shutdown.

Table 15. Shutting down a CICS adapter connection

Method of shutdown	**How this is handled by the adapter**
CKQC STOP *(A quiesced shutdown)*	Mark the status of the adapter as *Quiescing*. Allow both active and waiting tasks to complete. Allow syncpoint. Do not allow calls from a new task. The last task initiates disconnection from MQSeries.
CKQC STOP FORCE	Mark the status of the adapter as *StoppingForce*. Disconnect from MQSeries. Resume waiting tasks. Fail any in-flight or following MQI calls.
CICS warm shutdown	Issue message CSQC411I. Initiate a quiesced shutdown of the connection; see CKQC STOP, above.
CICS immediate shutdown	Issue message CSQC410I. Any in-flight tasks using MQSeries are backed out.
CICS abend	Issue message CSQC412I.
MQSeries quiesced	Initiate a quiesced shutdown of the connection; see CKQC STOP, above.
MQSeries abend or forced shutdown	Initiate a forced shutdown of connection; see CKQC STOP FORCE, above.

Notes:

1. If the connection is not active (for example, quiesced) when CICS or MQSeries shuts down, no action is taken and no messages are issued.
2. “Waiting tasks” includes instances of CKTI, which you must stop before shutdown completes.

Orderly shutdown

An orderly shutdown of the connection lets each CICS transaction terminate before thread subtasks are detached. When you use this method, there should be no in-doubt units of work when you reconnect CICS. An orderly termination occurs in each of the following situations:

- The CICS terminal operator issues a CKQC STOP command. CICS and MQSeries remain active. The command can be issued from the command line, from a terminal using the CKQC panels, or from a program, see page 137.
- The CICS terminal operator issues the CICS command:

  ```
  CEMT PERFORM SHUTDOWN
  ```

  For information about the CEMT PERFORM SHUTDOWN command, see the *CICS-Supplied Transactions* manual.
- MQSeries is quiesced by the command:

  ```
  +cpf STOP QMGR MODE(QUIESCE)
  ```

  This stops the MQSeries subsystem, allows the currently identified tasks to continue normal execution, and does not allow new tasks to identify themselves to MQSeries. CICS remains active.

Forced shutdown

A forced shutdown of the connection can abend CICS transactions connected to MQSeries. Therefore, there might be in-doubt units of work when the system is reconnected. A forced shutdown occurs in each of these situations:

- The CICS terminal operator issues the CKQC STOP FORCE command. The command can be issued from the command line, from a terminal using the CKQC panels, or from a program, see page 137.
- The CICS terminal operator issues the CICS immediate termination command:

  ```
  CEMT PERFORM SHUTDOWN IMMEDIATE
  ```

  For information about this command, see the *CICS-Supplied Transactions* manual.

  MQSeries remains active.
- The MQSeries forced termination command is issued:

  ```
  +cpf STOP QMGR MODE(FORCE) or +cpf STOP QMGR MODE(RESTART)
  ```

  CICS remains active.
- An MQSeries abend occurs. CICS remains active.
- CICS abend occurs. MQSeries remains active.

Shutting down a connection

Chapter 8. The MQSeries-CICS bridge

This chapter describes the CICS bridge.

This chapter contains the following sections:

- "Introduction to the CICS bridge"
- "Customizing the CICS bridge" on page 158
- "Starting the CICS bridge" on page 160
- "Shutting down the CICS bridge" on page 161

Introduction to the CICS bridge

The MQSeries-CICS bridge enables an application, not running in a CICS environment, to run a *program* or *transaction* on CICS and get a response back. This non-CICS application can be run from any environment that has access to an MQSeries network that encompasses MQSeries for OS/390.

A *program* is a CICS program that can be invoked using the EXEC CICS LINK command. It must conform to the DPL subset of the CICS API, that is, it must not use CICS terminal or syncpoint facilities.

A *transaction* is a CICS transaction designed to run on a 3270 terminal. This transaction can use BMS or TC commands. It can be conversational or part of a pseudoconversation. It is permitted to issue syncpoints. For further details about the transactions that can be run, see Part 5 of the *CICS Internet and External Interfaces Guide* (Bridging to 3270 transactions).

When to use the CICS bridge

The CICS bridge allows an application to run a single CICS program or a 'set' of CICS programs (often referred to as a unit of work). It caters for the application that waits for a response to come back before it runs the next CICS program (synchronous processing) and for the application that requests one or more CICS programs to run, but doesn't wait for a response (asynchronous processing).

The CICS bridge also allows an application to run a 3270-based CICS transaction, without knowledge of the 3270 data stream.

The CICS bridge uses standard CICS and MQSeries security features and can be configured to authenticate, trust, or ignore the requestor's user ID.

Given this flexibility, there any many instances where the CICS bridge can be used. For example, when you want:

- To write a new MQSeries application that needs access to logic or data (or both) that reside on your CICS server.
- To be able to run CICS programs from a Lotus Notes® application.
- To be able to access your CICS applications from
  - Your MQSeries Classes for Java client application
  - A web browser using the MQSeries Internet gateway

© Copyright IBM Corp. 1993,1999

For information about how to write an MQSeries-CICS bridge application, see the *MQSeries Application Programming Guide*.

System configuration for the CICS bridge

When you are setting your system up, you should ensure that:

- Both MQSeries and CICS are running in the same OS/390 image.
- The MQSeries request queue is local to the CICS bridge, however the response queue can be local or remote.
- The CICS bridge tasks run in the same CICS as the bridge monitor. The user programs can be in the same or a different CICS system.
- The MQSeries-CICS adapter is enabled.

Running CICS DPL programs

Data necessary to run the program is provided in the MQSeries message. The bridge builds a COMMAREA from this data, and runs the program using EXEC CICS LINK. Figure 52 shows the step sequence taken to process a single message to run a CICS DPL program:



Figure 52. Components and data flow to run a CICS DPL program

The following takes each step in turn, and explains what takes place:

1. A message, with a request to run a CICS program, is put on the request queue.
2. The CICS bridge monitor task, which is constantly browsing the queue, recognizes that a 'start unit of work' message is waiting (*CorrelId*=MQCI_NEW_SESSION).
3. Relevant authentication checks are made, and a CICS DPL bridge task is started with the appropriate authority (see "Security considerations for the CICS bridge" on page 457 for more information).
4. The CICS DPL bridge task removes the message from the request queue.
5. The CICS DPL bridge task builds a COMMAREA from the data in the message and issues an EXEC CICS LINK for the program requested in the message.
6. The program returns the response in the COMMAREA used by the request.
7. The CICS DPL bridge task reads the COMMAREA, creates a message, and puts it on the reply-to queue specified in the request message. All response messages (normal and error, requests and replies) are put to the reply-to queue with default context.
8. The CICS DPL bridge task ends.

A unit of work can be just a single user program, or it can be multiple user programs. There is no limit to the number of messages you can send to make up a unit of work.

In this scenario, a unit of work made up of many messages works in the same way, with the exception that the CICS bridge task waits for the next request message in the final step unless it is the last message in the unit of work.

Running CICS 3270 transactions

Data necessary to run the transaction is provided in the MQSeries message. The CICS transaction runs as if it has a real 3270 terminal, but instead uses one or more MQ messages to communicate between the CICS transaction and the MQSeries application

Unlike traditional 3270 emulators, the bridge does not work by replacing the VTAM® flows with MQSeries messages. Instead, the message consists of a number of parts called vectors, each of which corresponds to an EXEC CICS request. Therefore the application is talking directly to the CICS transaction, rather than via an emulator, using the actual data used by the transaction (known as application data structures or ADSs).

Figure 53 on page 156 shows the step sequence taken to process a single message to run a CICS 3270 transaction.

The following takes each step in turn, and explains what takes place:

1. A message, with a request to run a CICS transaction, is put on the request queue.
2. The CICS bridge monitor task, which is constantly browsing the queue, recognizes that a 'start unit of work' message is waiting (*CorrelId*=MQCI_NEW_SESSION).

Introduction to the CICS bridge



Figure 53. Components and data flow to run a CICS 3270 transaction

3. Relevant authentication checks are made, and a CICS 3270 bridge task is started with the appropriate authority (see “Security considerations for the CICS bridge” on page 457 for more information).
4. The MQ-CICS bridge exit removes the message from the queue and changes task to run a user transaction
5. Vectors in the message provide data to answer all terminal related input EXEC CICS requests in the transaction.
6. Terminal related output EXEC CICS requests result in output vectors being built.
7. The MQ-CICS bridge exit builds all the output vectors into a single message and puts this on the reply-to queue.
8. The CICS 3270 bridge task ends.

Note: The CICS bridge exit is an MQSeries supplied CICS exit associated with the bridge transaction.

A traditional CICS application usually consists of one or more transactions linked together as a pseudoconversation. In general, each transaction is started by the 3270 terminal user entering data onto the screen and pressing an AID key. This model of application can be emulated by an MQSeries application. A message is built for the first transaction, containing information about the transaction, and input

vectors. This is put on the queue. The reply message will consist of the output vectors, the name of the next transaction to be run, and a token that is used to represent the pseudoconversation. The MQSeries application builds a new input message, with the transaction name set to the next transaction and the facility token set to the value returned on the previous message. Vectors for this second transaction are added to the message, and the message put on the queue. This process is continued until the application ends.

An alternative approach to writing CICS applications is the conversational model. In this model, the original message might not contain all the data to run the transaction. If the transaction issues a request that cannot be answered by any of the vectors in the message, a message is put onto the reply-to queue requesting more data. The MQSeries application gets this message and puts a new message back to the queue with a vector to satisfy the request.

For more information about this, see the *CICS Internet and External Interfaces Guide*.

Customizing the CICS bridge

This section describes what you have to do to customize the MQSeries-CICS bridge. The bridge is described in “Introduction to the CICS bridge” on page 153.

Prerequisite APARs

To run 3270 transactions, you must be using CICS Transaction Server for OS/390 Release 2 or later, with APARs PQ13011 and PQ13012 applied.

Before you can run the bridge you must ensure that your OS/390 system has both the CICS and MQSeries components in place:

1. On your CICS system:
   a. Run the resource definition utility DFHCSDUP, using the sample thlqual.SCSQPROC(CSQ4CKBC) as input, to define the bridge transactions and programs:

CKBR	Bridge monitor transaction
CSQCBR00	Bridge monitor program
CKBP	Bridge ProgramLink transaction
CSQCBP00	Bridge ProgramLink program
CSQCBP10	Bridge ProgramLink abend handler program
CSQCBTX	Bridge error messages
CSQCBE00	3270 bridge exit for MQSeries
CBR1 through CBR8	3270 bridge transaction definitions

   b. Add the group, CSQCKB, to your startup group list.

   Notes:

   a. The bridge uses CICS temporary storage IDs with the prefix CKB. You should make sure these are not recoverable.

   b. By default, your CICS DPL programs will be run under transaction code CKBP. You will need to change the TASKDATALOC attribute to 'BELOW' if you are going to run 24-bit programs, otherwise you will get a CICS abend AEZC. If you wish to run your programs under different transaction codes you will need to install copies of the definition of CKBP, changing the transaction name to the ones of your choice. DPL bridge transactions must not be routed to a remote system.

2. On your MQSeries system:
   a. Define a local queue for the request messages.

      You can use the sample thlqual.SCSQPROC(CSQ4CKBM) to define a queue named SYSTEM.CICS.BRIDGE.QUEUE, or define your own. If you define your own, you must set the following attributes:

      SHARE
      So that both the monitor and the bridge tasks can read it.

      MSGDLVSQ(FIFO)
      So that messages are processed in FIFO sequence (not priority sequence).

If recovery is required, set the following attributes:

DEFPSIST(YES)
Set messages as persistent on the queue by default.

HARDENBO
Set HARDENBO to ensure that messages are not re-processed erroneously after an emergency restart.

b. Define one or more queues to hold the responses, as required. If your response queue is remote, you must define a transmission queue to hold the responses before they are forwarded to the response queue.

3. Security:

   You might need to add RACF definitions, depending on the authentication option you choose to use. See "Security considerations for the CICS bridge" on page 457 for more information about this.

If the bridge is to be accessed remotely from MQSeries for OS/390, you need channel and transmission queue definitions, and a remote queue definition for the request queue. For more information about using remote queues see the *MQSeries Intercommunication* manual.

Note: The MQSeries queue defined to hold requests for the CICS bridge must not be used by any other application. Each CICS bridge monitor task started requires its own MQSeries queue to hold requests.

Starting the CICS bridge

To start the bridge, you need to run the CKBR transaction providing a maximum of three parameters:

- Q=*qqq*, where *qqq* is the name of the queue holding requests. If you don't specify one, the default is:

  SYSTEM.CICS.BRIDGE.QUEUE

  Remember that names of objects within MQSeries are case-sensitive.

- WAIT=*nnn*, where *nnn* is the number of seconds that you want the bridge task to wait for second and subsequent requests before timing out when processing a unit of work that runs many user programs.

  The default wait time is unlimited.

  You are recommended to specify a wait time. If you don't, the CICS bridge might inhibit CICS or MQSeries shut down.

- AUTH=*xxx*, where *xxx* is the security option. The default is LOCAL. See “Security considerations for the CICS bridge” on page 457 for more information.

Start the CKBR task running by using one of the following methods:

- Input a single line from a terminal (3270 or other). Note that the terminal is not freed until the monitor ends. The format is:

  <trancode> <parameters>

  ```
  CKBR Q = <queue name>, AUTH = <auth option>,  WAIT = nnn
  ```

  For example:

  ```
  CKBR Q = MyQueue, AUTH = IDENTIFY, WAIT = 30
  ```

- Issue an EXEC CICS START for the CKBR program with the parameters as data.
- Issue an EXEC CICS LINK to the program CSQCBR00 with the parameters as data in the commarea.
- Use TRIGGER TRIGTYPE(FIRST) from the bridge request queue to a process specifying APPLICID(CKBR), with any parameters for the AUTH and WAIT options in USERDATA.

The level of security you want to use will influence how you start the monitor task. See “Security considerations for the CICS bridge” on page 457 for more information on the security options available to you.

Tuning considerations

You can control the throughput of the bridge by putting the bridge transaction, CKBP, in a class of its own and setting the CLASSMAXTASK to suit your requirements.

If a high volume of requests is expected, you could consider starting a second or subsequent monitor task. To do this, you must create another request queue for the sole use of this monitor (and the bridge tasks it starts).

Shutting down the CICS bridge

There are various ways in which you can shut down the CICS bridge:

- By altering the attributes of the request queue by setting GET(DISABLED)
- By shutting CICS down
- By shutting MQSeries down

Whichever method you choose, it will attempt to allow all the requests in progress to complete first.

However in the event that this is not possible, the problems encountered are reported on the CICS CSMT log.

Note: The CICS bridge does not stop CICS or MQSeries if either of them are in the process of shutting down, unless bridge tasks started with WAIT_UNLIMITED have **MQGET** calls outstanding for second or subsequent messages in a unit of work.

Restarting the monitor

The monitor requires exclusive use of the request queue during its initialization, so the monitor cannot be restarted until all bridge tasks for the queue have terminated.

Shutting down the CICS bridge

Part 4. MQSeries and IMS

Chapter 9. The MQSeries-IMS adapter 165
Introduction to the IMS adapter 165
Using the adapter 165
The IMS trigger monitor 166
Setting up the IMS adapter 167
Defining MQSeries to IMS 168
Defining the MQSeries subsystem to the IMS adapter 171
The IMS trigger monitor 173

Chapter 10. Operating the IMS adapter 175
Controlling IMS connections 175
Connecting from the IMS control region 176
Initializing the adapter and connecting to MQSeries 176
Thread attachment 177
Displaying in-doubt units of recovery 178
Recovering in-doubt units of recovery 178
Resolving residual recovery entries 179
Controlling IMS dependent region connections 180
Connecting from dependent regions 180
Region error options 180
Monitoring the activity on connections 180
Disconnecting from dependent regions 181
Disconnecting from IMS 182
Controlling the IMS trigger monitor 183
Starting CSQQTRMN 183
Stopping CSQQTRMN 184

Chapter 11. The MQSeries-IMS bridge 185
Introduction to the IMS bridge 185
What is OTMA? 185
Submitting IMS transactions from MQSeries 186
Customizing the IMS bridge 187
Controlling the IMS bridge 188
Controlling IMS connections 188
Controlling bridge queues 189
Deleting messages from IMS 189
Resynchronizing the IMS bridge 190
Security 191

© Copyright IBM Corp. 1993,1999

Chapter 9. The MQSeries-IMS adapter

This chapter introduces the MQSeries-IMS adapter (also referred to as the IMS adapter). It contains these sections:

- "Introduction to the IMS adapter"
- "Setting up the IMS adapter" on page 167

Introduction to the IMS adapter

The MQSeries adapters enable different application environments to send and receive messages through a message queuing network. The IMS adapter is the interface between IMS application programs and an MQSeries subsystem. It makes it possible for IMS application programs to use the MQI.

The IMS adapter provides access to MQSeries resources for programs running in:

- Task (TCB) mode
- Problem state
- Non-cross-memory mode
- Non-access register mode

The adapter provides a connection thread from an application task control block (TCB) to MQSeries.

The adapter supports a two-phase commit protocol for changes made to resources owned by MQSeries with IMS acting as the syncpoint coordinator.

The adapter also provides a trigger monitor transaction (CSQQTRMN). This is described in "The IMS trigger monitor" on page 166.

Using the adapter

The application programs and the IMS adapter run in the same address space. MQSeries for OS/390 is a separate OS/390 subsystem, in its own address space.

Each program that issues one or more MQI calls must be link-edited to a suitable IMS language interface module, and, unless it uses dynamic MQI calls, the MQSeries-supplied stub program, CSQQSTUB. When the application issues an MQI call, the stub transfers control to the adapter through the IMS external subsystem interface, which manages the processing of the request by the message queue manager.

Note: If the adapter detects an unexpected MQSeries subsystem error, it issues an OS/390 SNAP dump to DDname CSQSNAP, and issues reason code `MQRC_UNEXPECTED_ERROR` to the application.

If this occurs, rerun the application with a CSQSNAP DD statement included in the IMS dependent region JCL, and contact your IBM support center.

© Copyright IBM Corp. 1993,1999

The IMS trigger monitor

CSQQTRMN is an MQSeries-supplied IMS application that starts an IMS transaction when an MQSeries event occurs, for example, when a message is put onto a specific queue.

How it works

When a message is put onto a message queue, a trigger is generated if the trigger conditions are met. The queue manager then writes a message (containing some user defined data), known as a *trigger message*, to the initiation queue that has been specified for that message queue. In an IMS environment, an instance of CSQQTRMN can be started to monitor an initiation queue and to retrieve the trigger messages from it as they arrive. Typically, CSQQTRMN schedules another IMS transaction by an ISRT to the IMS message queue. The IMS application reads the message from the message queue and then processes it. CSQQTRMN must run as a non-message BMP.

Each copy of CSQQTRMN services a single initiation queue. Once started, the trigger monitor runs until MQSeries or IMS ends.

The APPLCTN macro for CSQQTRMN must specify SCHDTYP=PARALLEL.

Because the trigger monitor is a batch-oriented BMP, IMS transactions started by the trigger monitor will contain:

- Blanks in the LTERM field of the IOPCB
- The PSB name of the trigger monitor BMP in the Userid field of the IOPCB

If the target IMS transaction is RACF protected, you might need to define CSQQTRMN as a user ID to RACF.

Setting up the IMS adapter

This section tells you how to make the MQSeries-IMS adapter (referred to in this book as the IMS adapter) available to your IMS subsystem. If you are not familiar with tailoring an IMS subsystem, see the *IMS Customization Guide*.

To make the IMS adapter available to IMS applications, follow these steps:

1. Define MQSeries to IMS as an external subsystem using the IMS external subsystem attach facility (ESAF). See "Defining MQSeries to IMS" on page 168.
2. Include the MQSeries load library thlqual.SCSQAUTH in the JOBLIB or STEPLIB concatenation in the JCL for your IMS control region and for any dependent region that connects to MQSeries. If your JOBLIB or STEPLIB is not authorized, also include it in the DFSESL concatenation after the library containing the IMS modules (usually IMS RESLIB).

   Also include thlqual.SCSQANLx (where x is the language letter).
3. Copy the MQSeries assembler program CSQQDEFV from thlqual.SCSQASMS to a user library.
4. The supplied program, CSQQDEFV, contains one subsystem name CSQ1 identified as default with an IMS language interface token (LIT) of MQM1. You can retain this name for testing and installation verification. For production subsystems, you can change the NAME=CSQ1 to your own subsystem name or use CSQ1. You can add further subsystem definitions as required. See "Defining the MQSeries subsystem to the IMS adapter" on page 171.
5. Assemble and link-edit the program to produce the CSQQDEFV load module. For the assembly, include the library thlqual.SCSQMACS in your SYSLIB concatenation; use the link-edit parameters `RENT,AMODE=31,RMODE=ANY`. This is shown in the sample JCL in thlqual.SCSQPROC(CSQ4DEFV).
6. Include the user library containing the module CSQQDEFV that you created in the JOBLIB or STEPLIB concatenation in the JCL for your IMS control region and for any dependent region that connects to MQSeries. If you do not do this, you will receive a user 3041 abend from IMS.
7. If you want to use dynamic MQI calls (described in the *MQSeries Application Programming Guide*), build the dynamic stub, as shown in Figure 54 on page 168.
8. If you want to use the IMS trigger monitor, define the IMS trigger monitor application CSQQTRMN, and perform PSBGEN and ACBGEN. See "The IMS trigger monitor" on page 173.
9. If you are using RACF to protect resources in the OPERCMDS class, ensure that your MQSeries system has authority to issue the MODIFY command to any IMS system to which it might connect.

```
//DYNSTUB EXEC PGM=IEWL,PARM='RENT,REUS,MAP,XREF'
//SYSPRINT DD  SYSOUT=*
//ACSQMOD  DD DISP=SHR,DSN=thlqual.SCSQLOAD
//IMSLIB   DD  DISP=SHR,DSN=ims.reslib
//SYSLMOD  DD  DISP=SHR,DSN=private.load[4]
//SYSUT1   DD  UNIT=SYSDA,SPACE=(CYL,1)
//SYSLIN   DD  *
  INCLUDE ACSQMOD(CSQQSTUB)
  INCLUDE IMSLIB (DFSLI000)
  ALIAS MQCONN,MQDISC            MQI entry points
  ALIAS MQGET,MQPUT,MQPUT1       MQI entry points
  ALIAS MQOPEN,MQCLOSE           MQI entry points
  ALIAS MQBACK,MQCMIT            MQI entry points
  ALIAS CSQBBAK,CSQBCMT          MQI entry points
  ALIAS MQINQ,MQSET              MQI entry points
  ALIAS DFSPLI,PLITDLI           IMS entry points
  ALIAS DFSCOBOL,CBLTDLI         IMS entry points
  ALIAS DFSFOR,FORTDLI           IMS entry points
  ALIAS DFSASM,ASMTDLI           IMS entry points
  ALIAS DFSPASCL,PASTDLI         IMS entry points
  ALIAS DFHEI01,DFHEI1           IMS entry points
  ALIAS DFSAIBLI,AIBTDLI         IMS entry points
  ALIAS DFSESS,DSNWLI,DSNHLI     IMS entry points
  MODE AMODE(31),RMODE(ANY)      Note RMODE
  NAME CSQQDYNS(R)
/*
```

Figure 54. Sample JCL to link-edit the dynamic call stub. This includes the IMS language interface module and the MQSeries IMS stub CSQQSTUB.

Defining MQSeries to IMS

An MQSeries instance must be defined to the control region, and to each dependent region accessing that MQSeries subsystem. To do this, you must create a subsystem member (SSM) in the IMS.PROCLIB library, and identify the SSM to the applicable IMS regions.

Placing the subsystem member entry in IMS.PROCLIB

Each SSM entry in IMS.PROCLIB defines a connection from an IMS region to a different subsystem.

To name an SSM member, concatenate the value (one to four alphanumeric characters) of the IMSID field of the IMS IMSCTRL macro with any name (one to four alphanumeric characters) defined by your site.

One SSM member can be shared by all of the IMS regions, or a specific member can be defined for each region. This member contains as many entries as there are connections to external subsystems. Each entry is an 80-character record.

[4] Specify the name of a library accessible to IMS applications that wish to make dynamic calls to MQSeries.

Positional parameters: The fields in this entry are:

```
SSN,LIT,ESMT,RTT,REO,CRC
```

where:

SSN Specifies the MQSeries subsystem name. It is required, and must contain one through four characters. This name must be the name you specified in the subsystem name table (see "Updating the subsystem name table" on page 41).

LIT Specifies the language interface token (LIT) supplied to IMS. This field is required, its value must match one in the CSQQDEFV module.

ESMT Specifies the external subsystem module table (ESMT). This table specifies which attachment modules must be loaded by IMS. CSQQESMT is the required value for this field.

RTT This option is not supported by MQSeries.

REO Specifies the region error option (REO) to be used if an IMS application tries to reference a non-operational external subsystem or if resources are unavailable at create thread time. This field is optional and contains a single character, which can be:

R Passes a return code to the application, indicating that the request for MQSeries services failed.

Q Abends the application with an abend code U3051, backs out activity to the last commit point, does a PSTOP of the transaction, and requeues the input message. This option only applies when an IMS application tries to reference a non-operational external subsystem or if the resources are unavailable at create thread time.

MQSeries completion and reason codes are returned to the application if the MQSeries problem occurs while MQSeries is processing the request; that is, after the adapter has passed the request on to MQSeries.

A Abends the application with an abend code of U3047 and discards the input message. This option only applies when an IMS application tries to reference a non-operational external subsystem or if the resources are unavailable at create thread time.

MQSeries completion and reason codes are returned to the application if the MQSeries problem occurs while MQSeries is processing the request; that is, after the adapter has passed the request on to MQSeries.

CRC This option can be specified but is not used by MQSeries.

An example SSM entry is:

```
CSQ1,MQM1,CSQQESMT,,R,
```

where:

CSQ1 The default subsystem name as supplied with MQSeries. You can change this to suit your installation.
MQM1 The default LIT as supplied in CSQQDEFV.
CSQQESMT The external subsystem module name. You must use this value.
R REO option.

Keyword parameters: MQSeries parameters can be specified in keyword format; to do this you must specify `SST=DB2`. Other parameters are as described in "Positional parameters" on page 169, and shown in the following example:

```
SST=DB2,SSN=SYS3,LIT=MQM3,ESMT=CSQQESMT
```

where:

SYS3 The subsystem name
MQM3 The LIT as supplied in CSQQDEFV
CSQQESMT The external subsystem module name

Specifying the SSM EXEC parameter

Specify the SSM EXEC parameter in the start up procedure of the IMS control region. This parameter specifies the one-character to four-character subsystem member name (SSM).

If you specify the SSM for the IMS control region, any dependent region running under the control region can attach to the MQSeries subsystem named in the IMS.PROCLIB member specified by the SSM parameter. The IMS.PROCLIB member name is the IMS ID (IMSID=*xxxx*) concatenated with the one to four characters specified in the SSM EXEC parameter. The IMS ID is the IMSID parameter of the IMSCTRL generation macro.

IMS lets you define as many external subsystem connections as are required. More than one connection can be defined for different MQSeries subsystems. All MQSeries connections must be within the same OS/390 system. For a dependent region, you can specify a dependent region SSM or use the one specified for the control region. You can specify different region error options (REOs) in the dependent region SSM member and the control region SSM member. Table 16 on page 171 shows the different possibilities of SSM specifications.

Table 16. SSM specifications options

SSM for control region	SSM for dependent region	Action	Comments
No	No	None	No external subsystem can be connected.
No	Yes	None	No external subsystem can be connected.
Yes	No	Use the control region SSM	Applications scheduled in the region can access external subsystems identified in the control region SSM. Exits and control blocks for each attachment are loaded into the control region and the dependent region address spaces.
Yes	Yes (empty)	No SSM is used for the dependent region	Applications scheduled in this region can access DL/I databases only. Exits and control blocks for each attachment are loaded into the control region address space.
Yes	Yes (not empty)	Check the dependent region SSM with the control region SSM	Applications scheduled in this region can access only external subsystems identified in both SSMs. Exits and control blocks for each attachment are loaded into the control region and the dependent region address spaces.

There is no specific parameter to control the maximum number of SSM specification possibilities.

Defining the MQSeries subsystem to the IMS adapter

The IMS adapter cannot access the IMS PROCLIB so the names of the MQSeries subsystems and their corresponding LITs must be defined in the subsystem definition table, CSQQDEFV. Use the supplied CSQQDEFX macro to create the CSQQDEFV load module. Figure 55 shows the syntax of this assembler macro.

```
CSQQDEFX  TYPE=ENTRY|DEFAULT,NAME=subsystem,LIT=token
 or
CSQQDEFX  TYPE=END
```

Figure 55. CSQQDEFX macro syntax

Parameters

TYPE=ENTRY|DEFAULT

Specify either TYPE=ENTRY or TYPE=DEFAULT as follows:

TYPE=ENTRY

Specifies that a table entry describing an MQSeries subsystem available to an IMS application is to be generated. If this is the first entry, the table header is also generated, including a CSQQDEFV CSECT statement.

TYPE=DEFAULT

As for TYPE=ENTRY. The subsystem specified is the default subsystem to be used when **MQCONN** specifies a name that is all blanks. There must be only one such entry in the table.

NAME=*subsystem*

Specifies the name of the subsystem, as specified with **MQCONN**.

LIT=*token*

Specifies the name of the language interface token (LIT) that IMS uses to identify the subsystem. The LIT for each CSQQDEFX entry must be unique.

Note: An **MQCONN** call associates the *name* input parameter and the *hconn* output parameter with the name label and, therefore, the LIT in the CSQQDEFV entry. Further MQSeries calls passing the *hconn* parameter use the LIT from the CSQQDEFV entry identified in the **MQCONN** call to direct calls to the MQSeries instance defined in the IMS SSM PROCLIB member with that same LIT.

In summary, the *name* parameter on the **MQCONN** call identifies a LIT in CSQQDEFV and the same LIT in the SSM member identifies an MQSeries instance. (For information about the **MQCONN** call, see the *MQSeries Application Programming Reference* manual.)

TYPE=END

Specifies that the table is complete. If this parameter is omitted, TYPE=ENTRY is assumed.

Using the CSQQDEFX macro

Figure 56 shows the general layout of a subsystem definition table.

```
CSQQDEFX NAME=subsystem1,LIT=token1
CSQQDEFX NAME=subsystem2,LIT=token2,TYPE=DEFAULT
CSQQDEFX NAME=subsystem3,LIT=token3
  ...
CSQQDEFX NAME=subsystemN,LIT=tokenN
CSQQDEFX TYPE=END
END
```

Figure 56. Layout of a subsystem definition table

The IMS trigger monitor

Define the application to IMS using the model CSQQTAPL in the thlqual.SCSQPROC library (see Figure 57).

Generate the PSB and ACB using the model CSQQTPSB in the thlqual.SCSQPROC library (see Figure 58).

```
         TITLE 'CSQQTAPL - Transaction Definition for CSQQTRMN'
         SPACE 1
*                                                                     *
***********************************************************************
*                                                                     *
*   This is the application definition                                *
*   for the IMS Trigger Monitor BMP                                   *
*                                                                     *
*   The class parameter on the PGMTYPE keyword can be modified        *
*   to meet installation conventions.                                 *
*                                                                     *
***********************************************************************
         SPACE 1
         APPLCTN PSB=CSQQTRMN,                                        X
               PGMTYPE=BATCH,                                         X
               SCHDTYP=PARALLEL
         SPACE 1
```

Figure 57. Example CSQQTAPL transaction definition for CSQQTRMN

```
         TITLE 'CSQQTPSB - PSB for IMS trigger monitor'
         SPACE 1
***********************************************************************
*                                                                     *
* This is the PSB for the MQSeries IMS trigger monitor program,       *
*                   CSQQTRMN.                                         *
*                                                                     *
***********************************************************************
         SPACE 1
         PCB   TYPE=TP,            ALTPCB for transaction messages   X
               MODIFY=YES,         To "triggered" IMS transaction    X
               PCBNAME=CSQQTRMN
         PCB   TYPE=TP,            ALTPCB for diagnostic messages    X
               MODIFY=YES,         To LTERM specified or "MASTER"    X
               PCBNAME=CSQQTRMG,                                     X
               EXPRESS=YES
         PSBGEN LANG=ASSEM,                                          X
               PSBNAME=CSQQTRMN,   Runs program CSQQTRMN             X
               CMPAT=YES
         END
```

Figure 58. Example CSQQTPSB PSB definition for CSQQTRMN

Setting up the IMS adapter

Chapter 10. Operating the IMS adapter

This chapter describes how to operate the IMS adapter, which connects MQSeries to IMS systems.

Note: The IMS adapter does not incorporate any operations and control panels.

This chapter contains the following sections:

- "Controlling IMS connections"
- "Connecting from the IMS control region" on page 176
- "Displaying in-doubt units of recovery" on page 178
- "Controlling IMS dependent region connections" on page 180
- "Disconnecting from IMS" on page 182
- "Controlling the IMS trigger monitor" on page 183

Controlling IMS connections

IMS provides these operator commands to control and monitor the connection to MQSeries:

/CHANGE SUBSYS
Deletes an in-doubt unit of recovery from IMS.

/DISPLAY OASN SUBSYS
Displays outstanding recovery elements.

/DISPLAY SUBSYS
Displays connection status and thread activity.

/START SUBSYS
Connects the IMS control region to an MQSeries subsystem.

/STOP SUBSYS
Disconnects IMS from an MQSeries subsystem.

/TRACE
Controls the IMS trace.

For more information about these commands, see the *IMS/ESA Operator's Reference* manual for the level of IMS that you are using.

IMS command responses are sent to the terminal from which the command was issued. Authorization to issue IMS commands is based on IMS security.

© Copyright IBM Corp. 1993,1999

Connecting from the IMS control region

IMS makes one connection from its control region to each MQSeries subsystem. IMS can make the connection in these ways:

- Automatically during either:
  - A cold-start initialization.
  - A warm start of IMS, if the MQSeries connection was active when IMS was shut down.
- In response to the IMS command:

  `/START SUBSYS sysid`

  where *sysid* is the MQSeries subsystem name.

This command causes the following message to be displayed at the logical terminal (LTERM):

```
DFS058  START COMMAND COMPLETED
```

The command is issued regardless of whether MQSeries is active or not, and does not imply that the connection has been established.

The order in which you start IMS and MQSeries is not significant. If you start IMS first, then, when MQSeries starts, MQSeries posts the control region modify task, and IMS again tries to reconnect.

IMS cannot reconnect to MQSeries automatically if MQSeries is stopped with a `STOP QMGR` command, the `/STOP SUBSYS` IMS command, or an abnormal end.

Therefore, you must make the connection by using the `/START SUBSYS` IMS command.

Initializing the adapter and connecting to MQSeries

The adapter is a set of modules loaded into the IMS control and dependent regions, using the IMS external subsystem attach facility.

This procedure initializes the adapter and connects to MQSeries:

1. Read the subsystem member (SSM) from IMS.PROCLIB. The SSM chosen is an IMS EXEC parameter. There is one entry in the member for each MQSeries subsystem to which IMS can connect. Each entry contains control information about an MQSeries adapter.
2. Load the IMS adapter.

   Note: IMS loads one copy of the adapter modules for each MQSeries instance that is defined in the SSM member.
3. Attach the external subsystem task for MQSeries.
4. Run the adapter with the CTL EXEC parameter (IMSID) as the connection name.

The process is the same whether the connection is part of initialization or a result of the `/START SUBSYS` IMS command.

If MQSeries is active when IMS tries to make the connection, the following messages are sent:

- To the OS/390 console:

  DFS3613I ESS TCB INITIALIZATION COMPLETE

- To the IMS master terminal:

  CSQQ000I IMS/TM *imsid* connected to queue manager *ssnm*

When IMS tries to make the connection and *MQSeries is not active*, the following messages are sent to the IMS master terminal each time an application makes an MQI call:

```
CSQQ001I IMS/TM imsid not connected to queue manager ssnm.
         Notify message accepted
DFS3607I  MQM1     SUBSYSTEM  ID  EXIT FAILURE, FC = 0286, RC = 08,
JOBNAME = IMSEMPR1
```

If you get DFS3607I messages when you start the connection to IMS or on system startup, this indicates that MQSeries is not available. To prevent a large numbers of messages being generated, you must do one of the following:

1. Start the relevant MQSeries subsystem.
2. Issue a /STOP SUBSYS IMS command so that IMS does not expect to connect to the MQSeries subsystem.

If you do neither, a DFS2607I message and the associated CSQQ001I message are issued each time a job is scheduled in the region and each time a connection request to MQSeries is made by an application.

Thread attachment

In an MPP or IFP region, IMS makes a thread connection when the first application program is scheduled into that region, even if that application program does not make an MQSeries call. In a BMP region, the thread connection is made when the application makes its first MQSeries call (**MQCONN**). This thread is retained for the duration of the region or until the connection is stopped.

For both the message driven and non-message driven regions, the recovery thread cross-reference identifier, *Thread-xref*, associated with the thread is:

```
PSTid + PSBname
```

where:

PSTid	Partition specification table region identifier
PSBname	Program specification block name

You can use connection IDs as unique identifiers in MQSeries commands; if you do, MQSeries automatically inserts these IDs into any operator message that it generates.

Displaying in-doubt units of recovery

The operational steps used to list and recover in-doubt units of recovery are discussed here for relatively simple cases only. The subject of in-doubt units of recovery is treated in more detail in Chapter 16, “Understanding termination and restart” on page 285.

If MQSeries ends abnormally while connected to IMS, it is possible for IMS to commit or back out work without MQSeries being aware of it. When MQSeries restarts, that work is termed *in doubt*. A decision must be made about the status of the work.

To display a list of in-doubt units of recovery, issue the command:

```
+cpf DISPLAY THREAD(*) TYPE(INDOUBT)
```

MQSeries responds with the following messages:

```
CSQV401I +cpf DISPLAY THREAD REPORT FOLLOWS -
CSQV406I +cpf INDOUBT THREADS - 154
NAME     THREAD-XREF    URID    NID
IMSJ     0002MQSPRG1            IMSJ.5600000000
IMSJ     0001MQSINQ             IMSJ.5700000000
DISPLAY THREAD REPORT COMPLETE
CSQ9022I +cpf CSQVDT ' DISPLAY THREAD' NORMAL COMPLETION
```

where:

NAME The connection name, which is the IMS system ID (the IMSID parameter from the region JCL).

THREAD-XREF
The associated thread cross-reference, see “Thread attachment” on page 177.

NID The associated *net-node.number* taken from the IMS recovery token, where *net-node* is the IMS system ID (with trailing blanks suppressed), *number* is the OASN and commit number (leading zeros suppressed).

For a formal explanation of the displayed list, see the description of message CSQV406I in the *MQSeries for OS/390 Messages and Codes* manual.

Recovering in-doubt units of recovery

To recover in-doubt units of recovery, issue this command:

```
+cpf RESOLVE INDOUBT(connection-name) ACTION(COMMIT|BACKOUT)
             NID(net-node.number)
```

where:

connection-name	The IMS system ID.
ACTION	Indicates whether to commit (COMMIT) or back out (BACKOUT) this unit of recovery.
net-node.number	The associated net-node.number.

One of the following messages is generated after the `RESOLVE INDOUBT` command:

```
CSQV414I +cpf THREAD network-id COMMIT SCHEDULED

CSQV415I +cpf THREAD network-id BACKOUT SCHEDULED
```

Resolving residual recovery entries

At given times, IMS builds a list of residual recovery entries (RREs). RREs are units of recovery about which MQSeries could be in doubt. They arise in several situations:

- If MQSeries is not operational, IMS has RREs that cannot be resolved until MQSeries is operational. These RREs are not a problem.
- If MQSeries is operational and connected to IMS, and if IMS backs out the work that MQSeries has committed, the IMS adapter issues message CSQQ010E. If the data in the two systems must be consistent, there is a problem. Resolving it is discussed in “Recovering IMS units of recovery manually” on page 294.
- If MQSeries is operational and connected to IMS, there might still be RREs even though no messages have informed you of this problem. After the MQSeries connection to IMS has been established, you can issue the following IMS command to find out if there is a problem:

```
/DISPLAY OASN SUBSYS sysid
```

To purge the RRE, issue one of the following IMS commands:

```
/CHANGE SUBSYS sysid RESET
/CHANGE SUBSYS sysid RESET OASN nnnn
```

where *nnnn* is the originating application sequence number listed in response to your `+cpf` DISPLAY command. This is the schedule number of the program instance, giving its place in the sequence of invocations of that program since the last IMS cold start. IMS cannot have two in-doubt units of recovery with the same schedule number.

These commands reset the status of IMS; they do not result in any communication with MQSeries.

Controlling IMS dependent region connections

Controlling IMS dependent region connections involves these activities:

- Connecting from dependent regions
- Region error options
- Monitoring the activity on connections
- Disconnecting from dependent regions

Connecting from dependent regions

The IMS adapter used in the control region is also loaded into dependent regions. A connection is made from each dependent region to MQSeries. This connection is used to coordinate the commitment of MQSeries and IMS work. To initialize and make the connection, IMS does the following:

1. It reads the subsystem member (SSM) from IMS.PROCLIB.

   A subsystem member can be specified on the dependent region EXEC parameter. If it is not specified, the control region SSM is used. If the region is never likely to connect to MQSeries, to avoid loading the adapter, specify a member with no entries.

2. It loads the MQSeries adapter.

   For a batch message program, the load is not done until the application issues its first messaging command. At that time, IMS tries to make the connection.

   For a message-processing program region or IMS fast-path region, the attempt is made when the region is initialized.

Region error options

If MQSeries is not active, or if resources are not available when the first messaging command is sent from application programs, the action taken depends on the error option specified on the SSM entry. The options are:

R The appropriate return code is sent to the application.

Q The application ends abnormally with abend code U3051. The input message is re-queued.

A The application ends abnormally with abend code U3047. The input message is discarded.

Monitoring the activity on connections

A thread is established from a dependent region when an application makes its first successful MQSeries request. Information on connections and the applications currently using them can be displayed by issuing the following command from MQSeries:

```
+cpf DISPLAY THREAD (connection-name)
```

The command produces the following messages:

```
CSQV401I +cpf DISPLAY THREAD REPORT FOLLOWS -
CSQV402I +cpf ACTIVE THREADS -
NAME   ST   A   REQ   THREAD-XREF    USERID     ASID    URID
name   s    *   ct    thread-xref    auth-id    asid    urid
name   s    *   ct    thread-xref    auth-id    asid    urid
DISPLAY ACTIVE REPORT COMPLETE
CSQ9022I +cpf CSQVDT ' DIS THREAD' NORMAL COMPLETION
```

For the control region, *thread-xref* is the special value CONTROL. For dependent regions, it is the PSTid concatenated with the PSBname. *auth-id* is either the user field from the job card, or the ID from the OS/390 started procedures table.

For an explanation of the displayed list, see the description of message CSQV402I in the *MQSeries for OS/390 Messages and Codes* manual.

IMS provides a display command to monitor the connection to MQSeries. It shows which program is active on each dependent region connection, the LTERM user name, and the control region connection status. The command is:

```
/DISPLAY SUBSYS name
```

The status of the connection between IMS and MQSeries is shown as one of:

```
CONNECTED
NOT CONNECTED
CONNECT IN PROGRESS
STOPPED
STOP IN PROGRESS
INVALID SUBSYSTEM NAME=name
SUBSYSTEM name NOT DEFINED BUT RECOVERY OUTSTANDING
```

The thread status from each dependent region one of the following:

```
CONN
CONN, ACTIVE (includes LTERM of user)
```

Disconnecting from dependent regions

To change values in the SSM member of IMS.PROCLIB, you disconnect a dependent region. To do this, you must:

1. Issue the `/STOP REGION` IMS command
2. Update the SSM member
3. Issue the `/START REGION` IMS command

Disconnecting from IMS

The connection is ended when either IMS or MQSeries terminates. Alternatively, the IMS master terminal operator can explicitly break the connection by issuing the following IMS command:

```
/STOP SUBSYS sysid
```

The command sends the following message to the terminal that issued it, usually the master terminal operator (MTO):

```
DFS058I STOP COMMAND IN PROGRESS
```

The /START SUBSYS *sysid* IMS command is required to re-establish the connection.

Note: The /STOP SUBSYS IMS command will not be completed if an IMS trigger monitor is running.

Controlling the IMS trigger monitor

The IMS trigger monitor (the CSQQTRMN transaction) is described in "The IMS trigger monitor" on page 166.

Starting CSQQTRMN

1. Start a batch oriented BMP running the program CSQQTRMN for each initiation queue you want to monitor.
2. Modify your batch JCL (step 2 in "Setting up the IMS adapter" on page 167) to add a DDname of CSQQUT1 that points to a data set containing the following information:

```
QMGRNAME=q_manager_name       Comment: queue manager name
INITQUEUENAME=init_q_name     Comment: initiation queue name
LTERM=lterm                   Comment: LTERM to remove error messages
CONSOLEMESSAGES=YES           Comment: Send error messages to console
```

   where:

   `q_manager_name`
   : The name of the queue manager (if this is blank, the default nominated in CSQQDEFV is assumed)

   `init_q_name`
   : The name of the initiation queue to be monitored

   `lterm`
   : The IMS LTERM name for the destination of error messages (if this is blank, the default value is MASTER).

   `CONSOLEMESSAGES=YES`
   : Requests that messages sent to the nominated IMS LTERM are also sent to the OS/390 console. If this parameter is omitted or misspelled then the default is NOT to send messages to the console.

3. Add a DD name of CSQQUT2 if you want a printed report of the processing of CSQQUT1 input.

Notes:

1. The data set CSQQUT1 is defined with LRECL=80. Other DCB information is taken from the data set. The DCB for data set CSQQUT2 is RECFM=VBA and LRECL=125.
2. You can put only one keyword on each record. The keyword value is delimited by the first blank following the keyword; this means that you can include comments. An asterisk in column 1 means that the whole input record is a comment.
3. If you misspell either of the `QMGRNAME` or `LTERM` keywords, CSQQTRMN will use the default for that keyword.
4. Ensure that the subsystem is started in IMS (by the /START SUBSYS command) before submitting the trigger monitor BMP job. If it is not started, your trigger monitor job will terminate, with abend code U3042.

Stopping CSQQTRMN

Once started, CSQQTRMN runs until either the connection between MQSeries and IMS is broken due to one of the following events:

- MQSeries ending
- IMS ending

or an OS/390 STOP jobname command is entered.

Chapter 11. The MQSeries-IMS bridge

This chapter describes the IMS bridge.

This chapter contains the following sections:

- "Introduction to the IMS bridge"
- "Customizing the IMS bridge" on page 187
- "Controlling the IMS bridge" on page 188
- "Security" on page 191

Introduction to the IMS bridge

The MQSeries-IMS bridge is the component of MQSeries for OS/390 that allows direct access from MQSeries applications to applications on your IMS system. The bridge enables *implicit MQSeries API support*. This means that you can re-engineer legacy applications that were controlled by 3270-connected terminals to be controlled by MQSeries messages, without having to rewrite, recompile, or re-link them. The bridge is an IMS *Open Transaction Manager Access* (OTMA) client.

In bridge applications there are no MQSeries calls within the IMS application. The application gets its input using a GET UNIQUE (GU) to the IOPCB and sends its output using an INSERT (ISRT) to the IOPCB. MQSeries applications use the IMS header (the MQIIH structure) in the message data to ensure that the applications can execute as they did when driven by nonprogrammable terminals.

If you are using an IMS application that processes multi-segment messages, note that all segments should be contained within one MQSeries message. The IMS bridge is illustrated in Figure 59 on page 186.

A queue manager can connect to one or more IMS systems, and more than one queue manager can connect to one IMS system. The only restriction is that they must all belong to the same XCF group and must all be in the same sysplex.

What is OTMA?

The IMS OTMA facility is a transaction-based connectionless client/server protocol that runs on version 5.1 of IMS. It functions as an interface for host-based communications servers accessing IMS TM applications through the OS/390 *Cross Systems Coupling Facility* (XCF).

OTMA enables clients to connect to IMS in a high performance manner enabling the client to support interactions with IMS for a large network or large number of sessions. OTMA is implemented in an OS/390 sysplex environment. Therefore, the domain of OTMA is restricted to the domain of XCF. See the *IMS/ESA Open Transaction Manager Access Guide* for more information.

© Copyright IBM Corp. 1993,1999



Figure 59. The MQSeries-IMS bridge

Submitting IMS transactions from MQSeries

To submit an IMS transaction that uses the bridge, applications put messages on an MQSeries queue as usual. The messages contain IMS transaction data; they can have an IMS header (the MQIIH structure) or allow the MQSeries-IMS bridge to make assumptions about the data in the message. See the *MQSeries Application Programming Guide* for more information.

MQSeries then puts the message to an IMS queue (it is queued in MQSeries first to enable the use of syncpoints to assure data integrity). The storage class of the MQSeries queue determines whether the queue is an *OTMA queue* (that is, a queue used to transmit messages to the MQSeries-IMS bridge) and the particular IMS partner to which the message data is sent.

Remote queue managers can also start IMS transactions by writing to these OTMA queues on MQSeries for OS/390.

Data returned from the IMS system is written directly to the MQSeries reply-to queue specified in the message descriptor structure (MQMD). (This might be a transmission queue to the queue manager specified in the *ReplyToQMgr* field of the MQMD.)

Customizing the IMS bridge

This section describes what you have to do to customize the MQSeries-IMS bridge, and start sending messages across it to IMS. The bridge is described in "Introduction to the IMS bridge" on page 185.

1. Define the XCF and OTMA parameters for MQSeries.

   This step defines the XCF group and member names for your MQSeries system, and other OTMA parameters. MQSeries and IMS must belong to the same XCF group. Use the OTMACON keyword of the CSQ6SYSP macro to tailor these parameters in the system parameter load module.

   See "Using CSQ6SYSP" on page 69 for information about this.

2. Define the XCF and OTMA parameters to IMS.

   This step defines the XCF group and member names for the IMS system. IMS and MQSeries must belong to the same XCF group.

   Add the following parameters to your IMS parameter list, either in your JCL or in member DFSPBxxx in the IMS PROCLIB:

   OTMA=Y
   This starts OTMA automatically when IMS is started. (This is optional, if you specify OTMA=N you can also start OTMA by issuing the IMS command /START OTMA.)

   GRNAME=
   This gives the XCF group name.

   This is the same as the group name specified in the storage class definition (see Step 3), and in the `Group` parameter of the OTMACON keyword of the CSQ6SYSP macro.

   USERVAR=
   This gives the XCF member name of the IMS system.

   This is the same as the member name specified in the storage class definition (see Step 3).

   If you do not specify a name for USERVAR, the value of APPLID1 is used.

3. Tell MQSeries the XCF group and member name of the IMS system.

   This is specified by the storage class of a queue. If you want to send messages across the MQSeries-IMS bridge you need to specify this when you define the storage class for the queue. In the storage class, you need to define the XCF group and the member name of the target IMS system. To do this, either use the MQSeries operations and control panels, or use the MQSC commands as described in the *MQSeries Command Reference* manual.

4. Set up the security that you require.

   See "Security considerations for the IMS bridge" on page 459 for information about this.

Controlling the IMS bridge

There are no MQSeries commands to control the MQSeries-IMS bridge.

Start the MQSeries bridge by starting OTMA. Either use the IMS command `/START OTMA`, or start it automatically by specifying OTMA=YES in the IMS system parameters. If OTMA is already started, the bridge starts automatically when MQSeries startup has completed. An MQSeries event message is produced when OTMA is started.

Use the IMS command `/STOP OTMA` to stop OTMA communication. When this command is issued, an MQSeries event message is produced.

Controlling IMS connections

IMS provides these operator commands to control and monitor the connection to MQSeries:

/**DEQUEUE TMEMBER** *tmember* **TPIPE** *tpipe*
: Removes messages from a Tpipe, specify PURGE to remove all messages or PURGE1 to remove the first message only.

/**DISPLAY OTMA**
: Displays summary information about the OTMA server and clients, and client status.

/**DISPLAY TMEMBER** *name*
: Displays information about an OTMA client.

/**DISPLAY TRACE TMEMBER** *name*
: Displays information about what is being traced.

/**SECURE OTMA**
: Sets security options.

/**START OTMA**
: Enables communications through OTMA.

/**START TMEMBER** *tmember* **TPIPE** *tpipe*
: Starts the named Tpipe.

/**STOP OTMA**
: Stops communications through OTMA.

/**STOP TMEMBER** *tmember* **TPIPE** *tpipe*
: Stops the named Tpipe.

/**TRACE**
: Controls the IMS trace.

For more information about these commands, see the *IMS/ESA Operator's Reference* manual for the level of IMS that you are using.

IMS command responses are sent to the terminal from which the command was issued. Authorization to issue IMS commands is based on IMS security.

Controlling bridge queues

Issue the following IMS command to stop communicating with the MQSeries system with XCF member name *tmember* through the bridge:

```
/STOP TMEMBER tmember TPIPE ALL
```

Issue the following IMS command to resume communication:

```
/START TMEMBER tmember TPIPE ALL
```

To stop communication with the MQSeries system on a single Tpipe, issue the following IMS command:

```
/STOP TMEMBER tmember TPIPE tpipe
```

One or two Tpipes are created for each active bridge queue, so issuing this command stops communication with the MQSeries queue. Use the following IMS command to resume communication:

```
/START TMEMBER tmember TPIPE tpipe
```

Alternatively, you can alter the attributes of the MQSeries queue to make it get inhibited.

Deleting messages from IMS

A message that is destined for MQSeries via the IMS bridge can be deleted if the Tmember/Tpipe is stopped. To delete one message for the MQSeries system with XCF member name *tmember*, issue the following IMS command:

```
/DEQUEUE TMEMBER tmember TPIPE tpipe PURGE1
```

To delete all the message on the Tpipe, issue the following IMS command:

```
/DEQUEUE TMEMBER tmember TPIPE tpipe PURGE
```

Resynchronizing the IMS bridge

The IMS bridge is automatically restarted whenever MQSeries, IMS, or OTMA are restarted.

The first task undertaken by the IMS bridge is to resynchronize with IMS. This involves MQSeries and IMS checking sequence numbers on every synchronized Tpipe. A synchronized Tpipe is used when persistent messages are sent to IMS from an MQSeries-IMS bridge queue using commit mode 0 (commit-then-send).

If the bridge is unable to resynchronize with IMS at this time, the IMS sense code is returned in message CSQ2023E and the connection to OTMA is stopped. If the bridge is unable to resynchronize with an individual IMS Tpipe at this time, the IMS sense code is returned in message CSQ2025E and the Tpipe is stopped. If a Tpipe has been cold started, the recoverable sequence numbers are automatically reset to 1.

If the bridge discovers mismatched sequence numbers when resynchronizing with a Tpipe, message CSQ2020E is issued. Use the MQSeries command `RESET TPIPE` to initiate resynchronization with the IMS Tpipe. You need to provide the XCF group and member name, and the name of the Tpipe; this information is provided by the message.

You can also specify:

- A new recoverable sequence number to be set in the Tpipe for messages sent by MQSeries, and to be set as the partners receive sequence number. If you do not specify this, the partners receive sequence number is set to the current MQSeries send sequence number
- A new recoverable sequence number to be set in the Tpipe for messages received by MQSeries, and to be set as the partners send sequence number. If you do not specify this, the partners send sequence number is set to the current MQSeries receive sequence number

If there is an unresolved unit of recovery associated with the Tpipe, this is also notified in the message. Use the `RESET TPIPE` MQSeries command to specify whether to commit it or back it out. If you commit the unit of recovery, the batch of messages has already been sent to IMS, and is deleted from the bridge queue. If you back the unit of recovery out, the messages are returned to the bridge queue, to be subsequently sent to IMS.

Commit mode 1 (Send-then-commit) Tpipes are not synchronized.

Considerations for Commit mode 1 transactions

In IMS, commit mode 1 (CM1) transactions send their output replies before syncpoint.

It is possible that a CM1 transaction is unable to send its reply, for example because:

- The Tpipe on which the reply is to be sent is stopped
- OTMA is stopped
- The OTMA client (that is, MQSeries) has gone away
- The reply-to queue and dead-letter queue are unavailable

For all of the above reasons, the IMS application sending the message will pseudo-abend with code U0119. The IMS transaction and program are not stopped in this case.

These reasons often prevent messages being sent into IMS, as well as replies being delivered from IMS. A U0119 abend can occur if:

- The Tpipe, or OTMA, or MQSeries are stopped while the message is in IMS
- IMS replies on a different Tpipe to the incoming message, and that Tpipe is stopped
- IMS replies to a different OTMA client, and that client is unavailable.

Whenever a U0119 abend occurs, both the incoming message to IMS and the reply messages to MQSeries are lost. If the output of a CM0 transaction cannot be delivered for any of the above reasons, it is queued on the Tpipe within IMS.

Security

The `/SECURITY OTMA` IMS command determines the level of security to be applied to ***every*** MQSeries subsystem that connects to IMS through OTMA. See “Security considerations for the IMS bridge” on page 459 for information about what this should be set to.

IMS bridge security

Part 5. Operating and administering MQSeries

Chapter 12. Operating MQSeries for OS/390 195
Issuing commands 195
Issuing commands from an OS/390 console or its equivalent 196
Issuing commands from a TSO terminal 197
Issuing commands from the utility program CSQUTIL 197
Starting and stopping MQSeries 197
Before you start MQSeries 197
Starting MQSeries 198
Stopping MQSeries 201
Using the operations and control panels 203
Invoking the operations and control panels 204
Objects and Actions 204
Choosing a queue manager 206
Using the function keys 207
Using the initial panel 208
Defining a local queue 209
Defining other types of objects 213
Working with object definitions 213
Working with namelists 214
Rules for the operations and control panels 215

Chapter 13. Writing programs to administer MQSeries 217
Before you begin 217
Understanding how it all works 218
Using the command server 219
Identifying the queue manager that processes your commands 219
Starting the command server 219
Preparing queues for administration programs 220
Defining the system-command input queue 220
Defining a reply-to queue 220
Opening the system-command input queue 220
Opening a reply-to queue 221
Sending commands to the command server 222
Building a message that includes MQSeries commands 222
Putting messages on the system-command input queue 223
Using MQPUT1 and the system-command input queue 223
Retrieving replies to your commands 224
Waiting for a reply 224
The reply message descriptor 225
Interpreting the replies 226
Examples of commands and their replies 226
Messages from DISPLAY commands for MQSeries objects 228
Command attributes 231
If you do not receive a reply 232
Passing commands using MGCR or MGCRE 232

Chapter 14. Using the MQSeries utilities 233
How to read syntax diagrams 234
MQSeries utility program (CSQUTIL) 235
Invoking the MQSeries utility program 235

© Copyright IBM Corp. 1993,1999

Return codes 236
Monitoring the progress of the MQSeries utility program 236
Page set management functions 237
Formatting page sets (FORMAT) 237
Expanding a page set (COPYPAGE) 239
Copying a page set and resetting the log (RESETPAGE) 241
MQSeries command management functions 244
Issuing commands to MQSeries (COMMAND) 244
Producing a list of MQSeries define commands (SDEFS) 249
Queue management functions 251
Syncpoints 251
Copying queues into a data set while the queue manager is running (COPY) 252
Copying queues into a data set while the queue manager is not running (SCOPY) 255
Emptying a queue of all messages (EMPTY) 258
Restoring messages from a data set to a queue (LOAD) 260
The change log inventory utility (CSQJU003) 262
Invoking the CSQJU003 utility 262
Adding information about a data set to the BSDS (NEWLOG) 264
Deleting information about a data set from the BSDS (DELETE) 266
Supplying a password for archive log data sets (ARCHIVE) 267
Controlling the next restart (CRESTART) 268
Setting checkpoint records (CHECKPT) 269
Updating the highest written log RBA (HIGHRBA) 270
The print log map utility (CSQJU004) 271
Invoking the CSQJU004 utility 271
The log print utility (CSQ1LOGP) 272
Invoking the CSQ1LOGP utility 272
Input control parameters 273
Output 274

Chapter 12. Operating MQSeries for OS/390

This chapter describes the basic procedures you can use to operate MQSeries for OS/390. It includes information on how to use the MQSeries operations and control panels. The simplest elements of MQSeries operation are discussed in these sections:

- "Issuing commands"
- "Starting and stopping MQSeries" on page 197
- "Using the operations and control panels" on page 203

Normal operation also requires some more complex tasks. These are discussed in the following chapters:

- Chapter 7, "Operating the CICS adapter" on page 129 describes how to manage and operate the CICS adapter, and control and display the status of the connection.
- Chapter 17, "Understanding the log and the bootstrap data set" on page 305 describes the roles of the log and the log control data sets in preparing for restart and recovery, what happens when MQSeries terminates normally or abnormally, and how to restart it while maintaining data integrity.
- Chapter 18, "Planning for backup and recovery" on page 313 explains how to prepare for recovery.
- Chapter 21, "Example recovery scenarios" on page 345 explains how to recover both at your own site and at a remote site, and how to recover even when the BSDS or log is damaged.

Also, for information about connections to other MQSeries subsystems in distributed queuing applications, see the *MQSeries Intercommunication* manual.

Issuing commands

You can control most of the operational environment of MQSeries using the MQSeries commands. For details of the syntax of the MQSeries commands, see the *MQSeries Command Reference* manual. If you are a suitably authorized user, you can issue MQSeries commands from:

- The initialization input data sets (see "Task 10: Customize the initialization input data sets" on page 52).
- An OS/390 console
- The OS/390 master get command routine, MGCR and MGCRE (SVC 34)
- SDSF
- A TSO console
- The MQSeries utility, CSQUTIL
- The operations and control panels
- A user application, which can be:
  - A CICS program
  - A TSO program
  - An OS/390 batch program

© Copyright IBM Corp. 1993,1999

– An IMS program

See Chapter 13, “Writing programs to administer MQSeries” on page 217 for information about this.

Issuing commands from an OS/390 console or its equivalent

You can issue all MQSeries commands from an OS/390 console or its equivalent. This means you can also issue MQSeries commands from anywhere where you can issue OS/390 commands, such as SDSF or by a program using the MGCR macro.

The maximum amount of data that can be displayed as a result of a command typed in at the console is 32 KB.

Notes:

1. You cannot issue MQSeries commands using the IMS /SSR command format from an IMS terminal. This function is not supported by the IMS adapter.
2. The input field provided by SDSF might not be long enough for some commands, particularly those for channels.

Command prefix strings

Each MQSeries command must be prefixed with a command prefix string (CPF), as shown in Figure 61 on page 198.

Because more than one MQSeries subsystem can run under OS/390, the CPF is used to indicate which MQSeries subsystem processes the command. For example, to start a subsystem called CSQ1, whose CPF is ‘+cpf’, you issue the command +cpf START QMGR from the operator console. This CPF must be defined in the subsystem name table (for the subsystem CSQ1). For more information about CPFs, see “Using command prefix strings” on page 42. In the examples, the string ‘+cpf’ is used as the command prefix.

Using the OS/390 console to issue commands

You can type simple commands from the OS/390 console, for example, the DISPLAY command in Figure 60. However, for complex commands or for sets of commands that you issue frequently, the other methods of issuing commands are better.

```
+cpf DISPLAY QUEUE(TRANSMIT.QUEUE.PROD) TYPE(QLOCAL)
```

Figure 60. Issuing a DISPLAY command from the OS/390 console. The command is prefixed by a CPF of ‘+cpf’.

Command responses

Direct responses to commands are sent to the console that issued the command. MQSeries supports the *Extended Console Support* (EMCS) function available in OS/390, and therefore consoles with 4-byte IDs can be used. Additionally, all commands except START QMGR and STOP QMGR support the use of Command and Response Tokens (CARTs) when the command is issued by a program using the MGCRE macro.

Issuing commands from a TSO terminal

MQSeries uses ISPF to provide a set of operations and control panels. You can use the panels to construct system administrator commands for managing MQSeries objects. Figure 64 on page 208 shows an example of a MQSeries operations and control panel.

Using these panels, you can create MQSeries commands quickly and easily. The panels ensure that you supply all the information that MQSeries needs to complete the task. All the parameters of the command are displayed, together with their possible values.

"Using the operations and control panels" on page 203 describes how to use these panels.

Issuing commands from the utility program CSQUTIL

You can issue commands from a sequential data set using the COMMAND function of the utility program CSQUTIL. This utility transfers the commands to the *system-command input queue* and waits for the response, which is printed together with the original commands in SYSPRINT. For details of this, see the "MQSeries utility program (CSQUTIL)" on page 235.

Starting and stopping MQSeries

Starting and stopping MQSeries is relatively straightforward. When MQSeries stops under normal conditions, its last action is to take a termination checkpoint. This checkpoint, and the logs, give MQSeries the information it needs to restart.

This section discusses the START and STOP commands, and contains a brief overview of start up after an abnormal termination has occurred.

Before you start MQSeries

After you have installed MQSeries, it is defined as a formal OS/390 subsystem. This message appears during any initial program load (IPL) of OS/390:

```
CSQ3110I +cpf CSQ3UR00 - SUBSYSTEM ssnm READY FOR START COMMAND
```

where *ssnm* is the MQSeries subsystem name.

From now on, you can start MQSeries *from any OS/390 console that has been authorized to issue system control commands*; that is, an OS/390 SYS command group. The START command must be issued from the authorized console, and cannot be submitted through JES or TSO.

Starting MQSeries

You start MQSeries by issuing a START QMGR command. However, you cannot successfully use the START command unless you have appropriate authority. See Part 8, “Security” on page 401 for more information about MQSeries security. Figure 61 shows examples of the START command. See the *MQSeries Command Reference* manual for details about the syntax of this command.

```
+cpf START QMGR

+cpf START QMGR PARM(NEWLOG)
```

Figure 61. Starting the MQSeries subsystem from an OS/390 console. The second example specifies a system parameter module name.

Remember that you must prefix an MQSeries command with a command prefix string (CPF).

You cannot run the MQSeries subsystem as a batch job or start it using an OS/390 START command. These methods are likely to start an address space for MQSeries that then abends. You also cannot start MQSeries from the CSQUTIL utility program or a similar user application.

You can, however, start MQSeries from an APF-authorized program by passing a START QMGR command to the OS/390 MGCR or MGCRE (SVC 34) service.

User messages on start-up

When you start MQSeries successfully, it produces a set of start up messages similar to the ones in Figure 62 on page 199.

Notes:

1. If you are starting MQSeries for the first time, the messages are slightly different.
2. If any of the values in message CSQR004I is not zero, message CSQR007I is issued to provide the restart status table.
3. Messages CSQP018I and CSQP019I are issued every time a checkpoint is taken (see “Checkpoint records” on page 307). At checkpoint time, all pages that have not been changed for the two checkpoints are written out to DASD. Message CSQP019I is issued for each buffer pool, giving the number of pages written. You can use this information when balancing page sets in buffer pools.

   If you want to suppress these messages, see “Task 18: Suppress information messages” on page 96.
4. There might be periods during startup when no messages are produced; for example, if you are using indexed queues, no messages are produced while the queue indexes are being rebuilt.

```
$HASP373 CSQ1MSTR STARTED
IEF403I CSQ1MSTR - STARTED - TIME=17.06.43
CSQY000I +cpf IBM MQSeries for OS/390 - V2.1
CSQY001I +cpf SUBSYSTEM STARTING, USING PARAMETER MODULE CSQ1ZPRM
CSQY100I +cpf System parameters ...
CSQY101I +cpf CTHREAD=300, IDBACK=20, IDFORE=100, LOGLOAD=16000
CSQY102I +cpf CMDUSER=CSQOPR, QMCCSID=500, ROUTCDE=( 1)
CSQY103I +cpf SMFACCT=NO (00000000), SMFSTAT=NO (00000000), STATIME=30
CSQY104I +cpf OTMACON=
(        ,                ,DFSYDRU0,2147483647,CSQ)
CSQY105I +cpf TRACSTR=( 1), TRACTBL=500
CSQY106I +cpf EXITTCB=8, EXITLIM=30, WLMTIME=30
CSQY110I +cpf Logging parameters ...
CSQY111I +cpf INBUFF=28, OUTBUFF=400, MAXALLC=3, MAXARCH=500
CSQY112I +cpf TWOACTV=YES, TWOARCH=YES, TWOBSDS=YES
CSQY113I +cpf OFFLOAD=YES, WRTHRSH=20
CSQY120I +cpf Archive parameters ...
CSQY121I +cpf UNIT=SYSDA, ALCUNIT=BLK, PRIQTY=100, SECQTY=50,
BLKSIZE=24576
CSQY122I +cpf ARCPFX1=ABCD.CSQ1.ARCLOG1, ARCPFX2=ABCD.CSQ1.ARCLOG2,
TSTAMP=NO
CSQY123I +cpf ARCRETN=0, ARCWTOR=YES, ARCWRTC=( 1 ,3 ,4)
CSQY124I +cpf CATALOG=YES, COMPACT=NO, PROTECT=NO, QUIESCE=5
CSQJ127I +cpf SYSTEM TIME STAMP FOR BSDS=1998-07-10 17:05:47.71
CSQJ001I +cpf CSQJW007 CURRENT COPY 1 ACTIVE LOG
DATA SET IS DSNAME=ABCD.CSQ1.LOGCOPY1.DS01,
STARTRBA=000000000000,ENDRBA=00000021BFFF
CSQJ001I +cpf CSQJW007 CURRENT COPY 2 ACTIVE LOG
DATA SET IS DSNAME=ABCD.CSQ1.LOGCOPY2.DS01,
STARTRBA=000000000000,ENDRBA=00000021BFFF
CSQJ099I +cpf LOG RECORDING TO COMMENCE WITH
STARTRBA=000000167000
CSQR001I +cpf RESTART INITIATED
CSQR003I +cpf RESTART...PRIOR CHECKPOINT RBA=000000164B78
CSQR004I +cpf RESTART...UR STATUS COUNTS
IN COMMIT=0, INDOUBT=0, INFLIGHT=0, IN BACKOUT=0
CSQI049I +cpf PAGE SET 0 HAS MEDIA RECOVERY
RBA=00002568D9F1, CHECKPOINT RBA=00002568D9F1
CSQI049I +cpf PAGE SET 1 HAS MEDIA RECOVERY
RBA=00002568D9F1, CHECKPOINT RBA=00002568D9F1
CSQI049I +cpf PAGE SET 2 HAS MEDIA RECOVERY
RBA=00002568D9F1, CHECKPOINT RBA=00002568D9F1
CSQI049I +cpf PAGE SET 3 HAS MEDIA RECOVERY
RBA=00002568D9F1, CHECKPOINT RBA=00002568D9F1
CSQR030I +cpf FORWARD RECOVERY LOG RANGE
FROM RBA=00002568D9F1 TO RBA=00002568E24C
CSQR005I +cpf RESTART...COUNTS AFTER FORWARD RECOVERY
IN COMMIT=0, INDOUBT=0
CSQR032I +cpf BACKWARD RECOVERY LOG RANGE
FROM RBA=00002568E24C TO RBA=00002568E24C
CSQR006I +cpf RESTART...COUNTS AFTER BACKWARD RECOVERY
INFLIGHT=0, IN BACKOUT=0
CSQR002I +cpf RESTART COMPLETED
CSQP018I +cpf CSQPBCKW CHECKPOINT STARTED FOR ALL BUFFER POOLS
+cpf DISPLAY THREAD(*) TYPE(INDOUBT)
CSQP021I +cpf PAGE SET 0 NEW MEDIA RECOVERY
RBA=00002568F000, CHECKPOINT RBA=00002568F000
CSQP021I +cpf PAGE SET 1 NEW MEDIA RECOVERY
RBA=00002568F000, CHECKPOINT RBA=00002568F000
```

Figure 62 (Part 1 of 2). MQSeries startup messages for subsystem CSQ1

```
CSQP021I +cpf PAGE SET 2 NEW MEDIA RECOVERY
RBA=00002569072C, CHECKPOINT RBA=00002569072C
CSQP021I +cpf PAGE SET 3 NEW MEDIA RECOVERY
RBA=00002569072C, checkpoint RBA=00002569072C
CSQP019I +cpf CSQP1DWP CHECKPOINT COMPLETED FOR
BUFFER POOL 2, 2 PAGES WRITTEN
CSQP019I +cpf CSQP1DWP CHECKPOINT COMPLETED FOR
BUFFER POOL 3, 2 PAGES WRITTEN
CSQP019I +cpf CSQP1DWP CHECKPOINT COMPLETED FOR
BUFFER POOL 1, 5 PAGES WRITTEN
CSQP019I +cpf CSQP1DWP CHECKPOINT COMPLETED FOR
BUFFER POOL 0, 25 PAGES WRITTEN
CSQV401I +cpf DISPLAY THREAD REPORT FOLLOWS -
CSQV402I +cpf NO INDOUBT THREADS FOUND
CSQ9022I +cpf CSQVDT 'DISPLAY THREAD' NORMAL COMPLETION
CSQY022I +cpf QUEUE MANAGER INITIALIZATION COMPLETE
CSQ9022I +cpf CSQYASCP 'START QMGR' NORMAL COMPLETION
```

Figure 62 (Part 2 of 2). MQSeries startup messages for subsystem CSQ1. The command prefix string is +cpf.

Start options

When you start a queue manager, a special routine called the system parameter module is invoked. You can specify the name of a system parameter module if you use the PARM keyword. A system parameter module provides information specified when the queue manager was customized. In Figure 62 on page 199, the user message CSQY001I indicates the name of the system parameter module that was used, in this case, CSQ1ZPRM. For more information about this, see “Task 13: Tailor your system parameter module” on page 68.

You can also use the ENVPARM option to substitute one or more parameters in the JCL procedure for the queue manager.

For example, you can update your MQSeries startup procedure, so that the DDname CSQINP2 is a variable. This means that you can change the CSQINP2 DDname without changing the startup procedure. This is very useful for implementing changes, providing backouts for operators, and so on.

Suppose your start-up procedure, for queue manager CSQ1, looked like this:

```
//CSQ1MSTR PROC INP2=NORM
//MQMESA   EXEC PGM=CSQYASCP
//STEPLIB  DD   DISP=SHR,DSN=thqual.SCSQANLE
//         DD   DISP=SHR,DSN=thqual.SCSQAUTH
//BSDS1    DD   DISP=SHR,DSN=myqual.BSDS01
//BSDS2    DD   DISP=SHR,DSN=myqual.BSDS02
//CSQP0000 DD   DISP=SHR,DSN=myqual.PSID00
//CSQP0001 DD   DISP=SHR,DSN=myqual.PSID01
//CSQP0002 DD   DISP=SHR,DSN=myqual.PSID02
//CSQP0003 DD   DISP=SHR,DSN=myqual.PSID03
//CSQINP1  DD   DISP=SHR,DSN=myqual.CSQINP(CSQ1INP1)
//CSQINP2  DD   DISP=SHR,DSN=myqual.CSQINP(CSQ1&INP2.)
//CSQOUT1  DD   SYSOUT=*
//CSQOUT2  DD   SYSOUT=*
```

If you then start the your queue manager with the command:

```
+cpf START QMGR
```

the CSQINP2 actually used is a member called CSQ1NORM.

However, suppose you are putting a new suite of programs into production so that the next time you start queue manager CSQ1, the CSQINP2 definitions are to be taken from member CSQ1NEW. To do this, you would start MQSeries with this command:

```
+cpf START QMGR ENVPARM('INP2=NEW')
```

and CSQ1NEW would be used instead of CSQ1NORM. Note that OS/390 limits the `KEYWORD=value` specifications for symbolic parameters (as in `INP2=NEW`) to 48 characters.

Starting after an abnormal termination

MQSeries automatically detects whether restart follows a normal shutdown or an abnormal termination.

Starting MQSeries after it abends is different from starting it after the `+cpf` STOP QMGR command has been issued. After `+cpf` STOP QMGR, the system finishes its work in an orderly way and takes a termination checkpoint before stopping. When you restart MQSeries, it uses information from the system checkpoint and recovery log to determine the system status at shutdown.

However, if MQSeries abends, it terminates without being able to finish its work or take a termination checkpoint. When you restart MQSeries after an abend, it refreshes its knowledge of its status at termination using information in the log, and notifies you of the status of various tasks. Normally, the restart process resolves all inconsistent states. But, in some cases, you must take specific steps to resolve inconsistencies. For a discussion of the causes of inconsistencies, and how you can prepare to recover from them, see Chapter 16, “Understanding termination and restart” on page 285.

Stopping MQSeries

Before stopping MQSeries, all MQSeries-related write-to-operator-with-reply (WTOR) messages must receive replies, for example, getting log requests. Each of the commands in Figure 63 terminates a running MQSeries subsystem.

```
+cpf STOP QMGR

+cpf STOP QMGR MODE(QUIESCE)

+cpf STOP QMGR MODE(FORCE)

+cpf STOP QMGR MODE(RESTART)
```

Figure 63. Stopping MQSeries

The command `+cpf` STOP QMGR defaults to `+cpf` STOP QMGR MODE(QUIESCE).

In QUIESCE mode, MQSeries does not allow any new connection threads to be created, but allows existing threads to continue; it terminates only when all threads

have ended. Applications can request to be notified in the event of the queue manager quiescing. Therefore, use the QUIESCE mode where possible so that applications that have requested notification have the opportunity to disconnect. See the *MQSeries Application Programming Guide* for details.

If MQSeries does not terminate in a reasonable time in response to a `+cpf` STOP QMGR MODE(QUIESCE) command, use the `+cpf` DISPLAY THREAD(*) TYPE(ACTIVE) command to determine whether any connection threads exist, and take the necessary steps to terminate the associated applications. If there are no threads then issue a `+cpf` STOP QMGR MODE(FORCE) command.

The `+cpf` STOP QMGR MODE(QUIESCE) and `+cpf` STOP QMGR MODE(FORCE) commands deregister MQSeries from the MVS Automatic Restart Manager (ARM), preventing ARM from restarting the queue manager automatically. The `+cpf` STOP QMGR MODE(RESTART) command works in the same way as the `+cpf` STOP QMGR MODE(FORCE) command, except that it does not deregister MQSeries from ARM. This means that the queue manager is eligible for immediate automatic restart.

If the MQSeries subsystem is not registered with ARM, the STOP QMGR MODE(RESTART) command is rejected and the following message sent to the OS/390 console:

```
CSQY205I  ARM element arm-element is not registered
```

If this message is not issued, the queue manager is restarted automatically. For more information about ARM, see “Using the OS/390 Automatic Restart Manager (ARM)” on page 300.

Do not cancel the MQSeries address space unless `+cpf` STOP QMGR MODE(FORCE) does not cause MQSeries to terminate.

If MQSeries is stopped by either canceling the address space or by using the command `+cpf` STOP QMGR MODE(FORCE), consistency is maintained with connected CICS or IMS systems. Resynchronization of resources is started when MQSeries restarts and is completed when the connection to the CICS or IMS system is established. See Chapter 16, “Understanding termination and restart” on page 285.

Note: When you stop your MQSeries subsystem, you might find message IEF352I is issued. OS/390 issues this message if it detects that failing to mark the address space as unusable would lead to an integrity exposure. You can ignore this message.

Stop messages

After issuing a +cpf STOP QMGR command, you get the messages CSQY009I and CSQY002I, for example:

```
CSQY009I +cpf ' STOP QMGR' COMMAND ACCEPTED FROM
USER(userid), STOP MODE(FORCE)
CSQY002I +cpf SUBSYSTEM STOPPING
```

Where userid is the user ID that issued the +cpf STOP QMGR command, and the MODE parameter depends on that specified in command.

When the STOP command has completed successfully, these messages are displayed on the OS/390 console:

```
CSQ9022I +cpf CSQYASCP ' STOP QMGR' NORMAL COMPLETION
CSQ3104I +cpf CSQ3EC0X - TERMINATION COMPLETE
```

If you are using ARM, the following message is also displayed if you did not specify MODE(RESTART):

```
CSQY204I +cpf ARM DEREGISTER for element arm-element type
arm-element-type successful
```

You cannot restart MQSeries until the following message has been generated:

```
CSQ3100I +cpf CSQ3EC0X - SUBSYSTEM ssnm READY FOR START COMMAND
```

Using the operations and control panels

You can use the MQSeries operations and control panels to perform administration tasks on MQSeries objects. You use these panels to run commands for defining, displaying, altering, or deleting MQSeries objects.

The operations and control panels support the system control commands for distributed queuing without CICS (for example, to start a channel or a TCP/IP listener), for clustering, and for security. They also enable you to display information about threads and page set usage. The other system control commands are not available through the panels. These commands must be issued explicitly using one of the other methods, see “Issuing commands” on page 195.

Note: You cannot issue the MQSeries commands directly from the command line in the panels.

To use the operations and control panels, you must have the correct security authorization; see “Security checking for the operations and control panels” on page 407 for information.

Invoking the operations and control panels

If the ISPF/PDF primary options menu has been updated for MQSeries, you can access the MQSeries operations and control panels from that menu. For details about updating the menu, see “Updating the ISPF menu” on page 94.

You can access the MQSeries operations and control panels from the TSO command processor panel (usually option 6 on the ISPF/PDF primary options menu). The name of the exec that you run to do this is CSQOREXX. It has two parameters; `thlqual` is the high-level qualifier for the MQSeries libraries to be used, and `langletter` is the letter identifying the national language libraries to be used (for example, E for US English). The parameters can be omitted if the MQSeries libraries are permanently installed in your ISPF setup. Alternatively, you can issue CSQOREXX from the TSO command line.

These panels are designed to be used by operators and administrators with a minimum of formal training. Read these instructions with the panels running and try out the different tasks suggested.

Note: While using the panels, temporary dynamic queues with names of the form SYSTEM.CSQOREXX.* will be created.

Objects and Actions

The operations and control panels offer you many different types of object and a number of actions that you can perform on them. The actions are listed on the initial panel and enable you to manipulate the objects and display information about them. These objects include all the MQSeries objects, together with some extra ones. The objects fall into five categories.

1. Queues, Processes, Namelists, and Storage classes

These are the basic MQSeries objects. There can be many of each type. They can be defined and deleted, and have attributes that can be displayed and altered, using the DEFINE, DELETE, DISPLAY, and ALTER actions.

This category consists of the following objects:

QLOCAL	Local queue
QREMOTE	Remote queue
QALIAS	Alias queue for indirect reference to a queue
QMODEL	Model queue for defining queues dynamically
QUEUE	Any of QLOCAL, QREMOTE, QALIAS, or QMODEL
PROCESS	Information about an application to be started when a trigger event occurs
NAMELIST	List of names, such as queues or clusters
STGCLASS	Storage class

2. Channels

They are used for distributed queuing (not for the CICS mover). There can be many of each type, and they can be defined, deleted, displayed, and altered. They also have other functions available; the PERFORM action provides reset, ping, or resolve channel functions.

This category consists of the following objects:

CHANNEL	Any type of channel below
CHLSENDER	Sender channel
CHLSERVER	Server channel
CHLRECEIVER	Receiver channel

CHLREQUESTER Requester channel
CHLCLUSRCVR Cluster-receiver channel
CHLCLUSSDR Cluster-sender channel
CHLSVRCONN Server-connection channel (PERFORM not allowed)
CHLCLNTCONN Client-connection channel (PERFORM, START, STOP not allowed)

3. Cluster objects

They are created automatically for queues and channels that belong to a cluster. The base queue and channel definitions can be on another queue manager. There can be many of each type, and names can be duplicated. They can only be displayed, using the DISPLAY action.

This category consists of the following objects:

CLUSQ Cluster queue, created for a queue that belongs to a cluster
CLUSCHL Cluster channel, created for a channel that belongs to a cluster
CLUSQMGR Cluster queue manager, the same as a cluster channel but identified instead by its queue manager name

Cluster channels and cluster queue managers do have the PERFORM, START and STOP actions, but only indirectly through the DISPLAY action.

4. Queue Manager and Security

These have a single instance. They have attributes that can be displayed and altered (using the DISPLAY and ALTER actions), and have other functions available using the PERFORM action.

This category consists of the following objects:

MANAGER Queue manager - the PERFORM action provides suspend and resume clustering functions
SECURITY Security functions - the PERFORM action provides refresh and reverify functions

5. System

A collection of other functions.

This category consists of the following objects:

SYSTEM System functions
CONTROL (Synonym for SYSTEM)

The functions available are:

DISPLAY Display distributed queuing, threads, or page set usage information
PERFORM Refresh or reset clustering
START, STOP Start or stop the channel initiator or listeners

The actions that you can perform for each type of object are described in the following table:

Table 17 (Page 1 of 2). Valid operations and control panels actions for MQSeries objects

Object	Alter	Define	Delete	Display	Perform	Start	Stop
CHANNEL	√	√	√	√	√	√	√
CHLCLNTCONN	√	√	√	√			

Table 17 (Page 2 of 2). Valid operations and control panels actions for MQSeries objects

Object	Alter	Define	Delete	Display	Perform	Start	Stop
CHLCLUSRCVR	√	√	√	√	√	√	√
CHLCLUSSDR	√	√	√	√	√	√	√
CHLRECEIVER	√	√	√	√	√	√	√
CHLREQUESTER	√	√	√	√	√	√	√
CHLSENDER	√	√	√	√	√	√	√
CHLSERVER	√	√	√	√	√	√	√
CHLSVRCONN	√	√	√	√		√	√
CLUSCHL				√	√(1)	√(1)	√(1)
CLUSQ				√			
CLUSQMGR				√	√(1)	√(1)	√(1)
MANAGER	√			√	√		
NAMELIST	√	√	√	√			
PROCESS	√	√	√	√			
QALIAS	√	√	√	√			
QLOCAL	√	√	√	√			
QMODEL	√	√	√	√			
QREMOTE	√	√	√	√			
QUEUE	√	√	√	√			
SECURITY	√			√	√		
STGCLASS	√	√	√	√			
SYSTEM/CONTROL				√	√	√	√

Note:

1. Via Display

Choosing a queue manager

While you are viewing the initial panel, you are not connected to any queue manager. However, as soon as you press Enter, you are connected to the queue manager shown in “Connect to queue manager”. After this, any requests that you make are directed to that queue manager.

To change the queue manager, press function key F6 in the initial panel and then complete the **Change the Queue Manager** secondary window. From this window, you can also specify a target queue manager that is different from the one you connect to. If you do, any further requests you make are directed to that queue manager.

Queue manager defaults

When you first use the operations and control panels, the “Connect to queue manager ” and “Target queue manager” fields are normally blank. This means after you press Enter in the initial panel, you are using the default queue manager for batch applications. This is defined in CSQBDEFV (see “Task 15: Set up Batch, TSO, and RRS adapters” on page 92). If you return to the initial panel after having made some requests, you find fields filled in with the actual name. Similarly, if you set the “Connect to queue manager” field to blanks, any requests that follow are processed by the default queue manager for batch applications.

Using the function keys

To use the panels, you must use the function keys or enter the equivalent commands in the command area. The function keys have special settings for MQSeries. These settings can optionally be displayed on the panels, as shown in Figure 64 on page 208.

The function key settings in the operations and control panels conform to CUA® standards. Although you can change the key setting through normal ISPF procedures, you are not recommended to do so.

Displaying the function key menu

Type PFSHOW in the command area of any operations and control panel and then press Enter. Type KEYLIST ON in the command area of any operations and control panel and then press Enter.

Use the commands PFSHOW OFF and KEYLIST OFF to remove the display of the function key settings from the panels.

Note: PFSHOW and KEYLIST cause the function key settings to be displayed on any other logical ISPF screens that you have. The keys remain displayed when you leave the operations and control panels.

Getting things done

Press Enter to carry out the action requested on a panel. The information from the panel is sent to the queue manager for processing.

Each time you press Enter in the panels, MQSeries generates one or more operator messages. If the operation was successful, you get a confirmation message, CSQ9022I, otherwise you get some error messages.

Displaying MQSeries user messages

Press function key F10 in any panel to see the MQSeries user messages.

Ignoring what you have done

On the initial panel, both F3 and F12 exit the operations and control panels and return you to ISPF. No information is sent to the queue manager.

On any other panel, press function keys F3 or F12 to leave the current panel *ignoring any data you have typed since last pressing Enter*. Again, no information is sent to the queue manager.

- F3 takes you straight back to the initial panel.
- F12 takes you back to the previous panel.

Getting help

Each panel has help panels associated with it. The help panels use the ISPF protocols:

- Press function key F1 on any panel to see general help (extended help) about the task.
- Press function key F1 with the cursor on any field to see specific help about that field.
- Press function key F5 from any field help panel to get the general help.
- Press function key F3 to return to the base panel, that is, the panel from which you pressed function key F1.
- Press function key F6 from any help panel to get help about the function keys.

If the help information carries on into a second or subsequent pages, a **More** indicator is displayed in top right of the panel. Use these function keys to navigate through the help pages:

- F11 to get to the next help page (if there is one).
- F10 to get back to the previous help page (if there is one).

Using the initial panel

Figure 64 shows the panel that is displayed when you start a panel session.

```
                    IBM MQSeries for OS/390 - Main Menu

 Complete fields. Then press Enter.

 Action . . . . . _      1. Display   5. Perform
                         2. Define    6. Start
                         3. Alter     7. Stop
                         4. Delete

 Object type  . . . . . ___________  +
 Name . . . . . _____________________________________________
 Like . . . . . _____________________________________________

 Connect to queue
 manager  . . . . . :____
 Target queue manager :____
 Response wait time . : __   seconds

(C) Copyright IBM Corporation 1993,1999. All rights reserved.

 Command ===> ____________________________________________________________
  F1=Help      F2=Split     F3=Exit      F4=Prompt    F6=QueueMgr  F9=Swap
 F10=Messages F12=Cancel
```

Figure 64. The MQSeries operations and control initial panel

From this panel you can:

- Choose the local queue manager you want and whether you want the commands issued on that queue manager or on some remote queue manager. Press function key F6 if you need to change the queue manager name. For more information, see “Choosing a queue manager” on page 206.
- Select the action you want to perform by typing in the appropriate number in the **Action** field.

- Specify the object type that you want to work with. Press function key F4 for a list of object types if you are not sure what they are, or see “Objects and Actions” on page 204.
- Display a list of objects of the type specified. Type in an asterisk (*) in the **Name** field and press Enter to display a list of objects (of the type specified) that have already been defined on this subsystem. You can then select one or more objects to work with in sequence. Figure 65 shows a list of queues produced in this way.
- Define an object with the same attributes as an existing object. See “Defining a local queue using the Like field” on page 213.

```
                                List Queues                        ROW 1 OF 12

Type action codes. Then press Enter.
 1=Display  2=Define like  3=Alter  4=Delete


    Name                                                Type
_   CICS01.INITQ                                        QLOCAL
_   PROTO.APPL                                          QLOCAL
_   PROTO.TRIG                                          QLOCAL
_   LOCAL.QUEUE                                         QLOCAL
_   SYSTEM.CHANNEL.SEQNO                                QLOCAL
_   SYSTEM.COMMAND.INPUT                                QLOCAL
_   SYSTEM.COMMAND.REPLY.MODEL                          QMODEL
_   SYSTEM.DEFAULT.ALIAS.QUEUE                          QALIAS
_   SYSTEM.DEFAULT.LOCAL.QUEUE                          QLOCAL
_   SYSTEM.DEFAULT.MODEL.QUEUE                          QMODEL
_   SYSTEM.DEFAULT.REMOTE.QUEUE                         QREMOTE
_   TRANSMIT.QUEUE.PROD                                 QLOCAL
                    ******** End of list ********


Command ===> ____________________________________________________________________
 F1=Help      F2=Split     F3=Exit      F5=Refresh   F6=Clusinfo  F7=Bkwd
 F8=Fwd       F9=Swap     F10=Messages F12=Cancel
```

Figure 65. Listing queues

Defining a local queue

To define a local queue object from the operations and control panels, there are several panels to complete. When you have completed *all* the panels and you are satisfied that the attributes are correct, you press Enter to send your definition to the queue manager, which then creates the actual queue.

Starting from the initial panel, complete these fields:

Field	***Value***
Action	2 (Define)
Object type	QLOCAL
Name	QUEUE.YOU.LIKE

Press Enter to display the **Define a Local Queue** panel as shown in Figure 66 on page 210. The queue name displayed is the name you specified in the previous panel. You can type in your own description in the **Description** field. Complete the other fields as required. For example, type **Y** in the **Put enabled** field if suitably authorized applications can put messages on this queue.



Figure 66. Defining a local queue - first panel

You get field help by moving the cursor into a field and pressing function key F1. Field help provides information about the values that can be used for each attribute.

When you have completed the first panel, press function key F8 to display the second panel, see Figure 67 on page 211.

Hints:

1. Do *not* press Enter at this stage, otherwise the queue will be created before you have a chance to complete the remaining fields.
2. Do not press function key F3 or F12 either, or the data you typed will be lost.
3. If you do press Enter prematurely, do not worry; you can always alter your definition later on.

Press function key F8 repeatedly to see and complete the remaining panels, including the trigger definition, event control, and backout reporting panels.

```
                          Define a Local Queue

Press F7 or F8 to see other fields, or Enter to define queue.

                                                                  More:  - +

Default persistence . . . . . N  Y=Yes,N=No
Default priority  . . . . . . 5  0 - 9
Message delivery sequence . . P  P=Priority,F=FIFO
Permit shared access  . . . . Y  Y=Yes,N=No
Default share option  . . . . S  E=Exclusive,S=Shared
Index type  . . . . . . . . . N  N=None,M=MsgId,C=CorrelId,T=MsgToken
Maximum queue depth . . . . . 10000      0 - 999999999
Maximum message length  . . . 1000000  0 - 4194304
Retention interval  . . . . . 999999999  0 - 999999999 hours

Cluster name  . . . . . . . . _________________________________________________
Cluster namelist name . . . . _________________________________________________
Default bind  . . . . . . . . O  O=Open,N=Notfixed


Command ===> ____________________________________________________________________
 F1=Help      F2=Split     F3=Exit      F6=Clusinfo  F7=Bkwd      F8=Fwd
 F9=Swap     F10=Messages F12=Cancel
```

Figure 67. Defining a local queue - second panel

```
                          Define a Local Queue

Press F7 or F8 to see other fields, or Enter to define queue.

                                                                  More:  - +

Trigger Definition

Trigger type  . . . . . . . . F  F=First,E=Every,D=Depth,N=None

   Trigger set  . . . . . . . N  Y=Yes,N=No
   Trigger message priority . 0  0 - 9
   Trigger depth  . . . . . . 1          1 - 999999999
   Trigger data . . . . . . . ____________________________
                              ____________________________
   Process name . . . . . . . ________________________________________________
   Initiation queue . . . . . ________________________________________________


Command ===> ____________________________________________________________________
 F1=Help      F2=Split     F3=Exit      F6=Clusinfo  F7=Bkwd      F8=Fwd
 F9=Swap     F10=Messages F12=Cancel
```

Figure 68. Defining a local queue - trigger conditions

```
                          Define a Local Queue

Press F7 or F8 to see other fields, or Enter to define queue.


                                                                  More:  - +
Event Control

   Queue full . . . . . . . . E  E=Enabled,D=Disabled

   Upper queue depth  . . . . D  E=Enabled,D=Disabled
   Threshold  . . . . . . . . 80   0 - 100 %

   Lower queue depth  . . . . D  E=Enabled,D=Disabled
   Threshold  . . . . . . . . 40   0 - 100 %

   Service interval . . . . . N  H=High,O=OK,N=None
   Interval . . . . . . . . . 999999999  0 - 999999999 milliseconds



Command ===> ____________________________________________________________
  F1=Help      F2=Split     F3=Exit      F6=Clusinfo  F7=Bkwd      F8=Fwd
  F9=Swap     F10=Messages F12=Cancel
```

Figure 69. Defining a local queue - event control

```
                          Define a Local Queue

 Press F7 to see previous fields, or Enter to define queue.


                                                                  More:  -
 Backout Reporting


 Backout threshold . . . . . . 0          0=No backout reporting

    Harden backout counter . . N  Y=Yes,N=No
    Backout requeue name . . . ________________________________________________







 Command ===> ____________________________________________________________
  F1=Help      F2=Split     F3=Exit      F6=Clusinfo  F7=Bkwd      F8=Fwd
  F9=Swap     F10=Messages F12=Cancel
```

Figure 70. Defining a local queue - backout reporting

When your local queue definition is complete

When your definition is complete, press Enter to send the information to the queue manager for processing. The queue manager creates the queue according to the definition you have supplied. If you do not want the queue to be created, press function key F3 to exit and cancel the definition.

Defining a local queue using the Like field

You can use the **Like** field to define a local queue that has the same attributes as an existing local queue. This field is ignored for actions other than **Define**.

To do this, starting from the initial panel, use these values for the fields specified:

Field	*Value*
Action	2 (Define).
Object type	QLOCAL
Name	TRANSMIT.QUEUE.NEW This is the name of the queue you are defining.
Like	TRANSMIT.QUEUE.PROD This is the name of an existing queue.

When you press Enter, the attributes of the new queue, which are initially those of the queue named in the **Like** field, are displayed. You can modify these attributes as required.

You can use this method to define any type of object providing that the object specified in the **Like** field exists and it is the same kind of object as that specified in the **Object type** field.

Defining other types of objects

You can define objects other than just local queues. To do this, you start from the initial panel and complete these fields:

Field	*Value*
Action	2 (Define).
Object type	QALIAS, NAMELIST, PROCESS, CHANNEL, and so on.
Name	The name of the object you are defining.
Like	Leave blank or enter the name of an existing object of the same type.

Press Enter to display the corresponding DEFINE panels. Complete the fields as required and then press Enter again to send the information to the queue manager.

Like defining a local queue, defining a model queue requires several panels to be completed. Defining a namelist requires some additional work, as described in “Working with namelists” on page 214. A single panel is required to define each of the remaining objects.

Working with object definitions

Once an object has been defined, you can specify an action in the **Action** field, to alter, display, or delete an object definition. In each case, you start from the initial panel, where you specify the object you are working with by completing the **Object type** and **Name** fields.

Altering an object definition

To alter an object definition, specify action 3 and press Enter to see the ALTER panels. These panels are very similar to the DEFINE panels. You can alter any values you want. When your changes are complete, press Enter to send the information to the queue manager.

Displaying an object definition

If you just want to see the details of an object without being able to change them, specify action 1 and press Enter to see the DISPLAY panels. Again, these panels are similar to the DEFINE panels except that you cannot change any of the fields.

Deleting an object

To delete an object, specify action 4 and press Enter to see the DELETE panels. Again these are similar to the DEFINE panels except that when you press Enter, you are asked to confirm your request. If you press function key F3 or F12, the request is canceled. If you press Enter, the request is confirmed and passed to the queue manager. The object you specified is then deleted.

Note: You cannot delete most types of channel object unless the channel initiator is started.

Working with namelists

Start from the initial panel and complete these fields:

Field	***Value***
Action	1 to 4, as required
Object type	NAMELIST
Name	Specify the fully qualified name of a namelist (for example: MY.CSQ.NAMES)
Like	You can type the name of an existing namelist if you are defining a new namelist

Then press Enter. The panel you are shown lists the contents of that namelist.

For the actions DEFINE or ALTER, you must press function key F11 to add names to the list or to change the names in the list. This involves working with the ISPF editor and all the normal ISPF edit commands are available. Each name in the namelist must be entered on a separate line.

Note: When you use the ISPF editor in this way, the function key settings are the normal ISPF settings, and **not** those used by the other operations and control panels.

If you need to specify lowercase queue names, specify CAPS(OFF) on the editor panel command line. When you do this, all the namelists that you edit in the future are in lowercase until you specify CAPS(ON).

When you have finished editing the namelist, press function key F3 to end the ISPF edit session. Then press Enter to send the changes to the queue manager.

Attention: If you do not press Enter at this stage but press function key F3 instead, you lose any updates that you have typed in.

Rules for the operations and control panels

The *MQSeries Command Reference* manual defines the general rules for MQSeries character strings and names. However, there are some rules that apply only to the operations and control panels:

- Do not enclose strings, for example descriptions, in single or double quotes.
- If you need to use a quote mark in a description or other text field, for example:

  ```
  This is Maria's queue
  ```

  use just one quote. The panel processor doubles them for you to pass them to MQSeries. However, if it has to truncate your data to do this, it will do so.
- You can use uppercase or lowercase characters in most fields, and they are translated to uppercase characters when you press Enter. The exceptions are:
  - Storage class which must start with uppercase A through Z and be followed by uppercase A through Z or 0 through 9 characters.
  - The following fields, which are not translated:
    - Application ID
    - Description
    - Environment data
    - Object names (but if you use a lowercase object name, you might not be able to enter it at an OS/390 console)
    - Remote system name
    - Trigger data
    - User data
- In names, leading blanks and leading underscores are ignored. Therefore, you cannot have object names beginning with blanks or underscores.
- Underscores are used to show the extent of blank fields. When you press Enter, trailing underscores are replaced by blanks.
- Many description and text fields are presented in multiple parts, each part being handled by MQSeries independently. This means that trailing blanks *are retained* and the text is not contiguous.

Blank fields

When you specify the define action for an MQSeries object, each field on the define panel contains a value. See the general help (extended help) for the display panels for information on where MQSeries gets the values. If you type over a field with blanks, and blanks are not allowed, MQSeries puts the installation default value in the field.

When you specify the **Alter** action for an MQSeries object, each field on the alter panel contains the current value for that field. If you type over a field with blanks, and blanks are not allowed, the ALTER command fails and an error message is displayed.

Operations and control panels

Chapter 13. Writing programs to administer MQSeries

General-use programming interface

This chapter contains hints and guidance to enable you to issue MQSeries commands from an MQSeries application program.

It contains these sections:

- "Before you begin"
- "Understanding how it all works" on page 218
- "Using the command server" on page 219
- "Preparing queues for administration programs" on page 220
- "Sending commands to the command server" on page 222
- "Putting messages on the system-command input queue" on page 223
- "Retrieving replies to your commands" on page 224
- "Interpreting the replies" on page 226
- "If you do not receive a reply" on page 232
- "Passing commands using MGCR or MGCRE" on page 232

Note: In this chapter, the MQI calls are described using C-language notation. For typical invocations of the calls in the COBOL, PL/I, and assembler languages, see the *MQSeries Application Programming Reference* manual.

Before you begin

Before you can write an application program to issue MQSeries commands, you must be familiar with:

1. Issuing MQSeries commands and the command syntax. See the *MQSeries Command Reference* manual for more information.
2. Writing application programs that use the MQI.

   This includes:

   - Connecting to a queue manager using the **MQCONN** call.
   - Opening a queue using **MQOPEN**.
   - Opening a dynamic queue using **MQOPEN** and specifying the name of a model queue.
   - Putting messages on a queue using **MQPUT** and **MQPUT1**.
   - Getting messages from a queue using **MQGET**.

   You need to know about the messages including:

   - The message descriptor structure.
   - What the persistence attribute of a message means.
   - The types of MQSeries messages, in particular, *request messages* and the *reply messages* they generate.

   You can find all this information in the *MQSeries Application Programming Guide* and the *MQSeries Application Programming Reference* manual.

© Copyright IBM Corp. 1993,1999

3. User messages.

   These messages are generated by MQSeries to show the success or failure of, and the responses to, MQSeries commands. Each message is identified by an ID that contains the characters CSQ, for example, CSQN205I. For more information, see the *MQSeries for OS/390 Messages and Codes* manual.

If you want your MQSeries commands to be run on a remote queue manager, see the *MQSeries Intercommunication* manual.

MQSeries can also be set up to perform security checks. For example, to ensure that a user is authorized to issue a particular command for a particular resource. For more information, see Part 8, “Security” on page 401.

Understanding how it all works

In outline, the procedure for issuing commands from an application program is quite simple:

1. You build an MQSeries command into a type of MQSeries message called a *request message*.
2. You put (**MQPUT**) this message onto a special queue called the system-command input queue. The MQSeries command processor runs the command.
3. You retrieve (**MQGET**) the results of the command as *reply messages* on the reply-to queue. These messages contain the user messages that you need to determine whether your command was successful and, if it was, what the results were.

Then it is up to your application program to process the results.

Using the command server

The command server is an MQSeries component that works with the command processor component. The command server reads request messages from the system-command input queue, verifies them, and passes the valid ones as commands to the command processor. The command processor processes the commands and puts any replies as reply messages on to the reply-to queue that you specify. The first reply message contains the user message CSQN205I. See “Interpreting the replies” on page 226 for more information.

Identifying the queue manager that processes your commands

The queue manager that processes the commands you issue from an administration program is the queue manager that owns the system-command input queue that the message is put onto.

Starting the command server

Normally, the command server is started automatically when the queue manager is started. It becomes available as soon as the message CSQ9022I 'START QMGR' NORMAL COMPLETION is returned from the `+cpf` START QMGR command. The command server is stopped when all the connected tasks have been disconnected during the system termination phase.

You can control the command server yourself using the `+cpf` START CMDSERV and `+cpf` STOP CMDSERV commands. To prevent the command server starting automatically when MQSeries is restarted, you can add a `+cpf` STOP CMDSERV command to your CSQINP1 or CSQINP2 initialization data sets.

The `+cpf` STOP CMDSERV command stops the command server as soon as it has finished processing the current message or immediately, if no messages are being processed.

If the command server has been stopped by a `+cpf` STOP CMDSERV command in the program, no other commands from the program can be processed. To restart the command server, you must issue a `+cpf` START CMDSERV command from the OS/390 console.

If you stop and restart the command server while MQSeries is running, all the messages that are on the system-command input queue when the command server stops are processed when the command server is restarted. However, if you stop and restart MQSeries after the command server is stopped, only the persistent messages on the system-command input queue are processed when the command server is restarted. All nonpersistent messages on the system-command input queue are lost.

Preparing queues for administration programs

Before you can issue any **MQPUT** or **MQGET** calls, you must first define, and then open, the queues you are going to use.

Defining the system-command input queue

The system-command input queue is a local queue called SYSTEM.COMMAND.INPUT. The supplied CSQINP2 initialization data set, thlqual.SCSQPROC(CSQ4INSG), contains a default definition for the system-command input queue. See “System command objects” on page 56 for more information.

Defining a reply-to queue

You must define a reply-to queue to receive reply messages from the MQSeries command processor. It can be any queue whose attributes allow reply messages to be put on it. However, for normal operation, specify these attributes:

- MAXSMSGL(13000)
- USAGE(NORMAL)
- NOTRIGGER (unless your application uses triggering)

You should not normally use persistent messages for commands, but if you choose to do so, the reply-to queue must not be a temporary dynamic queue.

The supplied CSQINP2 initialization data set, thlqual.SCSQPROC(CSQ4INSG), contains a definition for a model queue called SYSTEM.COMMAND.REPLY.MODEL. You can use this model to create a dynamic reply-to queue.

Note: Replies generated by the command processor can be up to 13 000 bytes in length.

Opening the system-command input queue

Before you can open the system-command input queue, your application program must be connected to your MQSeries subsystem. Use the MQI call **MQCONN** to do this.

Then use the MQI call **MQOPEN** to open the system-command input queue. To use this call:

1. Set the *Options* parameter to MQOO_OUTPUT
2. Set the MQOD object descriptor fields as follows:

   ObjectType — MQOT_Q (the object is a queue)

   ObjectName — SYSTEM.COMMAND.INPUT

   ObjectQMgrName — Leave blank if you want to send your request messages to your local queue manager. This means that your commands are processed locally.

   If you want your MQSeries commands to be processed on a remote queue manager, put its name here. You must also have set up the correct queues and links, as described in the *MQSeries Intercommunication* manual.

Opening a reply-to queue

To be able to retrieve the replies from an MQSeries command, you must open a reply-to queue. On way of doing this is to specify the model queue, SYSTEM.COMMAND.REPLY.MODEL, in an **MQOPEN** call to create a permanent dynamic queue as your reply-to queue. To use this call:

1. Set the *Options* parameter to MQOO_INPUT_SHARED
2. Set the MQOD object descriptor fields as follows:

   ObjectType MQOT_Q (the object is a queue)

   ObjectName The name of your reply-to queue. If the queue name you specify is the name of a model queue object, the queue manager creates a dynamic queue.

   ObjectQMgrName To receive replies on your local queue manager, leave this field blank.

   DynamicQName Specify the name of the dynamic queue to be created.

Sending commands to the command server

For each command, you build a message containing the command and then you put it onto the system-command input queue.

Building a message that includes MQSeries commands

You can incorporate MQSeries commands in an application program by building request messages that include the required commands. For each such command you:

1. Create a buffer containing a character string representing the command.
2. Issue an **MQPUT** call specifying the buffer name in the *buffer* parameter of the call.

The simplest way to do this in C is to define a buffer using 'char'. For example:

```
char message_buffer[ ] = "ALTER QLOCAL(SALES) PUT(ENABLED)";
```

When you build a command, use a null-terminated character string. Do not specify a command prefix string (CPF) at the start of a command defined in this way. This means that you do not have to alter your command scripts if you want to run them on another queue manager. However, you must take into account that a CPF is included in any response messages that are put onto the reply-to queue.

The command server translates all characters to uppercase unless they are inside single quotes.

Commands can be any length up to a maximum 32 762 characters.

Putting messages on the system-command input queue

Use the **MQPUT** call to put request messages containing commands on the system-command input queue. In this call you specify the name of the reply-to queue that you have already opened.

To use the **MQPUT** call:

1. Set these **MQPUT** parameters:

   Hconn The connection handle returned by the **MQCONN** call.

   Hobj The object handle returned by the **MQOPEN** call for the system-command input queue.

   BufferLength The length of the formatted command.

   Buffer The name of the buffer containing the command.

2. Set these MQMD fields:

   MsgType MQMT_REQUEST

   ReplyToQ Name of your reply-to queue.

   ReplyToQMgr Leave blank if you want replies sent to your local queue manager. If you want your MQSeries commands to be sent to a remote queue manager, put its name here. You must also have set up the correct queues and links, as described in the *MQSeries Intercommunication* manual.

3. Set any other MQMD fields, as required. If you are not using the same code page as the queue manager, set `CodedCharSetId` as appropriate, and set `Format` to MQFMT_STRING, so that the command server can convert the message. You should normally use nonpersistent messages for commands.

4. Set any *PutMsgOpts* options, as required.

   If you specify MQPMO_SYNCPOINT (the default), you must follow the **MQPUT** call with a syncpoint call.

Using MQPUT1 and the system-command input queue

If you want to put just one message on the system-command input queue, you can use the **MQPUT1** call. This call combines the functions of an **MQOPEN**, followed by an **MQPUT** of one message, followed by an **MQCLOSE**, all in one call. If you use this call, modify the parameters accordingly. See the *MQSeries Application Programming Guide* for details.

Retrieving replies to your commands

When the command processor processes your commands, any reply messages are put onto the reply-to queue specified in the **MQPUT** call. The command server sends the reply messages with the same persistence as the command message it received.

Waiting for a reply

Use the **MQGET** call to retrieve a reply from your request message. One request message can produce several reply messages. For details, see “Interpreting the replies” on page 226.

You can specify a time interval that an **MQGET** call waits for a reply message to be generated. If you do not get a reply, use the checklist beginning on page 232.

To use the **MQGET** call:

1. Set these parameters:

Hconn	The connection handle returned by the **MQCONN** call.
Hobj	The object handle returned by the **MQOPEN** call for the reply-to queue.
Buffer	The name of the area to receive the reply.
BufferLength	The length of the buffer to receive the reply. This must be a minimum of 80 bytes.

2. To ensure that you only get the responses from the command that you issued, you must specify the appropriate *MsgId* and *CorrelId* fields. These depend on the report options, MQMD_REPORT, you specified in the **MQPUT** call:

Report option...	***Use this*** *MsgId*...
MQRO_NONE	Binary zero, '00...00' (24 nulls).
MQRO_NEW_MSG_ID	Binary zero, '00...00' (24 nulls). This is the default if none of these options has been specified.
MQRO_PASS_MSG_ID	The *MsgId* from the **MQPUT**.
Report option...	***Use this*** *CorrelId*...
MQRO_NONE	The *MsgId* from the **MQPUT** call.
MQRO_COPY_MSG_ID_TO_CORREL_ID	The *MsgId* from the **MQPUT** call. This is the default if none of these options has been specified.
MQRO_PASS_CORREL_ID	The *CorrelId* from the **MQPUT** call.

   For more details on report options, see the *MQSeries Application Programming Reference* manual.

3. Set the following *GetMsgOpts* fields:

Options	MQGMO_WAIT If you are not using the same code page as the queue manager, set MQGMO_CONVERT, and set *CodedCharSetId* as appropriate in the MQMD.
WaitInterval	For replies from the local queue manager, try 5 seconds. Coded in milliseconds, this becomes 5 000. For replies from a remote queue manager, and channel control and status commands, try 30 seconds. Coded in milliseconds, this becomes 30 000.

Discarded messages

If the command server finds that a request message is not valid, it discards this message and writes the message CSQN205I to the named reply-to queue. If there is no reply-to queue, the CSQN205I message is put onto the dead-letter queue. The return code in this message shows why the original request message was not valid:

Return code	***Message not valid because...***
00D5020F	It is not of type MQMT_REQUEST.
00D50210	It has zero length.
00D50212	It is longer than 32 762 bytes.
00D50211	It contains all blanks.
00D5483E	It needed converting, but *Format* was not MQFMT_STRING.
OTHER	See the *MQSeries for OS/390 Messages and Codes* manual.

The reply message descriptor

For any reply message, the following MQMD message descriptor fields are set:

MsgType	MQMT_REPLY
Feedback	MQFB_NONE
Encoding	MQENC_NATIVE
Priority	As for the MQMD in the message you issued.
Persistence	As for the MQMD in the message you issued.
CorrelId	Depends on the **MQPUT** report options.
ReplyToQ	None.

The command server sets the *Options* field of the MQPMO structure to MQPMO_NO_SYNCPOINT. This means that you can retrieve the replies as they are created, rather than as a group at the next syncpoint.

End of General-use programming interface

Interpreting the replies

Product-sensitive programming interface

Each request message correctly processed by MQSeries produces at least two reply messages. Each reply message contains a single MQSeries user message.

The length of a reply depends on the command that was issued. The longest reply you can get is from a DISPLAY NAMELIST, and that can be up to 13 000 bytes long.

The first user message, CSQN205I, always contains:

- A count of the replies (in decimal), which you can use as a counter in a loop to get the rest of the replies. The count includes this first message.
- The return code from the command preprocessor.
- A reason code, which is the return code from the command processor.

This message does not contain a CPF.

For example:

```
CSQN205I   COUNT=       4, RETURN=0000000C, REASON=00000008
```

The COUNT field is 8 bytes long and is right-justified. It always starts at position 18, that is, immediately after 'COUNT='. The RETURN field is 8 bytes long in character hex and is immediately after 'RETURN=' at position 35. The REASON field is 8 bytes long in character hex and is immediately after 'REASON=' at position 52.

If the RETURN= value is 00000000 and the REASON= value is 00000004, the set of reply messages is incomplete. After retrieving the replies indicated by the CSQN205I message, issue a further **MQGET** call to wait for a further set of replies. The first message in the next set of replies will again be CSQN205I, indicating how many replies there are, and whether there are more to come.

See the *MQSeries for OS/390 Messages and Codes* manual for more details about the individual messages.

If you are using a non-English language feature, the text and layout of the replies are different from those shown here. However, the size and position of the count and return codes in message CSQN205I are the same.

Examples of commands and their replies

Here are some examples of commands that could be built into MQSeries messages, and the user messages that are the replies. Unless otherwise stated, each line of the reply is a separate message.

Messages from the DEFINE command

Command:

```
DEFINE QLOCAL(Q1)
```

Messages:

```
CSQN205I   COUNT=       2, RETURN=00000000, REASON=00000000
CSQ9022I +cpf CSQMMSGP ' DEFINE QLOCAL' NORMAL COMPLETION
```

These reply messages are produced on normal completion.

Messages from the DELETE command

Command:

```
DELETE QLOCAL(Q2)
```

Messages:

```
CSQN205I   COUNT=       4, RETURN=0000000C, REASON=00000008
CSQM094I +cpf CSQMUQLC QLOCAL (Q2) WAS NOT FOUND
CSQM090I +cpf CSQMUQLC FAILURE REASON CODE X'00D44002'
CSQ9023I +cpf CSQMUQLC ' DELETE QLOCAL' ABNORMAL COMPLETION
```

These messages indicate that a local queue called Q2 does not exist.

Using the DISPLAY commands

To obtain information about MQSeries, use the MQSeries DISPLAY commands. Use these commands rather than **MQINQ** if you want:

- Information about objects on a remote queue manager. **MQINQ** only returns information from the local queue manager.
- Reply messages ready-formatted for printing. **MQINQ** returns information that is not formatted.
- Other information that **MQINQ** does not provide.

The format of the replies from these commands:

DISPLAY THREAD
DISPLAY TRACE
DISPLAY CMDSERV

is the same regardless of whether you issue the command from an application program or from an OS/390 console. However, if you issue DISPLAY commands for MQSeries objects, the format is different when they are issued from an application program.

Messages from the DISPLAY THREAD command

Command:

```
DISPLAY THREAD(*) TYPE(*)
```

Messages:

```
CSQN205I   COUNT=      20, RETURN=00000000, REASON=00000000.
CSQV401I +cpf DISPLAY THREAD REPORT FOLLOWS -
CSQV402I +cpf ACTIVE THREADS - 668
NAME     ST A   REQ THREAD-XREF              USERID   ASID   URID
ABCDEFG  T        3                          ABCDEFG  002D   000000000000
MQSCIC1  T        4                          MQSCIC1  0034   000000000000
MQSCIC1  T        0 00011128C3D2C1D40000023C MQSCIC1  0034   000000000000
MQSCIC1  T        3                          MQSCIC1  0034   000000000000
MQSCIC1  T        1                                   0034   000000000000
MQSCIC1  T        1                                   0034   000000000000
MQSCIC1  T        1                                   0034   000000000000
MQSCIC1  T        1                                   0034   000000000000
MQSCIC1  T        1                                   0034   000000000000
MQSCIC1  T        1                                   0034   000000000000
MQSCIC1  T        1                                   0034   000000000000
MQSCIC1  T        0 00012020C3D2E3C90000039C MQSCIC1  0034   000000000000
DISPLAY ACTIVE REPORT COMPLETE
CSQV412I +cpf CSQVDT NO INDOUBT THREADS FOUND FOR NAME=MQSCIC1
CSQV412I +cpf CSQVDT NO INDOUBT THREADS FOUND FOR NAME=ABCDEFG
CSQ9022I +cpf CSQVDT ' DISPLAY THREAD' NORMAL COMPLETION
```

The actual number and content of the messages depend on what is running in your queue manager.

Messages from DISPLAY commands for MQSeries objects

These DISPLAY command responses, acting on MQSeries objects, produce user messages with a different format when you issue them from an application program:

DISPLAY CHANNEL/CHSTATUS
DISPLAY CLUSQMGR
DISPLAY NAMELIST
DISPLAY PROCESS
DISPLAY QMGR
DISPLAY QUEUE
DISPLAY STGCLASS

The user messages in the replies are still in the form of character strings, however, the attribute values in a message have the fixed positions relative to the attribute name.

The format of the reply is:

```
msg_no +cpf attr_name(value) attr_name attr_name(value)
```

where:

```
msg_no       An 8 character message number
+cpf         The command prefix string
attr_name    The attribute or keyword name
value        The attribute value
```

Messages from the DEFINE QLOCAL command

The following examples show how the results from a command depend on the attributes specified in that command.

Example 1

You define a local queue using the command:

```
DEFINE QLOCAL(Q1) DESCR('A sample queue') GET(ENABLED) SHARE
```

You then issue the following command from an application program:

```
DISPLAY QUEUE(Q1) SHARE GET DESCR
```

These three user messages are returned:

```
CSQN205I   COUNT=       3, RETURN=00000000, REASON=00000000
CSQM401I +cpf QUEUE(Q1                                          ) TYPE(
QLOCAL  ) DESCR(A sample queue
        ) SHARE   GET(ENABLED   )
CSQ9022I +cpf CSQMDMSG ' DISPLAY QUEUE' NORMAL COMPLETION
```

Note: The second message, CSQM401I, is shown here occupying three lines.

Example 2

Two queues have names beginning with the letter “A”:

A1 is a local queue with its PUT attribute set to DISABLED.
A2 is a remote queue with its PUT attribute set to ENABLED.

You then issue the following command from an application program:

```
DISPLAY QUEUE(A*) PUT
```

These four user messages are returned:

```
CSQN205I   COUNT=       4, RETURN=00000000, REASON=00000000
CSQM401I +cpf QUEUE(A1                                          ) TYPE(
QLOCAL  ) PUT(DISABLED  )
CSQM406I +cpf QUEUE(A2                                          ) TYPE(
QREMOTE ) PUT(ENABLED   )
CSQ9022I +cpf CSQMDMSG ' DISPLAY QUEUE' NORMAL COMPLETION
```

Note: The second and third messages, CSQM401I and CSQM406I respectively, are shown here occupying two lines each.

Messages from the DEFINE NAMELIST command

A namelist is defined by the command:

```
DEFINE NAMELIST(N1) NAMES(Q1,SAMPLE_QUEUE)
```

You then issue the following command from an application program:

```
DISPLAY NAMELIST(N1) NAMES NAMCOUNT
```

The following three user messages are returned:

```
CSQN205I   COUNT=       3, RETURN=00000000, REASON=00000000
CSQM407I +cpf NAMELIST(N1                                          ) NA
MCOUNT(         2) NAMES(Q1
 ,SAMPLE_QUEUE                                  )
CSQ9022I +cpf CSQMDMSG ' DISPLAY NAMELIST' NORMAL COMPLETION
```

Note: The third message, CSQM407I, is shown here occupying three lines.

Finding out the name of the dead-letter queue

You want to find out the name of the dead-letter queue for a queue manager.

You issue this command from an application program:

```
DISPLAY QMGR DEADQ
```

The following three user messages are returned from which you can extract the required name:

```
CSQN205I   COUNT=       3, RETURN=00000000, REASON=00000000
CSQM409I +cpf QMNAME(CSQ1) DEADQ(SYSTEM.DEAD.QUEUE                 )
CSQ9022I +cpf CSQMDRTS ' DISPLAY QMGR' NORMAL COMPLETION
```

Command attributes

When using commands in administration programs, you should consider the following:

1. Not all attributes have associated values.
2. Each attribute or attribute and value pair is separated by one or more blanks.
3. Do not make any assumptions about the order in which attributes are returned.
4. The attribute values returned are fixed length and surrounded by parentheses.

   Integer values are ten characters long, right justified, and padded with blanks.

   Character values are left justified and padded with blanks. Their lengths are as follows:

   a. Character string lengths are the same as those given in the *MQSeries Application Programming Reference* manual.

   b. Attributes that return a keyword (for example, DEFSOPT returns EXCL or SHARED) are 10 characters long, left justified, and padded with blanks.

   c. Some attribute keywords can take negated values, for example, NOTRIGGER, NOSHARE, and NOHARDENBO. The attribute keywords that can have negated values take their length from the negated value. For example, the negated equivalent of SHARE is NOSHARE; it has a length of 7. These attributes are left justified and padded with blanks.
5. The number of attributes returned depends on what attributes are requested by the command.
6. The NAMES attribute of a namelist returns multiple values. This attribute returns a list of names, each of fixed length, separated by commas. Use the NAMCOUNT attribute to discover the number of names in the list. If there are no names in the list, the NAMES attribute is returned as NAMES().
7. Attributes that normally require quotes around the string because they contain embedded blanks, lowercase characters or special characters, are returned without the quotes.
8. When you want to use the reply to a `+cpf` DISPLAY command as input to another command, put single quotes (`' '`) around each attribute. For example, if you define this queue:

   ```
   +cpf DEFINE QLOCAL(SALES) DESCR('Sales enquiries queue')
   ```

   You can display it using the command:

   ```
   +cpf DISPLAY QUEUE(SALES) DESCR
   ```

   The DESCR attribute is displayed as:

   ```
   DESCR(Sales enquiries queue)
   ```

   To use this description in another command you must add the quotes as follows:

   ```
   DESCR('Sales enquiries queue')
   ```

   If the attribute itself contains any quotes, you must double them.

If you do not receive a reply

If you do not receive a reply to your request message, work through this checklist:

- ☐ Is the command server running?
- ☐ Is the *WaitInterval* long enough?
- ☐ Are the system-command input and reply-to queues correctly defined?
- ☐ Were the **MQOPEN** calls to these queues successful?
- ☐ Are both the system-command input and reply-to queues enabled for **MQPUT** and **MQGET** calls?
- ☐ Have you considered increasing the MAXDEPTH and MAXMSGL attributes of your queues?
- ☐ Are you are using the *CorrelId* and *MsgId* fields correctly?
- ☐ Is the MQSeries subsystem still running?
- ☐ Was the command built correctly?
- ☐ Are all your remote links defined and operating correctly?
- ☐ Were the **MQPUT** calls correctly defined?
- ☐ Has the reply-to queue been defined as a temporary dynamic queue instead of a permanent dynamic queue? (If the request message is persistent, you must use a permanent dynamic queue for the reply.)

When the command server generates replies but cannot write them to the reply-to queue that you specify, it tries to write them to the system dead-letter queue.

Passing commands using MGCR or MGCRE

If you have the correct authorization, you can pass MQSeries commands from your program to multiple MQSeries subsystems by the MGCR or MGCRE (SVC 34) OS/390 service. The value of the CPF identifies the particular MQSeries subsystem to which the command is directed. For details about CPFs, see "Updating the subsystem name table" on page 41.

If you use MGCRE, you can use a Command and Response Token (CART) to get the direct responses to the command.

End of Product-sensitive programming interface

Chapter 14. Using the MQSeries utilities

This chapter describes the MQSeries utility programs that are provided to help you perform various administrative tasks. Table 18 summarizes what you can do with these utilities.

Table 18. A summary of MQSeries utilities

Name	Purpose		See page
CSQUTIL (MQSeries utility program) ***Page set management***	FORMAT COPYPAGE RESETPAGE	Format VSAM data sets as MQSeries page sets. Copy MQSeries page sets. Copy MQSeries page sets and reset the log information.	237
CSQUTIL ***Command management***	COMMAND SDEFS	Issue MQSeries commands from a sequential data set. Produce a set of DEFINE commands for objects. Produce a client channel definition file. Produce a set of DEFINE commands for objects (offline).	244
CSQUTIL ***Queue management***	COPY SCOPY EMPTY LOAD	Copy contents of a queue to a data set. Copy contents of a queue to a data set (offline). Delete contents of a queue. Restore contents of a queue.	251
CSQUCVX (Data conversion exit utility)	Generates data conversion exit routines. For information about the CSQUCVX utility, see the *MQSeries Application Programming Guide*.		–
CSQJU003 (Change log inventory utility)	Changes the bootstrap data set. NEWLOG DELETE ARCHIVE CRESTART CHECKPT HIGHRBA	 Add active or archive log data sets. Delete active or archive log data sets. Supply passwords for archive logs. Control the next restart of MQSeries. Set checkpoint records. Update the highest written log RBA.	262
CSQJU004 (Print log map utility)	Lists information about the log.		271
CSQ1LOGP (Log print utility)	Prints the log.		272

These utilities are located in the main MQSeries load library thlqual.SCSQAUTH.

Note: Include the appropriate MQSeries language load library thlqual.SCSQANLx (where x is the language letter) in the STEPLIB concatenation before the thlqual.SCSQAUTH or thlqual.SCSQLOAD. The utility control statements are available only in US English.

© Copyright IBM Corp. 1993,1999

How to read syntax diagrams

This chapter contains syntax diagrams (sometimes referred to as “railroad” diagrams).

Each syntax diagram begins with a double right arrow and ends with a right and left arrow pair. Lines beginning with a single right arrow are continuation lines. You read a syntax diagram from left to right and from top to bottom, following the direction of the arrows.

Other conventions used in syntax diagrams are:

Table 19. How to read syntax diagrams

Convention	Meaning
	You must specify values `A`, `B`, and `C`. Required values are shown on the main line of a syntax diagram.
	You may specify value `A`. Optional values are shown below the main line of a syntax diagram.
	Values `A`, `B`, and `C` are alternatives, one of which you must specify.
	Values `A`, `B`, and `C` are alternatives, one of which you may specify.
	You may specify one or more of the values `A`, `B`, and `C`. Any required separator for multiple or repeated values (in this example, the comma (,)) is shown on the arrow.
	You may specify value `A` multiple times. The separator in this example is optional.
	Values `A`, `B`, and `C` are alternatives, one of which you may specify. If you specify none of the values shown, the default `A` (the value shown above the main line) is used.
 **Name:** 	The syntax fragment `Name` is shown separately from the main syntax diagram.
Punctuation and uppercase values	Specify exactly as shown.
Lowercase values (for example, *name*)	Supply your own text in place of the *name* variable.

MQSeries utility program (CSQUTIL)

The CSQUTIL utility program is provided with MQSeries to help you to perform backup, restoration, and reorganization tasks, and to issue MQSeries commands. Through this utility program, you can invoke functions in these groups:

- Page set management, see page 237
- Issuing commands, see page 244
- Queue management, see page 251

All of the page set management functions and some of the other functions operate while the queue manager is not running; for these therefore, you do not need any special authorization other than the appropriate access to the page set data sets. For the functions that operate while the queue manager is running, CSQUTIL runs as an ordinary OS/390 batch MQSeries program, issuing commands through the command server and using the MQSeries API to access queues. You need the necessary authority to use the command server queues (SYSTEM.COMMAND.INPUT, SYSTEM.COMMAND.REPLY.MODEL, and SYSTEM.CSQUTIL.*), to use the MQSC DISPLAY commands, and to use the MQSeries API to access any queues that you wish to manage. See the usage notes for each function for more information.

Invoking the MQSeries utility program

The CSQUTIL utility program runs as an OS/390 batch program, below the 16 MB storage line. In the PARM parameter of the EXEC statement of the JCL, specify the queue manager that the utility is to work with. For example, see Figure 71.

```
// EXEC  PGM=CSQUTIL,PARM='CSQ1'
```

Figure 71. Specifying the queue manager that a utility is to work with

If you specify a queue manager name as blanks, CSQUTIL uses the name of the default queue manager specified for OS/390 batch programs in CSQBDEFV. The utility then uses this queue manager for the whole job step. When the utility connects to the queue manager, the authorization of the “signed-on user name” is checked to see which functions the invocation is allowed to use.

You specify the functions required by statements in the SYSIN data set according to these rules:

- The data set must have a record length of 80.
- Only columns 1 through 72 are significant. Columns 73 through 80 are ignored.
- Records with an asterisk (*) in column 1 are interpreted as comments and are ignored.
- Blank records are ignored.
- Each statement must start on a new line.
- A trailing – means continue from column 1 of the next record.
- A trailing + means continue from the first non-blank column of the next record.
- The keywords of statements are not case-sensitive. However, some arguments, such as queue name, are case-sensitive.

The utility statements refer to the default or explicitly named DDnames for input and output. Your job can use the COPY and LOAD functions repeatedly and process different page sets or queues during a single run of the utility.

All output messages are sent to the SYSPRINT data set, which must have a record format VBA and a record length 125.

While running, CSQUTIL uses temporary dynamic queues with names of the form SYSTEM.CSQUTIL.*

Return codes

When CSQUTIL returns to the operating system, the return code can be:

0 All functions completed successfully.

4 Some functions completed successfully, some did not or forced a syncpoint.

8 All the attempted functions failed.

12 No functions attempted; there was a syntax error in the statements or the expected data sets were missing.

In most cases, if a function fails or is forced to take a syncpoint, no further functions are attempted. In this case, the message CSQU147I replaces the normal completion message CSQU148I.

See the usage notes for each function for more information about success or failure.

Monitoring the progress of the MQSeries utility program

To record the progress of CSQUTIL, every SYSIN statement is echoed to SYSPRINT.

The utility first checks the syntax of the statements in the SYSIN. The requested functions are started only if all the statements are syntactically correct.

Messages giving a commentary on the progress of each function are sent to SYSPRINT. When the processing of the utility is complete, statistics are printed with an indication of how the functions completed.

Page set management functions

These functions enable you to manage MQSeries page sets. You can format data sets as page sets, you can increase the size of page sets and, if required, reset the log information contained in a page set. The page set must not belong to a queue manager that is currently running.

Formatting page sets (FORMAT)

Use the FORMAT function to format page sets on all data sets specified by DDnames CSQP0000 through CSQP0099. In this way, you can format up to 100 page sets by invoking the utility program once. Use the FORCE parameter to reuse existing page sets.

Page set management (FORMAT)



Keywords and parameters

FORCE

Specifies that existing page sets are to be re-used without having to delete and redefine them first. You must define any page sets you want to re-use with the REUSE attribute in the AMS DEFINE CLUSTER statement. For more information about DEFINE CLUSTER, see the *DFSMS/MVS Access Method Services for VSAM* or the *DFSMS/MVS Access Method Services for the Integrated Catalog Facility* manual.

PAGES(nnn)

Specifies the minimum number of pages to format in each page set. This enables a data set that spans more than one volume to be formatted.

Formatting of the data set is always done in whole space allocations, as specified as primary or secondary quantities when the data set is defined. The number of space allocations formatted is the minimum necessary to provide the requested number of pages; if there is insufficient data set space available, as many extents as can be obtained are formatted. If an existing page set is being reused (with the FORCE keyword), the whole page set is formatted if that is larger.

The number of pages must be in the range 1 through 1 048 576 (because the maximum page set size is 4 GB (gigabytes)). The default is 1.

The number of pages formatted is reported by message CSQU092I for each page set.

Example

Figure 72 on page 238 illustrates how the FORMAT command is invoked from CSQUTIL. In this example, two page sets, referenced by CSQP0000 and CSQP0003 respectively, are formatted by CSQUTIL.

```
//FORMAT   EXEC PGM=CSQUTIL
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//CSQP0000 DD   DISP=OLD,DSN=pageset.dsname0
//CSQP0003 DD   DISP=OLD,DSN=pageset.dsname3
//SYSPRINT DD   SYSOUT=*
//SYSIN    DD   *
FORMAT
/*
```

Figure 72. Sample JCL for the FORMAT function of CSQUTIL

Usage notes

1. You cannot format page sets that belong to a queue manager that is still running.
2. When you use FORMAT, it is not necessary to specify a queue manager name.
3. If you use data set names in which the queue manager name is a high-level qualifier, you can more easily identify which page sets are used by which MQSeries subsystem, if more than one MQSeries subsystem is defined.
4. If there is an error when formatting a page set, it does not prevent other page sets from being formatted, although the FORMAT function is considered to have failed.
5. If FORMAT fails, no further CSQUTIL functions are attempted.

Expanding a page set (COPYPAGE)

Note: The COPYPAGE function is only used for *expanding* page sets. It is not used for making backup copies of page sets. If you want to do this, use AMS REPRO as described in "Backing up and recovering page sets" on page 339. When you have used the COPYPAGE function, the page sets cannot be used by a queue manager with a different name, so you must not rename your queue manager.

Use the COPYPAGE function to copy one or more page sets. All queues and messages on the page set are copied. If you copy page set zero, all the MQSeries object definitions are also copied. Each page set is copied to a destination data set that must be formatted as a page set. Copying to a smaller page set is not supported.

If you use this function, you must modify the page set definition in the startup procedure to reflect the change of the name of the data set on which the new page set resides.

To use the COPYPAGE function, define DDnames in the range CSQS0000 through CSQS0099 for the source data sets, and define DDnames for the target data sets from CSQT0000 through CSQT0099 respectively.

For more information, see Chapter 20, "Managing page sets" on page 333.

Page set management (COPYPAGE)



Keywords and parameters

There are no keywords or parameters.

Example

In Figure 73 on page 240, two existing page sets are copied onto two new page sets. The procedure for this is:

1. Set up the required DDnames, where:

   CSQP0005, CSQP0006 Identify the destination data sets. These DDnames are used by the FORMAT function.

   CSQS0005, CSQS0006 Identify the source data sets containing the two page sets you want to copy.

   CSQT0005, CSQT0005 Identify the destination data sets (page sets), but this time for the COPYPAGE function.

2. Format the destination data sets, referenced by DDnames CSQP0005 and CSQP0006, as page sets using the FORMAT function.
3. Copy the two existing page sets onto the new page sets using the COPYPAGE function.

```
//COPYPAGE EXEC PGM=CSQUTIL
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//CSQP0005 DD   DISP=OLD,DSN=pageset.newname5
//CSQP0006 DD   DISP=OLD,DSN=pageset.newname6
//CSQS0005 DD   DISP=OLD,DSN=pageset.oldname5
//CSQS0006 DD   DISP=OLD,DSN=pageset.oldname6
//CSQT0005 DD   DISP=OLD,DSN=pageset.newname5
//CSQT0006 DD   DISP=OLD,DSN=pageset.newname6
//SYSPRINT DD   SYSOUT=*
//SYSIN    DD   *
* Format new data sets (CSQP0005 and CSQP0006) as page sets
 FORMAT
* Copy old page sets CSQS0005 and CSQS0006 to new
* page sets CSQT0005 and CSQT0006
 COPYPAGE
/*
```

Figure 73. Sample JCL showing the use of the COPYPAGE function

Usage notes

1. You cannot use COPYPAGE on page sets of a queue manager that is running.
2. Using COPYPAGE involves stopping the queue manager. This will result in the loss of nonpersistent messages.
3. Before you use COPYPAGE, the new data sets must be pre-formatted as page sets. To do this, use the FORMAT function, as shown in Figure 73.
4. Ensure that the new (destination) data sets are larger than the old (source) data sets.
5. You cannot change the page set identifier (PSID) associated with a page set. For example, you cannot 'make' page set 03 become page set 05.
6. Failure of this function does not prevent other page set management functions from being completed.
7. If you attempt to use the COPYPAGE function after MQSeries has terminated abnormally, it is possible that the page sets have not been closed properly. If a page set has not been closed properly, you cannot successfully run the COPYPAGE function against it.

   To avoid this problem, run the AMS VERIFY command before using the COPYPAGE function. The AMS VERIFY command might produce error messages. However, it does close the page sets properly, so that the COPYPAGE function can complete successfully.

   For more information about the AMS VERIFY command, see the *DFSMS/MVS Access Method Services for VSAM* or the *DFSMS/MVS Access Method Services for the Integrated Catalog Facility* manual.

Copying a page set and resetting the log (RESETPAGE)

The RESETPAGE function is similar to the COPYPAGE function except that it also resets the log information in the new page sets. RESETPAGE lets you restart MQSeries from a known, valid set of page sets, even if the corresponding log data sets have been corrupted.

This function has been updated by APAR PQ24994.

The source page sets for RESETPAGE must be in a consistent state. They must be either:

- Page sets that have been through a successful MQSeries shutdown using the MQSeries STOP QMGR command.
- Copies of page sets that have been through a successful stop.

Important

The RESETPAGE function must not be run against copies of page sets made using fuzzy backup, or against page sets that are from an MQSeries system that has terminated abnormally.

RESETPAGE either:

- Copies page sets on all data sets referenced by DDnames CSQS0000 through CSQS0099 to new data sets referenced by DDnames CSQT0000 through CSQT0099 respectively. If you use this function, you must modify the page set definition in the startup procedure to reflect the change of the name of the data set on which the new page set resides.
- Resets the log information in the page set referenced by DDnames CSQP0000 through CSQP0099.

For more information, see Chapter 20, “Managing page sets” on page 333.

Using the RESETPAGE function

You can use the RESETPAGE function to update a set of consistent page sets so that they can be used with a set of new (clean) BSDS and log data sets to start MQSeries. You would only have to do this if both copies of the log have been lost or damaged for some reason; you can restart from backup copies of page sets (and accept the resulting loss of data from the time the copies were made), or from your existing page sets.

In this situation, you should use the RESETPAGE function on **all** the page sets of the affected queue manager. You must also create new BSDS and log data sets.

Note: The RESETPAGE function should not be used on a subset of the page sets known to MQSeries.

If you run the RESETPAGE function against any page sets, but do not provide clean BSDS and log data sets for the MQSeries subsystem, MQSeries will attempt to recover the logs from RBA zero, and will treat the page sets as empty.

For example, the following messages would be produced if you attempted to use the RESETPAGE function to generate page sets 0, 1, 2, and 3 without providing a clean set of BSDS and log data sets:

```
CSQI021I +cpf CSQIECUR PAGE SET 0 IS EMPTY. MEDIA RECOVERY STARTED
CSQI021I +cpf CSQIECUR PAGE SET 1 IS EMPTY. MEDIA RECOVERY STARTED
CSQI021I +cpf CSQIECUR PAGE SET 2 IS EMPTY. MEDIA RECOVERY STARTED
CSQI021I +cpf CSQIECUR PAGE SET 3 IS EMPTY. MEDIA RECOVERY STARTED
```

Page set management (RESETPAGE)



Keywords and parameters

FORCE

Specifies that the page sets specified by DDnames CSQP0000 through CSQP00nn are to be reset in place.

If FORCE is not specified, the page sets specified by DDnames CSQS0000 through CSQS00nn are copied to new page sets specified by DDnames CSQT0000 through CSQT00nn. This is the default.

Example

An existing page set, referenced by DDname CSQS0007, is copied to a new data set referenced by DDname CSQT0007. The new data set, which is also referenced by DDname CSQP0007, is already formatted as a page set before the RESETPAGE function is called.

```
//RESTPAGE EXEC PGM=CSQUTIL
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//CSQP0007 DD   DISP=OLD,DSN=pageset.newname7
//CSQS0007 DD   DISP=OLD,DSN=pageset.oldname7
//CSQT0007 DD   DISP=OLD,DSN=pageset.newname7
//SYSPRINT DD   SYSOUT=*
//SYSIN    DD   *
* Format new data set, CSQP0007, as page set
 FORMAT
* Copy page set CSQS0007 to CSQT0007 and reset it
 RESETPAGE
/*
```

Figure 74. Sample JCL showing the use of the RESETPAGE function

Usage notes

1. You should not attempt to use the RESETPAGE function against page sets after MQSeries has terminated abnormally. It is probable that page sets from an MQSeries system that terminated abnormally contain inconsistent data; using RESETPAGE on page sets in this state leads to data integrity problems.
2. You cannot use RESETPAGE on page sets belonging to a queue manager that is running.

3. Using RESETPAGE involves stopping the queue manager. This will result in the loss of nonpersistent messages.
4. Before you use RESETPAGE, the new data sets must be pre-formatted as page sets. To do this, use the FORMAT function, as shown in Figure 74 on page 242.
5. Ensure that the new (destination) data sets are larger than the old (source) data sets.
6. You cannot change the page set identifier (PSID) associated with a page set. For example, you cannot 'make' page set 03 become page set 05.
7. Failure of this function does not prevent other page set management functions from being completed.

MQSeries command management functions

These functions enable you to:

- Issue commands to MQSeries
- Produce a list of define commands describing the objects in your MQSeries subsystem

Issuing commands to MQSeries (COMMAND)

Use the COMMAND function to:

1. Pass MQSeries commands from an input data set to the queue manager.
2. Produce a list of MQSeries DEFINE commands that describe the objects in an MQSeries subsystem. The statements can be used to keep a record of the object definitions or to regenerate all or part of a queue manager's objects as part of a migration from one MQSeries system to another.
3. Make a client channel definition file.

The queue manager specified in the PARM parameter of the EXEC statement must be running.



Keywords and parameters

DDNAME(*ddname1***)**

Specifies that the MQSeries commands are to be read from a named input data set. If this keyword is omitted, the default DDname, CSQUCMD, is used.

ddname1 specifies the DDname that identifies the input data set from which MQSeries commands are to be read.

MAKEDEF(*ddname2***)**

Specifies that DEFINE commands are to be generated from any DISPLAY object commands in the input data set.

There is no default if this keyword is omitted.

ddname2 specifies the DDname that identifies the output data set in which the DEFINE statements are to be stored. The data set should be RECFM=FB, LRECL=80. This data set can then be used as input for a later invocation of the COMMAND function or it can be incorporated into the initialization data sets CSQINP1 and CSQINP2.

TGTQMGR(*qmgrname*)
Specifies the name of the (remote) queue manager where you want the commands to be performed.

The default is that commands are performed on the queue manager to which you are connected, as specified in the PARM field of the EXEC statement.

RESPTIME(*nnn*)
Specifies the time in seconds to wait for a response to each of the commands, in the range 5 through 999.

The default is 30 seconds.

MAKECLNT(*ddname3*)
Specifies that a client channel definition file, in binary format suitable for downloading to a client machine, is to be generated from any DISPLAY CHANNEL commands in the input data set that return information about client-connection channels.

If this keyword is omitted, no file is generated.

ddname3 specifies the DDname that identifies the output data set in which the generated file is to be stored; the data set should be RECFM=U, LRECL=2048, BLKSIZE=2048. The file can then be downloaded as binary data to the client machine by a suitable file transfer program.

CCSID(*ccsid*)
Specifies the coded character set identifier that is to be used for the data in a client channel definition file. The value must be in the range 1 through 65535; the default is 437. You can only specify CCSID if you also specify MAKECLNT.

Note: MQSeries assumes that the data is to be in ASCII, and that the encoding for numeric data is to be MQENC_INTEGER_REVERSED.

FAILURE
Specifies what action to take if an MQSeries command that is issued fails to execute successfully. Values are:

IGNORE Ignore the failure; continue reading and issuing commands, and treat the COMMAND function as being successful. This is the default.

CONTINUE Read and issue any remaining commands in the input data set, but treat the COMMAND function as being unsuccessful.

STOP Do not read or issue any more commands, and treat the COMMAND function as being unsuccessful.

Examples

Issuing commands: In Figure 75 on page 246, the data sets referenced by DDnames CSQUCMD and OTHER contain sets of MQSeries commands. The first COMMAND statement takes MQSeries commands from the default input data set MY.MQSERIES.COMMANDS(COMMAND1) and passes them to the command processor. The second COMMAND statement takes MQSeries commands from the input data set MY.MQSERIES.COMMANDS(OTHER1), which is referenced by DDname OTHER.

```
//COMMAND EXEC PGM=CSQUTIL,PARM='CSQ1'
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//CSQUCMD  DD DSN=MY.MQSERIES.COMMANDS(COMMAND1),DISP=SHR
//OTHER    DD DSN=MY.MQSERIES.COMMANDS(OTHER1),DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
* NEXT STATEMENT CAUSES COMMANDS TO BE READ FROM CSQUCMD DDNAME
COMMAND
* THE NEXT SET OF COMMANDS WILL COME FROM 'OTHER' DDNAME
COMMAND DDNAME(OTHER)
* THE NEXT STATEMENT CAUSES COMMANDS TO BE READ FROM CSQUCMD
* DDNAME AND ISSUED ON QUEUE MANAGER CSQ2 WITH A RESPONSE TIME
* OF 10 SECONDS
COMMAND TGTQMGR(CSQ2) RESPTIME(10)
/*
```

Figure 75. Sample JCL for issuing MQSeries commands using CSQUTIL

Making a list of DEFINE commands: In Figure 76, the data set referenced by DDname CMDINP contains a set of MQSeries DISPLAY commands. These DISPLAY commands specify generic names for each object type (except the queue manager itself). If you run these commands, a list is produced containing all the MQSeries objects (except the queue manager). In these DISPLAY commands, the ALL keyword is specified to ensure that all the attributes of all the objects are included in the list.

The MAKEDEF keyword causes this list to be converted into a corresponding set of DEFINE commands. These commands are put into a data set referenced by the *ddname2* parameter of the MAKEDEF keyword, that is, OUTPUT1. If you run this set of commands, MQSeries regenerates all the object definitions (except the queue manager) in the MQSeries subsystem.

```
//QDEFS   EXEC PGM=CSQUTIL,PARM='CSQ1'
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//OUTPUT1  DD   DISP=OLD,DSN=MY.MQSERIES.COMMANDS(DEFS)
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
COMMAND DDNAME(CMDINP) MAKEDEF(OUTPUT1)
/*
//CMDINP   DD *
DISPLAY STGCLASS(*)
DISPLAY QUEUE(*) ALL
DISPLAY NAMELIST(*) ALL
DISPLAY PROCESS(*) ALL
DISPLAY CHANNEL(*) ALL
/*
```

Figure 76. Sample JCL for using the MAKEDEF option of the COMMAND function

Making a client channel definition file: In Figure 77 on page 247, the data set referenced by DDname CMDCHL contains an MQSeries DISPLAY CHANNEL command. The DISPLAY command specifies a generic name and the ALL keyword is specified to ensure that all the attributes are included.

The MAKECLNT keyword causes this to be converted into a corresponding set of client channel definitions. These are put into a data set referenced by the *ddname3* parameter of the MAKECLNT keyword, that is, OUTCLNT, which is ready to be downloaded to the client machine.

```
//CLIENT  EXEC PGM=CSQUTIL,PARM='CSQ1'
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//OUTCLNT  DD   DISP=OLD,DSN=MY.MQSERIES.CLIENTS
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
COMMAND DDNAME(CMDCHL) MAKECLNT(OUTCLNT)
/*
//CMDCHL   DD *
DISPLAY CHANNEL(*) ALL TYPE(CLNTCONN)
/*
```

Figure 77. Sample JCL for using the MAKECLNT option of the COMMAND function

Usage notes

1. The format of commands issued from the COMMAND function is similar to the MQSeries operator command format. See the *MQSeries Command Reference* manual for information about the rules for building MQSeries commands.
2. The rules for specifying commands in the input data set are the same as for the initialization data sets:
   - The data set must have a record length of 80.
   - Only columns 1 through 72 are significant. Columns 73 through 80 are ignored.
   - Records with an asterisk (*) in column 1 are interpreted as comments and are ignored.
   - Blank records are ignored.
   - Each command must start on a new record.
   - A trailing – means continue from column 1 of the next record.
   - A trailing + means continue from the first non-blank column of the next record.
   - The maximum number of characters permitted in a command is 32762.

   With the additional rule:

   - A semicolon (;) can be used to terminate a command, the remaining data in the record is ignored.

3. If you specify the MAKEDEF keyword:
   - In the input data set, the DISPLAY commands for objects must contain the ALL parameter so that the complete definition of each object is produced. See Figure 76 on page 246.
   - To obtain a complete definition, you must DISPLAY the following:

     Queues
     Namelists
     Process definitions
     Channels
     Storage classes

     Note: DEFINE commands are not generated for any local queues that can be identified as dynamic, or for channels that were defined automatically.
   - Do not specify the same MAKEDEF data set for more than one COMMAND function, unless its DD statement specifies a sequential data set with DISP=MOD.
4. Whether or not the MAKEDEF or MAKECLNT keywords are used, the results of these DISPLAY commands are also sent to SYSPRINT.
5. If you specify the MAKECLNT keyword:
   - In the input data set, the display commands for channels must contain the ALL parameter so that the complete definition of each channel is produced.
   - If the DISPLAY commands return information for a given channel more than once, only the last set of information is used.
   - Do not specify the same client definition file data set for more than one COMMAND function, unless its DD statement specifies a sequential data set with DISP=MOD.
6. If you specify the FAILURE keyword, a command is considered to execute successfully or not according to the codes returned in message CSQN205I. If the return code is 00000000 and the reason code is 00000000 or 00000004, it is a success; for all other values it is a failure.
7. The COMMAND function is considered to be successful only if both:
   - All the commands in the input data set are read and issued and get a response from MQSeries, regardless of whether the response indicates successful execution of the command or not.
   - Every command issued executes successfully, if FAILURE(CONTINUE) or FAILURE(STOP) is specified.

   If COMMAND fails, no further CSQUTIL functions are attempted.
8. You need the necessary authority to use the command server queues (SYSTEM.COMMAND.INPUT, SYSTEM.COMMAND.REPLY.MODEL, and SYSTEM.CSQUTIL.*) and to use the MQSC commands that you wish to issue.

Producing a list of MQSeries define commands (SDEFS)

Use the SDEFS function to produce a list of DEFINE statements describing the objects in your MQSeries subsystem, when the queue manager is not running.

To use the SDEFS function, DDname CSQP0000 must specify the data set with page set zero for the subsystem required.

Command management (SDEFS)



Keywords and parameters

OBJECT

Specifies the type of object to be listed.

MAKEDEF(*ddname2*)

Specifies that define commands generated for the object are to be placed in the output data set identified by the DDname. The data set should be RECFM=FB, LRECL=80. This data set can then be used as input for a later invocation of the COMMAND function or it can be incorporated into the initialization data sets CSQINP1 and CSQINP2.

Note: DEFINE commands are not generated for any local queues that can be identified as dynamic, or for channels that were defined automatically.

Example

```
//SDEFS   EXEC PGM=CSQUTIL
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//CSQP0000 DD   DISP=OLD,DSN=pageset.dsname0
//OUTPUT1  DD   DISP=OLD,DSN=MY.MQSERIES.COMMANDS(DEFS)
//SYSPRINT DD   SYSOUT=*
//SYSIN    DD   *
SDEFS OBJECT(QUEUE) MAKEDEF(OUTPUT1)
/*
```

Figure 78. Sample JCL for the SDEFS function of CSQUTIL

Usage notes

1. You should not use SDEFS for a queue manager that is running because results will be unpredictable. You can avoid doing this accidentally by using DISP=OLD in the CSQP0000 DD statement.
2. When you use SDEFS, it is not necessary to specify a queue manager name.

3. To use the SDEFS function more than once in a job, specify different DDnames and data sets for each invocation of the function, or specify a sequential data set and DISP=MOD in the DD statements.

Queue management functions

Use the CSQUTIL queue management functions to back up and restore queues and page sets or to copy queues and page sets to another MQSeries system. You can use these functions to reset your MQSeries subsystem or for migrating from one MQSeries subsystem to another.

Specifically, you can:

- Copy messages from a queue to a data set
- Delete messages from a queue
- Restore previously copied messages to their respective queues

The scope of these functions can be either:

- A *queue*, in which case the function operates on all messages in the specified queue.
- A *page set*, in which case the function operates on all the messages, in all the queues, on the specified page set.

You should use these functions only for your own queues; do not use them for system queues (those with names beginning SYSTEM).

Syncpoints

The queue management functions run within a syncpoint so that, if a function fails, its effects can be backed out. The MQSeries entity, MAXSMSGS, specifies the maximum number of messages that a task can get or put within a single unit of recovery. MAXSMSGS should be greater than:

- The number of messages in the queue – if you are working with a single queue.
- The number of messages in the longest queue in the page set – if you are working with an entire page set.

Otherwise, the utility forcibly takes syncpoints as required and issues the warning message CSQU087I. If the function subsequently fails, the already committed changes will not be backed out. Do not simply re-run the job to correct the problem or you might get duplicate messages on your queues. Instead, use the current depth of the queue to work out, from the utility output, which messages have not been backed out. Then determine the most appropriate course of action. For example, you can empty the queue and start again or you can choose to accept duplicate messages on the queues.

Use the DISPLAY QLOCAL command to find out the value of the CURDEPTH attribute, which is the current depth of the queue. To find out the value of MAXSMSGS, use the DISPLAY MAXSMSGS command. See the *MQSeries Command Reference* manual for more information.

Copying queues into a data set while the queue manager is running (COPY)

Use the COPY function to copy queued messages to a sequential data set, when the queue manager is running, without destroying any messages in the original queues.

The scope of the COPY function is determined by the keyword that you specify in the first parameter. You can either copy all the messages from a named queue, or all the messages from all the queues on a named page set.

Use the complementary function, LOAD, to restore the messages to their respective queues.

Note: If you want to copy the object definitions from the named page set, use COPYPAGE. If you want to copy messages to a data set when the queue manager is not running, use SCOPY.



Keywords and parameters

QUEUE(*q-name*)
QUEUE specifies that messages in the named queue are to be copied. The keyword QUEUE can be abbreviated to Q.

q-name specifies the name of the queue to be copied. This name is case-sensitive.

PSID(*psid-number*)
PSID specifies that all the messages in all the queues in the specified page set are to be copied.

psid-number is the page set identifier, which specifies the page set to be used. This identifier is a two-digit integer (whole number) representing a single page set.

DEFTYPE
Specifies whether to copy dynamic queues:

ALL Copy all queues; this is the default.

PREDEFINED Do not include dynamic queues; this is the same set of queues that are selected by the COMMAND and SDEFS functions with the MAKEDEF parameter.

DDNAME
Specifies that the messages are to be copied to a named data set. If this keyword is omitted, the default DDname, CSQUOUT, is used. The keyword DDname can be abbreviated to DD.

ddname specifies the DDname of the destination data set, which is used to store the messages. The record format of this data set must be variable block spanned (VBS).

Example

```
//COPY   EXEC PGM=CSQUTIL,PARM='CSQ1'
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//OUTPUTA  DD DSN=SAMPLE.UTILITY.COPYA,DISP=(NEW,CATLG),
//            SPACE=(CYL,(5,1),RLSE),UNIT=SYSDA,
//            DCB=(RECFM=VBS,BLKSIZE=23200)
//CSQUOUT  DD DSN=SAMPLE.UTILITY.COPY3,DISP=(NEW,CATLG),
//            SPACE=(CYL,(5,1),RLSE),UNIT=SYSDA,
//            DCB=(RECFM=VBS,BLKSIZE=23200)
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
* COPY WHOLE PAGESET TO 'CSQUOUT'
COPY PSID(03)
* COPY ONE QUEUE TO 'OUTPUT'
COPY QUEUE(ABC123A) DDNAME(OUTPUTA)
/*
```

Figure 79. Sample JCL for the CSQUTIL COPY functions. The sample shows two instances of the COPY function—one COPY to the default DDNAME, CSQUOUT; the other to DDNAME OUTPUTA, which overrides CSQUOUT.

Usage notes

1. The queues or page set involved must not be in use when the function is invoked.
2. If you want to operate on a range of page sets, you must repeat the COPY function for each page set.
3. The function operates only on local queues.
4. A COPY PSID function is considered successful only if it successfully copies all the queues on the page set.
5. If you try to copy an empty queue (whether explicitly by COPY QUEUE or because there are one or more empty queues on a page set that you are copying), data indicating this is written to the sequential data set, and the copy is considered to be a success. However, if you attempt to copy a non-existent queue, or a page set containing no queues, the COPY function fails, and no data is written to the data set.
6. If COPY fails, no further CSQUTIL functions will be attempted.
7. To use the COPY function more than once in the job, specify different DDnames and data sets for each invocation of the function, or specify a sequential data set and DISP=MOD in the DD statements.
8. You need the necessary authority to use the command server queues (SYSTEM.COMMAND.INPUT, SYSTEM.COMMAND.REPLY.MODEL, and SYSTEM.CSQUTIL.*), to use the DISPLAY QUEUE and DISPLAY STGCLASS MQSC commands, and to use the MQSeries API to browse messages on the

queues that you wish to copy. See “Syncpoints” on page 251 for information about possible syncpoint restrictions.

Copying queues into a data set while the queue manager is not running (SCOPY)

Use the SCOPY function to copy queued messages to a sequential data set when the queue manager is not running, without destroying any messages in the original queues.

The scope of the SCOPY function is determined by the keyword that you specify in the first parameter. You can either copy all the messages from a named queue, or all the messages from all the queues on a named page set.

Use the complementary function, LOAD, to restore the messages to their respective queues.

To use the SCOPY function, DDname CSQP0000 must specify the data set with page set zero for the subsystem required.



Keywords and parameters

QUEUE(*q-name*)

QUEUE specifies that messages in the named queue are to be copied. The keyword QUEUE can be abbreviated to Q.

q-name specifies the name of the queue to be copied. This name is case-sensitive.

DDname CSQP00*nn* must specify the data set with page set *nn* for the subsystem required, where nn is the number of the page set where the queue resides.

PSID(*psid-number*)

PSID specifies that all the messages in all the queues in the specified page set are to be copied.

psid-number is the page set identifier, which specifies the page set to be used. This identifier is a two-digit integer (whole number) representing a single page set.

DDname CSQP00*psid-number* must specify the data set with the required page set for the subsystem required.

DEFTYPE

Specifies whether to copy dynamic queues:

ALL Copy all queues; this is the default.

PREDEFINED Do not include dynamic queues; this is the same set of queues that are selected by the COMMAND and SDEFS functions with the MAKEDEF parameter.

This parameter is only valid if you specify PSID.

DDNAME

Specifies that the messages are to be copied to a named data set. If this keyword is omitted, the default DDname, CSQUOUT, is used. The keyword DDname can be abbreviated to DD.

ddname specifies the DDname of the destination data set, which is used to store the messages. The record format of this data set must be variable block spanned (VBS).

Do not specify the same DDname on more than one SCOPY statement, unless its DD statement specifies a sequential data set with DISP=MOD.

Example

```
//SCOPY   EXEC PGM=CSQUTIL
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//OUTPUTA  DD DSN=SAMPLE.UTILITY.COPYA,DISP=(NEW,CATLG),
//            SPACE=(CYL,(5,1),RLSE),UNIT=SYSDA,
//            DCB=(RECFM=VBS,BLKSIZE=23200)
//CSQUOUT  DD DSN=SAMPLE.UTILITY.COPY3,DISP=(NEW,CATLG),
//            SPACE=(CYL,(5,1),RLSE),UNIT=SYSDA,
//            DCB=(RECFM=VBS,BLKSIZE=23200)
//CSQP0000 DD DISP=OLD,DSN=pageset.dsname0
//CSQP0003 DD DISP=OLD,DSN=pageset.dsname3
//CSQP0006 DD DISP=OLD,DSN=pageset.dsname6
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
* COPY WHOLE PAGE SET TO 'CSQUOUT'
SCOPY PSID(03)
* COPY ONE QUEUE TO 'OUTPUT' - QUEUE IS ON PAGE SET 6
SCOPY QUEUE(ABC123A) DDNAME(OUTPUTA)
/*
```

Figure 80. Sample JCL for the CSQUTIL SCOPY functions. The sample shows two instances of the SCOPY function—one SCOPY to the default DDNAME, CSQUOUT; the other to DDNAME OUTPUTA, which overrides CSQUOUT.

Usage notes

1. You should not use SCOPY for a queue manager that is running because results will be unpredictable. You can avoid doing this accidentally by using DISP=OLD in the page set DD statement.
2. When you use SCOPY, it is not necessary to specify a queue manager name.
3. If you want to operate on a range of page sets, you must repeat the SCOPY function for each page set.
4. The function operates only on local queues and only for persistent messages.
5. A SCOPY PSID function is considered successful only if it successfully copies all the queues on the page set that have messages; empty queues are ignored. If the page set has no queues with messages, the SCOPY function fails, and no data is written to the data set.
6. If you try to copy an empty queue explicitly by SCOPY QUEUE, data indicating this is written to the sequential data set, and the copy is considered to be a

success. However, if you attempt to copy a non-existent queue, the SCOPY function fails, and no data is written to the data set.

7. If the SCOPY function fails, no further CSQUTIL functions are attempted.
8. To use the SCOPY function more than once in the job, specify different DDnames and data sets for each invocation of the function, or specify a sequential data set and DISP=MOD in the DD statements.

Emptying a queue of all messages (EMPTY)

Use the EMPTY function to delete all messages from a named queue or all the queues on a page set. The queue manager must be running. The scope of the function is determined by the keyword that you specify in the first parameter.

Use this function with care. You should only delete messages of which copies have already been made.



Keywords and parameters

You must specify the scope of the EMPTY function. Choose one of these:

QUEUE(*q-name*)
QUEUE specifies that messages are to be deleted from a named queue. This keyword can be abbreviated to Q.

q-name specifies the name of the queue from which messages are to be deleted. This name is case-sensitive.

PSID(*psid-number*)
PSID specifies that all the messages are to be deleted from all queues in the named page set.

psid-number specifies the page-set identifier. This identifier is a two-digit integer (whole number) representing a single page set.

Example

```
//EMPTY  EXEC PGM=CSQUTIL,PARM=('CSQ1')
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
EMPTY QUEUE(SPARE)
EMPTY PSID(66)
/*
```

Figure 81. Sample JCL for the CSQUTIL EMPTY function

Usage notes

1. The queues or page sets involved must not be in use when the function is invoked.
2. This function operates only on local queues.
3. If you want to operate on a range of page sets, you must repeat the EMPTY function for each page set.
4. You cannot empty the system-command input queue (SYSTEM.COMMAND.INPUT).

5. An EMPTY PSID function is considered successful only if it successfully empties all the queues on the page set.
6. If you empty a queue that is already empty (whether explicitly by EMPTY QUEUE or because there are one or more empty queues on a page set that you are emptying), the EMPTY function is considered to be a success. However, if you attempt to empty a non-existent queue, or a page set containing no queues, the EMPTY function fails.
7. If EMPTY fails or is forced to take a syncpoint, no further CSQUTIL functions will be attempted.
8. You need the necessary authority to use the command server queues (SYSTEM.COMMAND.INPUT, SYSTEM.COMMAND.REPLY.MODEL, and SYSTEM.CSQUTIL.*), to use the DISPLAY QUEUE and DISPLAY STGCLASS MQSC commands, and to use the MQSeries API to get messages from the queues that you wish to empty. See “Syncpoints” on page 251 for information about possible syncpoint restrictions.

Restoring messages from a data set to a queue (LOAD)

The LOAD function of CSQUTIL is complementary to the COPY or SCOPY function. LOAD restores messages from the destination data set of an earlier COPY or SCOPY operation. The queue manager must be running.

The data set can contain messages from one queue only if it was created by COPY or SCOPY QUEUE, or from a number of queues if it was created by COPY PSID or several successive COPY or SCOPY QUEUE operations. Messages are restored to queues with the same name as those from which they were copied. You can specify that the first or only queue is loaded to a queue with a different name. (This would normally be used with a data set created with a single COPY queue operation to restore the messages to a queue with a different name.)



Keywords and parameters

QUEUE(*q-name***)**

QUEUE specifies that the messages from the first or only queue on the destination data set of a prior COPY or SCOPY operation are to be loaded to a named queue. Messages from any subsequent queues are loaded to queues with the same names as those they came from. The keyword QUEUE can be abbreviated to Q.

q-name specifies the name of the queue to which the messages are to be loaded. This name is case-sensitive. It must not be a model queue.

DDNAME(*ddname***)**

DDNAME specifies that messages are to be loaded from a named data set. This keyword can be abbreviated to DD.

ddname specifies the DDname that identifies the destination data set of a prior COPY or SCOPY operation—from which the messages are to be loaded. This name is not case-sensitive, and can be up to eight characters long.

If you omit DDname(*ddname*) the default DDname, CSQUINP, is used.

Example

```
//LOAD   EXEC PGM=CSQUTIL,PARM=('CSQ1')
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//OUTPUTA  DD DSN=MY.UTILITY.OUTPUTA,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
LOAD QUEUE(ABC123) DDNAME(OUTPUTA)
/*
```

Figure 82. Sample JCL for the CSQUTIL LOAD function

Usage notes

1. To use the LOAD function, the queues or page sets involved must not be in use when the function is invoked.
2. If the data set contains multiple queues, the LOAD function is considered successful only if it successfully loads all the queues on the data set.
3. If LOAD fails, or is forced to take a syncpoint, no further CSQUTIL functions will be attempted.
4. You need the necessary authority to use the MQSeries API to put messages on the queues that you wish to load. See “Syncpoints” on page 251 for information about possible syncpoint restrictions.

The change log inventory utility (CSQJU003)

The MQSeries change log inventory utility runs as an OS/390 batch job to change the bootstrap data set (BSDS). If you need more information about the MQSeries logs and the BSDS, see Chapter 17, “Understanding the log and the bootstrap data set” on page 305.

Through this utility, you can invoke these functions:

Function name	*Purpose*
NEWLOG	Add active or archive log data sets.
DELETE	Delete active or archive log data sets.
ARCHIVE	Supply passwords for archive logs.
CRESTART	Control the next restart of MQSeries.
CHECKPT	Set checkpoint records.
HIGHRBA	Update the highest written log RBA.

This utility should be run only when MQSeries is not running. This is because the active log data sets named in the BSDS are dynamically added for exclusive use to MQSeries and remain allocated exclusively to MQSeries until it terminates.

Invoking the CSQJU003 utility

The utility runs as an OS/390 batch program. Figure 83 gives an example of the JCL required.

```
//JU003   EXEC  PGM=CSQJU003
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//SYSPRINT DD  SYSOUT=*,DCB=BLKSIZE=629
//SYSUT1   DD  DISP=SHR,DSN=bsds.dsname
//SYSIN    DD  *
  NEWLOG DSNAME=CSQREPAL.A0001187,COPY1VOL=CSQV04,UNIT=SYSDA,
  STARTRBA=3A190000,ENDRBA=3A1F0000,CATALOG=YES,PASSWORD=SYSNKZX
/*
```

Figure 83. Sample JCL to invoke the CSQJU003 utility

Data definition (DD) statements

CSQJU003 requires DD statements with these DDnames:

SYSUT1
This statement is required; it names the BSDS.

SYSUT2
This statement is required if you use dual BSDSs; it names the second copy of the BSDS.

Dual BSDSs and CSQJU003

Each time you run the CSQJU003 utility, the BSDS time stamp field is updated with the current system time. If you run CSQJU003 separately for each copy of a dual copy BSDS, the time stamp fields are not synchronized so that MQSeries fails at startup, issuing error message CSQJ120E. Therefore, if CSQJU003 is used to update dual copy BSDSs, both BSDSs must be updated within a single run of CSQJU003.

SYSPRINT
This statement is required; it names a data set for print output. The logical record length (LRECL) is 125. The block size (BLKSIZE) must be 629.

SYSIN
This statement is required; it names the input data set for statements that specify what the utility is to do. The logical record length (LRECL) is 80.

You can use more than one statement of each type. In each statement, separate the operation name (NEWLOG, DELETE, ARCHIVE, CRESTART) from the first parameter by one or more blanks. You can use parameters in any order; separate them by commas with no blanks. Do not split a parameter description across two SYSIN records.

A statement containing an asterisk in column 1 is considered to be a comment, and is ignored. However, it appears in the output listing. To include a comment or sequence number in a SYSIN record, separate it from the last comma by a blank. When a blank follows a comma, the rest of the record is ignored.

Multiple statement operation

When running CSQJU003, a significant error in any statement causes the control statements for the statement in error and all following statements to be skipped. Therefore, BSDS updates cannot occur for any operation specified in the statement in error, or any following statements. However, all the remaining statements are checked for syntax errors.

Adding information about a data set to the BSDS (NEWLOG)

The NEWLOG function declares one of these data sets:

- A VSAM data set that is available for use as an active log data set.

  Use the keywords DSNAME=, COPY1, COPY2, and PASSWORD=.

- An active log data set that is replacing one that encountered an I/O error.

  Use the keywords DSNAME=, COPY1, COPY2, STRTRBA=, ENDRBA=, and PASSWORD=.

- An archive log data set volume.

  Use the keywords DSNAME=, COPY1VOL=, COPY2VOL=, STARTRBA=, ENDRBA=, UNIT=, CATALOG=, and PASSWORD=.



Keywords and parameters

DSNAME=*dsname*

Names a log data set. *dsname* can be up to 44 characters long.

PASSWORD=*password*

Assigns a password to the data set. It is stored in the BSDS and subsequently used in any access to the active or archive log data sets.

The password is a data set password, and should follow standard VSAM convention: 1 through 8 alphanumeric characters (A through Z, 0 through 9) or special characters (& * + – . ; ' /).

We recommend that you use an ESM such as RACF to provide your data set security requirements.

COPY1

Makes the data set an active log copy-1 data set.

COPY2

Makes the data set an active log copy-2 data set.

STARTRBA=*startrba*

Gives the log RBA (relative byte address within the log) of the beginning of the replacement active log data set or the archive log data set volume specified by DSNAME. *startrba* is a hexadecimal number of up to 12 characters. If you use fewer than 12 characters, leading zeros are added. The RBA can be obtained from messages or by printing the log map.

ENDRBA=*endrba*
Gives the log RBA (relative byte address within the log) of the end of the replacement active log data set or the archive log data set volume specified by DSNAME. *endrba* is a hexadecimal number of up to 12 characters. If you use fewer than 12 characters, leading zeros are added.

STARTIME=*startime*
Lets you record the start time of the RBA in the BSDS. This is an optional field. The time stamp format (with valid values in parentheses) is as follows:

yyyydddhhmmsst, where:

yyyy Indicates the year (1993 through 2099)
ddd Indicates the day of the year (0 through 365; 366 in leap years)
hh Indicates the hour (0 through 23)
mm Indicates the minutes (0 through 59)
ss Indicates the seconds (0 through 59)
t Indicates tenths of a second

If fewer than 14 digits are specified for the STARTIME and ENDTIME parameter, then trailing zeros will be added.

STARTRBA is required when STARTIME is specified.

ENDTIME=*endtime*
Enables you to record the end time of the RBA in the BSDS. This is an optional field. For time stamp format, see the STARTIME option. The ENDTIME value must be greater than or equal to the value of STARTIME.

COPY1VOL=*vol-id*
The volume serial of the copy-1 archive log data set named after DSNAME.

COPY2VOL=*vol-id*
The volume serial of the copy-2 archive log data set named after DSNAME.

UNIT=*unit-id*
The device type of the archive log data set named after DSNAME.

CATALOG
Tells whether the archive log data set is cataloged:

NO Indicates that the archive log data set is not cataloged. All subsequent allocations of the data set are made using the unit and volume information specified on the function. The default is NO.

YES Indicates that the archive log data set is cataloged. A flag is set in the BSDS indicating this, and all subsequent allocations of the data set are made using the catalog.

MQSeries requires that all archive log data sets on DASD be cataloged. Select CATALOG=YES if the archive log data set is on DASD.

Deleting information about a data set from the BSDS (DELETE)

Use the DELETE function to delete all information about a specified log data set or data set volume from the bootstrap data sets. For example, you can use this function to delete outdated archive log data sets.



Keywords and parameters

DSNAME=*dsname*

Specifies the name of the log data set. *dsname* can be up to 44 characters long.

COPY1VOL=*vol-id*

The volume serial number of the copy-1 archive log data set named after DSNAME.

COPY2VOL=*vol-id*

The volume serial number of the copy-2 archive log data set named after DSNAME.

Supplying a password for archive log data sets (ARCHIVE)

Use the ARCHIVE function to give a password to all archive data sets created after this operation. This password is added to the installation's OS/390 password data set each time a new archive log data set is created.

Use the NOPASSWD keyword to remove the password protection for all archives created after the archive operation.

Note: You should normally use an ESM, such as RACF, if you want to implement security on any MQSeries data sets.

ARCHIVE



Keywords and parameters

PASSWORD=*password*

PASSWORD specifies that a password is to be assigned to the archive log data sets.

password specifies the password, which is a data set password and it must follow the standard VSAM convention; that is, 1 through 8 alphanumeric characters (A through Z, 0 through 9) or special characters (& * + – . ; ' /).

NOPASSWD

Specifies that archive password protection is not to be active for all archives created after this operation. No other keyword can be used with NOPASSWD.

Controlling the next restart (CRESTART)

Use the CRESTART function to control the next restart of MQSeries, either by creating a new conditional restart control record or by cancelling the one currently active. These records limit the scope of the log data that will be used during restart. Any existing conditional restart control record governs every restart until one of these events occurs:

- A restart operation completes
- A CRESTART CANCEL is issued
- A new conditional restart control record is created

Attention: This can override MQSeries efforts to maintain data in a consistent state. You would normally only use this function when implementing the disaster recovery process described in "Preparing for disaster recovery" on page 318, or under the guidance of IBM service.

CRESTART



Keywords and parameters

CREATE

Creates a new conditional restart control record. When the new record is created, the previous control record becomes inactive.

CANCEL

Makes the currently active conditional restart control record inactive. The record remains in the BSDS as historical information.

No other keyword can be used with CANCEL.

ENDRBA=*endrba*

Gives the last RBA of the log to be used during restart, and the starting RBA of the next active log to be written after restart. Any log information in the bootstrap data set and the active logs, with an RBA greater than *endrba*, is discarded. If you omit this option, MQSeries determines the end of the log range.

endrba is a hexadecimal number of up to 12 digits. If you use fewer than 12 digits, leading zeros are added.

The value of ENDRBA must be a multiple of 4096. (The hexadecimal value must end in 000.)

Setting checkpoint records (CHECKPT)

Use the CHECKPT function to add or delete a record in the BSDS checkpoint queue. Use the STARTRBA and ENDRBA keywords to add a record, or the STARTRBA and CANCEL keywords to delete a record.

Attention: This can override MQSeries efforts to maintain data in a consistent state. You would normally only use this function when implementing the disaster recovery process described in "Preparing for disaster recovery" on page 318, or under the guidance of IBM service.

CHECKPT



Keywords and parameters

STARTRBA=*startrba*

Indicates the start checkpoint log record.

startrba is a hexadecimal number of up to 12 digits. If you use fewer than 12 digits, leading zeros are added. The RBA can be obtained from messages or by printing the log map.

ENDRBA=*endrba*

Indicates the end checkpoint log record corresponding to the start checkpoint record.

endrba is a hexadecimal number of up to 12 digits. If you use fewer than 12 digits, leading zeros are added. The RBA can be obtained from messages or by printing the log map.

TIME=*time*

Gives the time the start checkpoint record was written. The time stamp format (with valid values in parentheses) is as follows:

yyyydddhhmmsst, where:

yyyy	Indicates the year (1993 through 2099)
ddd	Indicates the day of the year (0 through 365; 366 in leap years)
hh	Indicates the hour (0 through 23)
mm	Indicates the minutes (0 through 59)
ss	Indicates the seconds (0 through 59)
t	Indicates tenths of a second

If fewer than 14 digits are specified for the TIME parameter, then trailing zeros are added.

CANCEL

Deletes the checkpoint queue record containing a starting RBA that matches the RBA specified by STARTRBA.

Updating the highest written log RBA (HIGHRBA)

Use the HIGHRBA function to update the highest written log RBA recorded in the BSDS for either the active or archive log data sets. Use the STARTRBA keyword to update the active log, and the OFFLRBA keyword to update the archive log.

Attention: This can override MQSeries efforts to maintain data in a consistent state. You would normally only use this function when implementing the disaster recovery process described in "Preparing for disaster recovery" on page 318, or under the guidance of IBM service.

HIGHRBA



Keywords and parameters

STARTRBA=*startrba*

Indicates the log RBA of the highest written log record in the active log data set.

startrba is a hexadecimal number of up to 12 digits. If you use fewer than 12 digits, leading zeros are added. The RBA can be obtained from messages or by printing the log map.

TIME=*time*

Specifies when the log record with the highest RBA was written to the log. The time stamp format (with valid values in parentheses) is as follows:

yyyydddhhmmsst, where:

yyyy	Indicates the year (1993 through 2099)
ddd	Indicates the day of the year (0 through 365; 366 in leap years)
hh	Indicates the hour (0 through 23)
mm	Indicates the minutes (0 through 59)
ss	Indicates the seconds (0 through 59)
t	Indicates tenths of a second

If fewer than 14 digits are specified for the TIME parameter, then trailing zeros will be added.

OFFLRBA=*offlrba*

Specifies the highest offloaded RBA in the archive log.

offlrba is a hexadecimal number of up to 12 digits. If you use fewer than 12 digits, leading zeros are added. The value must end with hexadecimal `'FFF'`.

The print log map utility (CSQJU004)

The MQSeries print log map utility runs as an OS/390 batch program to list this information:

- Log data set name and log RBA association for both copies of all active and archive log data sets
- Active log data sets available for new log data
- Contents of the queue of checkpoint records in the bootstrap data set (BSDS)
- Contents of the quiesce history record
- System and utility time stamps
- Passwords for the active and archive log data sets, if provided

The CSQJU004 program can be run regardless of whether MQSeries is running. However, if MQSeries is running, consistent results from the utility can be ensured only if both the utility and the MQSeries subsystem are running under control of the same OS/390 system.

To use this utility, the user ID of the job must have the requisite security authorization, or, if the BSDS is password protected, the appropriate VSAM password for the data set.

Invoking the CSQJU004 utility

Figure 84 shows an example of the JCL used to invoke the CSQJU004 utility:

```
//JU004   EXEC  PGM=CSQJU004
//STEPLIB  DD   DISP=SHR,DSN=thlqual.SCSQANLE
//         DD   DISP=SHR,DSN=thlqual.SCSQAUTH
//SYSPRINT DD  SYSOUT=*,DCB=BLKSIZE=629
//SYSUT1   DD  DISP=SHR,DSN=bsds.dsname
```

Figure 84. Sample JCL to invoke the CSQJU004 utility

Data definition statements

The CSQJU004 utility requires DD statements with the following DDnames:

SYSUT1 This statement is required to specify and allocate the bootstrap data set. If the BSDS must be shared with a concurrently executing MQSeries online subsystem, use DISP=SHR on the DD statement.

SYSPRINT
This statement is required to specify a data set or print spool class for print output. The logical record length (LRECL) is 125. The block size (BLKSIZE) must be 629.

“Finding out what the BSDS contains” on page 325 describes the output.

The log print utility (CSQ1LOGP)

You can use this utility to print information contained in the logs or the BSDS.

Invoking the CSQ1LOGP utility

You run the MQSeries log print utility as an OS/390 batch program. You can specify:

- A bootstrap data set (BSDS)
- Active logs (with no BSDS)
- Archive logs (with no BSDS)

Sample JCL to invoke the CSQ1LOGP utility is shown in figures 85, 86, and 87.

These DD statements should be provided:

SYSPRINT
All error messages, exception conditions and the detail report are written to this data set. The logical record length (LRECL) is 131.

SYSIN
Input selection criteria can be specified in this data set (see "Input control parameters" on page 273 for more information).

SYSSUMRY
If a summary report is requested, the output is written to this data set. The logical record length (LRECL) is 131.

BSDS
Name of the bootstrap data set (BSDS).

ACTIVEn
Name of an active log data set you want to print (n=number).

ARCHIVE
Name of an archive log data set you want to print.

Note: The utility will not run if MQSeries is active and you are trying to process active logs (using a BSDS or the active logs directly).

```
//PRTLOG EXEC PGM=CSQ1LOGP
//STEPLIB  DD DISP=SHR,DSN=thlqual.SCSQANLE
//         DD DISP=SHR,DSN=thlqual.SCSQLOAD
//BSDS     DD DSN=bsds.dsname,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSSUMRY DD SYSOUT=*
//SYSIN    DD *
  insert your input control statements here
/*
```

Figure 85. Sample JCL to invoke the CSQ1LOGP utility using a BSDS

```
//PRTLOG  EXEC PGM=CSQ1LOGP
//STEPLIB  DD DISP=SHR,DSN=thlqual.SCSQANLE
//         DD DISP=SHR,DSN=thlqual.SCSQLOAD
//ACTIVE1  DD DSN=bsds.logcopy1.ds01,DISP=SHR
//ACTIVE2  DD DSN=bsds.logcopy1.ds02,DISP=SHR
//ACTIVE3  DD DSN=bsds.logcopy1.ds03,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSSUMRY DD SYSOUT=*
//SYSIN DD *
  insert your input control statements here
/*
```

Figure 86. Sample JCL to invoke the CSQ1LOGP utility using active log data sets

```
//PRTLOG  EXEC PGM=CSQ1LOGP
//STEPLIB  DD DISP=SHR,DSN=thlqual.SCSQANLE
//         DD DISP=SHR,DSN=thlqual.SCSQLOAD
//ARCHIVE  DD DSN=bsds.archive1.ds01,DISP=SHR
//         DD DSN=bsds.archive1.ds02,DISP=SHR
//         DD DSN=bsds.archive1.ds03,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSSUMRY DD SYSOUT=*
//SYSIN    DD *
  insert your input control statements here
/*
```

Figure 87. Sample JCL to invoke the CSQ1LOGP utility using archive logs

Input control parameters

The keywords that you can use in the SYSIN data set are described below:

RBASTART(hexadecimal-constant)
Specifies the log RBA from which to begin processing. If you are using a BSDS, this parameter must be specified.

Normally you are only interested in the most recent additions to the log. Therefore, do not specify a value of zero. If you do, you create an enormous amount of data, most of which is of no interest to you.

You can also use the forms STARTRBA or ST. Specify this keyword only once.

RBAEND(hexadecimal-constant)
Specifies the last valid log RBA that is to be processed. If this keyword is omitted, processing continues to the end of the log (FFFFFFFFFFFF).

You can also use the forms ENDRBA or EN. Specify this keyword only once.

PAGESET(decimal-integer)
Specifies a page-set identifier. The number should be in the range 00 through 99. Only log records associated with the page set you specify will be processed.

URID (hexadecimal-constant)
Specifies a hexadecimal unit of recovery identifier. Changes to data occur in the context of an MQSeries unit of recovery. A unit of recovery is identified on the log via a BEGIN UR record. The log RBA of that BEGIN UR record is the URID value you must use. If you know the URID for a given UR that you are interested in, you can limit the extraction of information from the MQSeries log to that URID.

The hexadecimal-constant can consist of 1 through 12 characters (6 bytes), and leading zeros are not required.

You can specify a maximum of 10 URID keywords in any given CSQ1LOGP job. To narrow the search, you can specify URID keywords in a job that contains other keywords.

RM (resource_manager)
Specifies a particular resource manager. Only records associated with this resource manager will be processed. Valid values for this keyword are:

- RECOVERY
- DATA
- BUFFER

SUMMARY(YES|NO|ONLY)
Specifies whether a summary report is to be produced or not:

YES Produce a summary report in addition to the detail report.
NO Do not produce a summary report.
ONLY Produce only a summary report (no detail report).

Output

The detail report begins by echoing the input selection criteria specified via SYSIN, and then prints each valid log record encountered. Definitions of keywords in the detail report are as follows:

RM Resource manager that wrote the log record.
TYPE Type of log record.
URID BEGIN UR for this unit of recovery, see the description above.
LRID Logical record identifier in the form:

AAAAAAAA.BBBBBBCC

where:

AAAAAAAA Is the page set number.

BBBBBB Is the relative page number in the page set.

CC Is the relative record number on the page.

SUBTYPE Subtype of the log record type.
CHANGE LENGTH Length of the logged change.
CHANGE OFFSET Start position of the change.
BACKWARD CHAIN Pointer to the previous page.
FORWARD CHAIN Pointer to the next page.
RECORD LENGTH Length of the inserted record.

Part 6. Backup, recovery, and restart

Chapter 15. Introducing some recovery concepts 279
How changes are made to data 279
Units of recovery 279
Backing out work 280
How consistency is maintained 281
Consistency with CICS or IMS 281
How consistency is maintained after an abnormal termination 283

Chapter 16. Understanding termination and restart 285
What happens during termination 285
Normal termination 285
Abnormal termination 286
Connections and threads 286
Active threads 286
In-doubt threads 287
What happens during restart and recovery 287
Rebuilding queue indexes 288
How in-doubt units of recovery are resolved 289
How in-doubt units of recovery are resolved from CICS 289
How in-doubt units of recovery are resolved from IMS 290
How in-doubt units of recovery are resolved from RRS 291
Recovering CICS units of recovery manually 292
Recovering IMS units of recovery manually 294
Recovery procedure 294
Recovering RRS units of recovery manually 296
What happens when the CICS adapter restarts 297
What happens when the IMS adapter restarts 299
Using the OS/390 Automatic Restart Manager (ARM) 300
ARM couple data sets 300
ARM policies 301
Registering with ARM 302
Using ARM in an MQSeries network 302

Chapter 17. Understanding the log and the bootstrap data set 305
What logs are 305
Archiving 305
Dual logging 306
Log data 306
Unit-of-recovery log records 307
Checkpoint records 307
Page set control records 307
How the log is structured 307
How the logs are written 308
When the active log is written 309
When the archive log is written 309
What the bootstrap data set is for 311
Managing the logs and BSDS 312

Chapter 18. Planning for backup and recovery 313
Introduction 313

© Copyright IBM Corp. 1993,1999

General tips for backup and recovery . . . 313
Periodically take backup copies . . . 314
Do not discard archive logs you might need . . . 315
Do not change the DDname-to-page set association . . . 315
Planning your logging environment . . . 315
Use dual logging for your active log, archive log, and bootstrap data sets 315
Planning your archive storage . . . 316
Archiving to tape . . . 316
Archiving to DASD volumes . . . 316
Using SMS with archive log data sets . . . 317
Other recovery considerations . . . 317
Backup and recovery with DFHSM . . . 317
MQSeries recovery and CICS . . . 318
MQSeries recovery and IMS . . . 318
Using Extended Recovery Facility . . . 318
Preparing for disaster recovery . . . 318

Chapter 19. Managing the logs and the bootstrap data set . . . 321
Archiving logs with the ARCHIVE LOG command . . . 321
Discarding archive log data sets . . . 323
Automatic archive log data set deletion . . . 323
Manually deleting archive log data sets . . . 324
Printing log records . . . 325
Finding out what the BSDS contains . . . 325
Changing the BSDS . . . 327
BSDS recovery . . . 330
Recovering logs . . . 332

Chapter 20. Managing page sets . . . 333
Adding a page set to a queue manager . . . 333
When one of your page sets becomes full . . . 333
How to expand a page set . . . 334
How to balance loads on page sets . . . 335
Load balancing by moving queues . . . 336
How to reduce a page set . . . 338
Backing up and recovering page sets . . . 339
Creating a point of recovery . . . 339
Recovering page sets . . . 341
Backing up and restoring queues using CSQUTIL . . . 343

Chapter 21. Example recovery scenarios . . . 345
Active log problems . . . 346
CSQJ004I, dual logging is lost . . . 346
CSQJ030E, active log stopped . . . 347
CSQJ102E and CSQJ232E, one or both copies of the active log data set are damaged . . . 348
CSQJ105E, write I/O errors on an active log data set . . . 349
CSQJ106E, I/O errors occur while reading the active log . . . 349
CSQJ110E and CSQJ111A, active log is full or is becoming full . . . 351
Archive log problems . . . 353
CSQJ103E, allocation problems . . . 353
CSQJ128E, off-load task terminated abnormally . . . 353
CSQJ128E, insufficient DASD space to complete off-load processing . . . 354
Read I/O errors on the archive data set while MQSeries is restarting . . . 355

BSDS errors 356
CSQJ100E, error occurs while opening the BSDS 356
CSQJ102E, log content does not agree with the BSDS information 357
CSQJ107E, CSQJ117E, and CSQJ119E, both copies of the BSDS are damaged 357
CSQJ120E, unequal time stamps 358
CSQJ122E, out of synchronization 359
CSQJ126E, I/O error 359
Page set problems 361
CSQP004E, page set I/O errors 361
Page set full 362
Dealing with long running units of work 363
CSQR020I, old unit of work found 363
IMS-related problems 364
CSQQ001I, CSQQ002E through CSQQ007E, IMS is unable to connect to MQSeries 364
DFS555I message, IMS application problem 364
IMS is not operational 365
Hardware errors 366
Restarting if you have lost your log data sets 367
Performing a cold start of MQSeries 368

Chapter 15. Introducing some recovery concepts

This chapter describes the background concepts of recovery and restart, which you must understand before reading the other chapters in this part of the book.

The chapter contains the following sections:

- "How changes are made to data"
- "How consistency is maintained" on page 281

How changes are made to data

MQSeries must interact with other subsystems to keep all the data consistent. This section discusses *units of recovery*; what they are and how they are used in *back outs*.

Units of recovery

A *unit of recovery* is the processing done by a single MQSeries subsystem for an application program, that changes MQSeries data from one point of consistency to another. A *point of consistency* – also called a *syncpoint* or *commit point* – is a point in time when all the recoverable data that an application program accesses is consistent.



Figure 88. A unit of recovery within an application program. Typically, the unit of recovery consists of more than one MQI call. More than one unit of recovery can occur within an application program.

A unit of recovery begins with the first change to the data after the beginning of the program or following the previous point of consistency; it ends with a later point of consistency. Figure 88 shows the relationship between units of recovery, the point of consistency, and an application program. In this example, the application program makes changes to queues through MQI calls 1 and 2. The application program can include more than one unit of recovery or just one. However, any complete unit of recovery ends in a commit point.

© Copyright IBM Corp. 1993,1999

For example, a bank transaction transfers funds from one account to another. First, the program subtracts the amount from the first account, account A. Then, it adds the amount to the second account, B. After subtracting the amount from A, the two accounts are inconsistent and MQSeries cannot commit. They become consistent when the amount is added to account B. When both steps are complete, the program can announce a point of consistency through a commit, making the changes visible to other application programs.

Normal termination of an application program automatically causes a point of consistency. Some program requests in CICS and IMS programs also cause a point of consistency, for example, EXEC CICS SYNCPOINT.

Backing out work

If an error occurs within a unit of recovery, MQSeries removes any changes to data, returning the data to its state at the start of the unit of recovery; that is, MQSeries backs out the work. The events are shown in Figure 89.



Figure 89. A unit of recovery showing back out

How consistency is maintained

If data in an MQSeries subsystem is to be consistent with batch, CICS, IMS, or TSO, any data changed in one must be matched by a change in the other. Before one system commits the changed data, it must know that the other system can make the corresponding change. So, the systems must communicate.

During a *two-phase commit* (for example under CICS), one subsystem coordinates the process. That subsystem is called the *coordinator*; the other is the *participant*. CICS or IMS is always the coordinator in interactions with MQSeries, and MQSeries is always the participant. In the batch or TSO environment, MQSeries can participate in two-phase commit protocols coordinated by OS/390 RRS.

During a *single-phase commit* (for example under TSO or batch), MQSeries is always the coordinator in the interactions and completely controls the commit process.

Consistency with CICS or IMS

The CICS–MQSeries connection supports the following syncpoint protocols:

- Two-phase commit – for transactions that update resources owned by more than one resource manager.

  This is the standard distributed syncpoint protocol. It involves more logging and message flows than a single-phase commit.

- Single-phase commit – for transactions that update resources owned by a single resource manager.

  This protocol is optimized for logging and message flows.

- Bypass of syncpoint – for transactions that involve MQSeries but which do nothing in the queue manager that requires a syncpoint.

In each case, CICS acts as the syncpoint manager.

The stages of the two-phase commit that MQSeries uses to communicate with CICS or IMS are:

1. In phase 1 each system determines independently whether it has recorded enough recovery information in its log, and can commit its work.

At the end of the phase, the systems communicate. If they agree, each begins the next phase.

2. In phase 2, the changes are made permanent. If one of the systems abends during phase 2, the operation is completed by the recovery process during restart.

Illustration of the two-phase commit process

Figure 90 illustrates the two-phase commit process. Events in the CICS or IMS coordinator are shown on the upper line, events in MQSeries on the lower line.



Figure 90. The two-phase commit process

The numbers in the following discussion are linked to those in the figure.

1. The data in the coordinator is at a point of consistency.
2. An application program in the coordinator calls MQSeries to update a queue by adding a message.
3. This starts a unit of recovery in MQSeries.
4. Processing continues in the coordinator until an application synchronization point is reached.
5. The coordinator then starts commit processing. CICS programs use a SYNCPOINT command or a normal application termination to start the commit. IMS programs can start the commit by using a CHKP call, a SYNC call, a GET UNIQUE call to the IOPCB, or a normal application termination. Phase 1 of commit processing begins.
6. As the coordinator begins phase 1 processing, so does MQSeries.
7. MQSeries successfully completes phase 1, writes this fact in its log, and notifies the coordinator.
8. The coordinator receives the notification.

9. The coordinator successfully completes its phase 1 processing. Now both subsystems agree to commit the data changes, because both have completed phase 1 and could recover from any errors. The coordinator records in its log the instant of commit – the irrevocable decision of the two subsystems to make the changes.

   The coordinator now begins phase 2 of the processing – the actual commitment.

10. The coordinator notifies MQSeries to begin its phase 2.
11. MQSeries logs the start of phase 2.
12. Phase 2 is successfully completed, and this is now a new point of consistency for MQSeries. MQSeries then notifies the coordinator that it has finished its phase 2 processing.
13. The coordinator finishes its phase 2 processing. The data controlled by both subsystems is now consistent and available to other applications.

There are occasions when CICS or IMS invokes MQSeries when no MQSeries resource has been altered since the completion of the last commit process. This can happen, for example, when a SYNCPOINT request is issued after a series of commands have been processed, or when end-of-task is reached immediately after a SYNCPOINT request has been issued. When this occurs, the MQSeries subsystem performs both phases of the two-phase commit during the first commit phase, and records that the user or job is read-only in relation to its MQSeries processing.

How consistency is maintained after an abnormal termination

When MQSeries is restarted after an abnormal termination, it must determine whether to commit or to back out units of recovery that were active at the time of termination. For certain units of recovery, MQSeries has enough information to make the decision. For others, it does not, and must get information from the coordinator when the connection is reestablished.

Figure 90 shows four periods within the two phases: a, b, c, and d. The status of a unit of recovery depends on the period in which termination happened. The status can be:

In-flight
: MQSeries ended before finishing phase 1 (period a or b); during restart, MQSeries backs out the updates.

In-doubt
: MQSeries ended after finishing phase 1 and before starting phase 2 (period c); only the coordinator knows whether the error happened before or after the commit (point 9). If it happened before, MQSeries must back out its changes; if it happened after, MQSeries must make its changes and commit them. At restart, MQSeries waits for information from the coordinator before processing this unit of recovery.

In-commit
: MQSeries ended after it began its own phase 2 processing (period d); it makes committed changes.

In-backout
: MQSeries ended after a unit of recovery began to be backed out but before the process was complete (not shown in the figure); during restart, MQSeries continues to back out the changes.

Maintaining consistency

Chapter 16. Understanding termination and restart

This chapter describes what happens when MQSeries terminates abnormally, and how to start it again. It contains the following sections:

- "What happens during termination"
- "Connections and threads" on page 286
- "What happens during restart and recovery" on page 287
- "How in-doubt units of recovery are resolved" on page 289
- "Recovering CICS units of recovery manually" on page 292
- "Recovering IMS units of recovery manually" on page 294
- "Recovering RRS units of recovery manually" on page 296
- "What happens when the CICS adapter restarts" on page 297
- "What happens when the IMS adapter restarts" on page 299
- "Using the OS/390 Automatic Restart Manager (ARM)" on page 300

More information about restarting MQSeries is available in:

- "Restarting if you have lost your log data sets" on page 367
- "Performing a cold start of MQSeries" on page 368

What happens during termination

MQSeries terminates normally in response to the command STOP QMGR. If MQSeries stops for any other reason, the termination is considered to be abnormal.

Normal termination

In a normal termination, MQSeries stops all activity in an orderly way. You can use either STOP QMGR MODE(QUIESCE), STOP QMGR MODE(FORCE), or STOP QMGR MODE(RESTART). The effects are given in Table 20:

Table 20. Termination using QUIESCE, FORCE, and RESTART

Thread type	QUIESCE	FORCE	RESTART
Active threads	Run to completion	Back out	Back out
New threads	Can start	Not permitted	Not permitted
New connections	Not permitted	Not permitted	Not permitted
Deregister from ARM[1]	Yes	Yes	No

Note:

1. See "Using the OS/390 Automatic Restart Manager (ARM)" on page 300 for more information.

Batch applications are notified if a termination occurs while the application is still connected.

With CICS, a current thread runs only to the end of the unit of recovery. With CICS, STOP QMGR MODE(QUIESCE) stops the CICS adapter, and so if an active task contains more than one unit of recovery, the task does not necessarily run to completion.

© Copyright IBM Corp. 1993,1999

When you issue the STOP QMGR MODE(FORCE) or MODE(RESTART) command, no new threads are allocated, and work on connected threads is rolled back. Using these modes can create in-doubt units of recovery for threads that are between commit processing phases. They are resolved when MQSeries is reconnected with the controlling CICS, IMS, or RRS subsystem.

When you stop MQSeries, in any mode, the steps are:

- Connections are ended.
- MQSeries ceases to accept commands.
- MQSeries ensures that any outstanding updates to the page sets are completed.
- The DISPLAY USAGE command is issued internally by MQSeries so that the restart RBA is recorded on the OS/390 console log.
- The shutdown checkpoint is taken and the BSDS is updated.

Terminations that specify MODE (QUIESCE) do not affect in-doubt units of recovery. Any unit that is in doubt remains in doubt.

Abnormal termination

An abnormal termination can leave data in an inconsistent state, for example:

- A unit of recovery has been interrupted before reaching a point of consistency.
- Committed data has not been written to page sets.
- Uncommitted data has been written to page sets.
- An application program has been interrupted between phase 1 and phase 2 of the commit process, leaving the unit of recovery in doubt.

Note: MQSeries resolves any data inconsistencies arising from abnormal termination during restart and recovery.

Connections and threads

You can use the DISPLAY THREAD command (described in the *MQSeries Command Reference* manual) to get information about connections to MQSeries and their associated threads. You can display active threads to see what is currently happening, or to see what needs to be terminated in order to allow MQSeries to shut down. You can display in-doubt threads to help with recovery. Messages CSQV401I through CSQV406I describe the information returned, these are documented in the *MQSeries for OS/390 Messages and Codes* manual.

Active threads

Each current connection (**MQCONN**) to MQSeries is represented by one active thread, but certain connections (such as those by the CICS adapter or the mover) might have additional threads associated with them. Note that the CTHREAD system parameter in CSQ6SYSP (described in “Using CSQ6SYSP” on page 69) controls the number of *connections* (**MQCONN**s), not the number of threads.

In addition to the connection name, the display includes the associated user ID (if known), the number of MQSeries requests made by a thread, and the thread cross-reference identifier. The number of MQSeries requests is generally 0 for

associated threads. The thread cross-reference identifier is shown in character form if possible, but otherwise in hexadecimal; its format depends on the type of connection:

CICS Contains the CICS thread number, transaction name, and task number – see Table 33 on page 399.

IMS Contains the IMS PST region identifier and PSB name – see Table 34 on page 400.

Batch, TSO, and RRS
Contains nulls or blanks.

Mover
Blank for connections. Associated threads contain 'T' (X'E3') or 'XX**' (X'E7E75C5C') at character position 5.

In-doubt threads

An in-doubt thread is one that is in the second pass of the two-phase commit operation. Resources are held in MQSeries on its behalf. External intervention is needed to resolve the status or in-doubt threads. This might only involve starting the recovery coordinator (CICS, IMS, or RRS) or might involve more, as described in the following sections. They might have been in doubt at the last restart, or they might have become in doubt since the last restart.

The display includes the thread cross-reference identifier, which might be needed if manual recovery is necessary.

What happens during restart and recovery

MQSeries uses its recovery log and the bootstrap data set (BSDS) to determine what to recover when it restarts. The BSDS identifies the active and archive log data sets, and the location of the most recent MQSeries checkpoint in the log.

After MQSeries has been initialized, the restart process takes place as follows:

- Log initialization
- Current status rebuild
- Forward log recovery
- Backward log recovery
- Queue index rebuilding

When recovery has been completed:

- Committed changes are reflected in the data.
- In-doubt activity is reflected in the data. However, the data is locked and cannot be used until MQSeries recognizes and acts on the in-doubt decision. (For more information about in-doubt units of recovery, see “How consistency is maintained after an abnormal termination” on page 283.)
- Interrupted in-flight and in-abort changes have been removed from the queues. The messages are consistent and can be used.
- A new checkpoint has been taken.
- New indexes have been built for indexed queues containing persistent messages (see “Rebuilding queue indexes” on page 288).

For an example of the messages that are written to the MQSeries console during restart processing, see “User messages on start-up” on page 198.

Batch applications are not notified when restart occurs *after* the application has requested a connection.

If dual BSDSs are in use, MQSeries checks the consistency of the time stamps in the BSDS:

- If both copies of the BSDS are current, MQSeries tests whether the two time stamps are equal. If they are not, MQSeries issues message CSQJ120E and terminates. This can happen when the two copies of the BSDS are maintained on separate DASD volumes and one of the volumes was restored while MQSeries was stopped. MQSeries detects the situation at restart.

  To recover, copy the BSDS with the latest time stamp to the BSDS on the restored volume. Also recover any active log data sets on the restored volume, by copying the dual copy of the active log data sets onto the restored volume. For more detailed instructions, see “BSDS errors” on page 356.
- If one copy of the BSDS was deallocated, and logging continued with a single BSDS, a problem could arise. If both copies of the BSDS are maintained on a single volume, and the volume was restored, or if both BSDS copies were restored separately, MQSeries might not detect the restoration. In that case, log records not noted in the BSDS would be unknown to the system.

Rebuilding queue indexes

To increase the speed of **MQGET** operations on a queue where messages are not retrieved sequentially, you can use the INDXTYPE queue attribute. This attribute causes MQSeries to maintain an index of the message or correlation identifiers for all the messages on that queue (as described in the *MQSeries Application Programming Guide*).

When MQSeries is restarted, these indexes are rebuilt for each queue. This only applies to persistent messages; nonpersistent messages are deleted at restart. If your indexed queues contain large numbers of persistent messages, this will increase the time taken to restart MQSeries.

No messages are sent to the OS/390 console while these indexes are being rebuilt.

How in-doubt units of recovery are resolved

If MQSeries loses its connection to CICS, IMS, or RRS, it normally attempts to recover all inconsistent objects at restart. The information needed to resolve in-doubt units of recovery must come from the coordinating system. The next section describes the process of resolution.

How in-doubt units of recovery are resolved from CICS

The resolution of in-doubt units has no effect on CICS resources. CICS is in control of recovery coordination and, when it restarts, automatically commits or backs out each unit, depending on whether there was a log record marking the beginning of the commit. The existence of in-doubt objects does not lock CICS resources while MQSeries is being reconnected.

One of the functions of the CICS adapter is to keep data synchronized between CICS and MQSeries. If MQSeries abends while connected to CICS, it is possible for CICS to commit or back out work without MQSeries being aware of it. When MQSeries restarts, that work is termed *in doubt*.

MQSeries cannot resolve these in-doubt units of recovery (that is, commit or back out the changes made to MQSeries resources) until the connection to CICS is restarted or reconnected.

A process to resolve in-doubt units of recovery is initiated during startup of the CICS adapter. The process starts when the adapter requests a list of in-doubt units of recovery. Then:

- The adapter receives a list of in-doubt units of recovery for this connection ID from MQSeries, and passes them to CICS for resolution.
- CICS compares entries from this list with entries in its own. CICS determines from its own list what action it took for each in-doubt unit of recovery.

Under some circumstances, CICS cannot run the MQSeries process to resolve in-doubt units of recovery. When this happens, MQSeries sends one of these messages:

- CSQC404E
- CSQC405E
- CSQC406E
- CSQC407E

followed by the message CSQC408I.

For details of what these messages mean, see the *MQSeries for OS/390 Messages and Codes* manual.

For all resolved units, MQSeries updates the queues as necessary and releases the corresponding locks. Unresolved units can remain after restart. Resolve them by the methods described in “Recovering CICS units of recovery manually” on page 292.

How in-doubt units of recovery are resolved from IMS

Resolving in-doubt units of recovery in IMS has no effect on DL/I resources. IMS is in control of recovery coordination and, when it restarts, automatically commits or backs out incomplete DL/I work. The decision to commit or back out for online regions (non-fast-path) is on the presence or absence of IMS log record types X'3730' and X'3801' respectively. The existence of in-doubt units of recovery does not imply that DL/I records are locked until MQSeries connects.

During restart, MQSeries makes a list of in-doubt units of recovery. IMS builds its own list of residual recovery entries (RREs). The RREs are logged at IMS checkpoints until all entries are resolved.

When in-doubt units are resolved:

1. If MQSeries recognizes that it has marked an entry for commit and IMS has marked it to be backed out, MQSeries issues message CSQQ010E. MQSeries issues this message for all inconsistencies of this type between MQSeries and IMS.
2. If MQSeries has any remaining in-doubt units, the adapter issues message CSQQ008I.

For all resolved units, MQSeries updates queues as necessary and releases the corresponding locks.

MQSeries maintains locks on in-doubt work that was not resolved. This can cause a backlog in the system if important locks are being held. The connection remains active so you can resolve the IMS RREs. Recover the in-doubt threads by the methods described in “Controlling IMS connections” on page 175.

All in-doubt work should be resolved unless there are software or operating problems, such as with an IMS cold start. In-doubt resolution by the IMS control region takes place in two circumstances:

1. At the start of the connection to MQSeries, during which resolution is done synchronously.
2. When a program abends, during which the resolution is done asynchronously.

How in-doubt units of recovery are resolved from RRS

One of the functions of the RRS adapter is to keep data synchronized between MQSeries and other RRS-participating resource managers. If a failure occurs when MQSeries has completed phase one of the commit and is waiting for a decision from RRS (the commit coordinator), the unit of recovery enters the in-doubt state.

When communication is reestablished between RRS and MQSeries, RRS automatically commits or backs out each unit of recovery, depending on whether there was a log record marking the beginning of the commit. MQSeries cannot resolve these in-doubt units of recovery (that is, commit or back out the changes made to MQSeries resources) until the connection to RRS is reestablished.

Under some circumstances, RRS cannot resolve in-doubt units of recovery. When this happens, MQSeries sends one of the following messages to the OS/390 console:

- CSQ3011I
- CSQ3013I
- CSQ3014I
- CSQ3016I

For details of what these messages mean, see the *MQSeries for OS/390 Messages and Codes* manual.

For all resolved units of recovery, MQSeries updates the queues as necessary and releases the corresponding locks. Unresolved units of recovery can remain after restart. Resolve them by the method described in “Recovering RRS units of recovery manually” on page 296.

Recovering CICS units of recovery manually

If the adapter abends, CICS and MQSeries build in-doubt lists either dynamically or during restart, depending on which subsystem caused the abend.

Note: If you use the DFH£INDB sample program to show units of work, you might find that it does not always show MQSeries ones correctly.

When CICS connects to MQSeries, there might be one or more units of recovery, that have not been resolved.

One of the following messages is sent to the console:

- CSQC404E
- CSQC405E
- CSQC406E
- CSQC407E
- CSQC408I

For details of what these messages mean, see the *MQSeries for OS/390 Messages and Codes* manual.

CICS retains details of units of recovery that were not resolved during connection startup. An entry is purged when it no longer appears on the list presented by MQSeries.

Any units of recovery that CICS cannot resolve must be resolved manually using MQSeries commands. This manual procedure is rarely used within an installation, because it is required only where operational errors or software problems have prevented automatic resolution. *Any inconsistencies found during in-doubt resolution must be investigated.*

To recover the units of recovery:

1. Obtain a list of the units of recovery from MQSeries by issuing the following command:

```
+cpf DISPLAY THREAD(*) TYPE(INDOUBT)
```

   You receive the following messages:

```
CSQV401I +cpf DISPLAY THREAD REPORT FOLLOWS -
CSQV406I +cpf INDOUBT THREADS
NAME     THREAD-XREF  URID  NID
VICIC3   xref                VICIC3.A75E483235A90900
 DISPLAY THREAD REPORT COMPLETE
CSQ9022I +cpf CSQVDT ' DISPLAY THREAD' NORMAL COMPLETION
```

   For CICS connections, the NID consists of the CICS applid and a unique number provided by CICS at the time the syncpoint log entries are written. This unique number is stored in records written to both the CICS system log and the MQSeries log at syncpoint processing time. This value is referred to in CICS as the *recovery token*.

2. Scan the CICS log for entries related to a particular unit of recovery.

   Look for a PREPARE record, for the task-related installation where the recovery token field (JCSRMTKN) equals the value obtained from the network ID. The network ID is supplied by MQSeries in the DISPLAY THREAD command output.

   The PREPARE record in the CICS log for the units of recovery provides the CICS task number. All other entries on the log for this CICS task can be located using this number.

   You can use the CICS journal print utility DFHJUP when scanning the log. For details of using this program, see the *CICS Operations Guide*.

3. Scan the MQSeries log for entries related to a particular unit of recovery.

   To do this, scan the MQSeries log to locate the record with the NID required. Then use the URID from this record to obtain the rest of the log records for this unit of recovery.

   When scanning the MQSeries log, note that the MQSeries startup message CSQJ001I provides the start RBA for this session.

   The print log records program (CSQ1LOGP) can be used for that purpose.

4. If you need to, do in-doubt resolution in MQSeries.

   MQSeries can be directed to take the recovery action for a unit of recovery using an MQSeries RESOLVE INDOUBT command.

   For information about RESOLVE INDOUBT, see the *MQSeries Command Reference* manual.

   To recover all threads associated with *connection-name*, use the NID(⋆) option.

   The command produces one of the following messages showing whether the thread is committed or backed out:

```
CSQV414I +cpf THREAD network-id COMMIT SCHEDULED
CSQV415I +cpf THREAD network-id ABORT SCHEDULED
```

When performing in-doubt resolution, CICS and the adapter are not aware of the commands to MQSeries to commit or back out units of recovery, because only MQSeries resources are affected. However, CICS keeps details about the in-doubt threads that could not be resolved by MQSeries. This information is purged either when the list presented is empty, or when the list does not include a unit of recovery of which CICS has details.

Recovering IMS units of recovery manually

When IMS connects to MQSeries, MQSeries might have one or more in-doubt units of recovery that have not been resolved.

If MQSeries has in-doubt units of recovery that IMS did not resolve, the following message is issued at the IMS master terminal:

```
CSQQ008I  nn units of recovery are still in doubt in queue manager
```

When this message is issued, IMS was either cold-started or it was started with an incomplete log tape. This message can also be issued if MQSeries or IMS terminates abnormally because of a software error or other subsystem failure.

After receiving the CSQQ008I message:

- The connection remains active.
- IMS applications can still access MQSeries resources.
- Some MQSeries resources remain locked out.

If the in-doubt thread is not resolved, IMS message queues can start to build up. If the IMS queues fill to capacity, IMS terminates. Therefore, users must be aware of this potential difficulty and must monitor IMS until the in-doubt units of recovery are fully resolved.

Recovery procedure

Use the following procedure to recover the IMS units of work:

1. Force the IMS log closed, using /SWI OLDS, and then archive the IMS log. Use the utility, DFSERA10, to print the records from the previous IMS log tape. Type X'3730' log records indicate a phase-2 commit request and type X'38' log records indicate an abort request. Record the requested action for the last transaction in each dependent region.
2. Run the DL/I batch job to back out each PSB involved that has not reached a commit point. The process might take some time because transactions are still being processed. It might also lock up a number of records, which could impact the rest of the processing and the rest of the message queues.
3. Produce a list of the in-doubt units of recovery from MQSeries by issuing the following command:

   ```
   DISPLAY THREAD(*) TYPE(INDOUBT)
   ```

You receive the following messages:

```
CSQV401I +cpf DISPLAY THREAD REPORT FOLLOWS -
CSQV406I +cpf INDOUBT THREADS -
NAME     THREAD-XREF    URID  NID
name     xref                 network-id
name     xref                 network-id
 DISPLAY THREAD REPORT COMPLETE
CSQ9022I +cpf CSQVDT ' DISPLAY THREAD' NORMAL COMPLETION
```

For IMS, the NID consists of the IMS connection name and a unique number provided by IMS. The value is referred to in IMS as the *recovery token*. For more information, see the *IMS Customization Guide*.

4. Compare the NIDs (IMSID plus OASN in hexadecimal) displayed in the DISPLAY THREAD messages with the OASNs (4 bytes decimal) shown in the DFSERA10 output. Decide whether to commit or back out.
5. Perform in-doubt resolution in MQSeries with the RESOLVE INDOUBT command, as follows:

```
RESOLVE INDOUBT(connection-name)
       ACTION(COMMIT|BACKOUT)
       NID(network-id)
```

For information about RESOLVE INDOUBT, see the *MQSeries Command Reference* manual.

To recover all threads associated with *connection-name*, use the NID(⋆) option.

The command results in one of the following messages to indicate whether the thread is committed or backed out:

```
CSQV414I   THREAD network-id COMMIT SCHEDULED
CSQV415I   THREAD network-id BACKOUT SCHEDULED
```

When performing in-doubt resolution, IMS and the adapter are not aware of the commands to MQSeries to commit or back out in-doubt units of recovery because only MQSeries resources are affected.

Recovering RRS units of recovery manually

When RRS connects to MQSeries, MQSeries may have one or more in-doubt units of recovery that have not been resolved. If MQSeries has in-doubt units of recovery that RRS did not resolve, one of the following messages is issued at the OS/390 console:

- CSQ3011I
- CSQ3013I
- CSQ3014I
- CSQ3016I

Both MQSeries and RRS provide tools to display information about in-doubt units of recovery, and techniques for manually resolving them.

In MQSeries, use the `DISPLAY THREAD` command to display information about in-doubt MQSeries threads. The output from the command includes RRS unit of recovery IDs for those MQSeries threads that have RRS as a coordinator. This can be used to determine the outcome of the unit of recovery.

Use the MQSeries `RESOLVE INDOUBT` command to resolve the MQSeries in-doubt thread manually. This command can be used to either commit or back out the unit of recovery after you have determined what the correct decision is.

What happens when the CICS adapter restarts

For background information, see Chapter 6, “The MQSeries-CICS adapter” on page 115.

Whenever a connection is broken, the adapter has to go through a *restart phase* during the *reconnect process*. The restart phase resynchronizes resources. Resynchronization between CICS and MQSeries enables *in-doubt units of work* to be identified and resolved.

Resynchronization can be caused by:

- An explicit request from the distributed queuing component
- An implicit request when a connection is made to MQSeries

If the resynchronization is caused by connecting to MQSeries, the sequence of events is:

1. The connection process gets a list of unit of work (UOW) IDs that MQSeries thinks are in doubt.
2. The UOW IDs are displayed on the console in CSQC313I messages.
3. The UOW IDs are passed to CICS.
4. CICS initiates a resynchronization task (CRSY) for each in-doubt UOW ID.
5. The result of the task for each in-doubt UOW is displayed on the console.

You need to check the messages that are displayed during the connect process:

CSQC313I Shows that a UOW is in doubt.

CSQC400I Identifies the UOW and is followed by one of these messages:

- CSQC402I and CSQC403I show that the UOW was resolved successfully (committed or backed out).
- CSQC404E, CSQC405E, CSQC406E, and CSQC407E show that the UOW was not resolved.

CSQC409I Shows that all UOWs were resolved successfully.

CSQC408I Shows that not all UOWs were resolved successfully.

CSQC314I Warns that UOW IDs highlighted with a “*” will not be resolved automatically. These UOWs must be resolved explicitly by the distributed queuing component when it is restarted.

Figure 91 on page 298 shows an example set of restart messages displayed on the OS/390 console.

```
CSQ9022I +cpf CSQYASCP ' START QMGR' NORMAL COMPLETION
+CSQC323I VICIC1 CSQCQCON CONNECT received from TERMID=PB62 TRANID=CKCN
+CSQC303I VICIC1 CSQCCON CSQCSERV loaded. Entry point is 850E8918.
+CSQC313I VICIC1 CSQCCON  UOWID=VICIC1.A6E5A6F0E2178D25 is in doubt
+CSQC313I VICIC1 CSQCCON  UOWID=VICIC1.A6E5A6F055B2AC25 is in doubt
+CSQC313I VICIC1 CSQCCON  UOWID=VICIC1.A6E5A6EFFD60D425 is in doubt
+CSQC313I VICIC1 CSQCCON  UOWID=VICIC1.A6E5A6F07AB56D22 is in doubt
+CSQC307I VICIC1 CSQCCON Successful connection to subsystem VC2
+CSQC472I VICIC1 CSQCSERV Server subtask (TCB address=008BAD18) connect
successful.
+CSQC472I VICIC1 CSQCSERV Server subtask (TCB address=008BAA10) connect
successful.
+CSQC472I VICIC1 CSQCSERV Server subtask (TCB address=008BA708) connect
successful.
+CSQC472I VICIC1 CSQCSERV Server subtask (TCB address=008CAE88) connect
successful.
+CSQC472I VICIC1 CSQCSERV Server subtask (TCB address=008CAB80) connect
successful.
+CSQC472I VICIC1 CSQCSERV Server subtask (TCB address=008CA878) connect
successful.
+CSQC472I VICIC1 CSQCSERV Server subtask (TCB address=008CA570) connect
successful.
+CSQC472I VICIC1 CSQCSERV Server subtask (TCB address=008CA268) connect
successful.
+CSQC403I VICIC1 CSQCTRUE Resolved BACKOUT for
+CSQC400I VICIC1 CSQCTRUE UOWID=VICIC1.A6E5A6F0E2178D25
+CSQC403I VICIC1 CSQCTRUE Resolved BACKOUT for
+CSQC400I VICIC1 CSQCTRUE UOWID=VICIC1.A6E5A6F055B2AC25
+CSQC403I VICIC1 CSQCTRUE Resolved BACKOUT for
+CSQC400I VICIC1 CSQCTRUE UOWID=VICIC1.A6E5A6F07AB56D22
+CSQC403I VICIC1 CSQCTRUE Resolved BACKOUT for
+CSQC400I VICIC1 CSQCTRUE UOWID=VICIC1.A6E5A6EFFD60D425
+CSQC409I VICIC1 CSQCTRUE Resynchronization completed successfully
```

Figure 91. Example restart messages

The total number of CSQC313I messages should equal the total number of CSQC402I plus CSQC403I messages. If the totals are not equal, there are UOWs that the connection process cannot resolve. Those UOWs that cannot be resolved are caused by problems with CICS (for example, a cold start) or with MQSeries, or by distributing queuing. When these problems have been fixed, you can initiate another resynchronization by disconnecting and then reconnecting.

Alternatively, you can resolve each outstanding UOW yourself using the MQSeries RESOLVE INDOUBT command and the UOW ID shown in message CSQC400I. You must then initiate a disconnect and a connect to clean up the *unit of recovery descriptors* in CICS. You need to know the correct outcome of the UOW to resolve UOWs manually. See also “Recovering CICS units of recovery manually” on page 292.

All messages that are associated with unresolved UOWs are locked by MQSeries and no Batch, TSO, or CICS task can access them.

Note: If CICS fails and an emergency restart is necessary, *do not* vary the GENERIC APPLID of the CICS system. If you do and then reconnect to MQSeries, data integrity with MQSeries cannot be guaranteed. This is because MQSeries treats the new instance of CICS as a different CICS (because the APPLID is different). In-doubt resolution is then based on the wrong CICS log.

Similarly, if MQSeries fails, do not change the subsystem ID of the MQSeries system.

What happens when the IMS adapter restarts

For background information, see Chapter 9, “The MQSeries-IMS adapter” on page 165.

Whenever the connection to MQSeries is restarted, either following an MQSeries restart, or an IMS /START SUBSYS command, IMS initiates the following resynchronization process:

1. IMS presents the list of unit of work (UOW) IDs that it believes are in doubt to the MQSeries IMS adapter one at a time with a resolution parameter of Commit or Backout.
2. The IMS adapter passes the resolution request to MQSeries and reports the result back to IMS.
3. Having processed all the IMS resolution requests, the IMS adapter gets from MQSeries a list of all UOWs that MQSeries still holds in doubt that were initiated by the IMS system. These are reported to the IMS master terminal in message CSQQ008I.

   See “Recovering IMS units of recovery manually” on page 294 for information about recovering these UOWs.

Note: While a UOW is in doubt, any associated MQSeries message is locked by MQSeries and is not available to any application.

Using the OS/390 Automatic Restart Manager (ARM)

The OS/390 Automatic Restart Manager (ARM) is an OS/390 recovery function that can improve the availability of your MQSeries subsystems. When a job or task fails, or the system on which it is running fails, ARM can restart the job or task without operator intervention.

If a queue manager or a channel initiator has failed, ARM restarts it on the same OS/390 image. If OS/390, and hence a whole group of related subsystems and applications have failed, ARM can restart all the failed systems automatically, in a predefined order, on another OS/390 image within the sysplex. This is called a cross-system restart.

The channel initiator should be restarted by ARM only in exceptional circumstances. If the queue manager is restarted by ARM, the channel initiator should be restarted from the CSQINP2 initialization data set (see “Using ARM in an MQSeries network” on page 302).

You can use ARM to restart an MQSeries subsystem that uses LU 6.2 communication protocols on a different OS/390 image within the sysplex in the event of OS/390 failure. (You cannot do this if you use TCP/IP communication protocols.) The network implications of MQSeries ARM restart on a different OS/390 image are discussed in “Using ARM in an MQSeries network” on page 302.

To enable automatic restart:

- You must set up an ARM couple data set.
- You must define the automatic restart actions that you want OS/390 to perform in an *ARM policy*.
- You must start the ARM policy.

Also, MQSeries must register with ARM at startup (this happens automatically).

Note: If you want to restart queue managers in different OS/390 images automatically, every queue manager must be defined as a subsystem in each OS/390 image on which that queue manager might be restarted, with a sysplex wide unique 4-character subsystem name.

ARM couple data sets

You must ensure that you define the couple data sets required for ARM, and that they are online and active before you start any MQSeries subsystem for which you want ARM support. MQSeries automatic ARM registration fails if the couple data sets are not available at MQSeries startup. In this situation, MQSeries assumes that the absence of the couple data set means that you do not want ARM support, and initialization continues.

See the *OS/390 MVS Setting up a Sysplex* manual for information about ARM couple data sets.

ARM policies

ARM functions are controlled by a user-defined *ARM policy*. Each OS/390 image running a queue manager instance that is to be restart ed by ARM must be connected to an ARM couple data set with an active ARM policy.

IBM provides a default ARM policy. You can define new policies, or override the policy defaults by using the *administrative data utility* (IXCMIAPU) provided with OS/390. The *OS/390 MVS Setting up a Sysplex* manual describes this utility, and includes full details of how to define an ARM policy.

Figure 92 shows an example of an ARM policy. This sample policy will restart any MQSeries queue manager within a sysplex, in the event that either the queue manager failed, or a whole system failed.

```
//IXCMIAPU EXEC PGM=IXCMIAPU,REGION=2M
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
  DATA TYPE(ARM)
DEFINE POLICY NAME(ARMPOL1) REPLACE(YES)
 RESTART_GROUP(DEFAULT)
   ELEMENT(*)
     RESTART_ATTEMPTS(0)   /* Jobs not to be restarted by ARM   */
 RESTART_GROUP(GROUP1)
   ELEMENT(SYSMQMGRMQ*)    /* These jobs to be restarted by ARM */
/*
```

Figure 92. Sample ARM policy

Defining an ARM policy

We recommend that you set up your ARM policy as follows:

- Define RESTART_GROUPs for each queue manager instance which also contain any CICS or IMS subsystems that connect to that queue manager instance. If you use a subsystem naming convention, you might be able to use the '?' and '*' wild-card characters in your element names to achieve the above with minimum definition effort.
- Specify TERMTYPE(ELEMTERM) for your channel initiators to indicate that they will be restarted only if the channel initiator has failed and the OS/390 image has not failed.
- Specify TERMTYPE(ALLTERM) for your queue managers to indicate that they will be restarted if either the queue manager has failed or the OS/390 image has failed.
- Specify RESTART_METHOD(BOTH, PERSIST) for both queue managers and channel initiators. This tells ARM to restart using the JCL it saved (after resolution of system symbols) during the last startup. It tells ARM to do this irrespective of whether the individual element failed, or the OS/390 image failed.
- Accept the default values for all the other ARM policy options.

Activating an ARM policy

To start your automatic restart management policy, issue the following OS/390 command:

```
SETXCF START,POLICY,TYPE=ARM,POLNAME=mypol
```

When the policy is started, all systems connected to the ARM couple data set use the same active policy.

Use the SETXCF STOP command to disable automatic restarts.

Registering with ARM

MQSeries registers automatically as an *ARM element* during its startup phase (subject to ARM availability). It deregisters during its shutdown phase, unless requested not to.

At startup, the queue manager determines whether ARM is available. If it is, MQSeries registers using the name SYSMQMGR*ssid*, where *ssid* is the 4-character queue-manager name, and SYSMQMGR is the element type.

The STOP QMGR MODE(QUIESCE) and STOP QMGR MODE(FORCE) MQSeries commands deregister MQSeries from ARM (if it was registered with ARM at startup). This prevents ARM restarting this queue manager. The STOP QMGR MODE(RESTART) command does not deregister the queue manager from ARM. It is thus eligible for immediate automatic restart.

Each MQSeries channel initiator address space determines whether ARM is available, and if so will register with the element name SYSMQCH*ssid*, where *ssid* is the queue manager name, and SYSMQCH is the element type.

The channel initiator is always deregistered from ARM when it stops normally, and remains registered only if it ends abnormally. The channel initiator is always deregistered if the queue manager fails.

Using ARM in an MQSeries network

You should set up your MQSeries system so that the channel initiators and associated listeners are started automatically when MQSeries is restarted. To ensure fully automatic MQSeries restart on the same OS/390 image for both LU 6.2 and TCP/IP communication protocols:

- Start your channel initiator automatically by adding the appropriate START CHINIT command to the CSQINP2 data set.
- Start your listeners automatically by adding the appropriate START LISTENER command to the CSQINPX data set.

See “Task 10: Customize the initialization input data sets” on page 52 for information about the CSQINP2 data set and “Initialization commands for distributed queuing” on page 53 for information about the CSQINPX data set.

Restarting on a different OS/390 image using LU 6.2

If you use only LU 6.2 communication protocols you should also do the following to enable network reconnect after automatic restart of MQSeries on a different OS/390 image within the sysplex:

- Define each MQSeries queue manager within the sysplex with a unique subsystem name.
- Define each channel initiator within the sysplex with a unique LUNAME. This is specified in both the channel initiator parameter module and in the START LISTENER command.

  Note: The LUNAME names an entry in the APPC side table, which in turn maps this to the actual LUNAME.
- Set up a shared APPC side table, which is referenced by each OS/390 image within the sysplex. This should contain an entry for each channel initiator's LUNAME. See the *MVS Planning: APPC/MVS Management* manual for information about this.
- Set up an APPCPM*xx* member of SYS1.PARMLIB for each channel initiator within the sysplex to contain an LUADD to activate the APPC side table entry for that channel initiator. These members should be shared by each OS/390 image. The appropriate SYS1.PARMLIB member is activated by a SET APPC=*xx* OS/390 command which is issued automatically during ARM restart of MQSeries (and its channel initiator) on a different OS/390 image, as described below.
- Use the LU62ARM keyword of the CSQ6CHIP macro to specify the *xx* suffix of this SYS1.PARMLIB member for each channel initiator in the channel initiator parameter module. This will cause the channel initiator to issue the required SET APPC=*xx* OS/390 command to activate its LUNAME.

You should define your ARM policy to restart the channel initiator only if it fails while its OS/390 image stays up. You should not restart the channel initiator automatically if its OS/390 image also fails, but use the CSQINP2 and CSQINPX data sets to start the channel initiator and listeners.

Restarting on a different OS/390 image using TCP/IP

If you are using TCP/IP as your communication protocol, you can reallocate a TCP/IP address after moving MQSeries to a different OS/390 image only if you are using clusters.

OS/390 ARM responds to a system failure by restarting MQSeries on a different OS/390 image in the same sysplex; this system has a different TCP/IP address to the original OS/390 image. The following explains how you can use MQSeries clusters to re-assign a queue manager's TCP/IP address after it has been moved by ARM restart to a different OS/390 image.

When a client queue manager detects the MQSeries for OS/390 failure (as a channel failure), it responds to this by reallocating suitable messages on its cluster transmission queue to a different server queue manager that hosts a different instance of the target cluster queue. However, it cannot reallocate messages that are bound to the original server by affinity constraints, or messages that are in doubt because the server queue manager failed during end-of-batch processing.

In order to process these messages, you need to do the following:

1. Allocate a different cluster-receiver channel name and a different TCP/IP port to each OS/390 queue manager. Each queue manager needs a different port so that two systems can share a single TCP/IP stack on an OS/390 image. One of these is the queue manager originally running on that OS/390 image, and the other is the queue manager that ARM will restart on that OS/390 image following a system failure. You should configure each port on each OS/390 image, so that ARM can restart any queue manager on any OS/390 image.
2. Create a different channel initiator command input file (CSQINPX) for each queue manager and OS/390 image combination, to be referenced during channel initiator startup.

   Each CSQINPX file must include a START LISTENER PORT(port) command specific to that queue manager, and an ALTER CHANNEL command for a cluster-receiver channel specific to that queue manager and OS/390 image combination. The ALTER CHANNEL command needs to set the connection name to the TCP/IP name of the OS/390 image on which it is restarted. It must include the port number specific to the restarted queue manager as part of the connection name.

   The start-up JCL of each queue manager can have a fixed data set name for this CSQINPX file, and each OS/390 image must have a different version of each of these CSQINPX files on a non-shared DASD volume.

In the event of ARM restart, MQSeries for OS/390 advertises the changed channel definition to the cluster repository, which in turn publishes it to all the client queue managers that have expressed an interest in the server queue manager.

The client queue manager sees the server queue manager failure as a channel failure, and tries to restart the failed channel. When the client queue manager learns the new server connection-name, the channel restart reconnects the client queue manager to the restarted server queue manager. The client queue manager can then resynchronize its messages, resolve any in-doubt messages on the client queue manager's transmission queue, and normal processing can continue.

Chapter 17. Understanding the log and the bootstrap data set

MQSeries maintains *logs* of data changes and significant events as they occur. The *bootstrap data set* (BSDS) stores information about the data sets that contain the logs.

Note: You must set up the log data sets for MQSeries, see "Task 11: Create the bootstrap and log data sets" on page 61.

This chapter serves as a general introduction and reference to the logging mechanism. Day-to-day procedures for managing the log and the BSDS are not described here; you can find them in Chapter 19, "Managing the logs and the bootstrap data set" on page 321.

This chapter contains the following sections:

- "What logs are"
- "How the log is structured" on page 307
- "How the logs are written" on page 308
- "What the bootstrap data set is for" on page 311
- "Managing the logs and BSDS" on page 312

What logs are

MQSeries records all significant events in an *active log* as they occur. The log contains the information needed to recover:

- Persistent messages
- MQSeries objects, such as queues
- The MQSeries subsystem

Note: The log does not contain information for statistics, traces, or performance evaluation.

The active log comprises a series of data sets that are used cyclically. See "How the logs are written" on page 308 for more information.

Archiving

Because the active log is finite, MQSeries copies the contents of each log data set periodically to an *archive log*, which is normally a data set on a direct access storage device (DASD) or a magnetic tape. If there is a subsystem or transaction failure, MQSeries uses the active log and, if necessary, the archive log for recovery.

The archive log can contain up to 1000 sequential data sets. Each data set can be cataloged using the integrated catalog facility (ICF).

© Copyright IBM Corp. 1993,1999

Important note about archiving

Archiving is an essential component of MQSeries recovery. If a unit of recovery is a long-running one, it is possible that log records within that unit of recovery will be found in the archive log. In this case, recovery will require data from the archive log. However, if archiving is switched off, the active log records will wrap, overwriting earlier log records. This means that MQSeries will be unable to back out the unit of recovery and messages will be lost. MQSeries will then terminate abnormally with a reason code 00D94012.

Therefore, in a production environment, **you must never switch archiving off**. If you do, you run the risk of losing data after a system or transaction failure. Only if you are running in a test environment should you consider switching archiving off. If you need to do this, use the CSQ6LOGP macro (see "Using CSQ6LOGP" on page 76).

If you have applied APAR 28093, you will receive message CSQJ160I or CSQJ161I if a long-running unit of recovery is detected during active log offload. These messages are documented in Appendix F, "New messages and codes" on page 505.

Dual logging

You can configure MQSeries to run with either *single logging* or *dual logging*. With single logging, log records are written once to an active log data set. With dual logging, each log record is written to two different active log data sets. Dual logging minimizes the likelihood of data loss problems during restart. If possible, the two log data sets should be on separate volumes. This reduces the risk of them both being lost if one of the volumes is corrupted or destroyed. If both copies of the log are lost, the probability of data loss is high.

Note: You should always use dual logging and dual BSDSs rather than dual writing to DASD.

Single logging gives you 2 through 53 active log data sets, whereas dual logging gives you 4 through 106. Each active log data set is a single-volume, single-extent VSAM linear data set (LDS).

Although the minimum number of log data sets required is two, in practice you should have at least three, and on a busy system you might need more. This is to allow time for each log data set to be copied to archive before it is reused in the active log cycle.

Log data

The log can contain up to 280 million million ($2.8*10^{14}$) bytes. Each byte can be addressed by its offset from the beginning of the log, and that offset is known as its *relative byte address* (RBA).

The log is made up of *log records*, each of which is a set of log data treated as a single unit. A log record is identified by the RBA of the first byte of its header; that RBA is called the relative byte address of the record. The RBA uniquely identifies a record that starts at a particular point in the log.

Each log record has a header that gives its type, the MQSeries sub-component that made the record, and, for unit of recovery records, a unit of recovery identifier.

There are three types of log record, described under these headings:

- "Unit-of-recovery log records"
- "Checkpoint records"
- "Page set control records"

Unit-of-recovery log records

Most of the log records describe changes to MQSeries queues. All such changes are made within units of recovery.

MQSeries uses special logging techniques involving *undo/redo* and *compensating log records* to reduce restart times and improve system availability.

One effect of this is that the restart time is bounded. If a failure occurs during a restart so that MQSeries has to be restarted a second time, all the recovery activity that completed to the point of failure in the first restart does not need to be re-applied during a second restart. This means that successive restarts do not take progressively longer times to complete.

Checkpoint records

To reduce restart time, MQSeries takes periodic checkpoints during normal operation:

- When a predefined number of log records has been written.

  This number is defined by the checkpoint frequency operand called LOGLOAD of the installation macro CSQ6SYSP described in "Using CSQ6SYSP" on page 69.
- At the end of a successful restart.
- At normal termination.

At the time a checkpoint is taken, MQSeries issues the DISPLAY THREAD command internally so that a list of threads currently in doubt is written to the OS/390 console log.

Page set control records

These records register the page sets known to the MQSeries subsystem at each checkpoint.

How the log is structured

Each active log data set must be a VSAM linear data set (LDS). The physical output unit written to the active log data set is a 4 KB control interval (CI). Each CI contains one VSAM record.

Physical and logical log records

One VSAM CI is a *physical* record. The information to be logged at a particular time forms a *logical* record, whose length varies independently of the space available in the CI. So one physical record can contain:

- Several logical records
- One or more logical records and part of another logical record
- Part of one logical record only

The term “log record” refers to the *logical* record, regardless of how many *physical* records are needed to store it.

How the logs are written

MQSeries writes each log record to a DASD data set called the *active log*. When the active log is full, MQSeries copies its contents to a DASD or tape data set called the *archive log*. This process is called *off-loading*.

Figure 93 illustrates the process of logging. Log records typically go through the following cycle:

1. MQSeries notes changes to data and significant events in recovery log records.
2. MQSeries processes recovery log records and breaks them into segments, if necessary.
3. Log records are placed sequentially in *output log buffers*, which are formatted as VSAM CIs. Each log record is identified by a relative byte address in the range 0 through $2^{48}-1$.
4. The CIs are written to a set of predefined DASD active log data sets, which are used sequentially and recycled.
5. If archiving is active, as each active log data set becomes full, its contents are automatically off-loaded to a new archive log data set.



Figure 93. The logging process

When the active log is written

The in-storage log buffers are written to an active log data set whenever any of the following occur:

- The log buffers become full.
- The write threshold is reached (as specified in the CSQ6LOGP macro).
- Certain significant events occur, such as, a commit point.

When MQSeries is initialized, the active log data sets named in the BSDS are dynamically allocated *for exclusive use by MQSeries* and remain allocated *exclusively to MQSeries* until MQSeries terminates. To add or replace active log data sets, you must terminate and restart MQSeries (see "The change log inventory utility (CSQJU003)" on page 262). For details about setting log parameters, see "Using CSQ6LOGP" on page 76.

When the archive log is written

The process of copying active logs to archive logs is called *off-loading*. The relation of off-loading to other logging events is shown schematically in Figure 94.



Figure 94. The off-loading process

Triggering an off-load

The off-load of an active log to an archive log can be triggered by several events. For example:

- Filling an active log data set.

  Message CSQJ110E is issued when the last available active log is 75% full and at 5% increments thereafter, stating the percentage of the log's capacity in use. If all the active logs become full, MQSeries stops processing until off-loading occurs and issues this message:

  ```
  CSQJ111A +cpf OUT OF SPACE IN ACTIVE LOG DATA SETS
  ```

- Using the MQSeries command ARCHIVE LOG.
- An error occurring while writing to an active log data set.

The data set is truncated before the point of failure, and the record that failed to be written becomes the first record of the new data set. Off-load is triggered for the

truncated data set as it would be for a normal full log data set. If there are dual active logs, both copies are truncated so that the two copies remain synchronized.

The off-load process

When all the active logs become full, the MQSeries subsystem runs an off-load and halts processing until the off-load has been completed. If the off-load processing fails when the active logs are full, then MQSeries abends. For more information, see "Active log problems" on page 346.

When an active log is ready to be off-loaded, a request is sent to the OS/390 console operator to mount a tape or prepare a DASD unit. The value of the ARCWTOR option, discussed in "Using CSQ6ARVP" on page 79, determines whether the request is received. If you are using tape for off-loading, specify ARCWTOR=YES. If the value is YES, the request is preceded by a WTOR (message number CSQJ008E) telling the operator to prepare an archive log data set to be allocated.

The operator need not respond to this message immediately. However, delaying the response delays the off-load process. It does not affect MQSeries performance unless the operator delays the response for so long that MQSeries runs out of active logs.

The operator can respond by canceling the off-load. In which case, if the allocation is for the first copy of dual archive data sets, the off-load is merely delayed until the next active log data set becomes full. If the allocation is for the second copy, the archive process switches to single copy mode, but for this data set only.

Archive log data sets

Details of how to plan your archive storage are given in "Planning your archive storage" on page 316.

Day-to-day procedures for managing the archive log are given in Chapter 19, "Managing the logs and the bootstrap data set" on page 321.

Interruptions and errors while off-loading

A `+cpf` STOP QMGR command does not take effect until off-loading has finished. If MQSeries fails while off-loading is in progress, off-load begins again when MQSeries is restarted. Off-load handling of read I/O errors on the active log is discussed under "Active log problems" on page 346, and of write I/O errors on the archive log, under "Archive log problems" on page 353.

Messages during off-load

Off-load messages are sent to the OS/390 console by MQSeries and the off-load process. With the exception of the CSQJ139I message, these messages can be used to find the RBA ranges in the various log data sets. For an explanation of the off-load messages, see the *MQSeries for OS/390 Messages and Codes* manual.

What the bootstrap data set is for

The *bootstrap data set* (BSDS) is a VSAM key-sequenced data set (KSDS) that holds information needed by MQSeries. It contains:

- An inventory of all active and archived log data sets known to MQSeries. MQSeries uses this inventory to:
  - Track the active and archived log data sets
  - Locate log records so that it can satisfy log read requests during normal processing
  - Locate log records so that it can handle restart processing

  MQSeries stores information in the inventory each time an archive log data set is defined or an active log data set is reused. For active logs, the inventory shows which are full and which are available for reuse. The inventory holds the relative byte address (RBA) of each log data set. There can be more than one RBA if the log data set spans more than one volume.
- A *wrap-around* inventory of all recent MQSeries activity. This is needed if MQSeries has to be restarted.

The BSDS is required if the subsystem has an error and has to be restarted. MQSeries must have a BSDS; it is not optional. To minimize the likelihood of problems during a restart, MQSeries can be configured with dual BSDSs, each recording the same information. This is known as running in *dual mode*. If possible, the copies should be on separate volumes. This reduces the risk of them both being lost if the volume is corrupted or destroyed. You should use dual BSDSs rather than dual write to DASD.

The BSDS is set up when MQSeries is customized and the inventory can be managed using the change log inventory utility (CSQJU003). For further information, see “Changing the BSDS” on page 327. It is referenced by a DD statement in the MQSeries startup procedure.

Normally, MQSeries keeps duplicate copies of the BSDS. If an I/O error occurs, it deallocates the failing copy and continues with a single BSDS. (For details of how to restore dual mode, see “BSDS errors” on page 356.)

The active logs are first registered in the BSDS when MQSeries is installed. They cannot be replaced, nor can new ones be added, without terminating and restarting MQSeries.

Archive log data sets are dynamically allocated. When one is allocated, the data set name is registered in the BSDS. The list of archive log data sets expands as archives are added, and wraps when a user-determined number of entries has been reached. The maximum number of entries is 1000 for single archive logging and 2000 for dual logging.

You can use a tape management system to delete the archive log data sets. MQSeries does not have an automated method. Therefore, the information about an archive log data set can be in the BSDS long after the archive log data set has been deleted by the system administrator.

Conversely, the maximum number of archive log data sets could have been exceeded, and the data from the BSDS dropped long before the data set has

reached its expiry date. For additional information, see “Automatic archive log data set deletion” on page 323.

If CSQZPARM specifies that archive log data sets are cataloged when allocated, the BSDS points to the interactive catalog facility (ICF) catalog for the information needed for later allocations. Otherwise, the BSDS entries for each volume register the volume serial number and unit information that is needed for later allocations.

Archive log data sets and BSDS copies

Each time a new archive log data set is created, a copy of the BSDS is also created. If the archive log is on tape, the BSDS is the first data set on the first output volume. If the archive log is on DASD, the BSDS is a separate data set.

The data set names of the archive log and the BSDS copy are the same, except that the lowest-level qualifier of the archive log name begins with A and the BSDS copy begins with B, for example:

Archive log name	CSQ.ARCHLOG1.D93022.T2336229.*A*0000001
BSDS copy name	CSQ.ARCHLOG1.D93022.T2336229.*B*0000001

If there is a read error while copying the BSDS, the copy is not created, message CSQJ125E is issued, and the off-load to the new archive log data set continues without the BSDS copy.

Managing the logs and BSDS

Day-to-day procedures for managing the BSDS are described in Chapter 19, “Managing the logs and the bootstrap data set” on page 321.

In these procedures and the other specialized procedures that are described, you might need to copy log or BSDS data sets. Because they are VSAM data sets, use the Access Method Services REPRO function (or any equivalent) to do this.

For more information on the REPRO statement, see the *DFSMS/MVS Access Method Services for VSAM* or the *DFSMS/MVS Access Method Services for the Integrated Catalog Facility* manuals.

Chapter 18. Planning for backup and recovery

This chapter describes what you can do now to minimize problems following any future failure. Chapter 21, “Example recovery scenarios” on page 345 describes the procedures you should follow when particular failures occur.

This chapter contains these sections:

- “Introduction”
- “General tips for backup and recovery”
- “Planning your logging environment” on page 315
- “Planning your archive storage” on page 316
- “Other recovery considerations” on page 317

You can find more information about MQSeries recovery in information APAR II11758.

Introduction

Developing backup and recovery procedures at your site is vital to avoid costly and time-consuming losses of data. MQSeries provides means for recovering both queues and messages to their current state after a system failure. You should develop the following procedures for MQSeries:

- Creating a point of recovery
- Backing up page sets
- Recovering page sets
- Recovering from out-of-space conditions (MQSeries logs and page sets)

See Chapter 20, “Managing page sets” on page 333 for information about procedures for page sets and creating a point of recovery, and “Active log problems” on page 346 for information about dealing with problems with the log.

You should also be familiar with the procedures used at your site for the following:

- Recovering from a hardware or power failure
- Recovering from an OS/390 component failure
- Recovering from a site interruption, using off-site recovery

General tips for backup and recovery

The MQSeries restart process recovers your data to a consistent state by applying log information to the page sets. If your page sets are damaged or unavailable, you can resolve the problem using your backup copies of your page sets (provided that all the logs are available). If your log data sets are damaged or unavailable, it might not be possible to recover completely. This section introduces some backup and recovery tasks.

© Copyright IBM Corp. 1993,1999

Periodically take backup copies

A *point of recovery* is the term used to describe a set of backup copies of MQSeries page sets and the corresponding log data sets required to recover these page sets. These backup copies provide a potential restart point in the event of page set loss (for example, page set I/O error). If MQSeries were to be restarted using these backup copies, the data in MQSeries will be consistent up to the point that these copies were taken. Providing that all logs are available from this point, MQSeries can be recovered to the point of failure. See “Creating a point of recovery” on page 339 for more information about points of recovery.

The more recent your backup copies, the quicker MQSeries can recover the data in the page sets. The recovery of the page sets are dependent on all the necessary log data sets being available.

In planning for recovery, you need to determine how often to take backup copies and how many complete backup cycles to keep. These values tell you how long you must keep your log data sets and backup copies of page sets for MQSeries recovery.

In deciding how often to take backup copies, consider the time needed to recover a page set. It is determined by:

- The amount of log to traverse
- The time it takes an operator to mount and remove archive tape volumes
- The time it takes to read the part of the log needed for recovery
- The time needed to reprocess changed pages
- The storage medium used for the backup copies
- The method used to make and restore backup copies

In general, the more often you make backup copies, the less time recovery takes, but, the more time is spent making copies.

For each queue manager, you should take backup copies of:

- The archive log data sets
- The BSDS copies created at the time of the archive (see “Archive log data sets and BSDS copies” on page 312)
- The page sets
- Your object definitions

To reduce the risk of your backup copies being lost of damaged, you should consider:

- Storing the backup copies on different storage volumes to the original copies.
- Storing the backup copies at a different site to the original copies.
- Making at least two copies of each backup of your page sets and, if you are using single logging or a single BSDS, two copies of your archive logs and BSDS. If you are using dual logging or BSDS, a single copy of both archive logs or BSDS will suffice.

Before moving MQSeries to a production environment you should have tested and documented your backup procedures.

Backing up your object definitions

You should also back up copies of your object definitions. To do this, use the MAKEDEF feature of the CSQUTIL COMMAND function (described in “MQSeries command management functions” on page 244).

You should do this whenever you take backup copies of your queue manager data sets, and keep the most current version.

Do not discard archive logs you might need

MQSeries might need to use archive logs during restart. You must keep sufficient archive logs so the system can be fully restored. MQSeries might use an archive log to recover a page set from a restored backup copy. If you have discarded that archive log, MQSeries is not able to restore the page set to its current state. To find out when and how you should discard archive logs, see “Discarding archive log data sets” on page 323.

Do not change the DDname-to-page set association

MQSeries associates page set number 00 with DDname CSQP0000, page set number 01 with DDname CSQP0001, and so on up to CSQP0099. MQSeries writes recovery log records for a page set based on the DDname that the page set is associated with. For this reason, you must not move page sets that have already been associated with a PSID DDname.

Planning your logging environment

The MQSeries logging environment is established using the installation macros to specify options, such as whether to have single or dual active logs, what media to use for the archive log volumes, and how many log buffers to have. For details, see “Task 13: Tailor your system parameter module” on page 68.

Use dual logging for your active log, archive log, and bootstrap data sets

Dual logging minimizes the risk associated with DASD failure.

Important

In a production MQSeries subsystem, it is important to establish both of the following:

1. Archiving
2. Dual logging for:
   - Active logs
   - Archive logs
   - Bootstrap data sets

This minimizes the risk of losing your data, for example, because of DASD failures.

Planning your archive storage

This section describes the different ways of maintaining your archive log data sets.

Archive log data sets can be placed on standard-label tapes, or DASD, and can be managed by data facility hierarchical storage manager (DFHSM). Each OS/390 logical record in an archive log data set is a VSAM control interval from the active log data set. The block size is a multiple of 4 KB. For more information, see "Using CSQ6LOGP" on page 76.

Archive log data sets are dynamically allocated, with names chosen by MQSeries. The data set name prefix, block size, unit name, and DASD sizes needed for such allocations are specified in the CSQZPARM module. You can also choose, at installation time, to have MQSeries add a date and time to the archive log data set name. For more information, see "Using CSQ6ARVP" on page 79.

It is not possible to choose specific volumes for new archive logs. If allocation errors occur, off-loading is postponed until the next time off-loading is triggered.

If you specify dual archive logs at installation time, each log control interval retrieved from the active log is written to two archive log data sets. The log records that are contained in the pair of archive log data sets are identical, but the end-of-volume points are not synchronized for multi-volume data sets.

Archiving to tape

If the unit name reflects a tape device, MQSeries can extend to a maximum of twenty volumes.

If you choose to off-load to tape, you should consider adjusting the size of your active log data sets so that each nearly fills a tape volume. This minimizes tape handling and volume mounts, and maximizes the use of tape resources. However, such an adjustment is not essential.

If you are considering changing the size of the active log data set so that the set fits on one tape volume, you must bear in mind that a copy of the BSDS is placed on the same tape volume as the copy of the active log data set. Adjust the size of the active log data set downward to offset the space required for the BSDS on the tape volume.

Archiving to DASD volumes

MQSeries requires that all archive log data sets allocated on non-tape devices (DASD) be cataloged. If you choose to archive to DASD, the CATALOG parameter of the CSQ6ARVP macro must be YES. (For details, see "Using CSQ6ARVP" on page 79.) If this parameter is NO, and you decide to place archive log data sets on DASD, you receive message CSQJ072E each time an archive log data set is allocated, although the MQSeries subsystem still catalogs the data set.

If the unit name shows that the archive log data set is held on DASD, the archive log data sets cannot extend to another volume.

If you choose to use DASD, make sure that the primary space allocation (both quantity and block size) is large enough to contain either the data coming from the active log data set, or that from the corresponding BSDS, whichever is the larger of

the two. This minimizes the possibility of unwanted OS/390 B37 or E37 abends during the off-load process. The primary space allocation is set with the PRIQTY (primary quantity) parameter of the CSQ6ARVP macro discussed in “Using CSQ6ARVP” on page 79.

Using SMS with archive log data sets

If you have MVS/DFP storage management subsystem (DFSMS™) installed, you can write an automatic class selection (ACS) user-exit filter for your archive log data sets, which helps you convert them for the SMS environment. Such a filter, for example, can route your output to a DASD data set, which in turn can be managed by DFSMS. You must exercise caution if you use an ACS filter in this manner. Because SMS requires DASD data sets to be cataloged, you must make sure the CATALOG DATA field of the CSQ6ARVP macro contains YES. If it does not, message CSQJ072E is returned; however, the data set is still cataloged by MQSeries. For details about this macro, see “Using CSQ6ARVP” on page 79.

For more information about ACS filters, see the *DFP Storage Administration Reference* manual, and the *SMS Migration Planning Guide*.

Other recovery considerations

This section describes some other things that you should take into account when you are planning your backup and recovery procedures.

Backup and recovery with DFHSM

The data facility hierarchical storage manager (DFHSM) does automatic space- and data-availability management among storage devices in your system. If you use it, you need to know that it moves data to and from the MQSeries storage automatically.

DFHSM manages your DASD space efficiently by moving data sets that have not been used recently to alternate storage. It also makes your data available for recovery by automatically copying new or changed data sets to tape or DASD backup volumes. It can delete data sets, or move them to another device. Its operations occur daily, at a specified time, and allow for keeping a data set for a predetermined period before deleting or moving it.

All DFHSM operations can also be performed manually. The *Data Facility Hierarchical Storage Manager User’s Guide* explains how to use the DFHSM commands.

If you use DFHSM with MQSeries, note that DFHSM:

- Uses cataloged data sets
- Operates on page sets and logs
- Supports VSAM data sets

MQSeries recovery and CICS

The recovery of CICS resources is not affected by the presence of MQSeries. CICS recognizes MQSeries as a non-CICS resource (or external resource manager), and includes MQSeries as a participant in any syncpoint coordination requests using the CICS resource manager interface (RMI). For more information about CICS recovery, see the *CICS Recovery and Restart Guide*. For information about the CICS resource manager interface, see the *CICS Customization Guide*.

MQSeries recovery and IMS

IMS recognizes MQSeries as an external subsystem and as a participant in syncpoint coordination. IMS recovery for external subsystem resources is described in the *IMS Customization Guide*.

Using Extended Recovery Facility

MQSeries can be used in an extended recovery facility (XRF) environment. All MQSeries-owned data sets (executable code, BSDSs, logs, and page sets) must be on DASD shared between the active and alternate XRF processors. If you use XRF for recovery, you must stop MQSeries on the active processor and start it on the alternate. For CICS, this can be done using the command list table (CLT) provided by CICS, or manually by the system operator. For IMS, this is a manual operation and must be done after the coordinating IMS system has completed the processor switch. MQSeries utilities must be completed or terminated before MQSeries can be switched to the alternate processor. Consider the effect of this potential interruption carefully when planning your XRF recovery plans.

Take care to prevent MQSeries starting on the alternate processor before the MQSeries system on the active processor terminates. A premature start can cause severe integrity problems in data, the catalog, and the log. Using global resource serialization (GRS) helps avoid the integrity problems by preventing simultaneous use of MQSeries on the two systems. The BSDS must be included as a protected resource, and the active and alternate XRF processors must be included in the GRS ring.

Preparing for disaster recovery

In the case of a total loss of an MQSeries computing center, you can recover on another MQSeries system at a recovery site. To be able to do this, you must regularly back up the page sets and the logs. As with all data recovery operations, the objectives of disaster recovery are to lose as little data, workload processing (updates), and time as possible.

At the recovery site:

- The recovery MQSeries queue manager **must** have the same name as the lost queue manager.
- The system parameter module (CSQZPARM) used on the recovery queue manager should contain the same parameters as the lost queue manager.

The following process can be used to perform disaster recovery at the recovery site. It assumes that all that is available are:

- Copies of the archive logs and BSDSs created by normal running at the primary site (the active logs will have been lost along with the queue manager at the primary site).

- Copies of the page sets from the queue manager at the primary site that are the same age or older than the most recent archive log copies available.

If required, dual active and archive logs should be considered, and the BSDS updates applied to both copies:

1. Define new page set data sets and load them with the data in the copies of the page sets from the primary site.
2. Define new active log data sets.
3. Define a new BSDS data set and use Access Method Services REPRO to copy the **most recent** archived BSDS into it.
4. Use the print log map utility CSQJU004 to print information from this most recent BSDS. At the time this BSDS was archived, the most recent archived log you have would have just been truncated as an active log, and will not appear as an archived log. Record the STARTRBA and ENDRBA of this log.
5. Use Access Method Services REPRO to copy the most recent archived log into one of the active logs.
6. Use the change log inventory utility CSQJU003 to remove all active log information from the BSDS.
7. Use CSQJU003 to add active logs to the BSDS, including the RBA range of the logs used in Step 5 as found in Step 4.
8. Use CSQJU003 to add a restart control record to the BSDS. Specify:

   ```
   CRESTART CREATE,ENDRBA=highrba
   ```

   Where `highrba` is the high RBA of the most recent archive log available (found in Step 4), plus 1.

   The BSDS now describes one active log with an RBA range, all other active logs as being empty, all the archived logs you have available, and no checkpoints beyond the end of your logs.
9. Restart MQSeries with the usual START QMGR command. During initialization, an operator reply message such as the following will be issued:

   ```
   CSQJ245D +cpf RESTART CONTROL INDICATES TRUNCATION AT RBA highrba.
            REPLY Y TO CONTINUE, N TO CANCEL
   ```

   Reply Y to start MQSeries. MQSeries will start, and will recover data up to ENDRBA specified in the CRESTART statement.

See “The change log inventory utility (CSQJU003)” on page 262 for information about using CSQJU003 and “The print log map utility (CSQJU004)” on page 271 for information about using CSQJU004.

Figure 95 on page 320 shows sample input statements for CSQJU003 for steps 6, 7, and 8.

The things you need to consider for restarting the channel initiator at the recovery site are similar to those faced when using ARM to restart the channel initiator on a different OS/390 image. See “Restarting on a different OS/390 image using LU 6.2” on page 303 for more information.

Your recovery strategy should also cover recovery of the MQSeries product libraries and the application programming environments that use MQSeries (CICS, for example).

```
* Step 6
         DELETE DSNAME=MQM2.LOGCOPY1.DS01
         DELETE DSNAME=MQM2.LOGCOPY1.DS02
         DELETE DSNAME=MQM2.LOGCOPY1.DS03
         DELETE DSNAME=MQM2.LOGCOPY2.DS01
         DELETE DSNAME=MQM2.LOGCOPY2.DS02
         DELETE DSNAME=MQM2.LOGCOPY2.DS03

* Step 7
         NEWLOG DSNAME=MQM2.LOGCOPY1.DS01,COPY1
           STARTRBA=05C000,ENDRBA=000000062FFF
         NEWLOG DSNAME=MQM2.LOGCOPY1.DS02,COPY1
         NEWLOG DSNAME=MQM2.LOGCOPY1.DS03,COPY1
         NEWLOG DSNAME=MQM2.LOGCOPY2.DS01,COPY2
           STARTRBA=05C000,ENDRBA=000000062FFF
         NEWLOG DSNAME=MQM2.LOGCOPY2.DS02,COPY2
         NEWLOG DSNAME=MQM2.LOGCOPY2.DS03,COPY2

* Step 8
         CRESTART CREATE,ENDRBA=063000
```

Figure 95. Sample input statements for CSQJU003

Other functions of the change log inventory utility (CSQJU003) can also be used in disaster recovery scenarios. The HIGHRBA function allows the update of the highest RBA written and highest RBA offloaded values within the bootstrap data set. The CHECKPT function allows the addition of new checkpoint queue records or the deletion of existing checkpoint queue records in the BSDS. These functions might affect the integrity of the MQSeries system and should only be used in disaster recovery scenarios under the guidance of IBM service personnel.

Chapter 19. Managing the logs and the bootstrap data set

This chapter describes the tasks involved in managing the logs and the bootstrap data set. It contains these sections:

- "Archiving logs with the ARCHIVE LOG command"
- "Discarding archive log data sets" on page 323
- "Printing log records" on page 325
- "Finding out what the BSDS contains" on page 325
- "Changing the BSDS" on page 327
- "BSDS recovery" on page 330
- "Recovering logs" on page 332

Archiving logs with the ARCHIVE LOG command

An authorized operator can archive the current MQSeries active log data sets whenever required using the ARCHIVE LOG command.

When you issue the ARCHIVE LOG command, MQSeries truncates the current active log data sets, then runs an asynchronous off-load, and updates the BSDS with a record of the off-load.

The ARCHIVE LOG command has a MODE(QUIESCE) option. With this option, MQSeries users are quiesced after a commit point, and the resulting point of consistency is captured in the current active log before it is off-loaded.

Consider using the MODE(QUIESCE) option when planning a backup strategy for off site recovery. It creates a system-wide point of consistency, which minimizes the number of data inconsistencies when the archive log is used with the most current backup page set copy during recovery. For example:

```
ARCHIVE LOG MODE(QUIESCE)
```

If the ARCHIVE LOG command is issued without specifying a TIME parameter, the quiesce time period defaults to the value of the QUIESCE parameter of the CSQ6ARVP macro. If the time required for the ARCHIVE LOG MODE(QUIESCE) to complete is less than the time specified, the command completes successfully; otherwise, the command fails when the time period expires. You can specify the time period explicitly by using the TIME option, for example:

```
ARCHIVE LOG MODE(QUIESCE) TIME(60)
```

This command specifies a quiesce period of up to 60 seconds before ARCHIVE LOG processing occurs.

Attention: Using this option when time is critical can cause a significant disruption in MQSeries availability for all jobs and users that use MQSeries resources.

By default, the command is processed asynchronously from the time you submit the command. (To process the command synchronously with other MQSeries commands use the WAIT(YES) option QUIESCE, but be aware that the OS/390 console is locked from MQSeries command input for the entire QUIESCE period.)

© Copyright IBM Corp. 1993,1999

During the quiesce period:

- Jobs and users on MQSeries are allowed to go through commit processing, but are suspended if they try to update any MQSeries resource after the commit.
- Jobs and users that only read data can be affected, since they can be waiting for locks held by jobs or users that were suspended.
- New tasks can start, but they are not allowed to update data.

The DISPLAY THREAD output uses the message CSQV400I to indicate that a quiesce is in effect. For example:

```
CSQV401I +cpf DISPLAY THREAD REPORT FOLLOWS -
CSQV400I +cpf ARCHIVE LOG QUIESCE CURRENTLY ACTIVE
CSQV402I +cpf ACTIVE THREADS -
NAME     ST A   REQ THREAD-XREF  USERID      ASID   URID
BATCH    T       14              CON0327     0016   000000000000
DISPLAY ACTIVE REPORT COMPLETE
CSQ9022I +cpf CSQVDT ' DISPLAY THREAD' NORMAL COMPLETION
```

When all updates are quiesced, the quiesce history record in the BSDS is updated with the date and time that the active log data sets were truncated, and with the last-written RBA in the current active log data sets. MQSeries truncates the current active log data sets, switches to the next available active log data sets, and issues message CSQJ311E stating that off-load started.

If updates cannot be quiesced before the quiesce period expires, MQSeries issues message CSQJ317I, and ARCHIVE LOG processing terminates. The current active log data sets are not truncated and not switched to the next available log data sets, and off-load is not started.

Whether the quiesce was successful or not, all suspended users and jobs are then resumed, and MQSeries issues message CSQJ312I, stating that the quiesce is ended and update activity is resumed.

If ARCHIVE LOG is issued when the current active log is the last available active log data set, the command is not processed, and MQSeries issues this message:

```
CSQJ319I - csect-name CURRENT ACTIVE LOG DATA SET IS THE LAST
           AVAILABLE ACTIVE LOG DATA SET.  ARCHIVE LOG PROCESSING
           WILL BE TERMINATED.
```

If ARCHIVE LOG is issued when another ARCHIVE LOG command is already in progress, the new command is not processed, and MQSeries issues this message:

```
CSQJ318I - ARCHIVE LOG COMMAND ALREADY IN PROGRESS.
```

For information about the syntax of the ARCHIVE LOG command, see the *MQSeries Command Reference* manual. For information about the messages issued during archiving, see the *MQSeries for OS/390 Messages and Codes* manual.

Discarding archive log data sets

You must keep enough log records to recover units of recovery or perform media recovery if a page set is lost. Do not discard archive log data sets that might be required for recovery; if you discard these archive log data sets you might not be able to recover using your page set backups.

However, if you have confirmed that your archive log data sets can be discarded, you can do this in either of the following ways:

- Automatic archive deletion (see "Automatic archive log data set deletion")
- Manual archive deletion (see "Manually deleting archive log data sets" on page 324)

Automatic archive log data set deletion

You can use a DASD or tape management system to delete archive log data sets automatically. The retention period for MQSeries archive log data sets is specified by the retention period field ARCRETN in the CSQ6ARVP installation macro. See "Using CSQ6ARVP" on page 79 for more information. This value is passed to the management system in the JCL parameter RETPD.

The default for the retention period specifies that archive logs are to be kept for 9999 days (the maximum possible). **You can change the retention period but you must ensure that you can accommodate the number of backup cycles that you have planned for**.

MQSeries uses the value as the value for the JCL parameter RETPD when archive log data sets are created.

The retention period set by MVS/DFP's storage management subsystem (SMS) can be overridden by this MQSeries parameter. Typically, the retention period is set to the smaller value specified by either MQSeries or SMS. The storage administrator and MQSeries administrator must agree on a retention period value that is appropriate for MQSeries.

Note: Because some tape management systems provide external manual overrides of retention periods, MQSeries does not have an automated method to delete information about archive log data sets from the BSDS. Therefore, information about an archive log data set can still be in the BSDS long after the data-set retention period has expired and the data set has been scratched by the tape management system. Conversely, the maximum number of archive log data sets might have been exceeded and the data from the BSDS might have been dropped before the data set has reached its expiration date.

If archive log data sets are deleted automatically, remember that the operation does not update the list of archive logs in the BSDS. You can update the BSDS with the change log inventory utility, as described in "Changing the BSDS" on page 327. The update is not essential. Recording old archive logs wastes space in the BSDS, but does no other harm.

Manually deleting archive log data sets

You must keep all the log records as far back as the lowest RBA identified in messages CSQI024I and CSQI025I. This RBA is obtained using the DISPLAY USAGE command as issued when creating a point of recovery using “Method 1: Full backup” on page 339. **You should read “Creating a point of recovery” on page 339 before discarding any logs**.

Locate and discard archive log data sets

Having established the minimum log RBA required for recovery from your page set backup cycles, you can find archive log data sets that contain only earlier log records by performing the following procedure:

1. Use the print log map utility to print the contents of the BSDS. For an example of the output, see “The print log map utility (CSQJU004)” on page 271.
2. Find the sections of the output titled “ARCHIVE LOG COPY n DATA SETS”. If you use dual logging, there are two sections. The columns labeled STARTRBA and ENDRBA show the range of RBAs contained in each volume. Find the volumes whose ranges include the minimum RBA you found with messages CSQI024I and CSQI025I. These are the earliest volumes you need to keep. If you are using dual-logging, there are two such volumes.

   If no volumes have an appropriate range, one of these cases applies:

   - The minimum RBA has not yet been archived, and you can discard all archive log volumes.
   - The list of archive log volumes in the BSDS wrapped around when the number of volumes exceeded the number allowed by the MAXARCH parameter of the CSQ6LOGP macro. If the BSDS does not register an archive log volume, that volume cannot be used for recovery. Therefore, you should consider adding information about existing volumes to the BSDS. For instructions, see “Changes for archive logs” on page 328.

     You should also consider increasing the value of MAXARCH. For information, see “Using CSQ6LOGP” on page 76.
3. Delete any archive log data set or volume whose ENDRBA value is less than the STARTRBA value of the earliest volume you want to keep. If you are using dual logging, delete both such copies.

   Because BSDS entries wrap around, the first few entries in the BSDS archive log section might be more recent than the entries at the bottom. Look at the combination of date and time and compare their ages. Do not assume that you can discard all entries *above* the entry for the archive log containing the minimum LOGRBA.

   Delete the data sets. If the archives are on tape, erase the tapes. If they are on DASD, run an OS/390 utility to delete each data set. Then, if you want the BSDS to list only existing archive volumes, use the change log inventory utility (CSQJU003) to delete entries for the discarded volumes. See “Changes for archive logs” on page 328 for an example.

Printing log records

You can extract and print log records using the CSQ1LOGP utility. For instructions, see “The log print utility (CSQ1LOGP)” on page 272.

Finding out what the BSDS contains

The print log map utility (CSQJU004) is a batch utility that lists the information stored in the BSDS. For instructions on running it, see “The print log map utility (CSQJU004)” on page 271.

Time stamps in the BSDS

The output of the print log map utility shows the time stamps, which are used to record the date and time of various system events, that are stored in the BSDS.

The following time stamps are included in the header section of the report:

SYSTEM TIMESTAMP
Reflects the date and time the BSDS was last updated. The BSDS time stamp can be updated when:

- MQSeries starts.
- The write threshold is reached during log write activities. Depending on the number of output buffers you have specified and the system activity rate, the BSDS can be updated several times a second, or could not be updated for several seconds, minutes, or even hours. For details of the write threshold, see the WRTHRSH parameter of the CSQ6LOGP macro in the section “Using CSQ6LOGP” on page 76.
- MQSeries drops into a single BSDS mode from its normal dual BSDS mode due to an error. This can occur when a request to get, insert, point to, update, or delete a BSDS record is unsuccessful. When this error occurs, MQSeries updates the time stamp in the remaining BSDS to force a time stamp mismatch with the disabled BSDS.

UTILITY TIMESTAMP
The date and time the contents of the BSDS were altered by the change log inventory utility (CSQJU003).

The following time stamps are included in the active and archive log data sets portion of the report:

Active log date
The date the active log entry was created in the BSDS, that is, when the CSQJU003 NEWLOG was done.

Active log time
The time the active log entry was created in the BSDS, that is, when the CSQJU003 NEWLOG was done.

Archive log date
The date the archive log entry was created in the BSDS, that is, when the CSQJU003 NEWLOG was done or the archive itself was done.

Archive log time
The time the archive log entry was created in the BSDS, that is, when the CSQJU003 NEWLOG was done or the archive itself was done.

Active log data set status

The BSDS records the status of an active log data set as one of the following:

NEW The data set has been defined but never used by MQSeries, or the log was truncated to a point before the data set was first used. In either case, the data set starting and ending RBA values are reset to zero.

REUSABLE Either the data set has been defined but never used by MQSeries, or the data set has been off-loaded. In the print log map output, the start RBA value for the last REUSABLE data set is equal to the start RBA value of the last archive log data set.

NOT REUSABLE The data set contains records that have not been off-loaded.

STOPPED The off-load processor encountered an error while reading a record, and that record could not be obtained from the other copy of the active log.

TRUNCATED Either:

- An I/O error occurred, and MQSeries has stopped writing to this data set. The active log data set is off-loaded, beginning with the starting RBA and continuing up to the last valid record segment in the truncated active log data set. The RBA of the last valid record segment is lower than the ending RBA of the active log data set. Logging is switched to the next available active log data set, and continues uninterrupted.

or

- An ARCHIVE LOG function has been called, which has truncated the active log.

The status appears in the output from the print log map utility.

Changing the BSDS

You do not have to take special steps to keep the BSDS updated with records of logging events because MQSeries does that automatically. However, you might want to change the BSDS if you do any of the following:

- Add more active log data sets.
- Copy active log data sets to newly allocated data sets, for example, when providing larger active log allocations.
- Move log data sets to other devices.
- Recover a damaged BSDS.
- Discard outdated archive log data sets.

You can change the BSDS by running the change log inventory utility (CSQJU003). This utility can be run whether MQSeries is active or inactive. However, you are recommended **not** to run it when MQSeries is active, or you might get inconsistent results. The action of the utility is controlled by statements in the SYSIN data set. This section shows several examples. For complete instructions, see "The change log inventory utility (CSQJU003)" on page 262.

You can copy an active log data set only when MQSeries is inactive because MQSeries allocates the active log data sets as exclusive (DISP=OLD) at MQSeries startup.

Changes for active logs

You can add to, delete from, and record entries in the BSDS for active logs using the change log utility. Examples only are shown here; replace the data set names shown with the ones you want to use. For more details of the utility, see "The change log inventory utility (CSQJU003)" on page 262.

Adding record entries to the BSDS: If an active log has been flagged as "stopped", it is not reused for logging; however, it continues to be used for reading. Use the access method services to define new active log data sets, then use the change log inventory utility to register the new data sets in the BSDS. For example, use:

```
NEWLOG DSNAME=MQM111.LOGCOPY1.DS10,COPY1
NEWLOG DSNAME=MQM111.LOGCOPY2.DS10,COPY2
```

If you are copying the contents of an old active log data set to the new one, you can also give the RBA range and the starting and ending time stamps on the NEWLOG function.

Deleting information about the active log data set from the BSDS: To delete information about an active log data set from the BSDS, you could use:

```
DELETE DSNAME=MQM111.LOGCOPY1.DS99
DELETE DSNAME=MQM111.LOGCOPY2.DS99
```

Recording information about the log data set in the BSDS: To record information about an existing active log data set in the BSDS, use:

```
NEWLOG DSNAME=MQM111.LOGCOPY1.DS10,COPY2,STARTIME=19930212205198,
             ENDTIME=19930412205200,STARTRBA=6400,ENDRBA=94FF
```

Inserting a record containing this type of information in the BSDS might be necessary because:

- The entry for the data set has been deleted, but is needed again.
- You are copying the contents of one active log data set to another data set.
- You are recovering the BSDS from a backup copy.

Enlarging the active log: This procedure must only be used when MQSeries is inactive:

1. Stop MQSeries. This step is required because MQSeries allocates all active log data sets for its exclusive use when it is active.
2. Use Access Method Services ALTER with the NEWNAME option to rename your active log data sets.
3. Use Access Method Services DEFINE to define larger active log data sets.

   By reusing the old data set names, you do not have to run the change log inventory utility to establish new names in the BSDSs. The old data set names and the correct RBA ranges are already in the BSDSs.
4. Use Access Method Services REPRO to copy the old (renamed) data sets into their respective new data sets.
5. Start MQSeries.

Although it is not necessary for all log data sets to be the same size, it is operationally more consistent and efficient. If the log data sets are not the same size, it is more difficult to track your system's logs, and so space can be wasted.

Changes for archive logs

You can add to, delete from, and change the password of entries in the BSDS for archive logs. Examples only are shown here; you must replace the data set names shown with the ones you want to use. For more details of the utility, see "The change log inventory utility (CSQJU003)" on page 262.

Adding an archive log: When the recovery of an object depends on reading an existing archive log data set, the BSDS must contain information about that data set, so that MQSeries can find it. To register information about an existing archive log data set in the BSDS, use:

```
NEWLOG DSNAME=CSQARC1.ARCHLOG1.D92021.T2205197.A0000015,COPY1VOL=CSQV04,
             UNIT=TAPE,STARTRBA=3A190000,ENDRBA=3A1F0FFF,CATALOG=NO
```

Deleting an archive log: To delete an entire archive log data set on one or more volumes, use:

```
DELETE DSNAME=CSQARC1.ARCHLOG1.D92021.T2205197.A0000015,COPY1VOL=CSQV04
```

Changing the password of an archive log: If you change the password of an existing archive log data set, you must also change the information in the BSDS.

1. List the BSDS, using the print log map utility.
2. Delete the entry for the archive log data set with the changed password, using the DELETE function of the CSQJU003 utility (see page 262).
3. Name the same data set as a new archive log data set. Use the NEWLOG function of the CSQJU003 utility (see page 262), and give the new password, the starting and ending RBAs, and the volume serial numbers (which can be found in the print log map utility output, see page 271).

To change the password for new archive log data sets, use:

```
ARCHIVE PASSWORD=password
```

To stop placing passwords on new archive log data sets, use:

```
ARCHIVE NOPASSWD
```

Note: You should only use the ARCHIVE utility function if you do not have an external security manager.

BSDS recovery

If MQSeries is operating in dual BSDS mode and one BSDS becomes damaged, forcing MQSeries into single BSDS mode, MQSeries continues to operate without a problem (until the next restart). To return the environment to dual BSDS mode:

1. Use Access Method Services to rename or delete the damaged BSDS and to define a new BSDS with the same name as the damaged BSDS. Control statements can be found in job CSQ4BSDS in thlqual.SCSQPROC. (See "Task 11: Create the bootstrap and log data sets" on page 61.)
2. Issue the MQSeries command `+cpf` RECOVER BSDS to make a copy of the valid BSDS in the newly allocated data set and to reinstate dual BSDS mode.

If MQSeries is operating in single BSDS mode and the BSDS is damaged, or if MQSeries is operating in dual BSDS mode and both BSDSs are damaged, MQSeries stops and does not restart until the BSDS data sets are repaired. In this case:

1. Locate the BSDS associated with the most recent archive log data set. The data set name of the most recent archive log appears in the job log in the last occurrence of message CSQJ003I, which indicates that off-loading has been completed successfully. In preparation for the rest of this procedure, it is a good practice to keep a log of all successful archives noted by that message:
   - If archive logs are on DASD, the BSDS is allocated on any available DASD. The BSDS name is like the corresponding archive log data set name; change only the first letter of the last qualifier, from A to B, as in the example below:

     Archive log name CSQ.ARCHLOG1.*A*0000001
     BSDS copy name CSQ.ARCHLOG1.*B*0000001

   - If archive logs are on tape, the BSDS is the first data set of the first archive log volume. The BSDS is not repeated on later volumes.
2. If the most recent archive log data set has no copy of the BSDS (presumably because an error occurred when off-loading it), then locate an earlier copy of the BSDS from an earlier off-load.
3. Rename *damaged* BSDSs using the Access Method Services ALTER command with the NEWNAME option. If you decide to delete a damaged BSDS, use the Access Method Services DELETE command. For each damaged BSDS, use Access Method Services to define a new BSDS as a replacement data set. Job CSQ4BSDS in thlqual.SCSQPROC contains Access Method Services control statements to define a new BSDS. (See "Task 11: Create the bootstrap and log data sets" on page 61.)
4. Use Access Method Services to delete or rename the damaged data set, to define a replacement data set, and to copy the remaining BSDS to the replacement with DFDSS or the Access Method Services REPRO command.
5. Use DFDSS or the Access Method Services REPRO command to copy the BSDS from the archive log to one of the replacement BSDSs you defined in step 3. Do not copy any data to the second replacement BSDS—you do that in step 6 on page 332.
   a. Print the contents of the replacement BSDS.

Use the print log map utility (CSQJU004) to print the contents of the replacement BSDS. This enables you to review the contents of the replacement BSDS before continuing your recovery work.

b. Update the archive log data set inventory in the replacement BSDS.

   Examine the output from the print log map utility and check that the replacement BSDS does not contain a record of the archive log from which the BSDS was copied. If the replacement BSDS is an old copy, its inventory might not contain all archive log data sets that were created more recently. Therefore, the BSDS inventory of the archive log data sets must be updated to reflect the current subsystem inventory.

   Use the change log inventory utility (CSQJU003) NEWLOG statement to update the replacement BSDS, adding a record of the archive log from which the BSDS was copied. If the archive log data set is password-protected, be certain to use the PASSWORD option of the NEWLOG function. Also, make certain the CATALOG option of the NEWLOG function is properly set to CATALOG=YES if the archive log data set is cataloged. Use the NEWLOG statement to add any additional archive log data sets that were created later than the BSDS copy.

c. Update passwords in the replacement BSDS.

   The BSDS contains passwords for the archive log data sets and for the active log data sets. To ensure that the passwords in the replacement BSDS reflect the current passwords used by your installation, use the change log inventory ARCHIVE utility function with the PASSWORD option.

d. Update the active log data set inventory in the replacement BSDS.

   In unusual circumstances, your installation could have added, deleted, or renamed active log data sets since the BSDS was copied. In this case, the replacement BSDS does not reflect the actual number or names of the active log data sets your installation has currently in use.

   If you need to delete an active log data set from the replacement BSDS log inventory, use the change log inventory utility DELETE function.

   If you need to add an active log data set to the replacement BSDS log inventory, use the change log inventory utility NEWLOG function. Ensure that the RBA range is specified correctly on the NEWLOG function. If the active log data set is password-protected, be sure to use the PASSWORD option.

   If you need to rename an active log data set in the replacement BSDS log inventory, use the change log inventory utility DELETE function, followed by the NEWLOG function. Be sure that the RBA range is specified correctly on the NEWLOG function. If the active log data set is password-protected, be certain to use the PASSWORD option.

e. Update the active log RBA ranges in the replacement BSDS.

   Later, when MQSeries restarts, it compares the RBAs of the active log data sets listed in the BSDS with the RBAs found in the actual active log data sets. If the RBAs do not agree, MQSeries does not restart. The problem is magnified when a particularly old copy of the BSDS is used. To solve this problem, you can use the change log inventory utility (CSQJU003) to adjust the RBAs found in the BSDS using the RBAs in the actual active log data sets.

This can be done by:

- Using the print log records utility (CSQ1LOGP) to print a summary report of the active log data set. This shows the starting and ending RBAs.
- Comparing the actual RBA ranges with the RBA ranges you have just printed, when the RBAs of all active log data sets are known.

  If the RBA ranges are equal for all active log data sets, you can proceed to the next recovery step without any additional work.

  If the RBA ranges are not equal, then the values in the BSDS must be adjusted to reflect the actual values. For each active log data set that needs to have the RBA range adjusted, use the change log inventory utility DELETE function to delete the active log data set from the inventory in the replacement BSDS. Then use the NEWLOG function to redefine the active log data set to the BSDS. If the active log data sets are password-protected, be certain to use the PASSWORD option of the NEWLOG function.

f. If only two active log data sets are specified for each copy of the active log, MQSeries can have difficulty during restart. The problem can arise when one of the active log data sets is full and has not been off-loaded, while the second active log data set is close to filling. In this case, add a new active log data set for each copy of the active log and define each new active log data set in the replacement BSDS log inventory.

   Use the Access Method Services DEFINE command to define a new active log data set for each copy of the active log. The control statements to accomplish this task can be found in job CSQ4BSDS in thlqual.SCSQPROC. (See “Task 11: Create the bootstrap and log data sets” on page 61.) Once the active log data sets are physically defined and allocated, use the change log inventory utility NEWLOG function to define the new active log data sets in the replacement BSDS. The RBA ranges need not be specified on the NEWLOG statement; however, if the active log data sets are password-protected, be certain to use the PASSWORD option of the NEWLOG function.

6. Copy the updated BSDS to the second new BSDS data set. The BSDSs are now identical.

   Consider using the print log map utility (CSQJU004) to print the contents of the second replacement BSDS at this point.

7. See “Active log problems” on page 346 for information about what to do if you have lost your current active log data set.
8. Restart MQSeries, using the newly constructed BSDS. MQSeries determines the current RBA and what active logs need to be archived.

Recovering logs

Normally, you do not need to back up and restore the MQSeries logs, especially if you are using dual logging. However, in rare circumstances, such as an I/O error on a log, you might need to recover the logs. Use Access Method Services to delete and redefine the data set, and then copy the corresponding dual log into it.

Chapter 20. Managing page sets

This chapter describes how to create, copy, and generally manage the page sets associated with a queue manager. It contains these sections:

- "Adding a page set to a queue manager"
- "When one of your page sets becomes full"
- "How to balance loads on page sets" on page 335
- "How to reduce a page set" on page 338
- "Backing up and recovering page sets" on page 339
- "Backing up and restoring queues using CSQUTIL" on page 343

See "An overview of storage management" on page 15 for a description of page sets, storage classes, buffers, and buffer pools, and some of the performance considerations that apply.

Adding a page set to a queue manager

This description assumes that you have an MQSeries subsystem that is already running. You might need to add a page set if, for example, your MQSeries subsystem has to cope with new applications using new queues.

To add a new page set, use the following procedure:

1. Stop the queue manager by issuing a STOP QMGR command.
2. Define and format the new page set. You can use the sample JCL in thlqual.SCSQPROC(CSQ4PAGE) as a basis. For more information, see "Formatting page sets (FORMAT)" on page 237.

   Take care not to format any page sets that are in use, unless this is what you intend. If so, use the FORCE option of the FORMAT utility function.
3. Add the new page set to the startup procedure for your MQSeries subsystem.
4. Add a definition for the new page set to your CSQINP1 initialization data set. Use the DEFINE PSID command to associate the page set with a buffer pool.
5. Add the appropriate storage class definitions for your page set to your CSQINP2 initialization data set concatenation. This step is optional but recommended, see "Task 10: Customize the initialization input data sets" on page 52.
6. Restart the queue manager.

When one of your page sets becomes full

You can find out about the utilization of page sets by using the MQSeries command DISPLAY USAGE. For example, the command:

```
DISPLAY USAGE PSID(03)
```

displays the current state of the page set 03. This tells you how many free pages this page set has.

© Copyright IBM Corp. 1993,1999

Page set full

If you have defined secondary extents for your page sets, they will be dynamically expanded each time they fill up. Eventually, all secondary extents will be used, or no further disk space is available, in which case, and application will receive a return code MQRC_PAGESET_FULL.

If an application receives a return code of MQRC_PAGE_SET_FULL from an MQI call, this is a clear indication that this page set is over-utilized, that is, there is not enough space left on the page set. If the problem persists or is likely to reoccur, you must do something to solve it.

You can approach this problem in two ways:

1. Expand the page set.
2. Balance the load between page sets by moving queues from one page set to another.

How to expand a page set

You expand a page set by creating a new, larger page set and copying the messages from the old page set to the new one. You then have to ensure that the new page set is used when you restart the queue manager.

Note

This technique involves stopping and restarting the queue manager. This will result in any nonpersistent messages being deleted at restart time. If you have nonpersistent messages that you do not want to be deleted, consider load balancing (see "How to balance loads on page sets" on page 335).

Note: In this description, the page set that you want to expand is referred to as the *source* page set; the new, larger page set is referred to as the *destination* page set.

Follow these steps:

1. Stop the queue manager.
2. Define the destination page set, ensuring that it is larger than the source page set, with a larger secondary extent value.
3. Use the FORMAT function of CSQUTIL to format the destination page set. See "Formatting page sets (FORMAT)" on page 237 for more details.
4. Use the COPYPAGE function of CSQUTIL to copy all the messages from the source page set to the destination page set. See "Expanding a page set (COPYPAGE)" on page 239 for more details.
5. Restart the queue manager using the destination page set by doing one of the following:
   - Change the MQSeries startup procedure to reference the destination page set. See "Task 12: Define your page sets" on page 63 for more details.
   - Use Access Method Services to delete the source page set and then rename the destination page set, giving it the same name as that of the source page set.

Attention: Before you delete any MQSeries page set, be sure that you have made the required backup copies.

How to balance loads on page sets

Load balancing on page sets means moving the messages associated with one or more queues from one page set to another, less utilized page set.

Note

You should use this technique if it is not practical to expand the page set. It is possible that messages can be lost when uncommitted messages on the queue are committed or backed out during the load balancing operation.

Step 5 on page 336 uses the COPY function of CSQUTIL to off-load the messages to a data set. This only copies committed messages. Step 7 on page 336 deletes the queue that you are moving with the PURGE option, and only succeeds if there are no uncommitted messages on the queue. In the time between execution of these steps:

- **MQPUT** calls that are committed in this window are deleted with the queue
- **MQGET** calls that are backed out in this window are deleted with the queue

When identifying which queues are most suitable for moving you should therefore consider the following points:

- Do applications issue **MQPUT** or **MQGET** calls within syncpoint against the queue?

  If not, there is no potential for losing messages between the execution of steps 5 and 7 on page 336 because no commit or backout activity will occur during load balancing. These queues are therefore the most suitable for moving, and the considerations listed below do not apply.

- Do these applications ever issue **MQCLOSE** calls against the queue before issuing a syncpoint?

  If not, there is no potential for losing messages during the execution of steps 5 and 7 on page 336 because all commit or backout activity will have completed before the queue is closed. These queues are the next most suitable for moving and the considerations listed below do not apply.

- If applications **do** issue **MQCLOSE** calls against the queue before issuing a syncpoint, these queues are most likely to lose messages during the load balancing operation. This is because there might be uncommitted messages on the queue even though there are no open handles. These queues are therefore the least suitable for moving.

You should also consider the following points:

- There is no method for establishing whether there are uncommitted **MQPUT** or **MQGET** calls outstanding against the queue. In particular, the CURDEPTH attribute of a queue reflects both committed and uncommitted messages, and so is not a reliable indicator of whether all messages on the queue are committed.
- Using MQSeries security to restrict access to queues during the load balancing operation will not prevent the potential loss of messages between the execution of steps 5 and 7 on page 336 because it has no effect on the uncommitted activity on the queue.

To identify which queues are using a page set, use the appropriate MQSeries commands. For example, to find out which queues are mapped to page set 02, first, find out which storage classes map to page set 02, by using this command:

```
DISPLAY STGCLASS(*) PSID(02)
```

Then use this command:

```
DISPLAY QUEUE(*) TYPE(QLOCAL) STGCLASS
```

to find out which queues use which storage class.

Load balancing by moving queues

To move queues and their messages from one page set to another, use the COPY or SCOPY, LOAD, and COMMAND functions of the MQSeries utility program, CSQUTIL. These are described in Chapter 14, “Using the MQSeries utilities” on page 233.

When you have identified the queue or queues that you want to move to a new page set, follow this procedure for each of these queues:

1. Ensure that the queue to be moved is not in use by any applications, that is, the queue attributes IPPROCS and OPPROCS are zero.
2. Change the following queue attributes:
   - PUT(ENABLED)
   - GET(ENABLED)
3. Define a temporary queue with the same attributes as the queue that is being moved:

   ```
   DEFINE QL(TEMPQ) LIKE(Q_BEING_MOVED)
   ```

   Note: If this temporary queue already exists from a previous run, delete it before doing the define.
4. Prevent applications from putting messages on the queue being moved by altering the queue definition to disable **MQPUT**s. Change this queue attribute:
   - PUT(DISABLED)
5. Run the COPY (or SCOPY) function to off-load the messages to a data set. See “Copying queues into a data set while the queue manager is running (COPY)” on page 252.

   Note: Only committed messages will be copied.
6. Prevent applications from getting messages from the queue by altering the queue definition to disable **MQGET**s. Change this queue attribute:
   - GET(DISABLED)
7. Delete the queue you are moving, using the purge option to delete all messages associated with the queue.

   Note: The delete purge will fail if the queue is open for inquire, set, or browse, or if there are uncommitted messages on the queue.

8. Define a new storage class which maps to the required page set, for example:

   ```
   DEFINE STGCLASS(NEW) PSID(nn)
   ```

   Add the new storage class definition to CSQINP2 ready for the next MQSeries subsystem restart.

9. Redefine the queue that is being moved, changing the storage class attribute. When the queue is redefined, it is based on the temporary queue created in step 3 on page 336:

   ```
   DEFINE QL(Q_BEING_MOVED) LIKE(TEMPQ) STGCLASS(NEW)
   ```

10. The queue created in step 3 on page 336 is no longer required. Use the following command to delete it:

    ```
    DELETE QL(TEMPQ)
    ```

11. If the queue being moved was defined in the CSQINP2 concatenation, change the STGCLASS attribute of the appropriate DEFINE QLOCAL command in the CSQINP2 concatenation. Add the REPLACE keyword so that the existing queue definition is replaced.

12. Use the LOAD function to restore the messages onto the queue from the data set generated by the COPY or SCOPY function in step 5 on page 336.

Figure 96 shows an extract from a load balancing job.

```
//UTILITY  EXEC  PGM=CSQUTIL,PARM=('CSQ1')
//STEPLIB  DD    DSN=thlqual.SCSQANLE,DISP=SHR
//         DD    DSN=thlqual.SCSQAUTH,DISP=SHR
//OUTPUT   DD DSN=&&COPYMSG,
//            SPACE=(CYL,(5,1),RLSE),UNIT=SYSDA,
//            DCB=(RECFM=VBS,BLKSIZE=23200)
//SYSPRINT DD    SYSOUT=*
//SYSIN    DD    *
COMMAND DDNAME(PUTDIS)
COPY QUEUE(QUEUE_TO_MOVE) DDNAME(OUTPUT)
COMMAND DDNAME(DEFTEMP)
LOAD QUEUE(QUEUE_TO_MOVE) DDNAME(OUTPUT)
/*
//PUTDIS   DD    *
ALTER QL(QUEUE_TO_MOVE) GET(ENABLED) PUT(ENABLED)
DELETE QL(TEMP_QUEUE) PURGE
DEFINE QL(TEMP_QUEUE) LIKE(QUEUE_TO_MOVE)
ALTER QL(QUEUE_TO_MOVE) PUT(DISABLED)
/*
//DEFTEMP  DD    *
ALTER QL(QUEUE_TO_MOVE) GET(DISABLED)
DELETE QL(QUEUE_TO_MOVE) PURGE
DEFINE STGCLASS(NEW) PSID(2)
DEFINE QL(QUEUE_TO_MOVE) LIKE(TEMP_QUEUE) STGCLASS(NEW)
DELETE QL(TEMP_QUEUE)
/*
```

Figure 96. Extract from a load balancing job

How to reduce a page set

If you have a large page set that is mostly empty (as shown by the DISPLAY USAGE command), you might want to reduce its size. The procedure to do this involves using the COPY, EMPTY, RESETPAGE, FORMAT, LOAD, and COMMAND functions of CSQUTIL (see “MQSeries utility program (CSQUTIL)” on page 235). This procedure will not work for page set zero; it is not practical to reduce the size of this page set.

1. Prevent all users, other than the MQSeries administrator, from using the queue manager. This could be done by changing the access security settings for example.
2. Wait until all queue manager use has ended; you might have to stop and restart the queue manager to achieve this. (Remember that if you do this, you will lose all your nonpersistent messages.)
3. Run the COPY function of CSQUTIL with the PSID option to copy all message data from the large page set and save them in a sequential data set.
4. Run the EMPTY function of CSQUTIL with the PSID option to remove all messages from the page set. Use the `DISPLAY USAGE PSID(n)` command to verify that the page set is totally empty.
5. Use the `DISPLAY STGCLASS(*) PSID(n)` command to identify all storage classes that relate to the page set that is to be reduced in size.
6. Use the `DISPLAY QUEUE(*) TYPE(QLOCAL) STGCLASS` command to identify all queues that use any of the storage classes identified in step 5.
7. Alter each queue that you have identified to use a different storage class that maps to a different page set. This does not have to be a permanent change to the queue, but is essential for the queue manager to be able to restart. If you do not do this, you could get 00C91B01 abends when the queue manager attempts to start.

   Use the `ALTER QLOCAL(q-name) STGCLASS(stgcl-name)` command to alter the storage class attribute of each queue.
8. Use the `STOP QMGR` command with the `QUIESCE` or `FORCE` attribute to stop the queue manager.
9. Run the RESETPAGE function of CSQUTIL against all page sets other than the page set that is to be reduced in size. (You can choose to reset the page set in place, or you can copy and reset the page set.)
10. Define a new smaller page set data set to replace the large page set. Run the FORMAT function of CSQUTIL against it.
11. Define new log data sets (BSDS and active logs) with new data set names.
12. Restart the queue manager using the page sets created in steps 9 and 10 and the new BSDS and log data sets created in step 11.
13. Use the `ALTER QLOCAL(q-name) STGCLASS(stgcl-name)` command to reset the storage class attribute to the previous value for each queue altered in step 7.
14. Run the LOAD function of CSQUTIL to load back all the messages saved during step 3.
15. Allow all users access to the queue manager.

16. You can now delete the old large page set and the old BSDS and log data sets.

Backing up and recovering page sets

This section describes:

- "Creating a point of recovery"
- "Recovering page sets" on page 341

Creating a point of recovery

MQSeries can recover objects and persistent messages to their current state only if there is:

1. A copy of all page sets from an earlier point.
2. All the MQSeries logs since that point.

These represent a point of recovery.

Both objects and messages are held on page sets. Multiple objects and messages from different queues can exist on the same page set. Therefore, for recovery purposes, objects and messages cannot be backed up in isolation so that a page set must be backed up as a whole to ensure the proper recovery of the data.

The MQSeries recovery log contains a record of all persistent messages and changes made to objects. If MQSeries fails (for example, due to an I/O error on a page set), you can recover the page set by restoring the backup copy and restarting MQSeries. MQSeries applies the log changes to the page set from the point of the backup copy.

There are two ways of creating a point of recovery. The first involves stopping the queue manager thereby forcing all updates on to the page sets. The second involves taking 'fuzzy' backup copies of the page sets without stopping the queue manager.

The first will allow you to restart from the point of recovery, using only the backed up page set data sets and the logs from that point on.

If you use the second method, and your associated logs subsequently become damaged or lost you will not be able to use the fuzzy page set backup copies to recover. This is because the fuzzy page set backup copies contain an inconsistent view of the state of MQSeries and are dependent on the logs being available. If the logs are not available, you will have to return to the last set of backup page set copies taken while the subsystem was inactive (Method 1 below) and accept the loss of data from that time.

Method 1: Full backup

This method involves shutting MQSeries down. This forces all updates on to the page sets so that the page sets are in a consistent state.

1. Stop all MQSeries applications using the queue manager (allowing them to complete first). This could be done by changing the access security or queue settings, for example.
2. When all activity has completed, display and resolve any in-doubt units of recovery in the subsystem. (Use the MQSeries DISPLAY THREAD and

RESOLVE INDOUBT commands as described in the *MQSeries Command Reference* manual.)

This will bring the page sets to a consistent state; if you do not do this, or can't, your page sets might not be consistent, and you are effectively doing a "fuzzy" backup.

3. Issue the MQSeries command ARCHIVE LOG to ensure that the latest log data is written out to the log data sets.
4. Issue the MQSeries command STOP QMGR MODE(QUIESCE). Record the lowest RBA value in the CSQI024I or CSQI025I messages (see the *MQSeries for OS/390 Messages and Codes* manual for information about these messages). You should keep the log data sets starting from the one indicated by the RBA to the current one.
5. Take backup copies of the page sets (see "Backing up page sets").

Method 2: Fuzzy backup

This method does not involve shutting MQSeries down. Therefore, updates might be in virtual storage buffers during the backup process. This means that the page sets are not in a consistent state, and can only be used for recovery in conjunction with the logs.

1. Issue the MQSeries command DISPLAY USAGE and record the RBA value in the CSQI024I or CSQI205I message (see the *MQSeries for OS/390 Messages and Codes* manual for information about these messages).
2. Take backup copies of the page sets (see "Backing up page sets").
3. Issue the MQSeries command ARCHIVE LOG to ensure that the latest log data is written out to the log data sets. In order to restart from the point of recovery, you must keep copies of all the log data sets from that containing the recorded RBA value to that created by the ARCHIVE LOG command.

Backing up page sets

You can take a backup of your page sets in two ways:

- "Using Access Method Services"
- "Using volume dump and restore" on page 341.

To recover a page set, MQSeries needs to know how far back in the log to go. MQSeries maintains a log RBA number in page 0 of each page set, called the recovery log sequence number (LSN). This number is the starting RBA in the log from which MQSeries can recover the page set. When you back up a page set, this number is also copied.

If the copy is later used to recover the page set, MQSeries must have access to all of the log records from this RBA value to the current RBA. That means you must keep enough of the log records to enable MQSeries to recover from the oldest backup copy of a page set you intend to keep.

Using Access Method Services: You can use Access Method Services REPRO function (or any equivalent) to make copies of your page sets. You can do this whether or not MQSeries is running. If you want to do it while MQSeries is running, you must DEFINE the page sets with SHAREOPTIONS(2,3).

If you copy the page set while MQSeries is running you *must* use a copy utility that copies page 0 of the page set first – if you do not do this you could corrupt the data in your page set. Access Method Services REPRO meets this requirement.

If the process of dynamically expanding a page set is interrupted, for example by power to the system being lost, you can still use Access Method Services REPRO to take a backup of a page set.

If you perform an Access Method Services IDCAMS `LISTCAT ENT('page set data set name') ALLOC`, you will see that the `HI-ALLOC-RBA` will be higher than the `HI-USED-RBA`. Access Method Services REPRO will just copy the page set up to the high used RBA, and not give an error.

The next time this page set fills up it will be extended again, if possible, and the pages between the high used RBA and the highest allocated RBA will be used, along with another new extent.

For more information on the REPRO statement, see the *DFSMS/MVS Access Method Services for VSAM* or the *DFSMS/MVS Access Method Services for the Integrated Catalog Facility* manual.

Using volume dump and restore: Volume dump services dumps all the data sets on the volume. Likewise, restore volume services can (depending on the type of service) restore all the data sets.

Backing up your object definitions

You should also back up copies of your object definitions. To do this, use the MAKEDEF feature of the CSQUTIL COMMAND function (described in "MQSeries command management functions" on page 244).

You should do this whenever you take a backup copy of your queue manager, and keep the most current version.

Recovering page sets

If MQSeries has suffered a failure that has caused it to terminate, MQSeries can normally be restarted with all recovery being performed during restart. However, such recovery is not possible if any of your page sets or log data sets are not available. The extent to which you can now recover depends on the availability of backup copies of page sets and log data sets.

To restart from a point of recovery you must have:

- A backup copy of the page set that is to be recovered.
- If you used "fuzzy" backup, the log data set that included the recorded RBA value, the log data set that was made by the ARCHIVE LOG command, and all the log data sets between these.
- If you used full backup, but you do not have the log data set following that made by the ARCHIVE LOG command, you will need to use the RESETPAGE function of the CSQUTIL utility. The RBA identified using either method in "Creating a point of recovery" on page 339 is the restart point for the backed-up page sets. (Remember that to use the RESETPAGE function, MQSeries **must** have shut down cleanly.)

To recover a page set to its current state, you must also have all the log data sets and records since the ARCHIVE LOG command.

There are two methods for recovering a page set. To use either method, the queue manager must not be running.

Simple recovery

This is the simpler method, and is appropriate for most recovery situations.

1. Delete and redefine the page set you want to restore from backup.
2. Use Access Method Services REPRO to copy the backup copy of the page set into the new page set. You should define your new page set with a secondary extent value so that it can be expanded dynamically.

   Alternatively, you can rename your backup copy to the original name, or change the CSQP00xx DD statement in your queue manager procedure to point to your backup page set. However, if you then lose or corrupt the page set, you will no longer have a backup copy to restore from.
3. Restart the queue manager.
4. When the queue manager has restarted successfully, you can restart your applications
5. Reinstate your normal backup procedures for the restored page.

Advanced recovery

This method provides performance advantages if you have a large page set to recover, or if there has been a lot of activity on the page set since the last backup copy was taken. However, it requires more manual intervention than the simple method, which might increase the risk of error and the time taken to perform the recovery.

1. Delete and redefine the page set you want to restore from backup.
2. Use Access Method Services REPRO to copy the backup copy of the page set into the new page set. You should define your new page set with a secondary extent value so that it can be expanded dynamically.

   Alternatively, you can rename your backup copy to the original name, or change the CSQP00xx DD statement in your queue manager procedure to point to your backup page set. However, if you then lose or corrupt the page set, you will no longer have a backup copy to restore from.
3. Change the CSQINP1 definitions for your queue manager to make the buffer pool associated with the page set being recovered as large as possible. By making the buffer pool this large, you might be able to keep all of the changed pages resident in the buffer pool and reduce the amount of I/O to the page set.
4. Restart the queue manager.
5. When the queue manager has restarted successfully, stop it (using quiesce) and then restart it using the normal buffer pool definition for that page set. After this second restart completes successfully, you can restart your applications
6. Reinstate your normal backup procedures for the restored page.

What happens when MQSeries is restarted

When MQSeries is restarted, it applies all changes made to the page set that are registered in the log, beginning at the restart point for the page set. MQSeries can recover multiple page sets in this way. The page set will be dynamically expanded, if required, during media recovery.

During restart MQSeries determines the log RBA to start from by taking the lowest value from the following:

- Recovery LSN from the checkpoint log record for each page set.
- Recovery LSN from page 0 in each page set.
- The RBA of the oldest incomplete unit of recovery in the system at the time the backup was taken.

All object definitions are stored on page set 0. Messages can be stored on any available page set.

Note: MQSeries cannot restart if page set 0 is not available.

Backing up and restoring queues using CSQUTIL

You can use the CSQUTIL utility functions for backing up and restoring queues. To back up a queue, use the COPY or SCOPY function to copy the messages from a queue onto a data set. To restore the queue, use the complementary function LOAD. For more information, see “MQSeries utility program (CSQUTIL)” on page 235.

Backing up and restoring using CSQUTIL

Chapter 21. Example recovery scenarios

This chapter describes procedures for recovering MQSeries after various error conditions. These error conditions are grouped in the following categories:

- "Active log problems" on page 346
- "Archive log problems" on page 353
- "BSDS errors" on page 356
- "Page set problems" on page 361
- "Dealing with long running units of work" on page 363
- "IMS-related problems" on page 364
- "Hardware errors" on page 366

When the MQSeries subsystem encounters a problem, it issues a message. Table 21 describes such problems, mostly identified by message number, and suggests solutions to enable recovery from each one.

Some of these procedures have been updated by APAR PQ28083.

Table 21 (Page 1 of 2). Example recovery scenarios

Message or symptom	Error condition	Where to look next
CSQJ004I	Dual logging is lost.	"Active log problems" on page 346
CSQJ030E	Active log has stopped.	"Active log problems" on page 346
CSQJ100E	Error opening BSDS.	"BSDS errors" on page 356
CSQJ102E	Log content does not correspond with BSDS information.	"BSDS errors" on page 356
CSQJ102E CSQJ232E	One or both copies of the active log data set are damaged.	"Active log problems" on page 346
CSQJ103E	Archive data set allocation problem.	"Archive log problems" on page 353
CSQJ105E	Write errors on active log data set.	"Active log problems" on page 346
CSQJ106E	Read errors on active log data set.	"Active log problems" on page 346
CSQJ107E CSQJ117E CSQJ119E	Both copies of the BSDS are damaged.	"BSDS errors" on page 356
CSQJ110E CSQJ111A	Active log is full or is becoming full.	"Active log problems" on page 346
CSQJ120E	Unequal time stamps.	"BSDS errors" on page 356
CSQJ122E	Dual BSDS data sets are out of synchronization.	"BSDS errors" on page 356

© Copyright IBM Corp. 1993,1999

Table 21 (Page 2 of 2). Example recovery scenarios

Message or symptom	Error condition	Where to look next
CSQJ126E, followed by either CSQJ107E or CSQJ108E	I/O error on BSDS.	"BSDS errors" on page 356
CSQJ128E, preceded by IEC030I, IEC031I, or IEC032I	Insufficient DASD space to complete off-loading active log data sets.	"Archive log problems" on page 353
OS/390 error recovery program message and CSQJ128E	Off-load task has terminated abnormally, possibly due to write I/O errors.	"Archive log problems" on page 353
CSQP004E, and MQSeries terminates abnormally	A page set has an I/O error.	"Page set problems" on page 361
CSQQ001I, CSQQ002E through CSQQ007E	The IMS adapter cannot connect to MQSeries.	"IMS-related problems" on page 364
CSQR020I	A long-running unit of work is encountered.	"Dealing with long running units of work" on page 363
DFS555I	An IMS application terminates abnormally.	"IMS-related problems" on page 364
MQRC_PAGESET_FULL returned on **MQPUT**, **MQPUT1**, or **MQOPEN** calls, or on object manipulation commands	Insufficient space on the page set to complete the request.	"Page set problems" on page 361

Active log problems

This section covers some of the more likely active log problems:

- "CSQJ004I, dual logging is lost"
- "CSQJ030E, active log stopped" on page 347
- "CSQJ102E and CSQJ232E, one or both copies of the active log data set are damaged" on page 348
- "CSQJ105E, write I/O errors on an active log data set" on page 349
- "CSQJ106E, I/O errors occur while reading the active log" on page 349
- "CSQJ110E and CSQJ111A, active log is full or is becoming full" on page 351

CSQJ004I, dual logging is lost

Symptoms

MQSeries issues the following message:

```
CSQJ004I +cpf ACTIVE LOG COPY n INACTIVE, LOG IN SINGLE MODE,
          ENDRBA=...
```

Having completed one active log data set, MQSeries found that the subsequent (COPY n) data sets were not off-loaded or were marked stopped.

System action

MQSeries continues in single mode until off-loading has been completed, then returns to dual mode.

System programmer action

None.

Operator action

Check that the off-load is proceeding and is not waiting for a tape mount. It might be necessary to run the print log map utility to determine the state of all data sets. It might also be necessary to define additional data sets.

CSQJ030E, active log stopped

Symptoms

MQSeries issues the following message :

```
CSQJ030E +cpf RBA RANGE startrba TO endrba NOT AVAILABLE IN ACTIVE
          LOG DATA SETS
```

System action

The active log data sets that contain the RBA range reported in message CSQJ030E are unavailable to MQSeries. The status of these logs is STOPPED in the BSDS. MQSeries will terminate with a dump.

System programmer action

This problem must be resolved before restarting MQSeries. The log RBA range must be available for MQSeries to be recoverable. An active log that is marked as STOPPED in the BSDS will never be reused or archived and this will create a hole in the log.

Look for messages that indicate why the log data set has stopped, and follow the instructions for those messages.

The BSDS active log inventory needs to be modified to reset the STOPPED status. To do this, follow this procedure after MQSeries has terminated:

1. Use the print log utility (CSQJU004) to obtain a copy of the BSDS log inventory. This shows the status of the log data sets.
2. Use the DELETE function of the change log inventory utility (CSQJU003) to delete the active log data sets that are marked as STOPPED.
3. Use the NEWLOG function of CSQJU003 to add the active logs back into the BSDS inventory. The starting and ending RBA for each active log data set must be specified on the NEWLOG statement. (The correct values to use can be found from the print log utility report obtained in Step 1.)
4. Rerun CSQJU004. The active log data sets that were marked as STOPPED will now be shown as NEW and NOT REUSABLE. These active logs will be archived in due course.
5. Restart MQSeries.

Note: If your MQSeries subsystem is running in dual BSDS mode, you must update both BSDS inventories.

CSQJ102E and CSQJ232E, one or both copies of the active log data set are damaged

Symptoms

MQSeries issues the following messages:

```
CSQJ102E +cpf LOG RBA CONTENT OF LOG DATA SET DSNAME=...,
           STARTRBA=..., ENDRBA=...,
           DOES NOT AGREE WITH BSDS INFORMATION
CSQJ232E +cpf OUTPUT DATA SET CONTROL INITIALIZATION PROCESS FAILED
```

System action

MQSeries startup processing is terminated.

System programmer action

If one copy of the data set is damaged, carry out these steps:

1. Rename the damaged active log data set and define a replacement data set.
2. Copy the undamaged data set to the replacement data set.
3. Use the change log inventory utility to:
   - Remove information relating to the damaged data set from the BSDS.
   - Add information relating to the replacement data set to the BSDS.
4. Restart MQSeries.

If both copies of the active log data sets are damaged, the current page sets are available, **and MQSeries shut down cleanly**, carry out these steps:

1. Rename the damaged active log data sets and define replacement data sets.
2. Use the change log records utility to:
   - Remove information relating to the damaged data set from the BSDS.
   - Add information relating to the replacement data set to the BSDS.
3. Rename the current page sets and define replacement page sets.
4. Use CSQUTIL (FORMAT and RESETPAGE) to format the replacement page sets and copy the renamed page sets to them. The RESETPAGE function also resets the log information in the replacement page sets.

If MQSeries did not shut down cleanly, you must either restore your system from a previous known point of consistency, or perform a cold start (described in “Performing a cold start of MQSeries” on page 368).

Operator action

None.

CSQJ105E, write I/O errors on an active log data set

Symptoms

MQSeries issues the following message:

```
CSQJ105E +cpf csect-name LOG WRITE ERROR DSNAME=...,
          LOGRBA=..., ERROR STATUS=ccccffss
```

System action

MQSeries carries out these steps:

1. Marks the log data set that has the error as TRUNCATED in the BSDS.
2. Goes on to the next available data set.
3. If dual active logging is used, truncates the other copy at the same point.

The data in the truncated data set is off-loaded later, as usual.

The data set is not *stopped* and is reused on the next cycle.

System programmer action

None.

Operator action

If errors on this data set still exist, take MQSeries down after the next off-load. Then use Access Method Services (AMS) and the change log inventory utility to add a replacement. (For instructions, see "Changing the BSDS" on page 327.)

CSQJ106E, I/O errors occur while reading the active log

Symptoms

MQSeries issues the following message:

```
CSQJ106E +cpf LOG READ ERROR DSNAME=..., LOGRBA=...,
          ERROR STATUS=ccccffss
```

System action

This depends on when the error occurred:

- If the error occurs during the off-load process, the process tries to read the RBA range from a second copy.
  - If no second copy exists, the active log data set is stopped.
  - If the second copy also has an error, only the original data set that triggered the off-load is stopped. The archive log data set is then terminated, leaving a gap in the archived log RBA range.
  - This message is issued:

    ```
    CSQJ124E +cpf OFFLOAD OF ACTIVE LOG SUSPENDED FROM
               RBA xxxxxx TO RBA xxxxxx DUE TO I/O ERROR
    ```

  - If the second copy is satisfactory, the first copy is not stopped.
- If the error occurs during recovery, MQSeries provides data from specific log RBAs requested from another copy or archive. If this is unsuccessful, recovery does not succeed, and MQSeries terminates abnormally.
- If the error occurs during restart, MQSeries terminates. All the copies of the active log data sets must be available to MQSeries.

System programmer action

Look for system messages, such as IEC prefixed messages, and try to resolve the problem using the recommended actions for these messages.

If the active log data set has been stopped, it is not used for logging. The data set is not deallocated; it is still used for reading. Even if the data set is not stopped, an active log data set that gives persistent errors should nevertheless be replaced.

Operator action

None. You are not told explicitly whether the data set has been stopped.

Replacing the data set

How you replace the data set depends on whether you are using single or dual active logging.

If you are using dual active logging:

1. Ensure that the data has been saved.

   The data is saved on the other active log and this can be copied to a replacement active log.

2. Stop MQSeries and delete the data set in error using Access Method Services.
3. Redefine a new log data set using Access Method Services DEFINE so that you can write to it. Use DFDSS or Access Method Services REPRO to copy the good log into the redefined data set so that you have two consistent, correct logs again.
4. Use the change log inventory utility, CSQJU003, to update the information in the BSDS about the corrupt data set as follows:
   a. Use the DELETE function to remove information about the corrupt data set.
   b. Use the NEWLOG function to name the new data set as the new active log data set and give it the RBA range that was successfully copied.

      The DELETE and NEWLOG functions can be run in the same job step. Put the DELETE statement before NEWLOG statement in the SYSIN input data set.
5. Restart MQSeries.

If you are using single active logging:

1. Ensure that the data has been saved.
2. Stop MQSeries.
3. Determine whether the data set with the error has been off-loaded:
   a. Use the CSQJU003 utility to list information about the archive log data sets from the BSDS.
   b. Search the list for a data set whose RBA range includes the RBA of the corrupt data set.
4. If the corrupt data set has been off-loaded, copy its backup in the archive log to a new data set. Then, skip to step 6.

5. If an active log data set is stopped, an RBA is not off-loaded. Use DFDSS or Access Method Services REPRO to copy the data from the corrupt data set to a new data set.

   If further I/O errors prevent you from copying the entire data set, a gap occurs in the log.

   Note: MQSeries restart will not be successful if a gap in the log is detected.

6. Use the change log inventory utility, CSQJU003, to update the information in the BSDS about the corrupt data set as follows:

   a. Use the DELETE function to remove information about the corrupt data set.

   b. Use the NEWLOG function to name the new data set as the new active log data set and to give it the RBA range that was successfully copied.

      The DELETE and NEWLOG functions can be run in the same job step. Put the DELETE statement before NEWLOG statement in the SYSIN input data set.

7. Restart MQSeries.

CSQJ110E and CSQJ111A, active log is full or is becoming full

The active log can fill up for several reasons, for example, delays in off-loading and excessive logging.

Symptoms

An out-of-space condition on the active log has serious consequences. When the active log becomes full, the MQSeries subsystem halts processing until an off-load has been completed. If the off-load processing stops when the active log is full, the MQSeries subsystem can abend. Corrective action is required before MQSeries can be restarted.

Because of the serious implications of this event, the MQSeries subsystem issues the following warning message when the last available active log data set is 75% full:

```
CSQJ110E +cpf LAST COPYn ACTIVE LOG DATA SET IS nnn PERCENT FULL
```

and reissues the message after each additional 5% of the data set space is filled. Each time the message is issued, the off-load process is started.

If the active log fills to capacity, MQSeries issues the following message:

```
CSQJ111A +cpf OUT OF SPACE IN ACTIVE LOG DATA SETS
```

and an off-load is started. The MQSeries subsystem then halts processing until an off-load has been completed.

System action

MQSeries waits for an available active log data set before resuming normal MQSeries processing. Normal shutdown, with either QUIESCE or FORCE, is not possible because the shutdown sequence requires log space to record system events related to shutdown (for example, checkpoint records). If the off-load processing stops when the active log is full, MQSeries forces itself to stop using an X'6C6' abend; restart in this case requires special attention. For more details, see the *MQSeries for OS/390 Problem Determination Guide*.

System programmer action

Additional active log data sets can be provided as required before restarting MQSeries. This permits MQSeries to continue its normal operation while the error causing the off-load problems is corrected. To add new active log data sets, use the change log inventory utility (CSQJU003) when MQSeries is not active. For more details about adding new active log data sets, see "Changing the BSDS" on page 327.

You should also consider increasing the number of logs by:

1. Making sure MQSeries is stopped, then using the Access Method Services DEFINE command to define a new active log data set.
2. Defining the new active log data set in the BSDS using the change log inventory utility (CSQJU003).

Restarting MQSeries: off-load starts automatically during startup, and work in progress when MQSeries was forced to stop is recovered.

Operator action

Check whether the off-load process is waiting for a tape drive. If it is, mount the tape. If you cannot mount the tape, force MQSeries to stop by using OS/390 CANCEL.

Archive log problems

This section covers the most likely archive log problems:

- "CSQJ103E, allocation problems"
- "CSQJ128E, off-load task terminated abnormally"
- "CSQJ128E, insufficient DASD space to complete off-load processing" on page 354
- "Read I/O errors on the archive data set while MQSeries is restarting" on page 355

CSQJ103E, allocation problems

Symptoms

MQSeries issues the following message:

```
CSQJ103E +cpf LOG ALLOCATION ERROR DSNAME=dsname,
          ERROR STATUS=eeeeiiii
```

OS/390 dynamic allocation provides the ERROR STATUS. If the allocation was for off-load processing, the following message is also displayed:

```
CSQJ115E +cpf OFFLOAD FAILED, COULD NOT ALLOCATE AN ARCHIVE
          DATA SET
```

System action

The following actions take place:

- If the input is needed for recovery, recovery is not successful, and MQSeries will abend.
- If the active log had become full and an off-load was scheduled but not completed, off-load tries again the next time it is triggered. The active log does not reuse a data set that has not yet been archived.

System programmer action

None.

Operator action

Check the allocation error code for the cause of the problem, and correct it. Ensure that drives are available, and either restart or wait for the off-load to be retried. Be careful if a DFP/DFSMS ACS user-exit filter has been written for an archive log data set, because this can cause a device allocation error when the MQSeries subsystem tries to read the archive log data set. For details of how to solve this problem, see "Archiving to DASD volumes" on page 316.

CSQJ128E, off-load task terminated abnormally

Symptoms

No specific MQSeries message is issued for write I/O errors.

Only an OS/390 error recovery program message appears. If you get MQSeries message CSQJ128E, the off-load task has terminated abnormally and you should consult the *MQSeries for OS/390 Messages and Codes* manual.

System action

The following actions take place:

- Off-load abandons the output data set; no entry is made in the BSDS.
- Off-load dynamically allocates a new archive and restarts off-loading from the point at which it was previously triggered.
- If an error occurs on the new data set, then:
  - In dual archive mode, this message is generated and the off-load processing changes to single mode:

    ```
    CSQJ114I +cpf ERROR ON ARCHIVE DATA SET, OFFLOAD
              CONTINUING WITH ONLY ONE ARCHIVE DATA SET BEING
              GENERATED
    ```

  - In single archive mode, the output data set is abandoned. Another attempt to off-load this RBA range is made the next time off-load is triggered.
  - The active log does not wrap around; if there are no more active logs, data is not lost.

System programmer action

None.

Operator action

Ensure that off-load is allocated on a reliable drive and control unit.

CSQJ128E, insufficient DASD space to complete off-load processing

Symptoms

While off-loading the active log data sets to DASD, the process terminates unexpectedly. MQSeries issues the following message:

```
CSQJ128E +cpf LOG OFF-LOAD TASK FAILED FOR ACTIVE LOG nnnnn
```

The error is preceded by OS/390 messages IEC030I, IEC031I, or IEC032I.

System action

MQSeries de-allocates the data set on which the error occurred. If MQSeries is running in dual archive mode, MQSeries changes to single archive mode and continues the off-load. If the off-load cannot be completed in single archive mode, the active log data sets cannot be off-loaded, and the state of the active log data sets remains NOT REUSABLE. Another attempt to off-load the RBA range of the abandoned active log data sets is made the next time the off-load process is triggered.

System programmer action

Quiesce the MQSeries subsystem (using `+cpf STOP QMGR MODE(QUIESCE)`) to restrict logging activity until the OS/390 abend is resolved.

The most likely causes of these symptoms are:

- The size of the archive log data set is too small to contain the data from the active log data sets during off-load processing. All the secondary space allocations have been used. This condition is normally accompanied by OS/390 message IEC030I.

To solve the problem, either increase the primary or secondary allocations (or both) for the archive log data set (in CSQZPARM), or reduce the size of the active log data set. If the data to be off-loaded is particularly large, you can mount another online storage volume or make one available to MQSeries.

- All available space on the DASD volumes to which the archive data set is being written has been exhausted. This condition is normally accompanied by OS/390 message IEC032I.

  To solve the problem, make more space available on the DASD volumes, or make available another online storage volume for MQSeries.

- The primary space allocation for the archive log data set (as specified in CSQZPARM) is too large to allocate to any available online DASD device. This condition is normally accompanied by OS/390 message IEC032I.

  To solve the problem, make more space available on the DASD volumes, or make available another online storage volume for MQSeries. If this is not possible, you must adjust the value of PRIQTY in CSQ6ARVP to reduce the primary allocation. (For details, see "Using CSQ6ARVP" on page 79.)

  Note: If the primary allocation is reduced, the size of the secondary space allocation might have to be increased to avoid future abends.

Operator action

None.

Read I/O errors on the archive data set while MQSeries is restarting

Symptoms

No specific MQSeries message is issued; only the OS/390 error recovery program message appears.

System action

This depends on whether a second copy exists:

- If a second copy exists, it is allocated and used.
- If a second copy does not exist, restart is not successful.

System programmer action

None.

Operator action

Try to restart, using a different drive.

BSDS errors

For background information about the bootstrap data set (BSDS), see “What the bootstrap data set is for” on page 311.

This section describes the more likely BSDS problems:

- “CSQJ100E, error occurs while opening the BSDS”
- “CSQJ102E, log content does not agree with the BSDS information” on page 357
- “CSQJ107E, CSQJ117E, and CSQJ119E, both copies of the BSDS are damaged” on page 357
- “CSQJ120E, unequal time stamps” on page 358
- “CSQJ122E, out of synchronization” on page 359
- “CSQJ126E, I/O error” on page 359

Normally, there are two copies of the BSDS, but if one is damaged, MQSeries immediately changes to single BSDS mode. However, the damaged copy of the BSDS must be recovered before restart. If you are in single mode and damage the only copy of the BSDS, or if you are in dual mode and damage both copies, see “BSDS recovery” on page 330.

This section covers some of the BSDS problems that can occur at startup. Problems *not* covered here include:

- `+cpf` RECOVER BSDS command errors (messages CSQJ301E - CSQJ307I)
- Change log inventory utility errors (message CSQJ123E)
- Errors in the BSDS backup being dumped by off-load (message CSQJ125E)

For information about those problems, see the *MQSeries for OS/390 Messages and Codes* manual.

CSQJ100E, error occurs while opening the BSDS

Symptoms

MQSeries issues the following message:

`CSQJ100E +cpf ERROR OPENING BSDS`*`n`* `DSNAME=...,` `ERROR STATUS=`*`eeii`*

where *eeii* is the VSAM return code. For information about VSAM codes, see the *DFSMS/MVS Macro Instructions for Data Sets* manual. For an explanation of this message, see the *MQSeries for OS/390 Messages and Codes* manual.

System action

During system initialization, the startup is terminated.

During a `+cpf` RECOVER BSDS command, the system continues in single BSDS mode.

System programmer action

None.

Operator action

Carry out these steps:

1. Run the print log map utility on both copies of the BSDS, and compare the lists to determine which copy is accurate or current.
2. Rename the data set that had the problem, and define a replacement for it.
3. Copy the accurate data set to the replacement data set, using Access Method Services.
4. Restart MQSeries.

CSQJ102E, log content does not agree with the BSDS information

Symptoms

MQSeries issues the following message:

```
CSQJ102E +cpf LOG RBA CONTENT OF LOG DATA SET DSNAME=...,
           STARTRBA=..., ENDRBA=...,
           DOES NOT AGREE WITH BSDS INFORMATION
```

This message indicates that the change log inventory utility was used incorrectly or that a down-level data set is being used.

System action

MQSeries startup processing is terminated.

System programmer action

None.

Operator action

Run the print log map utility and the change log inventory utility to print and correct the contents of the BSDS.

CSQJ107E, CSQJ117E, and CSQJ119E, both copies of the BSDS are damaged

Symptoms

MQSeries issues the following messages:

```
CSQJ107E +cpf READ ERROR ON BSDS
           DSNAME=... ERROR STATUS=0874
CSQJ117E +cpf REG8 INITIALIZATION ERROR READING BSDS
           DSNAME=... ERROR STATUS=0874
CSQJ119E +cpf BOOTSTRAP ACCESS INITIALIZATION PROCESSING FAILED
```

System action

MQSeries startup processing is terminated.

System programmer action

Carry out these steps:

1. Rename the data set, and define a replacement for it.
2. Locate the BSDS associated with the most recent archive log data set, and copy it to the replacement data set.
3. Use the print log map utility to print the contents of the replacement BSDS.

4. Use the print log records utility to print a summary report of the active log data sets missing from the replacement BSDS, and to establish the RBA range.
5. Use the change log inventory utility to update the missing active log data set inventory in the replacement BSDS.
6. If dual BSDS data sets had been in use, copy the updated BSDS to the second copy of the BSDS.
7. Restart MQSeries.

Operator action

None.

CSQJ120E, unequal time stamps

Symptoms

MQSeries issues the following message:

```
CSQJ120E +cpf DUAL BSDS DATA SETS HAVE UNEQUAL TIME STAMPS,
           SYSTEM BSDS1=...,BSDS2=...,
           UTILITY BSDS1=...,BSDS2=...
```

The possible causes are:

- One copy of the BSDS has been restored. All information on the restored BSDS is down-level. The down-level BSDS has the lower time stamp.
- One of the volumes containing the BSDS has been restored. All information on the restored volume is down-level. If the volume contains any active log data sets or MQSeries data, they are also down-level. The down-level volume has the lower time stamp.
- Dual logging has degraded to single logging, and you are trying to start without recovering the damaged log.
- The MQSeries subsystem terminated abnormally after updating one copy of the BSDS but before updating the second copy.

System action

MQSeries startup is terminated.

System programmer action

None.

Operator action

Carry out these steps:

1. Run the print log map utility on both copies of the BSDS, compare the lists to determine which copy is accurate or current.
2. Rename the down-level data set and define a replacement for it.
3. Copy the good data set to the replacement data set, using Access Method Services.
4. If applicable, determine whether the volume containing the down-level BSDS has been restored. If it has been restored, all data on that volume, such as the active log data, is also down-level.

   If the restored volume contains active log data and you were using dual active logs on separate volumes, you need to copy the current

version of the active log to the down-level log data set. “Recovering logs” on page 332 tells you how to do this.

CSQJ122E, out of synchronization

Symptoms

MQSeries issues the following message:

```
CSQJ122E +cpf DUAL BSDS DATA SETS ARE OUT OF SYNCHRONIZATION
```

The system time stamps of the two data sets are identical. Differences can exist if operator errors occurred while the change log inventory utility was being used. (For example, the change log inventory utility was only run on one copy.) The change log inventory utility sets a private time stamp in the BSDS control record when it starts, and a close flag when it ends. MQSeries checks the change log inventory utility time stamps and, if they are different, or they are the same but one close flag is not set, MQSeries compares the copies of the BSDSs. If the copies are different, CSQJ122E is issued.

System action

MQSeries startup is terminated.

System programmer action

None.

Operator action

Carry out these steps:

1. Run the print log map utility on both copies of the BSDS, and compare the lists to determine which copy is accurate or current.
2. Rename the data set that had the problem, and define a replacement for it.
3. Copy the accurate data set to the replacement data set, using access method services.
4. Restart MQSeries.

CSQJ126E, I/O error

Symptoms

MQSeries changes to single BSDS mode and issues the user message:

```
CSQJ126E +cpf BSDS ERROR FORCED SINGLE BSDS MODE
```

This is followed by one of these messages:

```
CSQJ107E +cpf READ ERROR ON BSDS
           DSNAME=... ERROR STATUS=...

CSQJ108E +cpf WRITE ERROR ON BSDS
           DSNAME=... ERROR STATUS=...
```

System action

The BSDS mode changes from dual to single.

System programmer action

None.

Operator action

Carry out these steps:

1. Use Access Method Services to rename or delete the damaged BSDS and to define a new BSDS with the same name as the BSDS that had the error. Control statements can be found in job CSQ4BSDS in thlqual.SCSQPROC.
2. Issue the MQSeries command `+cpf` RECOVER BSDS to make a copy of the good BSDS in the newly allocated data set and reinstate dual BSDS mode. See also “BSDS recovery” on page 330.

Page set problems

This section covers the problems that you might encounter with page sets:

- "CSQP004E, page set I/O errors" describes what happens if a page set is damaged.
- "Page set full" on page 362 describes what happens if there is not enough space on the page set for any more MQI operations.

CSQP004E, page set I/O errors

Problem A page set has an I/O error.

Symptoms

This message is issued:

```
CSQP004E +cpf csect-name I/O ERROR STATUS ret-code
PSID psid RBA rba
```

System action

MQSeries terminates abnormally.

System programmer action

None.

Operator action

Repair the I/O error cause.

If none of the page sets are damaged, restart MQSeries. MQSeries automatically restores the page set to a consistent state from the logs.

If one or more page sets are damaged:

1. Rename the damaged page sets and define replacement page sets.
2. Copy the most recent backup page sets to the replacement page sets.
3. Restart MQSeries. MQSeries automatically applies any updates that are necessary from the logs.

You cannot restart MQSeries if page set zero is not available. However, if one of the other page sets is not available, you can comment out the page set DD statement in the MQSeries start-up JCL procedure. This lets you defer recovery of the defective page set, enabling other users to continue accessing MQSeries.

When you add the page set back to the JCL procedure, system restart will read the log from the point where the page set was removed from the JCL to the end of the log. This could take a long time if a lot of data has been logged.

A reason code of MQRC_PAGESET_ERROR is returned to any application that tries to access a queue defined on a page set that is not available. When you have restored the defective page set, restore its associated DD statement and restart MQSeries.

The operator actions described here are only possible if all log data sets are available. If your log data sets are lost or damaged, see "Restarting if you have lost your log data sets" on page 367.

Page set full

Problem

There is not enough space on a page set for one of the following:

- **MQPUT** or **MQPUT1** calls to be completed
- Object manipulation commands to be completed (for example, DEFINE QLOCAL)
- **MQOPEN** calls for dynamic queues to be completed

Symptoms

The request fails with reason code MQRC_PAGESET_FULL. The queue manager is unable to complete the request because, there is not enough space remaining on the page set.

The cause of this problem could be due to messages accumulating on a transmission queue because they cannot be sent to another system.

System action

Further requests that use this page set are blocked until enough messages are removed or objects deleted to make room for the new incoming requests.

Operator action

Use the MQSeries command DISPLAY USAGE PSID(*) to identify which page set is full.

System programmer action

You can either enlarge the page set involved or reduce the loading on that page set by moving queues to another page set. See Chapter 20, “Managing page sets” on page 333 for more information about these tasks. If the cause of the problem is messages accumulating on the transmission queue, consider starting distributed queuing to transmit the messages.

Dealing with long running units of work

This section explains what to do if you encounter a long-running unit of work during restart. In this context, this means a unit of work that has been active for a long period of time (possibly days or even weeks) so that the origin RBA of the unit of work is outside the scope of the current active logs. This means that restart could take a long time, because all of the log records relating to the unit of work have to be read, which might involve reading archive logs.

CSQR020I, old unit of work found

To use this function, you need to apply APAR PQ27752.

Problem A unit of work with an origin RBA that predates the oldest active log has been detected during restart.

Symptoms

MQSeries issues the following message:

```
CSQR020I +cpf OLD UOW FOUND
```

System action

Information about the unit of work is displayed, and message CSQR021D is issued, requesting a response from the operator.

System programmer action

None.

Operator action

Decide whether to commit the unit of work or not. If you choose not to commit the unit of work, it will be handled by normal restart recovery processing. Because the unit of work is old, this is likely to involve using the archive log, and so will take longer to complete.

IMS-related problems

This section includes plans for problems that you might encounter in the IMS environment:

- "CSQQ001I, CSQQ002E through CSQQ007E, IMS is unable to connect to MQSeries"
- "DFS555I message, IMS application problem"
- "IMS is not operational" on page 365

CSQQ001I, CSQQ002E through CSQQ007E, IMS is unable to connect to MQSeries

Problem

The IMS adapter cannot connect to MQSeries.

Symptoms

IMS remains operative. The IMS adapter issues these messages for control region connect:

CSQQ001I
CSQQ002E
CSQQ003E
CSQQ004E
CSQQ005E
CSQQ007E

For details, see the *MQSeries for OS/390 Messages and Codes* manual.

If an IMS application program tries to access MQSeries while the IMS adapter cannot connect, it can either receive a completion code and reason code or terminate abnormally. This depends on the value of the REO option in the SSM member of IMS PROCLIB.

System action

All connection errors are also reported in the IMS message DFS3611.

System programmer action

None.

Operator action

Analyze and correct the problem, then restart the connection with the IMS command:

```
/START SUBSYS subsysname
```

IMS requests the adapter to resolve in-doubt units of recovery.

DFS555I message, IMS application problem

Problem

An IMS application terminates abnormally.

Symptoms

The following message is sent to the user's terminal:

```
DFS555I  TRANSACTION tranid ABEND abcode
MSG IN PROCESS: message data:
```

where *tranid* represents any IMS transaction that is terminating abnormally and *abcode* is the abend code.

System action
IMS requests the adapter to resolve the unit of recovery. IMS remains connected to MQSeries.

System programmer action
None.

Operator action
As indicated in message DFS554A on the IMS master terminal.

IMS is not operational

Problem
IMS is not operational.

Symptoms
More than one symptom is possible:

- IMS waits or loops

  Because MQSeries cannot detect a wait or loop in IMS, you must find the origin of the wait or loop. This can be IMS, IMS applications, or the IMS adapter.

- IMS terminates abnormally.
  - See the manuals *IMS/ESA Messages and Codes* and *IMS/ESA Failure Analysis Structure Tables* for more information.
  - If threads are connected to MQSeries when IMS terminates, MQSeries issues message CSQ3201E. This message indicates that MQSeries end-of-task (EOT) routines have been run to clean up and disconnect any connected threads.

System action
MQSeries detects the IMS error and:

- Backs out in-flight work.
- Saves in-doubt units of recovery to be resolved when IMS is reconnected.

System programmer action
None.

Operator action
Resolve and correct the problem that caused IMS to terminate abnormally, then carry out an emergency restart of IMS. The emergency restart:

- Backs out in-flight transactions that changed IMS resources.
- Remembers the transactions with access to MQSeries that might be in doubt.

It might be necessary to restart the connection to MQSeries with the IMS command:

```
/START SUBSYS subsysname
```

During startup, IMS requests the adapter to resolve in-doubt units of recovery.

Hardware errors

If a hardware error causes data to be unreadable on your subsystem, MQSeries can still be recovered by using the *media recovery* technique:

1. To recover the data, you need a backup copy of the data. Use DFDSS or Access Method Services REPRO regularly to make a copy of your data.
2. Reinstate the most recent backup copy.
3. Restart MQSeries.

The more recent your backup copy, the more quickly your subsystem can be made available again.

When MQSeries restarts, it uses the archive logs to reinstate changes made since the backup copy was taken. You must keep sufficient archive logs to enable MQSeries to reinstate the subsystem fully. Do not delete archive logs until there is a backup copy that includes all the changes in the log.

Restarting if you have lost your log data sets

If, after stopping MQSeries (using the STOP QMGR command), both copies of the log are lost or found to be corrupt, it is possible to restart MQSeries providing you have a consistent set of page sets (produced using “Method 1: Full backup” on page 339).

Follow this procedure:

1. Define new page sets to correspond to each existing page set in your MQSeries subsystem. See “Task 12: Define your page sets” on page 63 for information about page set definition.

   Ensure that each new page set is larger than the corresponding source page set.

2. Use the FORMAT function of CSQUTIL to format the destination page set. See “Formatting page sets (FORMAT)” on page 237 for more details.

3. Use the RESETPAGE function of CSQUTIL to copy the existing page sets or reset them in place, and reset the log RBA in each page. (Remember that to use the RESETPAGE function, MQSeries **must** have shut down cleanly.) See “Copying a page set and resetting the log (RESETPAGE)” on page 241 for more information about this function.

4. Redefine your MQSeries log data sets and BSDS using CSQJU003 (see “The change log inventory utility (CSQJU003)” on page 262).

5. Restart MQSeries, using the new page sets. To do this, you do one of the following:

   - Change the MQSeries startup procedure to reference the new page sets. See “Task 12: Define your page sets” on page 63 for more details.
   - Use Access Method Services to delete the old page sets and then rename the new page sets, giving them the same names as the old page sets.

Attention: Before you delete any MQSeries page set, be sure that you have made the required backup copies.

Performing a cold start of MQSeries

If MQSeries has terminated abnormally you might not be able to restart it. This could be because your page sets or logs have been lost, truncated, or corrupted. If this has happened, you will have to perform a *cold start* to restart MQSeries.

Attention

Performing a cold start will enable you to recover your MQSeries system and your object definitions; you will **not** be able to recover your message data. This means that you should only perform a cold start if you are unable to restart MQSeries any other way.

When you have successfully restarted, all your MQSeries objects will be defined and available for use, but there will be no message data.

To cold start MQSeries, follow this procedure:

1. Prepare the object definition statements that will be used when you restart MQSeries. To do this, either:
   - If page set zero is available, use the CSQUTIL SDEFS function (see "Producing a list of MQSeries define commands (SDEFS)" on page 249)
   - If page set zero is not available, use the definitions from the last time you backed up your object definitions (see "Backing up your object definitions" on page 315)
2. Redefine your queue manager data sets (do not do this until you have completed step 1).
   - See "Task 11: Create the bootstrap and log data sets" on page 61 for information about redefining your log data sets and BSDS.
   - See "Task 12: Define your page sets" on page 63 for information about redefining your page sets.
3. Restart MQSeries using the newly defined and initialized log data sets, BSDS, and page sets. Use the object definition input statements that you created in step 1 as input in the CSQINP2 initialization input data set.

Part 7. Monitoring performance and resource usage

Chapter 22. Monitoring performance and resource usage 371
Getting snapshots of MQSeries 372
Using DISPLAY commands 372
Using CICS adapter statistics 372
Investigating performance problems 372
Symptoms of reduced performance 373
Investigating the overall system 373
Using System Management Facility 374
Allocating additional SMF buffers 374
Reporting data in SMF 374
Using other products with MQSeries 375
Using Resource Measurement Facility 375
Using Performance Reporter for OS/390 375
Using the CICS monitoring facility 375
Using MQSeries trace 376
Starting MQSeries trace 376
Controlling MQSeries trace 376
Specifying trace keywords 376
Effect of trace on MQSeries performance 377
Using MQSeries events 378

Chapter 23. Interpreting MQSeries performance statistics 379
SMF type 115 record layout 379
SMF type 115 record header description 379
Processing type 115 SMF records 380
Record subtypes 380
Where the information comes from 380
Self-defining sections for type 115 records 381
Message manager statistics 382
Interpretation 382
Data manager statistics 383
Interpretation 383
Buffer manager statistics 384
Interpreting buffer manager statistics 385
Buffer pool management 385
Log manager statistics 389
Interpreting log manager statistics 390
Sample SMF statistics records 391

Chapter 24. Interpreting MQSeries accounting data 395
SMF type 116 record layout 395
SMF type 116 record header description 395
Processing type 116 SMF records 396
Where the information comes from 396
Self-defining sections 397
Message manager accounting 398
Interpretation 399
Sample SMF accounting record 400

© Copyright IBM Corp. 1993,1999

Chapter 22. Monitoring performance and resource usage

This part describes how to monitor the performance and resource usage of an MQSeries subsystem.

- It outlines some of the information that you can retrieve and briefly describes a general approach to investigating performance problems. (You can find information about dealing with performance problems in the *MQSeries for OS/390 Problem Determination Guide*.)
- It describes how you can obtain statistics related to the performance of an MQSeries subsystem by using SMF records.
- It describes how to gather accounting data to enable you to charge your customers for their use of your MQSeries subsystems.
- It describes how to use MQSeries events (alerts) to monitor your systems.

These are some of the tools you might use to monitor MQSeries; they are described in the sections that follow:

- Tools provided by MQSeries:
  - "Using DISPLAY commands" on page 372
  - "Using CICS adapter statistics" on page 372
  - "Using MQSeries events" on page 378
- OS/390 service aids:
  - "Using System Management Facility" on page 374
- Other IBM licensed programs:
  - "Using Resource Measurement Facility" on page 375
  - "Using Performance Reporter for OS/390" on page 375
  - "Using the CICS monitoring facility" on page 375

Information about interpreting the data gathered by the performance statistics trace is given in Chapter 23, "Interpreting MQSeries performance statistics" on page 379.

Information about interpreting the data gathered by the accounting trace is given in Chapter 24, "Interpreting MQSeries accounting data" on page 395.

© Copyright IBM Corp. 1993,1999

Getting snapshots of MQSeries

You can get an idea of the current the state of your MQSeries subsystem by using the DISPLAY commands and, for the CICS adapter, the CICS adapter panels.

Using DISPLAY commands

You can use the MQSeries DISPLAY commands to obtain information about the current state of MQSeries. They provide information on the status of the command server, process definitions, queues, the queue manager, and so on. These commands are:

- DISPLAY CHANNEL
- DISPLAY CHSTATUS
- DISPLAY CMDSERV
- DISPLAY CLUSQMGR
- DISPLAY DQM
- DISPLAY PROCESS
- DISPLAY QUEUE
- DISPLAY QMGR
- DISPLAY SECURITY
- DISPLAY STGCLASS
- DISPLAY THREAD
- DISPLAY TRACE
- DISPLAY USAGE

These commands provide a snapshot of the system *only* at the moment the command was processed. If you want to examine trends in the system, you must start an MQSeries trace and analyze the results over a period of time.

Note: You must be authorized to use these commands.

For the detailed syntax of each command, see the *MQSeries Command Reference* manual. All of the functions of these commands (except DISPLAY CMDSERV and DISPLAY TRACE) are also available through the operations and control panels.

Using CICS adapter statistics

If you are an authorized CICS user, you can use the CICS adapter control panels to display CICS adapter statistics dynamically. These statistics provide a snapshot of information related to CICS thread usage and situations when all threads are busy. The display connection panel can be refreshed by pressing the Enter key. For more information, see “Displaying details of connections and CICS tasks” on page 141.

Investigating performance problems

The performance measurement tools discussed so far are useful for monitoring MQSeries, as well as for MQSeries problem determination.

This section presents an overview of problem investigation and analyzes reports generated by performance monitoring tools.

Symptoms of reduced performance

Performance can be adversely affected by:

- Buffer pools that are the wrong size
- Lack of real storage
- I/O contention for page sets
- I/O contention for the logs
- Log buffer thresholds that are set wrongly
- Wrong numbers of log buffers
- Large messages
- Units of recovery that last a long time, incorporating many messages per syncpoint
- Messages that remain on a queue for a long time
- RACF auditing
- Unnecessary security checks
- Inefficient program design

When you analyze performance data, always start by looking at the overall system before you decide that you have a specific MQSeries problem. Remember that almost all symptoms of reduced performance are magnified when there is contention. For example, if there is contention for DASD, transaction response times can increase.

Also, the more transactions there are in the system, the greater the processor overhead and greater the demand for both virtual and real storage.

In such situations, the system shows heavy use of *all* its resources. However, the system is actually experiencing normal system stress, and this might be hiding the cause of a performance reduction. To find the cause of such a loss of performance, you must consider all items that might be affecting your active tasks.

Investigating the overall system

Within MQSeries, the performance problem is either reduced response time or an unexpected and unexplained heavy use of resources. You should first check factors such as total processor usage, DASD activity, and paging. An IBM tool for this is resource management facility (RMF™). In general, you need to look at the system in some detail to see why tasks are progressing slowly, or why a given resource is being heavily used.

Start by looking at general task activity, then focus on particular activities, such as specific tasks or a specific time interval.

Another possibility is that the system has limited real storage; therefore, because of paging interrupts, the tasks progress more slowly than expected.

Using System Management Facility

System management facility (SMF) is an OS/390 service aid used to collect information from various OS/390 subsystems. This information is dumped and reported periodically, for example, hourly. You can use SMF with the MQSeries trace facility to collect data from MQSeries. In this way you can monitor *trends*, for example, in system utilization and performance, and collect accounting information about each user ID using the MQSeries subsystem.

To record performance statistics (record type 115) to SMF specify the following in the SMFPRMxx member of SYS1.PARMLIB or with the SETSMF OS/390 operator command.

```
SYS(TYPE(115))
```

To record accounting information (record type 116) to SMF specify the following in the SMFPRMxx member of SYS1.PARMLIB or with the SETSMF OS/390 operator command.

```
SYS(TYPE(116))
```

To use the SETSMF OS/390 operator command, either PROMPT(ALL) or PROMPT(LIST) must be specified in the SMFPRM*xx* member. See the *OS/390 MVS Initialization and Tuning Reference* and the *OS/390 MVS System Commands* manuals for more information.

You must also set the SMFSTAT and SMFACCT parameters to YES; this is described in "Using CSQ6SYSP" on page 69.

SMF must be running before you can send data to it. For more information about SMF, see the *MVS System Management Facilities (SMF)* manual.

Allocating additional SMF buffers

When you invoke a trace, you must ensure that you allocate adequate SMF buffers. Specify SMF buffering on the VSAM BUFSP parameter of the access method services DEFINE CLUSTER statement. Specify CISZ(4096) and BUFSP(81920) on the DEFINE CLUSTER statement for each SMF VSAM data set.

If an SMF buffer shortage occurs, SMF rejects any trace records sent to it. MQSeries sends a CSQW133I message to the OS/390 operator when this occurs. MQSeries treats the error as temporary and remains active even though SMF data could be lost. When the shortage has been alleviated and trace recording has resumed, MQSeries sends a CSQW123I message to the OS/390 operator.

Reporting data in SMF

You can use the SMF program IFASMFDP to dump SMF records to a sequential data set so that they can be processed.

There are several ways to report on this data, for example:

- Write an application program to read and report information from the SMF data set. You can then tailor the report to fit your exact needs.
- Use Performance Reporter to process the records (see "Using Performance Reporter for OS/390" on page 375).

Using other products with MQSeries

You can use other products to help you to improve the presentation of, or to augment statistics related to, performance and accounting.

Using Resource Measurement Facility

Resource Management Facility (RMF) is an IBM licensed program (program number 5685-029) that provides system-wide information on processor utilization, I/O activity, storage, and paging. You can use RMF to monitor the utilization of physical resources across the whole system dynamically. For more information, see the *MVS Resource Measurement Facility User's Guide*.

Using Performance Reporter for OS/390

You can use Performance Reporter for OS/390 to interpret RMF and SMF records.

Performance Reporter for OS/390 is an IBM licensed program (program number 5695-101) that enables you to manage the performance of your system by collecting performance data in a DB2 database and presenting the data in a variety of formats for use in systems management. Performance Reporter can generate graphic and tabular reports using systems management data it stores in its DB2 database. It includes an administration dialog, a reporting dialog, and a log collector, all of which interact with a standard DB2 database.

This is described in the *Performance Reporter for OS/390 Administration Guide*.

Using the CICS monitoring facility

The CICS monitoring facility provides performance information about each CICS transaction running. It can be used to investigate the resources used and the time spent processing transactions. For background information, see the *CICS Performance Guide* and the *CICS Customization Guide*.

Using MQSeries trace

You can record performance statistics and accounting data for MQSeries by using the MQSeries trace facility. The data generated by MQSeries is sent to:

- The System Management Facility (SMF), specifically as SMF record type 115, subtypes 1 and 2 for the performance statistics trace
- The SMF, specifically as SMF record type 116, for the accounting trace.

If you prefer, the data generated by the MQSeries accounting trace can also be sent to the generalized trace facility (GTF).

Starting MQSeries trace

You can start the MQSeries trace facility at any time by issuing the MQSeries command, `+cpf` START TRACE.

Note: Accounting data can be lost if the accounting trace is started or stopped while applications are running. In order to collect accounting data successfully, the following conditions must apply:

- The accounting trace must be active when an application starts, and it must still be active when the application finishes.
- If the accounting trace is stopped, any accounting data collection that was active will cease.

You can also start collecting trace information automatically if you specify YES on the SMFSTAT (SMF STATISTICS) and SMFACCT (SMF ACCOUNTING) parameters of the CSQ6SYSP macro. You can also use the CSQ6SYSP macro to control the collection interval for the statistics trace with the STATIME parameter.

For details, see “Using CSQ6SYSP” on page 69 but, before invoking an MQSeries trace, read “Using System Management Facility” on page 374.

Controlling MQSeries trace

To control the MQSeries trace data collection at start up, specify values for the parameters in the CSQ6SYSP macro when you install MQSeries, see page 69.

You can control MQSeries tracing when MQSeries is running with these commands:

- `+cpf` START TRACE
- `+cpf` ALTER TRACE
- `+cpf` STOP TRACE

For information about these commands, see the *MQSeries Command Reference* manual.

Specifying trace keywords

The commands and keywords you can specify to control trace are described in the *MQSeries Command Reference* manual. When you specify a trace number, you must also specify the trace type.

Specifying a destination

The DEST keyword specifies the location to which trace data is sent. Possible destinations are:

SMF System Management Facility
GTF Generalized Trace Facility (accounting trace only)
SRV Serviceability routine for diagnostic use by IBM service personnel

The default destination for trace data is SMF.

When you specify a destination with the DEST keyword, use the appropriate abbreviation. For example, DEST(SMF).

For daily monitoring, information is sent to SMF. SMF data sets usually contain information from other systems; this information is not available for reporting until the SMF data set is dumped.

Effect of trace on MQSeries performance

Using the MQSeries trace facility can have a significant effect on MQSeries and transaction performance. For example, if you start a global trace for class 1 or for all classes, it is likely to increase CPU usage and transaction response times by approximately 50%. However, if you start a global trace for classes 2 to 4 alone, or a statistics or accounting trace, the increase in CPU usage and transaction response times is likely to be less than 1%.

Using MQSeries events

MQSeries *instrumentation events* provide information about errors, warnings, and other significant occurrences in a queue manager. You can monitor the operation of all your queue managers by incorporating these events into your own system management application.

MQSeries instrumentation events fall into the following categories:

Queue manager events
These events are related to the definitions of resources within queue managers. For example, an application attempts to put a message to a queue that does not exist.

Performance events
These events are notifications that a threshold condition has been reached by a resource. For example, a queue depth limit has been reached, or the queue was not serviced within a predefined time limit.

Channel events
These events are reported by channels as a result of conditions detected during their operation. For example, when a channel instance is stopped.

Note: Channel events are not produced if you are using the "CICS mover" for distributed queuing.

When an event occurs, the queue manager puts an *event message* on the appropriate *event queue*, if defined. The event message contains information about the event that can be retrieved by a suitable MQI application.

MQSeries events can be enabled using the MQSC commands or the operations and control panels. Channel events can only be disabled by altering the definition of the event queue to PUT(DISABLED).

See the *MQSeries Programmable System Management* for information about the MQSeries events that cause event messages to be generated, and for information about the format of these messages. See the *MQSeries Command Reference* for information about enabling the events.

Chapter 23. Interpreting MQSeries performance statistics

You must process any data you collect from SMF to extract useful information. To do this, you must understand the format of the type 115 records from SMF.

SMF type 115 record layout

The standard layout for SMF records involves three parts:

Part of record	*What it is used for*
SMF header	Provides format, identification, and time and date information about the record itself.
Self-defining section	Defines the location and size of the individual data records within the SMF record.
Data records	The actual data from MQSeries that you want to analyze.

For more information about SMF record formats, see the *MVS System Management Facilities (SMF)* manual.

SMF type 115 record header description

Table 22 shows the format of SMF record header (SM115).

Table 22. SMF record header description

Offsets						
Dec	**Hex**	**Type**	**Len**	**Name**	**Description**	**Example**
0	***(0)***	***Structure***	***28***	***SM115***	***SMF record header.***	
0	(0)	Unsigned	2	SM115LEN	SMF record length.	0294
2	(2)		2		Reserved.	0000
4	(4)	Unsigned	1	SM115FLG	System indicator.	1E
5	(5)	Unsigned	1	SM115RTY	Record type. The SMF record type, for MQSeries statistics records this is always 115 (X'73').	73
6	(6)	Unsigned	4	SM115TME	Time when SMF moved record.	004C551B
10	(A)	Unsigned	4	SM115DTE	Date when SMF moved record.	0098149F
14	(E)	Character	4	SM115SID	OS/390 subsystem ID. Defines the OS/390 subsystem on which the records were collected.	D4E5F4F1 (MV41)
18	(12)	Character	4	SM115SSI	MQSeries subsystem ID.	D4D8F3F7 (MQ37)
22	(16)	Unsigned	1	SM115STF	Record subtype.	02
23	(17)		1		Reserved.	00
24	(18)		4	SM115BUF	Reserved.	00000000
28	(1C)	Character	0	SM115END	End of SMF header and start of self-defining section.	

Note: The (hexadecimal) values in the right-hand column relate to Figure 97.

© Copyright IBM Corp. 1993,1999

Figure 97 shows an example of part of an SMF type 115 record. The numbers in the left-hand column represent the offset, in hexadecimal, from the start of the record. Each line corresponds to sixteen bytes of data, where each byte is two hexadecimal characters, for example 0C. The characters in the right-hand column represent the printable characters for each byte. Non-printable characters are shown by a period (.) character. In this example, alternate fields are underlined to help you to see them; refer to Table 22 to identify them.

```
+00000000                                     0294 |              .m|
+00000002  00001E73 004C551B 0098149F D4E5F4F1 |.....<...q..MV41|
+00000012  D4D8F3F7 02000000 00000000 02700024 |MQ37.............|
+00000022  0001000000440030 0001000000740040 |...............<|
+00000032  00010000 00C00068 00040000 02600010 |.....{.......-..|
+00000042  0001                               |..              |
⋮
```

Figure 97. Part of an SMF record showing the header and self-defining sections. Alternate fields in the header are underlined. The characters highlighted in bold represent a self-defining section.

Processing type 115 SMF records

When you process the data, verify that the records are from MQSeries and that they are the records you are expecting.

Validate the values of the following fields:

- SM115RTY, the SMF record number = X'73' (115)
- SM115STF, the record subtype, must be 01 or 02

Record subtypes

MQSeries statistics can be collected for two subtypes:

01 System information, for example, related to the logs.

02 MQSeries information about number of messages, MQSeries buffer and paging information, and so on.

The subtype is specified in the SM115STF field, see Table 22 on page 379. For example, in Figure 97, the record subtype is 02. “Sample SMF statistics records” on page 391 shows example of records for both subtypes.

Where the information comes from

The information provided in the SMF records comes from specific functional components of MQSeries. These are:

Component	*Function*
Message manager	Processes all MQI requests.
Data manager	Manages the links between messages and queues. It calls the buffer manager to process the pages with messages on them.
Buffer manager	Manages the buffer pools in virtual storage and the writing of pages to page sets as the buffer pools become full. Also manages the reading of pages from page sets.

Log manager Manages the writing of log records, which are essential for maintaining the integrity of the system, if there is a backout request, or for recovery, if there is a system or media failure.

Self-defining sections for type 115 records

A self-defining section of a type 115 SMF record tells you where to find a statistics record, how long it is, and how many times that type of record is repeated (with different values). The self-defining sections follow after the header, at fixed offsets from the start of the SMF record.

Four types of self-defining section are available to users for type 115 records. Each self-defining section points to statistics data related to one of four MQSeries components. Table 23 summarizes the sources of the statistics, and the offsets to the start of the SMF record header.

Table 23. Offsets to self-defining sections. Offsets are from the start of the SMF record and are fixed for each type of statistics source.

Source of statistics	Record subtype (SM115STF)	Offsets		See page
		Dec	Hex	
Message manager	02	36	(X'24')	382
Data manager	02	44	(X'2C')	383
Buffer manager	02	52	(X'34')	384
Log manager	01	116	(X'74')	389
Note: Other self-defining sections refer to data for IBM use only.				

Each self-defining record is two fullwords long and has this format:

```
ssssssssllllnnnn
```

where:

ssssssss Fullword containing the offset from start of the SMF record.
llll Halfword giving the length of this data record.
nnnn Halfword giving the number of data records in this SMF record.

For example, in Figure 97 on page 380, the self-defining section for message manager statistics is shown in bold. It is located at offset X'24' from the start of the SMF record and contains this information:

- The offset of the message manager statistics is located X'00000044' bytes from the start of the SMF record.
- The message manager record is X'0030' bytes long.
- There is one record (X'0001').

Similarly, in Figure 97, the buffer manager self-defining section at X'34' specifies that the offset to the buffer manager statistics is X'000000C0', is of length X'0068', and occurs X'0004' times.

Note: Always use offsets in the self-defining sections to locate the statistics records.

Message manager statistics

The following table shows the format of the message manager statistics record:

Table 24. Structure of the message manager statistics record QMST

Offsets					
Dec	**Hex**	**Type**	**Len**	**Name**	**Description**
0	***(0)***	***Structure***	***48***	***QMST***	***Message manager statistics***
0	(0)	Bitstring	2	QMSTID	Control block identifier
2	(2)	Unsigned	2	QMSTLL	Control block length
4	(4)	Character	4	QMSTEYEC	Control block eye catcher (QMST)
8	(8)	Signed	4	QMSTOPEN	Number of **MQOPEN** requests
12	(C)	Signed	4	QMSTCLOS	Number of **MQCLOSE** requests
16	(10)	Signed	4	QMSTGET	Number of **MQGET** requests
20	(14)	Signed	4	QMSTPUT	Number of **MQPUT** requests
24	(18)	Signed	4	QMSTPUT1	Number of **MQPUT1** requests
28	(1C)	Signed	4	QMSTINQ	Number of **MQINQ** requests
32	(20)		4		Reserved
36	(24)	Signed	4	QMSTSET	Number of **MQSET** requests
40	(28)		4		Reserved
44	(2C)	Signed	4	QMSTCALH	Number of “close handle” requests

Interpretation

The data gives you counts of different MQI requests.

Data manager statistics

The following table shows the format of the data manager statistics record:

Table 25. Structure of the data manager statistics record QIST

Offsets					
Dec	**Hex**	**Type**	**Len**	**Name**	**Description**
0	***(0)***	***Structure***	***60***	***QIST***	***Data manager statistics***
0	(0)	Bitstring	2	QISTID	Control block identifier
2	(2)	Unsigned	2	QISTLL	Control block length
4	(4)	Character	4	QISTEYEC	Control block eye catcher (QIST)
8	(8)	Unsigned	4	QISTMGET	Number of message get requests
12	(C)	Unsigned	4	QISTMPUT	Number of message put requests
16	(10)		4		Reserved
20	(14)	Signed	4	QISTDCRE	Number of object create requests
24	(18)	Signed	4	QISTDPUT	Number of object put requests
28	(1C)	Signed	4	QISTDDEL	Number of object delete requests
32	(20)	Signed	4	QISTDGET	Number of object get requests
36	(24)	Signed	4	QISTDLOC	Number of object locate requests
40	(28)		4		Reserved
44	(2C)	Signed	4	QISTALST	Number of Stgclass change requests
48	(30)		4		Reserved
52	(34)		4		Reserved
56	(38)		4		Reserved
60	(3C)		4		Reserved
64	(40)		4		Reserved
68	(44)		4		Reserved
72	(48)		4		Reserved

Interpretation

The data gives you counts of different object requests.

Buffer manager statistics

The following table shows the format of the buffer manager statistics record.

Note: If you have defined a buffer pool, but not used it, no values are set so the buffer manager statistics record will not contain any data.

Table 26. Structure of the buffer manager statistics record QPST

Offsets					
Dec	**Hex**	**Type**	**Len**	**Name**	**Description**
0	***(0)***	***Structure***	***104***	***QPST***	***Buffer manager statistics.***
0	(0)	Bitstring	2	QPSTID	Control block identifier.
2	(2)	Unsigned	2	QPSTLL	Control block length.
4	(4)	Character	4	QPSTEYEC	Control block eye catcher (QPST).
8	(8)	Signed	4	QPSTPOOL	Buffer pool identifier (0000-0003).
12	(C)	Signed	4	QPSTNBUF	Number of buffers in this buffer pool.
16	(10)	Signed	4	QPSTCBSL	Lowest number of available buffers.
20	(14)	Signed	4	QPSTCBS	Number of available buffers.
24	(18)	Signed	4	QPSTGETP	The number of page get requests where the current page contents are required. This might involve a read DASD operation if the page is not currently in the buffer pool.
28	(1C)	Signed	4	QPSTGETN	The number of get requests for a new - or empty - page (that is, no read operation is necessary).
32	(20)	Signed	4	QPSTRIO	The number of page read DASD operations.
36	(24)	Signed	4	QPSTSTW	The number of page updates.
40	(28)	Signed	4	QPSTTPW	Number of pages written to DASD.
44	(2C)	Signed	4	QPSTWIO	The number of page write operations.
48	(30)	Signed	4	QPSTIMW	The number of synchronous page write operations.
52	(34)	Signed	4	QPSTDWT	The number of times the asynchronous write processor was started.
56	(38)	Signed	4	QPSTDMC	The number of times the synchronous page processor was started because the synchronous write threshold was reached.
60	(3C)	Signed	4	QPSTSTL	The number of times a page get request did not find the page already in the buffer pool.
64	(40)	Signed	4	QPSTSTLA	Number of times the hash chain has been changed during a buffer steal.
68	(44)	Signed	4	QPSTSOS	The number of times NO available buffers were found.
72	(48)		32		Reserved.

Interpreting buffer manager statistics

The buffer manager is the component of MQSeries that handles the movement of data between DASD and virtual storage.

Buffer pools are areas of MQSeries virtual storage reserved to satisfy the buffering requirements for MQSeries queues. Each buffer pool contains an installation defined number of 4 KB virtual storage pages or buffers. Page sets are VSAM linear data sets and each page set is associated with a buffer pool. Queues are mapped to page sets via their storage class attribute. For more information on the relationship between these entities, see “Storage classes - mapping queues to page sets” on page 15.

A buffer pool can be the holding storage for many message queues. To be able to estimate the required size of the buffer pools, you must understand their characteristics and how to interpret the buffer manager statistics generated by MQSeries.

A buffer pool can hold MQSeries objects, as well as messages, in 4 KB virtual storage pages. MQSeries is designed to keep these pages in buffer pool virtual storage as long as possible in order to obtain the best performance.

However, if a buffer pool starts to fill up, updated pages are written out to their relevant DASD page sets to free up buffer pool space. This happens if, for example, messages are being put onto queues associated with the buffer faster than they are being taken off.

Information contained in pages that have been written out to DASD page sets can be read in again on demand.

Nonpersistent messages can also be written out to DASD if the buffer pools in which they reside become short on storage. This is because the page sets are the backing store for the buffer pools during MQSeries operation.

Ideally, a transaction pattern should be such that messages do not spend a long time on a queue waiting to be retrieved. This means that messages never have to spill over to DASD because the pages used to hold them remain in virtual storage.

Buffer pool management

To manage your buffer pools efficiently, you must consider the factors that affect the buffer pool I/O operations and also the statistics associated with the buffer pools.

DASD operations

The following factors affect buffer pool I/O operations.

- If a page containing the required data is not found in the buffer pool, it is read in synchronously to an available buffer from its DASD page set.
- Whenever a page is updated, it is put on an internal queue of pages to be (potentially) written out to DASD. This means that the buffer used by that page is unavailable for use by any other page until the buffer has been written to DASD.

- If the number of pages queued to be written to DASD exceeds 85% of the total number of buffers in the pool, an asynchronous write processor is started in order to put the buffers to DASD.

  Similarly, should the number of buffers available for page get requests become less than 15% of the total number of buffers in the pool, then the asynchronous write processor is started in order to perform the write I/O operations.

  The write processor stops when the number of pages queued to be written to DASD has fallen to 75% of the total number of buffer in the pool.

- If the number of pages queued for writing to DASD exceed 95% of the total number of buffers in the pool, all updates result in a synchronous write of the page to DASD.

  Similarly, if the number of buffers available for page get requests becomes less than 5% of the total number of buffers in the pool, all updates result in a synchronous write of the page to DASD.

- If the number of buffers available for page get requests ever reaches zero, a transaction that encounters this condition is suspended until the asynchronous write processor has finished.

- If a page is frequently updated, the page spends most of its time on the queue of pages waiting to be written to DASD. Because this queue is in least recently used order, it is possible that a frequently updated page placed on this least recently used queue will never be written out to DASD. For this reason, at the time of update, if the page is found to have been waiting on the write to DASD queue for at least 2 checkpoints, it will be synchronously written to DASD. Updating occurs at checkpoint time.

  The aim of the above algorithm is to maximize the time pages spend in buffer pool memory while allowing the system to function should system load put the buffer pool usage under stress.

Buffer pool statistics

MQSeries writes statistics to SMF for each buffer pool, if statistics trace gathering has been requested. Table 26 on page 384 shows the statistics that are recorded. The statistics are reset each time they are output.

When interpreting the statistics, you are recommended to consider the following factors because the values of these fields can be used to improve the performance of your system:

1. If QPSTSOS, QPSTSTLA, or QPSTDMC is greater that zero, you should either increase the size of the buffer pool or reallocate the page sets to different buffer pools.

   QPSTSOS is the number of times that there were no buffers available for page get requests. If QPSTSOS ever becomes non-zero, it shows that MQSeries is under severe stress. The buffer pool size should be significantly increased. If increasing the buffer pool size does not make the value of QPSTSOS zero, there might be I/O contention on the DASD page sets.

   QPSTDMC is the number of updates that were performed synchronously because there was either more than 95% of the pages in the buffer pool waiting for write I/O, or there was less than 5% of the buffer pool available for read requests. If this number is not zero, the buffer pool might be too small

and should be enlarged. If increasing the buffer pool size does not reduce QPSTDMC to zero, there might be I/O contention on the DASD page sets.

QPSTIMW is a count of the number of times pages were written out synchronously. If QPSTDMC is zero, QPSTIMW is the number of times pages were found on the queue waiting for write I/O that had been there for at least two checkpoints.

2. For buffer pool zero and buffer pools that contain short-lived messages:
   - QPSTDWT should be zero, and the percentage QPSTCBSL/QPSTNBUF should be greater than 15%.

     QPSTDWT is the number of times the asynchronous write processor was started because there was either more than 85% of the pages in the buffer pool waiting for write I/O, or there was less than 15% of the buffer pool available for read requests. Increasing the buffer pool size should reduce this value. If it does not, the pattern of access is one of long delays between puts and gets.
   - QPSTTPW might be greater that zero due to checkpointing activity.
   - QPSTRIO should be zero unless messages are being read from a page set after the queue manager is restarted.

     The ratio of QPSTRIO to QPSTGETP shows the efficiency of page retrieval within the buffer pool. Increasing the buffer pool size should decrease this ratio and, therefore, increase the page retrieval efficiency. If this does not happen, it indicates that pages are not being frequently reaccessed. This implies a transaction pattern where there is a long delay between messages being put and then subsequently retrieved.

     The ratio of QPSTGETN to QPSTGETP indicates the number of times an empty page, as opposed to a non-empty page, has been requested. This ratio is more an indication of transaction pattern, than a value that can be used to tune the system.
   - If QPSTSTL has a value greater than zero, this indicates that pages that have not been used before are now being used. This might be caused by an increased message rate, messages not being processed as fast as they were previously (leading to a buildup of messages), or larger messages being used.

     QPSTSTL is a count of the number of times a page access request did not find the page already in the buffer pool. Again, the lower the ratio of QPSTSTL to (QPSTGETP + QPSTGETN) is, the higher the page retrieval efficiency. Increasing the buffer pool size should decrease this ratio but, if it does not, it is an indication that there are long delays between puts and gets.
   - You are recommended to have sufficient buffers to handle your peak message rate.
3. For buffer pools with long-lived messages, where there are more messages than will fit into the buffer pool:
   - (QPSTRIO+QPSTWIO)/Statistics interval is the I/O rate to page sets. If this value is high, you should consider using multiple page sets on different volumes to allow I/O to be carried out in parallel.

The higher the ratio of QPSTSTW to QPSTWIO, the better the efficiency of the asynchronous write processor. You can increase this ratio, and therefore the efficiency of the asynchronous write processor, by increasing the buffer pool size.

- Over the period of time that the messages are processed (for example, if messages are written to a queue during the day and processed overnight) the number of read I/Os (QPSTRIO) should be approximately the total number of pages written (QPSTTPW). This shows that one disk is read for every page written.

  If QPSTRIO is much larger than QPSTTPW, this shows that pages are being read in multiple times. This might be a result of the application using **MQGET** by *MsgId* or *CorrelId* when the queue is not indexed, or browsing messages on the queue using get next.

  The following actions might relieve this problem:

  a. Increase the size of the buffer pool so that there are enough pages to hold the queue, in addition to any changed pages.

  b. Use the INDXTYPE queue attribute, which allows a queue to be indexed by *MsgId* or *CorrelId* and eliminates the need for a sequential scan of the queue.

  c. Change the design of the application to eliminate the use of **MQGET** with *MsgId* or *CorrelId*, or the get next with browse option.

     Note: Applications using long-lived messages typically process the first available message and do not use **MQGET** with *MsgId* or *CorrelId*, and they might browse only the first available message.

  d. Move page sets to a different buffer pool to reduce contention between messages from different applications.

Log manager statistics

The following table shows the format of the log manager statistics record:

Table 27. Structure of the log manager statistics record QJST

Offsets					
Dec	**Hex**	**Type**	**Len**	**Name**	**Description**
0	***(0)***	***Structure***	***64***	***QJST***	***Log manager statistics.***
0	(0)	Character	2	QJSTID	Control block identifier.
2	(2)	Signed	2	QJSTLL	Control block length.
4	(4)	Character	4	QJSTEID	Control block eye catcher (QJST).
8	(8)	Signed	4	QJSTWRW	Write_request count - Wait. Tasks are suspended until the write to active log is complete.
12	(C)	Signed	4	QJSTWRNW	Write_request count - No wait. Asynchronous writes to the active log. Tasks are not suspended.
16	(10)	Signed	4	QJSTWRF	Write_request count - Force. Tasks are suspended until all the log records for this unit of recovery are written to the active log data set.
20	(14)	Signed	4	QJSTWTB	Wait count for unavailable buffers. Number of times a task was suspended because all the buffers were waiting to be written to the active log data set.
24	(18)	Signed	4	QJSTRBUF	Number of read log requests satisfied from in-storage buffers.
28	(1C)	Signed	4	QJSTRACT	Number of read log requests satisfied from the active log data set.
32	(20)	Signed	4	QJSTRARH	Number of read log requests satisfied from an archive log data set.
36	(24)	Signed	4	QJSTWTL	Number of read log requests delayed because the MAXALLC parameter in CSQ6LOGP limited the number of archive log data sets that could be used.
40	(28)	Signed	4	QJSTBSDS	Total number of bootstrap data set (BSDS) access requests.
44	(2C)	Signed	4	QJSTBFFL	The number of active log control intervals (CIs) created (log pages used).
48	(30)	Signed	4	QJSTBFWR	Number of calls made that wrote to active log buffers.
52	(34)	Signed	4	QJSTALR	Number of times an archive log data set was allocated for a read request.
56	(38)	Signed	4	QJSTALW	Number of times an archive log data set was allocated for a write request.
60	(3C)	Signed	4	QJSTCIOF	Count of CIs off-loaded to the archive data set.
64	(40)	Signed	4	QJSTLLCP	Number of times that checkpoint was invoked.

Interpreting log manager statistics

These counts are important:

1. The total number of log write requests:

   $N_{logwrite}$ = QJSTWRW + QJSTWRNW + QJSTWRF

2. The total number of log read requests:

   $N_{logread}$ = QJSTRBUF + QJSTRACT + QJSTRARCH

The problem symptoms that can be examined using log manager statistics are described in Table 28.

Table 28 (Page 1 of 2). Problem symptoms that can be examined using log manager statistics

Symptom 1	QJSTWTB is non-zero.
Reason	Tasks are being suspended while the in-storage buffer is being written to the active log. There might be problems writing to the active log. The OUTBUFF parameter within CSQ6LOGP is too small.
Action	Investigate the problems writing to the active log. Increase the value of the OUTBUFF parameter within CSQ6LOGP.
Symptom 2	The ratio: QJSTRARH/$N_{logread}$ is larger than normal.
Reason	Most log read requests should come from the output buffer or the active log. To satisfy requests for back out, unit-of-recovery records are read from the in-storage buffer, the active log, and the archived logs. A long-running unit of recovery, extending over a period of many minutes, might have log records spread across many different logs. This degrades performance because extra work has to be done to recover the log records.
Action	Change the application to reduce the length of a unit of recovery. Also, consider increasing the size of the active log to reduce the possibility of a single unit of recovery being spread out over more than one log.
Other pointers	The ratio $N_{logread}/N_{logwrite}$ gives an indication of how much work has to be backed out.
Symptom 3	The ratio: QJSTWTL/$N_{logread}$ is greater than 1%.
Reason	Log reads were initiated that had to read from an archive log, but MQSeries was not able to allocate a data set because MAXALLC data sets were already allocated.
Action	Increase MAXALLC.

Table 28 (Page 2 of 2). Problem symptoms that can be examined using log manager statistics	
Symptom 4	QJSTLLCP is more than 10 per hour.
Reason	On a busy system you would expect to see typically 10 checkpoints an hour. If the QJSTLLCP value is larger than this, it indicates a problem in the setup of the queue manager. The most likely reason for this is that the LOGLOAD parameter in CSQ6SYSP is too small. The other event that causes a checkpoint is when an active log fills up and switches to the next active log data set. If your logs are too small, this can cause frequent checkpoints.
Action	Increase the LOGLOAD parameter, or increase the size of your log data sets as required.

Note: In the first set of statistics produced after system startup, there might be significant log activity due to the resolution of in-flight units of recovery.

Sample SMF statistics records

Figure 98 shows the SMF record for subtype 1. Subtype 1 includes the log manager statistics record. In this figure, the SMF record header, the self-defining section, and the statistics record are underlined.

In this example, the self-defining section, at offset X'74', refers to log manager statistics, see Table 27 on page 389. The statistics are located at offset X'00000164' from the start of the header and is X'40' bytes long. There is only one set of statistics identified by the eye catcher string QJST.

Figure 99 on page 393 shows the SMF record for subtype 2. Subtype 2 includes the buffer manager statistics. The SMF record header, the self-defining section, and the buffer manager statistics record are shown underlined. In this example, the self-defining section, at offset X'34', refers to buffer manager statistics (see Table 26 on page 384). The statistics are located at offset X'000000B0' from the start of the header and is X'68' bytes long.

There are four sets of statistics corresponding the four buffer pools numbered 0, 1, 2, and 3 respectively. Each set of data related to the buffer manager can be identified by the eye catcher string QPST.

The eye catcher strings are:

QIST Data manager
QJST Log manager (subtype 1, see Figure 98 on page 392)
QMST Message manager
QPST Buffer manager

Sample SMF statistics records

```
00000000. 01C80000 1E730030 C47A0093 238FD4E5 |.H......D:.l..MV|
00000010. E2D4E5C3 E3F8010C 00000000₁         |SMVCT8......    |

0000001C.                           000001A4 |            ...u|
00000020. 00240001 00000000 00000000 00000000 |................|
00000030. 00000000 00000000 00000000 0000007C |...............@|
00000040. 00400001 000000BC 00600001 00000000 |. .......-......|
00000050. 00000000 00000000 00000000 00000000 |................|
00000060. 00000000 0000011C 00480001 00000000 |................|
00000070. 00000000 00000164 00400001₂         |........ ..     |

0000007C.                           00002086 |            ...f|
00000080. 00000000 00002086 000040FA 00000000 |.......f.. .....|
00000090. 00000000 00000000 00000005 00002078 |................|
000000A0. 0000207E 00000000 00000005 00000000 |...=............|
000000B0. 0000208D 00000000 00000000          |.............   |

000000BC.                           00000000 |             ...|
000000C0. 00000000 00000000 00000000 00000000 |................|
000000D0. 00000000 00000003 00000001 00000000 |................|
000000E0. 00000001 00000000 00000000 00000001 |................|
000000F0. 00000000 00000207 00000000 00000000 |................|
00000100. 00000000 00000000 00000000 00000000 |................|
0000011C. 00000000 00000000 00000000          |............    |

00000110.                           003C0048 |            ....|
00000120. D8E2E2E3 0000209E 00002080 00000002 |QSST............|
00000130. 00000114 00000085 0000054A 00000536 |.......e...¢....|
00000140. 00000575 0000088C 00000011 00004D64 |..............(.|
00000150. 00004CE7 00000000 00000000 00000000 |..[X............|
00000160. 00000000                            |....            |

00000164.          00930044 D8D1E2E3 00000000 |    .l. QJST....|
00000170. 000059BA 00000883 00000000 00000EED |.......c........|
00000180. 0000009D 00000000 00000000 00000068 |................|
00000190. 00000218 000011E9 00000000 00000000 |.......Z........|
000001A0. 00000000 00000002₃                  |........        |

000001A8.                   0024011A 00010C10 |        ........|
000001B0. 0F049158 E5C3E3F8 A7FDDCC5 D3C24101 |..j.VCT8x..ELB..|
000001C0. 00000001 00000005 00000002          |............    |
```

Figure 98. SMF record 115, subtype 1. The subscripts identify: (1) the SMF record header, (2) the self-defining section, and (3) the log manager statistics record.

```
+00000000                                     0294 |             .m|
+00000002  00001E73 004C551B 0098149F D4E5F4F1 |.....<...q..MV41|
+00000012  D4D8F3F7 02000000 00000000 02700024 |MQ37.........|
+00000022  00010000 00440030 00010000 0074004C |.............<|
+00000032  00010000 00C00068 00040000 02600010 |.....{.......-..|
+00000042  0001                               |..              |
+00000044      D40F 0030D8D4 E2E30000 00070000 |  M...QMST......|
+00000052  00060000 000D0000 000E0000 00000000 |................|
+00000062  00000000 00000000 00000000 00000000 |................|
+00000072  0000                               |..              |

+00000074      C90F 004CD8C9 E2E30000 000D0000 |  I..<QIST......|
+00000082  000E0000 00000000 00000000 00000000 |................|
+00000092  00000000 001A0000 000E0000 00000000 |................|
+000000A2  00000000 00000000 00000000 00000000 |................|
+000000B2  00000000 00000000 00000000 0003     |.............   |

+000000C0                                     D70F |             P.|
+000000C2  0068D8D7 E2E30000 00000000 07D00000 |..QPST.......}..|
+000000D2  07CD0000 07CD0000 00210000 00000000 |.............|
+000000E2  00000000 00210000 00000000 00000000 |.............|
+000000F2  00000000 00000000 00000000 00000000 |.............|
+00000102  00000000 00000000 00000000 00000000 |.............|
+00000112  00000000 00000000 00000000 00000000 |.............|
+00000122  00000000 0000                       |......          |

+00000128              D70F 0068D8D7 E2E30000 |      P...QPST..|
+00000132  00010000 07D00000 07CA0000 07CA0000 |.....}.........|
+00000142  00300000 00040000 00000000 00290000 |.............|
+00000152  00000000 00000000 00000000 00000000 |.............|
+00000162  00000000 00030000 00000000 00000000 |.............|
+00000172  00000000 00000000 00000000 00000000 |.............|
+00000182  00000000 00000000 00000000 0000     |.............   |

+00000190                                     D70F |             P.|
+00000192  0068D8D7 E2E30000 00020000 041A0000 |..QPST.........|
+000001A2  041A0000 00000000 00000000 00000000 |.............|
+000001B2  00000000 00000000 00000000 00000000 |.............|
+000001C2  00000000 00000000 00000000 00000000 |.............|
+000001D2  00000000 00000000 00000000 00000000 |.............|
+000001E2  00000000 00000000 00000000 00000000 |.............|
+000001F2  00000000 0000                       |......          |

+000001F8              D70F 0068D8D7 E2E30000 |      P...QPST..|
+00000202  00030000 041A0000 041A0000 00000000 |.............|
+00000212  00000000 00000000 00000000 00000000 |.............|
+00000222  00000000 00000000 00000000 00000000 |.............|
+00000232  00000000 00000000 00000000 00000000 |.............|
+00000242  00000000 00000000 00000000 00000000 |.............|
+00000252  00000000 00000000 00000000 0000     |.............   |

+00000260                                     D30F |             L.|
+00000262  0010D8D3 E2E30000 00000000 0000     |..QLST........  |
```

Figure 99. SMF record 115, subtype 2. The underlined sections indicate the SMF record header, the self-defining section, and a buffer manager statistics record.

Sample SMF statistics records

Chapter 24. Interpreting MQSeries accounting data

You must process any accounting data you collect from SMF to extract useful information. To do this, you must understand the format of the type 116 records from SMF.

SMF type 116 record layout

The standard layout for SMF records involves three parts:

Part of record	*What it is used for*
SMF header	Provides format, identification, and time and date information about the record itself.
Self-defining section	Defines the location and size of the individual data records within the SMF record.
Data records	The actual data from MQSeries that you want to analyze.

For more information about SMF record formats, see the *MVS System Management Facilities (SMF)* manual.

SMF type 116 record header description

Table 29 shows the format of SMF record header (SM116).

Table 29 (Page 1 of 2). SMF record header description

Offsets						
Dec	**Hex**	**Type**	**Len**	**Name**	**Description**	**Example**
0	***(0)***	***Structure***	***28***	***SM116***	***SMF record header.***	
0	(0)	Unsigned	2	SM116LEN	SMF record length.	01A4
2	(2)		2		Reserved.	0000
4	(4)	Unsigned	1	SM116FLG	System indicator.	1E
5	(5)	Unsigned	1	SM116RTY	Record type. The SMF record type, for MQSeries accounting records this is always 116 (X'74').	74
6	(6)	Unsigned	4	SM116TME	Time when SMF moved record.	005BD9BD
10	(A)	Unsigned	4	SM116DTE	Date when SMF moved record.	0094088F
14	(E)	Character	4	SM116SID	OS/390 subsystem ID. Defines the OS/390 subsystem on which the records were collected.	D7D4C5E2 (PMES)
18	(12)	Character	4	SM116SSI	MQSeries subsystem ID.	E5C3F140 (VC1)
22	(16)	Unsigned	1	SM116STF	Record subtype.	00
23	(17)		1		Reserved.	00
24	(18)		4	SM116SEQ	Reserved.	00000000
24	(18)		4	SM116BUF	Reserved.	00000000

© Copyright IBM Corp. 1993,1999

Table 29 (Page 2 of 2). SMF record header description

Offsets		Type	Len	Name	Description	Example
Dec	Hex					
28	(1C)	Character	0	SM116END	End of SMF header and start of self-defining section.	

Note: The (hexadecimal) values in the right-hand column relate to Figure 100.

Figure 100 shows an example of part of an SMF type 116 record. The numbers in the left-hand column represent the offset, in hexadecimal, from the start of the record. Each line corresponds to sixteen bytes of data, where each byte is two hexadecimal characters, for example 0C. The characters in the right-hand column represent the printable characters for each byte. Non-printable characters are shown by a period (.) character. In this example, alternate fields are underlined to help you to see them; refer to Table 29 to identify them.

```
00000000. 01A40000 1E74005B D9BD0094 088FD7D4 |.u.....$R..m..PM|
00000010. C5E2E5C3 F1400000 00000000 00000134 |ESVC1 ..........|
00000020. 00700001 00000054 00B00001 00000104 |................|
00000030. 00300001 00000000 00000000 00000000 |................|
00000040. 00000000                           |....            |
```

Figure 100. Part of an SMF record showing the header and self-defining sections. Alternate fields in the header are underlined. The characters highlighted in bold represent a self-defining section.

Processing type 116 SMF records

When you process the data, verify that the records are from MQSeries and that they are the records you are expecting.

Validate the value of the following fields:

- SM116RTY, the SMF record number = X'74' (116)
- SM116STF, the record subtype, must be 00

Where the information comes from

The information provided in the SMF records comes from the message manager component of MQSeries. This component processes all MQI requests.

Self-defining sections

A self-defining section of an SMF record tells you where to find an accounting record, how long it is, and how many times that type of record is repeated (with different values). The self-defining sections follow the header, at a fixed offset from the start of the SMF record.

Two types of self-defining section are available to users for type 116 records. Each self-defining section points to accounting related data. Table 30 summarizes the offsets from the start of the SMF record header.

Table 30. Offsets to self-defining sections. Offsets are from the start of the SMF record and are fixed for each type of accounting source.

Source of accounting data	Offsets		See...
	Dec	Hex	
Message manager	28	(X'1C')	Table 31 on page 398
Message manager	44	(X'2C')	Table 32 on page 398

Note: Other self-defining sections refer to data for IBM use only.

Each self-defining record is two fullwords long and has this format:

```
ssssssssllllnnnn
```

where:

ssssssss Fullword containing the offset from start of the SMF record.
llll Halfword giving the length of this data record.
nnnn Halfword giving the number of data records in this SMF record.

For example, in Figure 100, the self-defining section for the type of message manager accounting data is shown in bold. It is located at offset X'2C' from the start of the SMF record and contains this information:

- The offset of the message manager accounting data is located X'00000104' bytes from the start of the SMF record.
- This message manager record is X'0030' bytes long.
- There is one record (X'0001').

Note: Always use offsets in the self-defining sections to locate the accounting records.

Message manager accounting

The following tables show the format of the message manager accounting records:

Table 31. Structure of the message manager accounting record QWHS

Offsets					
Dec	**Hex**	**Type**	**Len**	**Name**	**Description**
0	***(0)***	***Structure***	***112***	***QWHS***	***Message manager accounting data.***
0	(0)		12		Reserved.
12	(0C)	Character	4	QWHSSSID	Subsystem name.
16	(10)		24		Reserved.
40	(28)	Character	8	QWHCAID	User ID associated with the OS/390 job.
48	(30)	Character	12	QWHCCV	Thread cross reference (see “Thread cross reference data” on page 399).
60	(3C)	Character	8	QWHCCN	Connection name.
68	(44)		8		Reserved.
76	(4C)	Character	8	QWHCOPID	User ID associated with the transaction.
84	(54)	Signed	4	QWHCATYP	Type of connecting system (1=CICS, 2=Batch or TSO, 3=IMS control region, 4=IMS MPP or BMP, 5=Command server, 6=Channel initiator, 7=RRS Batch).
88	(58)	Character	22	QWHCTOKN	Accounting token set to the OS/390 accounting information for the user.
110	(6E)		2		Reserved.

Table 32 (Page 1 of 2). Structure of the message manager accounting record QMAC

Offsets					
Dec	**Hex**	**Type**	**Len**	**Name**	**Description**
0	***(0)***	***Structure***	***48***	***QMAC***	***Message manager accounting data.***
0	(0)	Bitstring	2	QMACID	Control block identifier.
2	(2)	Unsigned	2	QMACLL	Control block length.
4	(4)	Character	4	QMACEYEC	Control block eye catcher (QMAC).
8	(8)	Character	8	QMACCPUT	CPU time used (TOD format).
16	(10)	Signed	4	QMACPUTA	Number of **MQPUT** requests for messages of length 0 through 99 bytes.
20	(14)	Signed	4	QMACPUTB	Number of **MQPUT** requests for messages of length 100 through 999 bytes.
24	(18)	Signed	4	QMACPUTC	Number of **MQPUT** requests for messages of length 1000 through 9999 bytes.
28	(1C)	Signed	4	QMACPUTD	Number of **MQPUT** requests for messages of length greater than or equal to 10000 bytes.
32	(20)	Signed	4	QMACGETA	Number of **MQGET** requests for messages of length 0 through 99 bytes.
36	(24)	Signed	4	QMACGETB	Number of **MQGET** requests for messages of length 100 through 999 bytes.

Table 32 (Page 2 of 2). Structure of the message manager accounting record QMAC

Offsets		Type	Len	Name	Description
Dec	Hex				
40	(28)	Signed	4	QMACGETC	Number of **MQGET** requests for messages of length 1000 through 9999 bytes.
44	(2C)	Signed	4	QMACGETD	Number of **MQGET** requests for messages of length greater than or equal to 10000 bytes.

Interpretation

The QMAC data gives you information about the CPU time spent processing MQSeries calls, and counts of the number of **MQPUT** and **MQGET** requests for messages of different sizes.

The QWHC data gives you information about the user (for example, the user ID (QWHCAID) and the type of application (QWHCATYP)).

Records containing zero CPU time

Records are sometimes produced that contain zero CPU time in the QMACCPUT field. These records occur when long running TCBs identified to MQSeries either terminate or are prompted to output accounting records by accounting trace being stopped. Such TCBs exist in the CICS adapter and in the channel initiator (for distributed queuing without CICS). The number of these TCBs with zero CPU time depends upon how much activity there has been in the system:

- For the CICS adapter, this can result in up to nine records with zero CPU time.
- For the channel initiator, the number of records with zero CPU time can be up to the sum of `Adapters + Dispatchers + 6`, as defined in the channel initiator parameters.

These records reflect the amount of work done under the TCB, and can be ignored.

Thread cross reference data

The interpretation of the data in the thread cross reference (QWHCCV) field varies. This depends on what the data relates to:

- CICS (QWHCATYP=1) – see Table 33
- IMS (QWHCATYP=3 or 4) – see Table 34 on page 400
- Batch, TSO, or RRS Batch (QWHCATYP=2 or 7) – this field consists of binary zeros
- Others – no meaningful data

Table 33. Structure of the thread cross reference record for a CICS system

Offsets		Type	Len	Name	Description
Dec	Hex				
48	(30)	Character	4	QWHCTNO	CICS thread number.
52	(34)	Character	4	QWHCTRN	CICS transaction name.
56	(38)	Signed	4	QWHCTASK	CICS task number.

Some entries contain blank characters. These apply to the TCB, rather than to a specific transaction.

Table 34. Structure of the thread cross reference record for an IMS system

Offsets		Type	Len	Name	Description
Dec	Hex				
48	(30)	Character	4	QWHCPST	IMS partition specification table (PST) region identifier.
52	(34)	Character	8	QWHCPSB	IMS program specification block (PSB) name.

Special considerations when using IMS accounting records

A single IMS application might write two SMF records. In this case, the figures from both records should be added to provide the correct totals for the IMS application.

Sample SMF accounting record

Figure 101 shows a type 116 SMF record. In this figure, the SMF record header, the self-defining section, and the accounting data record are underlined.

```
00000000. 01A40000 1E74005B D9BD0094 088FD7D4 |.u.....$R..m..PM|
00000010. C5E2E5C3 F1400000 00000000(1)       |ESVC1 ......    |
0000001C.                           00000134  |            ....|
00000020. 00700001 00000054 00B00001 00000104 |................|
00000030. 00300001 00000000 00000000 00000000 |................|
00000040. 00000000 00000000 00000000 00000000 |................|
00000050. 00000000(2)                         |....
00000054.          A90CA45A 76B71A04 A90CA45C |    z.u!....z.u*|
00000060. 0F95CE03 00000000 0BE78EC5 00000000 |.n.......X.E....|
00000070. 2E052997 00000000 01F3BD00 00000000 |...p.....3......|
00000080. 02577700 0000000C 40404040 40404040 |........        |
00000090. 00000000 00000000 00000001 00000000 |................|
000000A0. 00000000 00000000 00000000 00000000 |................|
000000B0. 00000000 00000000 00000000 00000000 |................|
000000C0. 00000000 00000000 00000000 00000000 |................|
000000D0. 00000000 00000000 00000000 00000000 |................|
000000E0. 00000000 00000000 00000000 00000000 |................|
000000F0. 00000000 00000000 00000000 00000000 |................|
00000100. 00000000                            |....            |
00000104.          D4140030 D8D4C1C3 00000000 |    M...QMAC....|
00000110. 1D7AF539 0000000A 0000000A 0000000A |.:5.............|
00000120. 0000000A 00000000 00000000 00000000 |................|
00000130. 00000000(3)                         |....            |
00000134.          0024011A 00030710 02DAACF0 |    ...........0|
00000140. E5C3F140 A90CA45C 0FC24E03 00000003 |VC1 z.u*.B+.....|
00000150. 00000003 00000001 004C0200 C3D6D5F0 |.........<..CON0|
00000160. F3F4F040 00000000 00000000 00000000 |340 ............|
00000170. D7C1E4D3 D7E4E340 00000000 00000000 |PAULPUT ........|
00000180. C3D6D5F0 F3F4F040 00000002 00000000 |CON0340 ........|
00000190. 00000000 00000000 00000000 00000000 |................|
000001A0. 00000000                            |....            |
```

Figure 101. SMF record 116. The subscripts identify: (1) the SMF record header, (2) the self-defining section, and (3) an example of a message manager accounting record.

Part 8. Security

Chapter 25. Introduction to MQSeries security 403
Why you need to protect MQSeries resources 403
Implementing MQSeries security 404
Security controls and options 404
Resources you can protect 405
Connection security 405
API-resource security 405
Command security 407
Command resource security 407

Chapter 26. Using RACF classes and profiles 409
Using RACF security classes 410
RACF profiles 411
Switch profiles 411
How switches work 412
Profiles used to protect MQSeries resources 414
Profiles for connection security 414
Profiles for queue security 416
Profiles for processes 423
Profiles for namelists 424
Profiles for alternate user security 425
Profiles for context security 427
API-resource security access quick reference 429
Profiles for command security 431
Profiles for command resource security 432
Using the RESLEVEL security profile 435
RESLEVEL and Batch/TSO connections 435
RESLEVEL and system utilities 435
RESLEVEL and CICS connections 435
RESLEVEL and IMS connections 436
RESLEVEL and channel initiator connections 437
The RESLEVEL profile 438
Important notes on using RESLEVEL 440
User IDs for security checking 440
User IDs for connection security 440
User IDs for command security and command resource security 441
User IDs for resource security (MQOPEN and MQPUT1) 441
Blank user IDs and UACC levels 446
Auditing considerations 447
Auditing RESLEVEL 447
Statistics 448

Chapter 27. MQSeries security implementation 449
Security implementation checklist 449
MQSeries security management 451
User ID timeouts 451
User ID reverification 452
Security refreshes 452
Displaying security status 453
Customizing security 454

© Copyright IBM Corp. 1993,1999

Security considerations for using MQSeries with CICS 455
Controlling the security of CICS transactions supplied by MQSeries 455
CICS adapter user IDs 456
Security considerations for the CICS bridge 457
Security considerations for using MQSeries with IMS 459
Using the OPERCMDS class 459
Security considerations for the IMS bridge 459
Security considerations for distributed queuing 463
Security considerations for cluster support 465
Security installation tasks 466
Setting up MQSeries data set and system security 466
Example security scenario 468
Security switch settings 468
MQSeries object definitions 469
User IDs used in scenarios 470
Security profiles and accesses required 470
Security problem determination 474
Violation messages 474
What to do if access is allowed or disallowed incorrectly 475

Chapter 25. Introduction to MQSeries security

Important

This section assumes you are using Resource Access Control Facility (RACF) as the external security manager (ESM) in your installation. Therefore, if you are using a different ESM, you must modify the techniques described here.

It also assumes that you are familiar with MQSeries concepts and terminology described in the *MQSeries Application Programming Guide*.

Where profile names are shown, replace the subsystem identifier (ssid) in the profile name with the name of the MQSeries subsystem you are using.

Why you need to protect MQSeries resources

Because MQSeries handles the transfer of information that is potentially valuable, it needs the safeguard of a security system. This is to ensure that the resources MQSeries owns and manages are protected from unauthorized access that might lead to the loss or disclosure of the information. It is essential that none of the following are accessed or changed by any unauthorized user or process:

- Connections to MQSeries
- MQSeries objects such as queues, processes, and namelists
- MQSeries transmission links
- MQSeries system control commands
- MQSeries messages
- Context information associated with messages

If you do nothing

If you do nothing about security, the most likely effect is that ***all*** users can access and change ***every*** resource. This includes not only local users, but also those on remote systems using distributed queuing or clients, where the logon security controls might be less strict than is normally the case for OS/390.

To provide the necessary security, MQSeries uses the OS/390 system authorization facility (SAF) to route authorization requests to an ESM, for example, RACF. MQSeries does no security verification of its own. Where distributed queuing or clients are being used, additional security measures might be required, for which MQSeries provides channel exits and the MCAUSER channel attribute.

The decision to allow access to an object is made by the ESM and MQSeries follows that decision. If the ESM cannot make a decision, MQSeries prevents access to the object.

© Copyright IBM Corp. 1993,1999

Implementing MQSeries security

It is easier to set up and administer your security if you first decide on a set of naming conventions for your MQSeries objects.

To implement the security strategy for your MQSeries subsystem, you must decide:

- How security is to be used and implemented.
- Who is going to use the MQSeries system and resources.

Read through the topics listed above, noting the work that must be done before anyone uses the system. Then work through "Security implementation checklist" on page 449 to set up the security you need for each of your MQSeries subsystems. See "Security installation tasks" on page 466 to see how to tailor your security system.

To use the RACF examples as shown in this manual, you must be a suitably authorized user, for example, a SYSTEM SPECIAL user. You can enter the commands from either TSO in the RACF command form or the RACF ISPF panels.

Security controls and options

You can specify whether security is turned on for the whole MQSeries subsystem, and you can also control the number of user IDs checked for API-resource security.

Subsystem security

Subsystem security is a control that specifies whether any security checking is done on the whole MQSeries subsystem. If the security on your CICS, IMS, TSO, or batch system is adequate, you can turn off security checking for the MQSeries subsystem so that no further security checking takes place.

Note: This is the only check that affects other security checks. That is, if you turn off checking for the MQSeries subsystem, no other MQSeries checking is done; if you leave it turned on, MQSeries checks your security requirements for other MQSeries resources.

RESLEVEL

RESLEVEL is a RACF profile that controls the number of user IDs checked for MQSeries resource security. Normally, when a user attempts to access an MQSeries resource, RACF checks the relevant user ID or IDs to see if access is allowed to that resource. By defining a RESLEVEL profile you can control whether zero, one or, where applicable, two user IDs are checked.

There is only one RESLEVEL profile per queue manager. Control is implemented by the access that a user ID has to this profile.

Resources you can protect

When MQSeries starts, or when instructed by an operator command, MQSeries determines which resources you want to protect. You can control which security checks are performed for each individual queue manager. For example, you could implement a number of security checks on a production queue manager, but none on a test queue manager.

Connection security

Connection security checking is carried out either when an application program tries to connect to a queue manager by issuing an **MQCONN** request or when the CICS or IMS adapter issues a connection request. You can turn connection security checking off for a particular MQSeries subsystem, but if you do any user can connect to that subsystem.

For the CICS adapter, only the CICS address space user ID is used for the connection security check—not the individual CICS terminal user ID. For the IMS adapter, when the IMS control or dependent regions connect to MQSeries, the IMS address space user ID is checked.

API-resource security

Resources are checked when an application opens an object with an **MQOPEN** or an **MQPUT1** call. The RACF access needed to open an object depends on what open options are specified when the queue is opened.

API-resource security is subdivided into these checks:

- Queue
- Process
- Namelist
- Context
- Alternate user

No security checks are performed when opening the queue manager object.

Queue security

Queue security checking controls who is allowed to open which queue, and what options they are allowed to open it with. For example, a user might be allowed to open a queue called PAYROLL.INCREASE.SALARY to browse the messages on the queue (via the MQOO_BROWSE option), but not to remove messages from the queue (via one of the MQOO_INPUT_* options). If you turn checking for queues off, any user can open any queue with any valid open option (that is, any valid MQOO_* option on an **MQOPEN** or **MQPUT1** call).

Process security

Process security checking is carried out when a user opens a process definition object. If you turn checking for processes off, any user can open any process.

Namelist security

Namelist security checking is carried out when a user opens a namelist. If you turn checking for namelists off, any user can open any namelist.

Alternate user security

Alternate user security controls whether one user ID can use the authority of another user ID to open an MQSeries object.

For example:

- A server program running under user ID PAYSERV retrieves a request message from a queue that was put on the queue by user ID USER1.
- When the server program gets the request message, it processes the request and puts the reply back into the reply-to-queue specified with the request message.
- Instead of using its own user ID (PAYSERV) to authorize opening the reply-to-queue, the server can specify some other user ID, in this case, USER1. In this example, alternate user security would control whether user ID PAYSERV is allowed to specify user ID USER1 as an alternate user ID when opening the reply-to-queue.

If alternate user security is not active, any user can use any other user ID as an alternate user ID.

The alternate user ID is specified in the *AlternateUserId* field of the object descriptor (MQOD).

Note: You can use alternate user IDs on any MQSeries object, for example, processes or namelists. It does not affect the user ID used by any other resource managers, for example, for CICS security or for OS/390 data set security. See “Profiles for alternate user security” on page 425 for more information.

Context security

Context is information that is applicable to a particular message and is contained in the message descriptor (MQMD) that is part of the message. The context information comes in two sections:

Identity section The user of the application that first put the message to a queue. It consists of the following fields:

- *UserIdentifier*
- *AccountingToken*
- *ApplIdentityData*

Origin section The application that put the message on the queue where it is currently stored. It consists of the following fields:

- *PutApplType*
- *PutApplName*
- *PutDate*
- *PutTime*
- *ApplOriginData*

Applications can specify the context data when either an **MQOPEN** or an **MQPUT1** call is made. This data might be generated by the application, it might be passed

on from another message, or it might be generated by the queue manager by default. For example, context data can be used by server programs to check the identity of the requester, that is, did this message come from the correct application? Typically, the *UserIdentifier* field is used to determine the user ID of an alternate user.

You use context security to control whether the user can specify any of the context options on any **MQOPEN** or **MQPUT1** call. For information about the context options, see the *MQSeries Application Programming Guide*; for descriptions of the message descriptor fields relating to context, see the *MQSeries Application Programming Reference* manual. If you turn context security checking off, any user can use any of the context options that the queue security allows.

See "Profiles for context security" on page 427 for more information.

Command security

Command security checking is carried out when a user issues an MQSeries *command* from any of the sources described in "Managing MQSeries with commands and utilities" on page 19. A separate check can be made on the resource specified by the command as described in "Command resource security."

If you turn off command checking, issuers of commands are not checked to see whether they have the authority to issue the command.

If MQSeries commands are entered from a console, the console must have the OS/390 SYS console authority attribute. Commands that are issued from the CSQINP1 or CSQINP2 data sets, or internally by the queue manager, are exempt from all security checking while those for CSQINPX use the user ID of the channel initiator address space. You should control who is allowed to update these data sets through normal data set protection. See "Profiles for command security" on page 431 for more information.

Security checking for the operations and control panels

If you are going to use the operations and control panels, you must have the appropriate authority to issue the commands corresponding to the actions that you choose. In addition, you must have READ access to all the ssid.DISPLAY.*object* profiles in the MQCMDS class (see Table 45 on page 433) because the panels use the various DISPLAY commands to gather the information that they present.

Command resource security

Some MQSeries commands, for example defining a local queue, involve the manipulation of MQSeries resources. When command resource security is active, each time a command involving a resource is issued, MQSeries checks to see if the user is allowed to change the definition of that resource.

You can use command resource security to help enforce naming standards. For example, a payroll administrator might be allowed to delete and define only queues with names beginning "PAYROLL". If command resource security is inactive, no security checks are made on the resource that is being manipulated by the command. Do not confuse command resource security with command security; the two are independent.

Note: Turning off command resource security checking does not affect the resource checking that is done specifically for other types of processing that do not involve commands.

See “Profiles for command resource security” on page 432 for more information.

Chapter 26. Using RACF classes and profiles

This chapter discusses the following subjects:

- "Using RACF security classes" on page 410
- "RACF profiles" on page 411
- "Switch profiles" on page 411
- "Profiles used to protect MQSeries resources" on page 414
- "Profiles for command security" on page 431
- "Profiles for command resource security" on page 432
- "Using the RESLEVEL security profile" on page 435
- "User IDs for security checking" on page 440
- "Auditing considerations" on page 447

© Copyright IBM Corp. 1993,1999

Using RACF security classes

RACF classes are used to hold the profiles required for MQSeries security checking. Each RACF class holds one or more profiles used at some point in the checking sequence, as shown in Table 35.

Table 35. RACF classes used by MQSeries

Member class	Group class	Contents
MQADMIN	GMQADMIN	Profiles: Used mainly for holding profiles for administration-type functions. For example: • Profiles for MQSeries security switches • The RESLEVEL security profile • Profiles for alternate user security • The context security profile • Profiles for command resource security
MQCONN		Profiles used for connection security
MQCMDS		Profiles used for command security
MQQUEUE	GMQQUEUE	Profiles used in queue resource security
MQPROC	GMQPROC	Profiles used in process resource security
MQNLIST	GMQNLIST	Profiles used in namelist resource security

Some classes have a related *group class* that enables you to put together groups of resources that have similar access requirements. For details about the difference between the member and group classes and when to use a member or group class, see the *Security Server (RACF) Security Administrator's Guide*.

The classes must be activated before security checks can be made. To activate all of the MQSeries classes, you use can use this RACF command:

```
SETROPTS CLASSACT(MQADMIN,MQQUEUE,MQPROC,MQNLIST,MQCONN,MQCMDS)
```

You should also ensure that you set up the classes so that they can accept generic profiles. You also do this with the RACF command SETROPTS, for example:

```
SETROPTS GENERIC(MQADMIN,MQQUEUE,MQPROC,MQNLIST,MQCONN,MQCMDS)
```

RACF profiles

All RACF profiles used by MQSeries are prefixed with the name of the subsystem that they are to be used by. For example, if queue manager STCD has a queue called QUEUE_FOR_LOST_CARD_LIST, the appropriate profile would be defined to RACF as:

```
RDEFINE MQQUEUE STCD.QUEUE_FOR_LOST_CARD_LIST
```

This means that different MQSeries subsystems sharing the same RACF database can have different security options. The subsystem ID in the profile cannot be generic.

Note: MQSeries allows the use of the percent character (%) in object names. However, RACF uses the % character as a single-character wild card. This means that when you define an object name with a % character in its name, you must consider this when you define the corresponding profile.

For example, for the queue CREDIT_CARD_%_RATE_INQUIRY, on queue manager CRDP, the profile would be defined to RACF as follows:

```
RDEFINE MQQUEUE CRDP.CREDIT_CARD_%_RATE_INQUIRY
```

This queue cannot be protected by a generic profile, such as, CRDP.**.

Switch profiles

To control the security checking performed by MQSeries, you must define *switch profiles*. A switch profile is a normal RACF profile that has a special meaning to MQSeries. The access list in switch profiles is not used by MQSeries.

Each switch profile that MQSeries detects turns off the checking for that type of resource. Switch profiles are activated during startup of the queue manager. If you change the switch profiles while the queue manager is running, you can get MQSeries to recognize the changes by issuing the MQSeries command REFRESH SECURITY.

The switch profiles must always be defined in the MQADMIN class. Table 36 on page 412 shows the valid switch profiles and the security type they control. Do not define them in the GMQADMIN class.

Note: In the descriptions that follow, the parts of profile names shown in uppercase must be entered exactly as shown. The lowercase 'ssid' part must be replaced by the queue manager name for the MQSeries subsystem you are setting up.

Switch profiles

Table 36. Switch profiles	
Switch profile name	**Type of resource or checking that is controlled**
ssid.NO.SUBSYS.SECURITY	Subsystem security
ssid.NO.CONNECT.CHECKS	Connection security
ssid.NO.QUEUE.CHECKS	Queue security
ssid.NO.PROCESS.CHECKS	Process security
ssid.NO.NLIST.CHECKS	Namelist security
ssid.NO.CONTEXT.CHECKS	Context security
ssid.NO.ALTERNATE.USER.CHECKS	Alternate user security
ssid.NO.CMD.CHECKS	Command security
ssid.NO.CMD.RESC.CHECKS	Command resource security
Note: Generic switch profiles such as ssid.NO.** are not detected by MQSeries	

How switches work

MQSeries maintains a switch, which is associated with each of the switch profiles shown in Table 36. When a security switch is set on, the security checks associated with the switch are performed. When a security switch is set off, the security checks associated with switch are bypassed.

When a queue manager is started or when the MQADMIN class is refreshed by the MQSeries command REFRESH SECURITY, the queue manager first checks the status of RACF and the MQADMIN class. It sets its subsystem security switch off if it discovers one of these conditions:

- RACF is inactive or not installed
- The MQADMIN class is not defined
- The MQADMIN class has not been activated

If both RACF and the MQADMIN class are active, the queue manager checks the MQADMIN class to see whether any of the switch profiles have been defined. It first checks for the ssid.NO.SUBSYS.SECURITY profile. If this profile is defined, the queue manager sets its subsystem security switch off, and performs no further checks. If this profile is not defined, the queue manager sets the subsystem security switch on and checks whether any of the other switch profiles are present. If they are, the corresponding MQSeries switch is set off and that type of security is deactivated.

However, if any MQSeries switch is set on, the queue manager checks the status of the RACF class associated with the type of security corresponding to the MQSeries switch. If the class is not installed or not active, the MQSeries switch is set off. For example, process security checks are not carried out if the MQPROC class has not been activated. The class not being active is equivalent to defining an ssid.NO.PROCESS.CHECKS for every queue manager that uses this RACF database.

An example of defining switches

Three MQSeries subsystems have been defined called PROD, DEVT, and TEST respectively and all MQSeries RACF classes have been defined and activated. These subsystems have different security requirements:

- Queue manager PROD requires all MQSeries security checking to be active.

  This is done by ensuring no PROD.NO.xx profiles are defined in the MQADMIN class. You can check this by using the RACF command, SEARCH, for example:

```
SEARCH CLASS(MQADMIN) MASK(PROD.NO)
```

  and checking the resulting output.

- Queue manager DEVT requires only connection and queue security to be active.

  This is done by defining DEVT.NO.xx profiles for each of the security types you do *not* want. For example:

```
RDEFINE MQADMIN DEVT.NO.CMD.CHECKS
RDEFINE MQADMIN DEVT.NO.CMD.RESC.CHECKS
RDEFINE MQADMIN DEVT.NO.PROCESS.CHECKS
RDEFINE MQADMIN DEVT.NO.NLIST.CHECKS
RDEFINE MQADMIN DEVT.NO.CONTEXT.CHECKS
RDEFINE MQADMIN DEVT.NO.ALTERNATE.USER.CHECKS
```

  You should also check there are no other DEVT.NO.xx profiles defined in the MQADMIN class.

- Queue manager TEST does not require any security checking at all.

  This is done by defining the NO.SUBSYS.SECURITY profile for TEST as follows:

```
RDEFINE MQADMIN TEST.NO.SUBSYS.SECURITY
```

Once MQSeries is active, you can display the current security settings by issuing the MQSeries command DISPLAY SECURITY.

You can also change the switch settings when MQSeries is running by defining or deleting the appropriate switch profile in the MQADMIN class. To make the changes to the switch settings active, you must issue the MQSeries command REFRESH SECURITY for the MQADMIN class.

See “Security refreshes” on page 452 for more details about using the MQSeries commands DISPLAY SECURITY and REFRESH SECURITY.

Profiles used to protect MQSeries resources

In addition to the switch profiles that might have been defined, RACF profiles must be defined to protect the MQSeries resources.

If you do not have a resource profile defined for a particular security check, and a user issues a request that would involve making that check, MQSeries denies access.

You do not need to define profiles for security types relating to any security switch profiles that you have deactivated.

Profiles for connection security

If connection security is active, you must define profiles in the MQCONN class and permit the necessary groups or user IDs access to those profiles, so that they can connect to MQSeries subsystems.

To enable a connection to be made, you must grant users RACF READ access to the appropriate profile.

Notes:

1. For information about the user IDs checked for different security requests, see “User IDs for security checking” on page 440.
2. Resource level security (RESLEVEL) checks are also made at connection time. For details, see “Using the RESLEVEL security profile” on page 435.

Connection security profiles for the Batch/TSO adapter

Profiles for checking connections from Batch or TSO take the form:

```
ssid.BATCH
```

RRS uses the Batch/TSO adapter for connection security.

For connection requests through Batch or TSO, you must permit the job or TSO user ID to access the connection profile. For example, the following RACF command allows Batch and TSO users in the CONNTQM1 group to connect to the queue manager TQM1:

```
RDEFINE MQCONN TQM1.BATCH UACC(NONE)
PERMIT TQM1.BATCH CLASS(MQCONN) ID(CONNTQM1) ACCESS(READ)
```

Connection security profiles for the CICS adapter

Profiles for checking connections from CICS take the form:

```
ssid.CICS
```

For connection requests by CICS, you need only define the CICS address space user ID access to the connection profile.

For example, the following RACF commands allow the CICS address space user ID KCBCICS to connect to the queue manager TQM1:

```
RDEFINE MQCONN TQM1.CICS UACC(NONE)
PERMIT TQM1.CICS CLASS(MQCONN) ID(KCBCICS) ACCESS(READ)
```

Connection security profiles for the IMS adapter

Profiles for checking connections from IMS take the form:

```
ssid.IMS
```

For connection requests by IMS, define access to the connection profile for the IMS control and dependent region user IDs.

For example, the following RACF commands allow:

- The IMS region user ID, IMSREG, to connect to the queue manager TQM1.
- Users in group BMPGRP to submit BMP jobs.

```
RDEFINE MQCONN TQM1.IMS UACC(NONE)
PERMIT TQM1.IMS CLASS(MQCONN) ID(IMSREG,BMPGRP) ACCESS(READ)
```

Connection security profiles for distributed queuing

Profiles for checking connections from distributed queuing (without CICS ISC) take the form:

```
ssid.CHIN
```

For connection requests by the channel initiator, define access to the connection profile for the user ID used by the channel initiator started task address space.

For example, the following RACF commands allow the channel initiator address space running with user ID DQCTRL to connect to the queue manager TQM1:

```
RDEFINE MQCONN TQM1.CHIN UACC(NONE)
PERMIT TQM1.CHIN CLASS(MQCONN) ID(DQCTRL) ACCESS(READ)
```

Profiles for queue security

If queue security is active, you must define profiles in the MQQUEUE or GMQQUEUE classes and permit the necessary groups or user IDs access to these profiles, so they can issue MQSeries API requests that use queues.

Profiles for queue security take the form:

```
ssid.queuename
```

where `queuename` is the name of the queue being opened, as specified in the object descriptor on the **MQOPEN** or **MQPUT1** call. For details of how queue security operates when the queue name is that of an alias or a model queue, see "Considerations for alias queues" on page 417 and "Considerations for model queues" on page 419.

The RACF access required to open a queue depends on the **MQOPEN** or **MQPUT1** options specified. If more than one of the MQOO_★ and MQPMO_★ options is coded, the queue security check is performed for the highest RACF authority required.

Table 37. Access levels for queue security

MQOPEN or MQPUT1 option	**RACF access level required to access ssid.queuename**
MQOO_BROWSE	READ
MQOO_INQUIRE	READ
MQOO_BIND_★	UPDATE
MQOO_INPUT_★	UPDATE
MQOO_OUTPUT or MQPUT1	UPDATE
MQOO_PASS_ALL_CONTEXT MQPMO_PASS_ALL_CONTEXT	UPDATE
MQOO_PASS_IDENTITY_CONTEXT MQPMO_PASS_IDENTITY_CONTEXT	UPDATE
MQOO_SAVE_ALL_CONTEXT	UPDATE
MQOO_SET_IDENTITY_CONTEXT MQPMO_SET_IDENTITY_CONTEXT	UPDATE
MQOO_SET_ALL_CONTEXT MQPMO_SET_ALL_CONTEXT	UPDATE
MQOO_SET	ALTER

For example, on MQSeries subsystem QM77, all user IDs in the RACF group PAYGRP are to be given access to get messages from or put messages to all queues with names beginning with 'PAY.'. You can do this using these RACF commands:

```
RDEFINE MQQUEUE QM77.PAY.** UACC(NONE)
PERMIT QM77.PAY.** CLASS(MQQUEUE) ID(PAYGRP) ACCESS(UPDATE)
```

Also, all user IDs in the PAYGRP group must have access to put messages on queues that do not follow the PAY naming convention. For example:

```
REQUEST_QUEUE_FOR_PAYROLL
SALARY.INCREASE.SERVER
REPLIES.FROM.SALARY.MODEL
```

You can do this by defining profiles for these queues in the GMQQUEUE class and giving access to that class as follows:

```
RDEFINE GMQQUEUE PAYROLL.EXTRAS UACC(NONE)
        ADDMEM(QM77.REQUEST_QUEUE_FOR_PAYROLL,
               QM77.SALARY.INCREASE.SERVER,
               QM77.REPLIES.FROM.SALARY.MODEL)
PERMIT PAYROLL.EXTRAS CLASS(GMQQUEUE) ID(PAYGRP) ACCESS(UPDATE)
```

Note: If the RACF access level that an application has to a queue security profile is changed, the changes will only take effect for any new object handles obtained (that is, new **MQOPEN**s) for that queue. Those handles already in existence at the time of the change retain their existing access to the queue. If an application is required to use its changed access level to the queue rather than its existing access level, it must close and re-open the queue for each object handle that requires the change.

Other types of security checks might also occur at the time the queue is opened depending on the open options specified and the types of security that are active. See also "Profiles for context security" on page 427 and "Profiles for alternate user security" on page 425. For a summary table showing the open options and the security authorization needed when queue, context, and alternate user security are all active, see Table 44 on page 429.

Considerations for alias queues

When you issue an **MQOPEN** or **MQPUT1** call for an alias queue, MQSeries makes a resource check against the queue name specified in the object descriptor (MQOD) on the call. It does not check if the user is allowed access to the target queue name.

For example, an alias queue called PAYROLL.REQUEST resolves to a target queue of PAY.REQUEST. If queue security is active, you need only be authorized to access the queue PAYROLL.REQUEST. No check is made to see if you are authorized to access the queue PAY.REQUEST.

Using alias queues to distinguish between MQGET and MQPUT requests

The range of MQI calls available in one access level can cause a problem if you want to restrict access to a queue to allow only the **MQPUT** call or only the **MQGET** call. A queue can be protected by defining two aliases that resolve to that queue: one that enables applications to get messages from the queue, and one that enable applications to put messages on the queue.

The following text gives you an example of how you can define your queues to MQSeries:

```
DEFINE QLOCAL(MUST_USE_ALIAS_TO_ACCESS) GET(ENABLED)
       PUT(ENABLED)

DEFINE QALIAS(USE_THIS_ONE_FOR_GETS) GET(ENABLED)
       PUT(DISABLED) TARGQ(MUST_USE_ALIAS_TO_ACCESS)

DEFINE QALIAS(USE_THIS_ONE_FOR_PUTS) GET(DISABLED)
       PUT(ENABLED) TARGQ(MUST_USE_ALIAS_TO_ACCESS)
```

You must also make these RACF definitions:

```
RDEFINE MQQUEUE ssid.MUST_USE_ALIAS_TO_ACCESS UACC(NONE)
RDEFINE MQQUEUE ssid.USE_THIS_ONE_FOR_GETS UACC(NONE)
RDEFINE MQQUEUE ssid.USE_THIS_ONE_FOR_PUTS UACC(NONE)
```

Then you ensure no users have access to the queue ssid.MUST_USE_ALIAS_TO_ACCESS, and give the appropriate users or groups access to the alias. You can do this using these RACF commands:

```
PERMIT ssid.USE_THIS_ONE_FOR_GETS CLASS(MQQUEUE)
       ID(GETUSER,GETGRP) ACCESS(UPDATE)
PERMIT ssid.USE_THIS_ONE_FOR_PUTS CLASS(MQQUEUE)
       ID(PUTUSER,PUTGRP) ACCESS(UPDATE)
```

This means user ID GETUSER and user IDs in the group GETGRP are only allowed to get messages on MUST_USE_ALIAS_TO_ACCESS through the alias queue USE_THIS_ONE_FOR_GETS; and user ID PUTUSER and user IDs in the group PUTGRP are only allowed to put messages through the alias queue USE_THIS_ONE_FOR_PUTS.

If you want to use a technique like this, you must inform your application developers, so they can design their programs appropriately.

Considerations for model queues

When you open a model queue, MQSeries security makes two queue security checks:

1. Are you authorized to access the model queue?
2. Are you authorized to access the dynamic queue to which the model queue resolves?

If the dynamic queue name contains a trailing ⋆ character, this ⋆ is replaced by a character string generated by MQSeries, to create a dynamic queue with a unique name. However, because the whole name, including this generated string, is used for checking authority, you should define generic profiles for these queues.

For example, an **MQOPEN** call uses a model queue name of CREDIT.CHECK.REPLY.MODEL and a dynamic queue name of CREDIT.REPLY.⋆ on queue manager MQSP. To do this, you must issue the following RACF commands to define the necessary queue profiles:

```
RDEFINE MQQUEUE MQSP.CREDIT.CHECK.REPLY.MODEL
RDEFINE MQQUEUE MQSP.CREDIT.REPLY.⋆⋆
```

You must also issue the corresponding RACF PERMIT commands to allow the user access to these profiles.

A typical dynamic queue name created by an **MQOPEN** is something like CREDIT.REPLY.A346EF00367849A0. The precise value of the last qualifier is unpredictable; this is why you should use generic profiles for such queue names.

A number of MQSeries utilities put messages on dynamic queues. You should define profiles for the following dynamic queue names, and provide RACF UPDATE access to the relevant user IDs (see “User IDs for security checking” on page 440 for the correct user IDs):

```
SYSTEM.CSQUTIL.*  (used by CSQUTIL)
SYSTEM.CSQOREXX.* (used by the operations and control panels)
SYSTEM.CSQXCMD.*  (used by the channel initiator when processing CSQINPX)
CSQ4SAMP.*        (used by the MQSeries supplied samples)
```

You might also consider defining a profile to control use of the dynamic queue name used by default in the application programming copy members. The MQSeries-supplied copybooks contain a default *DynamicQName*, which is CSQ.⋆. This enables an appropriate RACF profile to be established.

Note: Do not allow application programmers to specify a single ⋆ for the dynamic queue name. If you do, you must define an ssid.⋆⋆ profile in the MQQUEUE class, and you would have to give it wide-ranging access. This means that this profile could also be used for other non-dynamic queues that do not have a more specific RACF profile. Your users could, therefore, gain access to queues you do not want them to access.

Close options on permanent dynamic queues

If an application opens a permanent dynamic queue that was created by another application and then attempts to delete that queue with an **MQCLOSE** option, some extra security checks are applied when the attempt is made. See Table 38.

Table 38. Access levels for close options on permanent dynamic queues

MQCLOSE option	RACF access level required to ssid.queuename
MQCO_DELETE	ALTER
MQCO_DELETE_PURGE	ALTER

Security and remote queues

When a message is put on a remote queue, the queue security that is performed by the local queue manager depends on how the remote queue is specified when it is opened. For example:

1. If the remote queue has been defined on the local queue manager through the MQSeries command, DEFINE QREMOTE, the queue that is checked is the name of the remote queue. For example, if a remote queue is defined on queue manager MQS1 as follows:

```
DEFINE QREMOTE(BANK7.CREDIT.REFERENCE)
       RNAME(CREDIT.SCORING.REQUEST)
       RQMNAME(BNK7)
       XMITQ(BANK1.TO.BANK7)
```

   In this case, a profile for BANK7.CREDIT.REFERENCE, must be defined in the MQQUEUE class.

2. If the *ObjectQMgrName* for the request does not resolve to the local queue manager, the queue used for queue security is the name of the transmission queue used to send messages to the remote queue manager specified by the *MQOD_ObjectQMgrName*.

   For example, the transmission queue BANK1.TO.BANK7 is defined on queue manager MQS1. An **MQPUT1** request is then issued on MQS1 specifying *ObjectName* as BANK1.INTERBANK.TRANSFERS and an *ObjectQMgrName* of BANK1.TO.BANK7. In this case, the user performing the request must have access to MQS1.BANK1.TO.BANK7.

3. If you make an **MQPUT** request to a queue and specify *ObjectQMgrName* as the name of an alias of the local queue manager, only the queue name is checked for security, not that of the queue manager.

When the message gets to the remote queue manager it might be subject to additional security processing. For more information, see the *MQSeries Intercommunication* manual.

Dead-letter queue security

Undelivered messages can be put on a special queue called the dead-letter queue. If you have sensitive data that could possibly end up on this queue, you must consider the security implications of this because you do not want unauthorized users to be able to retrieve this data.

Each of the following must be able to put messages onto the dead-letter queue:

- Application programs.
- The channel initiator address space and any MCA user IDs. (If the RESLEVEL profile is not present, or is defined so that network-received user IDs are checked, the network-received user ID also needs authority to put messages on the dead-letter queue.)
- For distributed queuing using CICS, the various MCA transactions.
- CKTI, the MQSeries-supplied CICS task initiator.
- CSQQTRMN, the MQSeries-supplied IMS trigger monitor.

The only application able to retrieve messages from the dead-letter queue should be a 'special' application that processes these messages. However, a problem arises if you give applications RACF UPDATE authority to the dead-letter queue for **MQPUT**s because they can then automatically retrieve messages from the queue using **MQGET** calls. You cannot disable the dead-letter queue for get operations because, if you do, not even the 'special' applications could retrieve the messages.

One solution to this problem is set up a two-level access to the dead-letter queue. CKTI, message channel agent transactions or the channel initiator address space, and 'special' applications have direct access; other applications can only access the dead-letter queue through an alias queue. This alias is defined to allow applications to put messages on the dead-letter queue, but not to get messages from it.

This is how it might work:

1. Define the real dead-letter queue with attributes PUT(ENABLED) and GET(ENABLED), as shown in the sample thlqual.SCSQPROC(CSQ4INYG).
2. Give RACF UPDATE authority for the dead-letter queue to the following user IDs:
   - User IDs that the CKTI and the MCAs or channel initiator address space run under.
   - The user IDs associated with the 'special' dead-letter queue processing application.
3. Define an alias queue that resolves to the real dead-letter queue, but give the alias queue these attributes: PUT(ENABLED) and GET(DISABLED). Give the alias queue a name with the same stem as the dead-letter queue name but append the characters ".PUT" to this stem. For example, if the dead-letter queue name is ssid.DEAD.QUEUE, the alias queue name would be ssid.DEAD.QUEUE.PUT.

4. To put a message on the dead-letter queue, an application uses the alias queue. This what your application must do:
   - Retrieve the name of the real dead-letter queue. To do this, it opens the queue manager object using **MQOPEN** and then issues an **MQINQ** to get the dead-letter queue name.
   - Build the name of the alias queue by appending the characters '.PUT' to this name, in this case, ssid.DEAD.QUEUE.PUT.
   - Open the alias queue, ssid.DEAD.QUEUE.PUT.
   - Put the message on the real dead-letter queue by issuing an **MQPUT** against the alias queue.
5. Give the user ID associated with the application RACF UPDATE authority to the alias, but no access (authority NONE) to the real dead-letter queue. This means that:
   - The application can put messages onto the dead-letter queue using the alias queue.
   - The application cannot get messages from the dead-letter queue using the alias queue because the alias queue is disabled for get operations.

   The application cannot get any messages from the real dead-letter queue either because it does have the correct RACF authority.

Table 39 summarizes the RACF authority required for the various participants in this solution.

Table 39. RACF authority to the dead-letter queue and its alias

Associated user IDs	**Real dead-letter queue (ssid.DEAD.QUEUE)**	**Alias dead-letter queue (ssid.DEAD.QUEUE.PUT)**
MCA or channel initiator address space and CKTI	UPDATE	NONE
'Special' application (for dead-letter queue processing)	UPDATE	NONE
User-written application user IDs	NONE	UPDATE

If you use this method, the application cannot determine the maximum message length, MAXMSGL, of the dead-letter queue. This is because the MAXMSGL attribute cannot be retrieved from an alias queue. Therefore, your application should assume that the maximum message length is 4 MB, the maximum size MQSeries for OS/390 supports. The real dead-letter queue should also be defined with a MAXMSGL attribute of 4 MB.

Note: User-written application programs should not normally use alternate user authority to put messages on the dead-letter queue. This reduces the number of user IDs that have access to the dead-letter queue.

System queue security

Many of the system queues are accessed by the ancillary parts of the queue manager:

- The CSQUTIL utility
- The operations and control panels
- The channel initiator address space for distributed queuing without CICS
- The CICS transactions for distributed queuing using CICS

The user IDs under which these run must be given RACF access to these queues, as shown in the following table:

	CSQUTIL	Operations and control panels	Channel initiator for distributed queuing without CICS	Transactions for distributed queuing with CICS
SYSTEM.ADMIN.CHANNEL.EVENT			UPDATE	
SYSTEM.CHANNEL.COMMAND				UPDATE
SYSTEM.CHANNEL.INITQ			UPDATE	
SYSTEM.CHANNEL.SEQNO				UPDATE
SYSTEM.CHANNEL.SYNCQ			UPDATE	
SYSTEM.CLUSTER.COMMAND.QUEUE			ALTER	
SYSTEM.CLUSTER.REPOSITORY.QUEUE			UPDATE	
SYSTEM.CLUSTER.TRANSMIT.QUEUE			ALTER	
SYSTEM.COMMAND.INPUT	UPDATE	UPDATE	UPDATE	
SYSTEM.COMMAND.REPLY.MODEL	UPDATE	UPDATE	UPDATE	
SYSTEM.CSQOREXX.*		UPDATE		
SYSTEM.CSQUTIL.*	UPDATE			
SYSTEM.CSQXCMD.*			UPDATE	

Profiles for processes

If process security is active, you must define profiles in the MQPROC or GMQPROC classes and permit the necessary groups or user IDs access to these profiles, so they can use MQI requests that use processes. Profiles for processes take the form:

```
ssid.processname
```

where `processname` is the name of the process being opened. The following table shows the access required for opening a process.

Table 40. Access levels for process security	
MQOPEN option	**RACF access level required to ssid.processname**
MQOO_INQUIRE	READ

For example, on queue manager MQS9, the RACF group INQVPRC must be able to inquire (**MQINQ**) on all processes starting with the letter V. The RACF definitions for this would be:

```
RDEFINE MQPROC MQS9.V* UACC(NONE)
PERMIT MQS9.V* CLASS(MQPROC) ID(INQVPRC) ACCESS(READ)
```

Alternate user security might also be active, depending on the open options specified when a process definition object is opened.

Profiles for namelists

If namelist security is active, you define profiles in the MQNLIST or GMQNLIST classes and give the necessary groups or user IDs access to these profiles.

Profiles for namelists take the form:

```
ssid.namelistname
```

where `namelistname` is the name of the namelist being opened. The following table shows the access required for opening a namelist.

Table 41. Access levels for namelist security	
MQOPEN option	**RACF access level required to ssid.namelistname**
MQOO_INQUIRE	READ

For example, on queue manager PQM3, the RACF group DEPT571 must be able to inquire (**MQINQ**) on these namelists:

- All namelists starting with “DEPT571.”
- PRINTER/DESTINATIONS/DEPT571
- AGENCY/REQUEST/QUEUES
- WAREHOUSE.BROADCAST

The RACF definitions to do this are:

```
RDEFINE MQNLIST PQM3.DEPT571.** UACC(NONE)
PERMIT PQM3.DEPT571.** CLASS(MQNLIST) ID(DEPT571) ACCESS(READ)

RDEFINE GMQNLIST NLISTS.FOR.DEPT571 UACC(NONE)
        ADDMEM(PQM3.PRINTER/DESTINATIONS/DEPT571,
               PQM3.AGENCY/REQUEST/QUEUES,
               PQM3.WAREHOUSE.BROADCAST)
PERMIT NLISTS.FOR.DEPT571 CLASS(GMQNLIST) ID(DEPT571) ACCESS(READ)
```

Alternate user security might be active, depending on the options specified when a namelist object is opened.

Profiles for alternate user security

If alternate user security is active, you must define profiles in the MQADMIN class and permit the necessary groups or user IDs access to these profiles, so that they can use the ALTERNATE_USER_AUTHORITY options when the queue is opened.

Profiles for alternate user security take the following form:

```
ssid.ALTERNATE.USER.alternateuserid
```

where `alternateuserid` is the value of the *AlternateUserId* field in the object descriptor. The following table shows the access when specifying an alternate user option.

Table 42. Access levels for alternate user security

MQOPEN or MQPUT1 option	RACF access level required
MQOO_ALTERNATE_USER_AUTHORITY MQPMO_ALTERNATE_USER_AUTHORITY	UPDATE

In addition to alternate user security checks, other security checks for queue, process, namelist, and context security can also be made. The alternate user ID, if provided, is only used for security checks on queue, process definition, or namelist resources. For alternate user and context security checks, the user ID requesting the check is used. For details about how user IDs are handled, see “User IDs for security checking” on page 440. For a summary table showing the open options and the security checks required when queue, context and alternate user security are all active, see Table 44 on page 429.

An alternate user profile gives the requesting user ID access to resources associated with the user ID specified in the alternate user ID. For example, the payroll server running under user ID PAYSERV on queue manager QMPY processes requests from personnel user IDs, all of which start with PS. To cause the work performed by the payroll server to be carried out under the user ID of the requesting user, alternate user authority is used. The payroll server knows which user ID to specify as the alternate user ID because the requesting programs generate messages using the MQPMO_DEFAULT_CONTEXT put message option.

See “User IDs for security checking” on page 440 for more details about from where alternate user IDs are obtained.

The following example RACF definitions enable the server program to specify alternate user IDs starting with the characters PS:

```
REDEFINE MQADMIN QMPY.ALTERNATE.USER.PS* UACC(NONE)
PERMIT QMPY.ALTERNATE.USER.PS* CLASS(MQADMIN) ID(PAYSERV) ACCESS(UPDATE)
```

Notes:

1. The *AlternateUserId* field in the object descriptor is 12 bytes long. All 12 bytes are used in the profile checks, but only the first eight bytes are used as the user ID by MQSeries. If this user ID truncation is not desirable, application programs making the request should translate any alternate user ID over 8 bytes into something more appropriate.
2. If you specify MQOO_ALTERNATE_USER_AUTHORITY or MQPMO_ALTERNATE_USER_AUTHORITY and you do not specify an *AlternateUserId* field in the object descriptor, a user ID of blanks is used. For the purposes of the alternate user security check the user ID used for the *AlternateUserId* qualifier is -BLANK-. For example:

   ```
   RDEF MQADMIN ssid.ALTERNATE.USER.-BLANK-
   ```

   If the user is allowed to access this profile, all further checks are made with a user ID of blanks. For details of blank user IDs, see “Blank user IDs and UACC levels” on page 446.

The administration of alternate user IDs is easier if you have a naming convention for user IDs that enables you to use generic alternate user profiles. If they do not, you could use the RACF RACVARS feature. For details about using RACVARS, see the *Security Server (RACF) Security Administrator's Guide*.

When a message is put to a queue that has been opened with alternate user authority and the context of the message has been generated by the queue manager, the MQMD_USER_IDENTIFIER field is set to the alternate user ID.

Profiles for context security

If context security is active, you must define a profile in the MQADMIN class called:

```
ssid.CONTEXT
```

You must give the necessary groups or user IDs access to this profile. The following table shows the access level required, depending on the specification of the context options when the queue is opened.

Table 43. Access levels for context security

MQOPEN or MQPUT1 option	**RACF access level required to ssid.CONTEXT**
MQPMO_NO_CONTEXT	No context security check
MQPMO_DEFAULT_CONTEXT	No context security check
MQOO_SAVE_ALL_CONTEXT	No context security check
MQOO_PASS_IDENTITY_CONTEXT MQPMO_PASS_IDENTITY_CONTEXT	READ
MQOO_PASS_ALL_CONTEXT MQPMO_PASS_ALL_CONTEXT	READ
MQOO_SET_IDENTITY_CONTEXT MQPMO_SET_IDENTITY_CONTEXT	UPDATE
MQOO_SET_ALL_CONTEXT MQPMO_SET_ALL_CONTEXT	CONTROL
MQOO_OUTPUT or MQPUT1 (Usage=XMITQ)	CONTROL

Note: The user ID of the receiving channel initiator address space (or the MCA user ID if one has been specified) requires CONTROL access to `ssid.CONTEXT` in order to put messages on the destination queue. If the RESLEVEL profile requires that two user IDs are checked, the network-received user ID also needs CONTROL access to `ssid.CONTEXT`.

If you put commands on the system-command input queue, use the default context put message option to associate the correct user ID with the command.

For example, the MQSeries-supplied utility program CSQUTIL can be used to off-load and reload messages in queues. When off-loaded messages are restored to a queue, the CSQUTIL utility uses the MQOO_SET_ALL_CONTEXT option to return the messages to their original state. In addition to the queue security required by this open option, context authority is also required. For example, if this authority is required by the group BACKGRP on queue manager MQS1, this would be defined by:

```
RDEFINE MQADMIN MQS1.CONTEXT UACC(NONE)
PERMIT MQS1.CONTEXT CLASS(MQADMIN) ID(BACKGRP) ACCESS(CONTROL)
```

Depending on the options specified, and the types of security performed, other types of security checks might also occur when the queue is opened. These include queue security (see “Profiles for queue security” on page 416), and alternate user security (see “Profiles for alternate user security” on page 425). For a summary table showing the open options and the security checks required when queue, context and alternate user security are all active, see Table 44 on page 429.

API-resource security access quick reference

Table 44 summarizes the **MQOPEN**, **MQPUT1**, and **MQCLOSE** options and the access required by the different resource security types.

Table 44. MQOPEN, MQPUT1, and MQCLOSE options and the security authorization required. Callouts shown like this **(1)** *refer to the notes following this table.*

	Minimum RACF access level required		
RACF class: RACF profile:	MQQUEUE **(1)** **(2)**	MQADMIN **(3)**	MQADMIN **(4)**
MQOPEN option			
MQOO_INQUIRE **(1)**	READ **(5)**	No check	No check
MQOO_BROWSE	READ	No check	No check
MQOO_INPUT_*	UPDATE	No check	No check
MQOO_SAVE_ALL_CONTEXT **(6)**	UPDATE	No check	No check
MQOO_OUTPUT (USAGE=NORMAL) **(7)**	UPDATE	No check	No check
MQOO_PASS_IDENTITY_CONTEXT **(8)**	UPDATE	READ	No check
MQOO_PASS_ALL_CONTEXT **(8)** **(9)**	UPDATE	READ	No check
MQOO_SET_IDENTITY_CONTEXT **(8)** **(9)**	UPDATE	UPDATE	No check
MQOO_SET_ALL_CONTEXT **(8)** **(10)**	UPDATE	CONTROL	No check
MQOO_OUTPUT (USAGE=XMITQ) **(11)**	UPDATE	CONTROL	No check
MQOO_SET	ALTER	No check	No check
MQOO_ALTERNATE_USER_AUTHORITY **(1)**	**(12)**	**(12)**	UPDATE
MQPUT1 option			
Put on a normal queue **(7)**	UPDATE	No check	No check
MQPMO_PASS_IDENTITY_CONTEXT	UPDATE	READ	No check
MQPMO_PASS_ALL_CONTEXT	UPDATE	READ	No check
MQPMO_SET_IDENTITY_CONTEXT	UPDATE	UPDATE	No check
MQPMO_SET_ALL_CONTEXT	UPDATE	CONTROL	No check
MQOO_OUTPUT Put on a transmission queue **(11)**	UPDATE	CONTROL	No check
MQPMO_ALTERNATE_USER_AUTHORITY	**(13)**	**(13)**	UPDATE
MQCLOSE option			
MQCO_DELETE **(14)**	ALTER	No check	No check
MQCO_DELETE_PURGE **(14)**	ALTER	No check	No check

Notes:

1. This option is not restricted to queues. Use the MQNLIST class for namelists, and the MQPROC class for processes.
2. Use RACF profile: ssid.localresourcename
3. Use RACF profile: ssid.CONTEXT
4. Use RACF profile: ssid.ALTERNATE.USER.`alternateuserid`

   `alternateuserid` is the user identifier that is specified in the *AlternateUserId* field of the object descriptor. Note that all 12 characters of the *AlternateUserId* field are used for this check, unlike other checks where only the first 8 characters of a user identifier are used.
5. No check is made when opening the queue manager for inquiries.

6. MQOO_INPUT_* must be specified as well. This is valid for a local, model or alias queue.
7. This check is done for a local or model queue that has a *Usage* queue attribute of MQUS_NORMAL, and also for an alias or remote queue (that is defined to the connected queue manager.) If the queue is a remote queue that is opened specifying an *ObjectQMgrName* (not the name of the connected queue manager) explicitly, the check is carried out against the queue with the same name as *ObjectQMgrName* (which must be a local queue with a *Usage* queue attribute of MQUS_TRANSMISSION).
8. MQOO_OUTPUT must be specified as well.
9. MQOO_PASS_IDENTITY_CONTEXT is implied as well by this option.
10. MQOO_PASS_IDENTITY_CONTEXT, MQOO_PASS_ALL_CONTEXT and MQOO_SET_IDENTITY_CONTEXT are implied as well by this option.
11. This check is done for a local or model queue that has a *Usage* queue attribute of MQUS_TRANSMISSION, and is being opened directly for output. It does not apply if a remote queue is being opened.
12. At least one of MQOO_INQUIRE, MQOO_BROWSE, MQOO_INPUT_*, MQOO_OUTPUT or MQOO_SET must be specified as well. The check carried out is the same as that for the other options specified.
13. The check carried out is the same as that for the other options specified.
14. This only applies when a permanent dynamic queue has been opened directly, that is, not opened through a model queue.

Profiles for command security

If you have not defined the command security switch profile, ssid.NO.CMD.CHECKS because you want security checking for commands, you must add profiles to the MQCMDS class.

The names of the RACF profiles for command security checking are based on the command names themselves. These profiles take the form:

```
ssid.verb.pkw
```

For example, the profile name for the MQSeries command ALTER QLOCAL in subsystem AMQS is:

```
AMQS.ALTER.QLOCAL
```

Table 45 on page 433 shows, for each MQSeries command, the profiles required for command security checking to be carried out, and the corresponding access level for each profile in the MQCMDS class.

Profiles for command resource security

If you have not defined the command resource security switch profile, ssid.NO.CMD.RESC.CHECKS, because you want security checking for resources associated with commands, you must add resource profiles to the MQADMIN class for each resource.

Profiles for command resource security checking take the form:

```
ssid.type.localresourcename
```

For example, the RACF profile name for command resource security checking against the model queue CREDIT.WORTHY in subsystem AMQS is:

```
AMQS.QUEUE.CREDIT.WORTHY
```

Because the profiles for all types of command resource are held in the MQADMIN class, the “type” part of the profile name is needed in the profile to distinguish between resources of different types that have the same name. The “type” part of the profile name can be CHANNEL, QUEUE, PROCESS, or NAMELIST. For example, a user might be authorized to define ssid.QUEUE.PAYROLL.ONE, but not authorized to define ssid.PROCESS.PAYROLL.ONE.

Table 45 on page 433 shows for each MQSeries command, the profiles you need to enable command resource security checking to be carried out, and the access level that you need for each in the MQADMIN class.

Command resource security checking for alias queues

When you define an alias queue, command resource security checks are only performed against the name of the alias queue, not against the name of the target queue to which the alias resolves.

Alias queues can resolve to both local and remote queues. If you do not want to permit users access to certain local or remote queues, you must do both of the following:

1. Do not allow the users access to these local and remote queues.
2. Restrict the users from being able to define aliases for these queues. That is, prevent them from being able to issue DEFINE QALIAS and ALTER QALIAS commands.

Command resource security checking for remote queues

When you define a remote queue, command resource security checks are performed only against the name of the remote queue. No checks are performed against the names of the queues specified in the RNAME or XMITQ attributes in the remote queue object definition. For more information about the attributes of queues, see the *MQSeries Command Reference* manual.

Table 45 (Page 1 of 2). Commands, profiles, and their access levels

Command	MQCMDS		MQADMIN	
	Profile	**Access level**	**Profile**	**Access level**
ALTER CHANNEL	ssid.ALTER.CHANNEL	ALTER	ssid.CHANNEL.channel	ALTER
ALTER NAMELIST	ssid.ALTER.NAMELIST	ALTER	ssid.NAMELIST.namelist	ALTER
ALTER PROCESS	ssid.ALTER.PROCESS	ALTER	ssid.PROCESS.process	ALTER
ALTER QALIAS	ssid.ALTER.QALIAS	ALTER	ssid.QUEUE.queue	ALTER
ALTER QLOCAL	ssid.ALTER.QLOCAL	ALTER	ssid.QUEUE.queue	ALTER
ALTER QMGR	ssid.ALTER.QMGR	ALTER	No check	
ALTER QMODEL	ssid.ALTER.QMODEL	ALTER	ssid.QUEUE.queue	ALTER
ALTER QREMOTE	ssid.ALTER.QREMOTE	ALTER	ssid.QUEUE.queue	ALTER
ALTER SECURITY	ssid.ALTER.SECURITY	ALTER	No check	
ALTER STGCLASS	ssid.ALTER.STGCLASS	ALTER	No check	
ALTER TRACE	ssid.ALTER.TRACE	ALTER	No check	
ARCHIVE LOG	ssid.ARCHIVE.LOG	CONTROL	No check	
DEFINE BUFFPOOL	ssid.DEFINE.BUFFPOOL	ALTER	No check	
DEFINE CHANNEL	ssid.DEFINE.CHANNEL	ALTER	ssid.CHANNEL.channel	ALTER
DEFINE MAXSMSGS	ssid.DEFINE.MAXSMSGS	ALTER	No check	
DEFINE NAMELIST	ssid.DEFINE.NAMELIST	ALTER	ssid.NAMELIST.namelist	ALTER
DEFINE PROCESS	ssid.DEFINE.PROCESS	ALTER	ssid.PROCESS.process	ALTER
DEFINE PSID	ssid.DEFINE.PSID	ALTER	No check	
DEFINE QALIAS	ssid.DEFINE.QALIAS	ALTER	ssid.QUEUE.queue	ALTER
DEFINE QLOCAL	ssid.DEFINE.QLOCAL	ALTER	ssid.QUEUE.queue	ALTER
DEFINE QMODEL	ssid.DEFINE.QMODEL	ALTER	ssid.QUEUE.queue	ALTER
DEFINE QREMOTE	ssid.DEFINE.QREMOTE	ALTER	ssid.QUEUE.queue	ALTER
DEFINE STGCLASS	ssid.DEFINE.STGCLASS	ALTER	No check	
DELETE CHANNEL	ssid.DELETE.CHANNEL	ALTER	ssid.CHANNEL.channel	ALTER
DELETE NAMELIST	ssid.DELETE.NAMELIST	ALTER	ssid.NAMELIST.namelist	ALTER
DELETE PROCESS	ssid.DELETE.PROCESS	ALTER	ssid.PROCESS.process	ALTER
DELETE QALIAS	ssid.DELETE.QALIAS	ALTER	ssid.QUEUE.queue	ALTER
DELETE QLOCAL	ssid.DELETE.QLOCAL	ALTER	ssid.QUEUE.queue	ALTER
DELETE QMODEL	ssid.DELETE.QMODEL	ALTER	ssid.QUEUE.queue	ALTER
DELETE QREMOTE	ssid.DELETE.QREMOTE	ALTER	ssid.QUEUE.queue	ALTER
DELETE STGCLASS	ssid.DELETE.STGCLASS	ALTER	No check	
DISPLAY CHANNEL	ssid.DISPLAY.CHANNEL	READ	No check	
DISPLAY CHSTATUS	ssid.DISPLAY.CHSTATUS	READ	No check	
DISPLAY CLUSQMGR	ssid.DISPLAY.CLUSQMGR	READ	No check	
DISPLAY CMDSERV	ssid.DISPLAY.CMDSERV	READ	No check	
DISPLAY DQM	ssid.DISPLAY.DQM	READ	No check	
DISPLAY MAXSMSGS	ssid.DISPLAY.MAXSMSGS	READ	No check	
DISPLAY NAMELIST	ssid.DISPLAY.NAMELIST	READ	No check	
DISPLAY PROCESS	ssid.DISPLAY.PROCESS	READ	No check	
DISPLAY QMGR	ssid.DISPLAY.QMGR	READ	No check	
DISPLAY QUEUE	ssid.DISPLAY.QUEUE	READ	No check	

Command resources profiles

Table 45 (Page 2 of 2). Commands, profiles, and their access levels

Command	MQCMDS		MQADMIN	
	Profile	**Access level**	**Profile**	**Access level**
DISPLAY THREAD	ssid.DISPLAY.THREAD	READ	No check	
DISPLAY SECURITY	ssid.DISPLAY.SECURITY	READ	No check	
DISPLAY STGCLASS	ssid.DISPLAY.STGCLASS	READ	No check	
DISPLAY TRACE	ssid.DISPLAY.TRACE	READ	No check	
DISPLAY USAGE	ssid.DISPLAY.USAGE	READ	No check	
PING CHANNEL	ssid.PING.CHANNEL	CONTROL	ssid.CHANNEL.channel	CONTROL
RECOVER BSDS	ssid.RECOVER.BSDS	CONTROL	No check	
REFRESH CLUSTER	ssid.REFRESH.CLUSTER	ALTER	No check	
REFRESH SECURITY	ssid.REFRESH.SECURITY	ALTER	No check	
RESET CHANNEL	ssid.RESET.CHANNEL	CONTROL	ssid.CHANNEL.channel	CONTROL
RESET CLUSTER	ssid.RESET.CLUSTER	CONTROL	No check	
RESET TPIPE	ssid.RESET.TPIPE	CONTROL	No check	
RESOLVE CHANNEL	ssid.RESOLVE.CHANNEL	CONTROL	ssid.CHANNEL.channel	CONTROL
RESOLVE INDOUBT	ssid.RESOLVE.INDOUBT	CONTROL	No check	
RESUME QMGR	ssid.RESUME.QMGR	CONTROL	No check	
RVERIFY SECURITY	ssid.RVERIFY.SECURITY	ALTER	No check	
START CHANNEL	ssid.START.CHANNEL	CONTROL	ssid.CHANNEL.channel	CONTROL
START CHINIT	ssid.START.CHINIT	CONTROL	No check	
START CMDSERV	ssid.START.CMDSERV	CONTROL	No check	
START LISTENER	ssid.START.LISTENER	CONTROL	No check	
START TRACE	ssid.START.TRACE	CONTROL	No check	
STOP CHANNEL	ssid.STOP.CHANNEL	CONTROL	ssid.CHANNEL.channel	CONTROL
STOP CHINIT	ssid.STOP.CHINIT	CONTROL	No check	
STOP CMDSERV	ssid.STOP.CMDSERV	CONTROL	No check	
STOP LISTENER	ssid.STOP.LISTENER	CONTROL	No check	
STOP QMGR	ssid.STOP.QMGR	CONTROL	No check	
STOP TRACE	ssid.STOP.TRACE	CONTROL	No check	
SUSPEND QMGR	ssid.SUSPEND.QMGR	CONTROL	No check	

Notes:

- MQSeries does not check the authority of the user who issues the `+cpf` START QMGR command. However, you can use RACF facilities to protect the START xxxxMSTR command that is issued as a result of the `+cpf` START QMGR command. This is done by controlling access to the MVS.START.STC.xxxxMSTR profile in the RACF operator commands (OPERCMDS) class. For details of this, see the *Security Server (RACF) Security Administrator's Guide*. If you use this technique, and an unauthorized user tries to start MQSeries, MQSeries terminates with a reason code of 00F30216.
- The DISPLAY THREAD and DISPLAY USAGE commands might be issued internally by the queue manager; no authority is checked in these cases.

Using the RESLEVEL security profile

You can define a special profile in the MQADMIN class to control the number of user IDs checked for API-resource security. How this RESLEVEL profile affects API-resource security depends on how you are accessing MQSeries.

RESLEVEL and Batch/TSO connections

By default, when an MQSeries resource is being accessed through the Batch/TSO adapter, the user must be authorized to access that resource for the particular operation. You can bypass the security check by setting up an appropriate RESLEVEL definition.

Whether the user is checked or not is based on the user ID used at connect time; the TSO user ID or the job user ID.

For example, you can set up RESLEVEL so that when a user you trust accesses certain resources from Batch/TSO, no API-resource security checks are done; but when a user you do not trust tries to access the same resources, security checks are carried out as normal. You should set up RESLEVEL checking to bypass API-resource security checks only when you sufficiently trust the user and the programs run by that user.

RESLEVEL and system utilities

The operations and control panels and the CSQUTIL utility are batch applications. You can use RESLEVEL to bypass security checking for the SYSTEM.COMMAND.INPUT and SYSTEM.COMMAND.REPLY.MODEL queues that they use, but **not** for the dynamic queues SYSTEM.CSQOREXX.* and SYSTEM.CSQUTIL.*. Users must be authorized to use these queues as described in “System queue security” on page 423 in addition to any RESLEVEL authorization they are given.

RESLEVEL and CICS connections

By default, when an API-resource security check is made on a CICS connection, two user IDs are checked to see if access is allowed to the resource.

User IDs checked

The first user ID checked is that of the CICS address space. This is the user ID on the job card of the CICS job, or the user ID assigned to the CICS started task by the OS/390 STARTED class or the started procedures table. (It is not the CICS DFLTUSER.)

The second user ID checked is the user ID associated with the CICS transaction.

Completion codes

If one of these user IDs does not have access to the resource, the request fails with a completion code of MQRC_NOT_AUTHORIZED. Both the CICS address space user ID and the user ID of the person running the CICS transaction must have access to the resource at the correct level.

How RESLEVEL can affect the checks made

Depending on how you set up your RESLEVEL profile, you can change which user IDs are checked when access to a resource is requested. The possible checks are:

- Check the CICS address space user ID and the transaction user ID.
- Check the CICS address space user ID only.
- If the transaction is defined to CICS with RESSEC(NO), check the CICS address space user ID only[5].
- If the transaction is defined to CICS with RESSEC(YES), check the CICS address space user ID and the transaction user ID[5].
- Do not check any user IDs.

The user IDs checked depend on the user ID used at connection time, that is, the CICS address space user ID. This control enables you to bypass API-resource security checking for MQSeries requests coming from one system (for example, a test system, TESTCICS,) but to implement them for another (for example, a production system, PRODCICS).

Note: If you set up your CICS address space user ID with the "trusted" attribute in the STARTED class or the RACF started procedures table ICHRIN03, this overrides any user ID checks for the CICS address space established by the RESLEVEL profile for your queue manager (that is, the queue manager does not perform the security checks for the CICS address space). For more information, see the *CICS RACF Security Guide*.

RESLEVEL and IMS connections

By default, when an API-resource security check is made for an IMS adapter, two user IDs are checked to see if access is allowed to the resource.

The first user ID checked is that of the address space of the IMS region. This is taken from either the USER field from the job card or the user ID assigned to the region from the OS/390 STARTED class or the started procedures table (SPT).

The second user ID checked is associated with the work being done in the dependent region. It is determined according to the type of the dependent region as shown in Table 53 on page 442.

The setting of MQ RESLEVEL profiles cannot alter the user ID under which IMS transactions are scheduled from the IBM-supplied MQ-IMS trigger monitor program CSQQTRMN. This user ID is the PSBNAME of that trigger monitor, which by default is CSQQTRMN.

---

[5] The status of the CICS security is NOT checked when taking into consideration the transaction RESSEC setting. For example, if CICS has been started with SEC=NO, but the transaction has been defined with RESSEC(YES), MQSeries still checks both user IDs.

Completion codes

If either the first or second IMS user ID does not have access to the resource, the request fails with a completion code of MQRC_NOT_AUTHORIZED.

How RESLEVEL can affect the checks made

Depending on how you set up your RESLEVEL profile, you can change which user IDs are checked when access to a resource is requested. The possible checks are:

- Check the IMS region address space user ID and the second user ID.
- Check IMS region address space user ID only.
- Do not check any user IDs.

RESLEVEL and channel initiator connections

By default, when an API-resource security check is made by the channel initiator, two user IDs are checked to see if access is allowed to the resource.

The user IDs checked can be that specified by the MCAUSER channel attribute, that received from the network, that of the channel initiator address space, or the alternate user ID for the message descriptor. This depends on the communication protocol you are using and the setting of the PUTAUT channel attribute. See “User IDs used by the channel initiator” on page 443 for more information.

Completion codes

If one of these user IDs does not have access to the resource, the request fails with a completion code of MQRC_NOT_AUTHORIZED.

How RESLEVEL can affect the checks made

Depending on how you set up your RESLEVEL profile, you can change which user IDs are checked when access to a resource is requested, and how many are checked.

The RESLEVEL profile

When an application tries to connect to MQSeries, MQSeries checks the access that the user ID associated with the adapter has to a profile in the MQADMIN class called:

```
ssid.RESLEVEL
```

The user IDs associated with each adapter are:

- The batch job ID or TSO user ID for the Batch/TSO adapter
- The CICS address space user ID for the CICS adapter
- The IMS region address space user ID for the IMS adapter
- The channel initiator address space user ID for the non-CICS mover.

This check is always performed unless the ssid.NO.SUBSYS.SECURITY switch has been set.

If there is no RESLEVEL profile, MQSeries enables checking of both the job and task (or alternate user) ID for a CICS or an IMS connection. For a batch connection, MQSeries enables checking of the job (or alternate) user ID. For the non-CICS mover, MQSeries enables checking of the MCA user ID and the channel (or alternate) user ID.

If there is a RESLEVEL profile, the level of checking depends on the environment and access level for the profile.

Table 46 shows the checks made for batch and TSO connections.

Table 46. Checks made at different RACF access levels for the Batch/TSO adapter

RACF access level	Level of checking
NONE	Check the job/TSO (or alternate) user ID.
READ	Check the job/TSO (or alternate) user ID.
UPDATE	Check the job/TSO (or alternate) user ID.
CONTROL	No check.
ALTER	No check.

Table 47 shows the checks made for CICS connections.

Table 47. Checks made at different RACF access levels for the CICS adapter

RACF access level	Level of checking
NONE	Check the CICS address space user ID and the task or alternate user ID.
READ	Check the CICS address space user ID.
UPDATE	Check the CICS address space user ID and, if the transaction has been defined with RESSEC=YES, also check the task or alternate user ID.
CONTROL	No check.
ALTER	No check.

Table 48 on page 439 shows the checks made for IMS connections.

Table 48. Checks made at different RACF access levels for the IMS adapter

RACF access level	Level of checking
NONE	Check the IMS address space user ID and the IMS second user ID.
READ	Check the IMS address space user ID.
UPDATE	Check the IMS address space user ID.
CONTROL	No check.
ALTER	No check.

Table 49 shows the checks made for channel initiator connections.

Table 49. Checks made at different RACF access levels for channel initiator connections

RACF access level	Level of checking
NONE	Check two user IDs.
READ	Check one user ID.
UPDATE	Check one user ID.
CONTROL	No check.
ALTER	No check.
Note: See “User IDs used by the channel initiator” on page 443 for a definition of the user IDs checked	

Table 50 through Table 56 on page 445 show how RESLEVEL affects which user IDs are checked for different MQI requests.

For example, you have a queue manager called QM66, where:

- User WS21B is to be exempt from resource security.
- CICS started task WXNCICS running under address space user ID CICSWXN is to perform full resource checking only for transactions defined with RESSEC(YES).

To define the appropriate RESLEVEL profile, issue the RACF command:

```
RDEFINE MQADMIN QM66.RESLEVEL UACC(NONE) AUDIT(ALL)
```

Then give the users access to this profile:

```
PERMIT QM66.RESLEVEL CLASS(MQADMIN) ID(WS21B) ACCESS(CONTROL)
PERMIT QM66.RESLEVEL CLASS(MQADMIN) ID(CICSWXN) ACCESS(UPDATE)
```

If you make these changes while the user IDs are connected to queue manager QM66, the users must disconnect and connect again before the change takes place.

If subsystem security is not active when a user connects but, while this user is still connected, subsystem security becomes active, full resource security checking is applied to the user. The user must re-connect to get the correct RESLEVEL processing.

Important notes on using RESLEVEL

1. RESLEVEL is a very powerful option; it can cause the bypassing of all resource security checks, so that they cannot be audited by RACF.
2. Using the RESLEVEL profile means that normal security audit records are not taken. For example, if you put UAUDIT on a user, the access to the ssid.RESLEVEL profile in MQADMIN is not audited.
3. If you use the RACF WARNING option on the ssid.RESLEVEL profile, no RACF warning messages are produced.
4. If you do not have a RESLEVEL profile defined, you must be careful that no other profile in the MQADMIN class matches ssid.RESLEVEL. For example, if you have a profile in MQADMIN called ssid.** and no ssid.RESLEVEL profile, beware of the consequences of the ssid.** profile because it is used for the RESLEVEL check.

   You should define an ssid.RESLEVEL profile and set the UACC to NONE, rather than not have a RESLEVEL profile at all. You should have as few users or groups in the access list as possible. For details about how to audit RESLEVEL access, see “Auditing considerations” on page 447.
5. If you make any changes to the RESLEVEL profile users must disconnect and connect again before the change takes place. (This includes stopping and restarting the channel initiator if the access that the distributed queuing address space user ID has to the RESLEVEL profile is changed.)

User IDs for security checking

MQSeries initiates security checks based on user IDs associated with users, terminals, applications, and so on. The following sections show the contents of the user IDs used for each type of security check.

User IDs for connection security

Issued from...	User ID contents
Batch/TSO, CICS, IMS	The user ID normally found for connection security is one of these: • The TSO user ID. • The user ID assigned to a batch job via the USER JCL parameter. • The user ID assigned to a started task by the STARTED class or the started procedures table.

User IDs for command security and command resource security

Issued from...	User ID contents
CSQINP1 or CSQINP2	No check is made.
System command input queue	The user ID found in the *UserIdentifier* of the message descriptor of the message which contains the command. If the message does not contain a *UserIdentifier*, a user ID of blanks is passed to the security manager.
Console	The user ID signed onto the console. If the console is not signed on, the default user ID from the MQSeries subsystem initialization parameter module (CSQZPARM). This default is set the by CMDUSER operand on the CSQ6SYSP macro. To issue commands from a console, the console must have the OS/390 SYS AUTHORITY attribute.
SDSF/TSO console	TSO or job user ID.
MGCR (SVC34)	If MGCR is used with Utoken, the user ID in the Utoken. If MGCR is issued without the Utoken, the TSO or job user ID is used.
CSQUTIL	Job user ID.
CSQINPX	User ID of the channel initiator address space.

User IDs for resource security (MQOPEN and MQPUT1)

Table 50 through Table 56 on page 445 show the contents of the user IDs for normal and alternate user IDs for each type of adapter. The number of checks is defined by the RESLEVEL profile. The user ID checked is that used for **MQOPEN** or **MQPUT1** calls.

Note: All user ID fields are checked *exactly* as they are received. No conversions take place, and, for example, three user ID fields containing Bob, BOB, and bob are not equivalent.

User IDs checked for Batch

Table 50. User ID checking for Batch/TSO-type user IDs

	Alternate user ID specified on open?	
Profile name	***No***	***Yes***
ssid.ALTERNATE.USER.userid	–	JOB
ssid.CONTEXT	JOB	JOB
ssid.localresourcename	JOB	ALT

Key:

ALT Alternate user ID.

JOB
- The TSO user ID.
- The user ID assigned to a batch job.
- The user ID assigned to a started task by the STARTED class or the started procedures table.

User IDs checked for CICS

Table 51. User ID checking for CICS-type user IDs

	Alternate user ID specified on open?			
	No		*Yes*	
Profile name	*1 Check*	*2 Checks*	*1 Check*	*2 Checks*
ssid.ALTERNATE.USER.userid	–	–	ADS	ADS+TXN
ssid.CONTEXT	ADS	ADS+TXN	ADS	ADS+TXN
ssid.localresourcename	ADS	ADS+TXN	ADS	ADS+ALT

Key:

ALT Alternate user ID
ADS The user ID associated with the CICS batch job or, if CICS is running as a started task, through the STARTED class or the started procedures table.
TXN The user ID associated with the CICS transaction. This is normally the user ID of the terminal user who started the transaction. It can be the CICS DFLTUSER, a PRESET security terminal, or a manually signed-on user.

User IDs checked for IMS

Table 52. User ID checking for IMS-type user IDs

	Alternate user ID specified on open?			
	No		*Yes*	
Profile name	*1 Check*	*2 Checks*	*1 Check*	*2 Checks*
ssid.ALTERNATE.USER.userid	–	–	REG	REG+SEC
ssid.CONTEXT	REG	REG+SEC	REG	REG+SEC
ssid.localresourcename	REG	REG+SEC	REG	REG+ALT

Key:

ALT Alternate user ID.
REG The user ID is normally set through the STARTED class or the started procedures table or, if IMS is running, from a submitted job, via the USER JCL parameter.
SEC The second user ID is associated with the work being done in a dependent region. It is determined according to Table 53.

Table 53. How the second user ID is determined for the IMS adapter

Types of dependent region	Hierarchy for determining the second user ID
• BMP message driven and successful GET UNIQUE issued. • IFP and GET UNIQUE issued. • MPP.	User ID associated with the IMS transaction if the user is signed on. LTERM name if available. PSBNAME.
• BMP message driven and successful GET UNIQUE not issued. • BMP not message driven. • IFP and GET UNIQUE not issued.	User ID associated with the IMS dependent region address space if this is not all blanks or all zeros. PSBNAME.

User IDs used by the channel initiator

The following sections describe the user IDs used and checked for TCP/IP channels, LU 6.2 channels, and client MQI requests issued over server-connection channels for both TCP/IP and LU 6.2.

You can use the PUTAUT parameter of the channel definition to determine the type of security checking used. To get consistent security checking throughout your MQSeries network, you can use the ONLYMCA and ALTMCA options.

User IDs checked for channels using TCP/IP

MCA user ID (MCA)

The user ID specified for the MCAUSER channel attribute at the receiver; if blank, the channel initiator address space user ID of the receiver or requester side is used.

Channel user ID (CHL)

For TCP/IP, where security is not supported by the communication system for the channel, the user ID of the channel initiator address space of the receiver or requestor end is used as the channel user ID on channels defined with PUTAUT set to DEF or CTX.

If PUTAUT is set to ONLYMCA or ALTMCA for the channel, the channel user ID is ignored and the MCA user ID of the receiver or requester is used.

Table 54. User IDs checked for TCP/IP channels

	PUTAUT option specified on receiver or requester channel							
	DEF		**CTX**		**ONLYMCA**		**ALTMCA**	
Profile Name	**1 Check**	**2 Checks**	**1 Check**	**2 Checks**	**1 Check**	**2 Checks**	**1 Check**	**2 Checks**
ssid.ALTERNATE.USER.userid	-	-	CHL	CHL + MCA	-	-	MCA	MCA
ssid.CONTEXT	CHL	CHL + MCA	CHL	CHL + MCA	MCA	MCA	MCA	MCA
ssid.localresourcename	CHL	CHL + MCA	CHL	CHL + ALT	MCA	MCA	MCA	MCA + ALT

Key:

ALT Alternate user ID.
CHL Channel user ID.
MCA MCA user ID.

User IDs checked for channels using LU 6.2

MCA user ID (MCA)

The user ID specified for the MCAUSER channel attribute at the receiver; if blank, the channel initiator address space user ID of the receiver or requester side is used.

Channel user ID (CHL)

Sender-receiver, sender-requester, and server-requester channels

If PUTAUT is set to DEF or CTX on the receiver or requester channel, the channel user ID is the user ID received from the communications system when the channel is initiated.

- If the user ID received is blank, or no user ID is received, a channel user ID of blanks is used.
- If the sending channel is on OS/390, the channel user ID received is the channel initiator address space user ID of the sender.
- If the sending channel is on a different platform (for example, AIX or HP-UX, the channel user ID received is typically provided by the USERID parameter of the channel definition.

If PUTAUT is set to ONLYMCA or ALTMCA for the channel, any user ID received from the network is ignored, and the MCA user ID of the receiver is used.

Requester-server channels

If the channel is started from the requester, there is no opportunity to receive a network user ID (the channel user ID)

If PUTAUT is set to DEF or CTX on the requester channel, the channel user ID is that of the channel initiator address space of the requester because no user ID is received from the network.

If PUTAUT is set to ONLYMCA or ALTMCA, the channel user ID is ignored and the MCA user ID of the requester is used.

Table 55. User IDs checked for LU 6.2 channels

	PUTAUT option specified on receiver or requester channel							
	DEF		**CTX**		**ONLYMCA**		**ALTMCA**	
Profile Name	**1 Check**	**2 Checks**	**1 Check**	**2 Checks**	**1 Check**	**2 Checks**	**1 Check**	**2 Checks**
ssid.ALTERNATE.USER.userid	-	-	CHL	CHL + MCA	-	-	MCA	MCA
ssid.CONTEXT	CHL	CHL + MCA	CHL	CHL + MCA	MCA	MCA	MCA	MCA
ssid.localresourcename	CHL	CHL + MCA	CHL	CHL + ALT	MCA	MCA	MCA	MCA + ALT

Key:

ALT Alternate user ID.
CHL Channel user ID.
MCA MCA user ID.

User IDs checked for client MQI requests: This section described the user IDs checked for client MQI requests issued over server-connection channels for TCP/IP and LU 6.2. The MCA user ID and channel user ID are as for the TCP/IP and LU 6.2 channels described in the previous sections.

For server-connection channels, the MCA user ID received from the client is used if the MCAUSER attribute is blank. However, for the clients that use the MQ_USER_ID environment variable to supply the user ID, it is possible that no environment variable is set. In this case, the user ID that started the server channel is used. This is the user ID assigned to the channel initiator started task by the OS/390 started procedures table.

See the *MQSeries Clients* manual for more information.

For client **MQOPEN** and **MQPUT1** requests, use the following rules to determine the profile that will be checked:

- If the request specifies alternate user authority, a check is made against the *ssid*.ALTERNATE.USER.*userid* profile.
- If the request specifies context authority, a check is made against the *ssid*.CONTEXT profile.
- For all **MQOPEN** and **MQPUT1** requests, a check is made against the *ssid.localresourcename* profile.

When you have determined which profiles are checked, use the following table to determine which user IDs are checked against these profiles.

Table 56. User IDs checked for LU 6.2 and TCP/IP server-connection channels

	PUTAUT option specified on server-connection channel							
	DEF				**ONLYMCA**			
	Alternate user ID specified on open?				**Alternate user ID specified on open?**			
	No		**Yes**		**No**		**Yes**	
Profile Name	**1 Check**	**2 Checks**	**1 Check**	**2 Checks**	**1 Check**	**2 Checks**	**1 Check**	**2 Checks**
ssid.ALTERNATE.USER.userid	-	-	CHL	CHL + MCA	-	-	MCA	MCA
ssid.CONTEXT	CHL	CHL + MCA	CHL	CHL + MCA	MCA	MCA	MCA	MCA
ssid.localresourcename	CHL	CHL + MCA	CHL	CHL + ALT	MCA	MCA	MCA	MCA + ALT

Key:

ALT Alternate user ID.
CHL Channel user ID.
MCA MCA user ID.

Examples

How you use these tables is best explained by some examples.

Example 1: In a CICS transaction where the RESLEVEL profile is set to READ, determine which user IDs are checked.

Answer: First, see how many CICS user IDs are checked based on the CICS address space user ID access to the RESLEVEL profile. From Table 47 on page 438, only one user ID is checked if the RESLEVEL profile is set to READ. Then, in Table 51, look in the appropriate "*1 Check*" column, depending on whether the alternate user authority open option is specified. In either case, the CICS address space (ADS) user ID is checked.

Example 2: Determine the user IDs checked for the following conditions:

- The RACF access level to the RESLEVEL profile, for a CICS address space user ID, is set to NONE.
- An **MQOPEN** call is made against a queue with MQOO_OUTPUT and MQOO_PASS_IDENTITY_CONTEXT.

Answer: First, see how many CICS user IDs are checked based on the CICS address space user ID access to the RESLEVEL profile. From Table 47 on page 438, two user IDs are checked if the RESLEVEL profile is set to NONE. Then, from Table 51, these checks are carried out:

- The ssid.ALTERNATE.USER.userid profile is not checked.
- The ssid.CONTEXT profile is checked with both the CICS address space user ID and the CICS transaction user ID.
- The ssid.localresourcename profile is checked with both the CICS address space user ID and the CICS transaction user ID.

This means that four security checks are made for this **MQOPEN** call.

Blank user IDs and UACC levels

Blank user IDs can exist when a user is manipulating messages using context or alternate user security, or when MQSeries is passed a blank user ID. For example, a blank user ID is used when a message is written to the system-command input queue without context.

Note: A user ID of '* ' (that is, an asterisk character followed by seven spaces) is treated as a blank user ID.

MQSeries passes the blank user ID to RACF and a RACF undefined user is signed on. All security checks then use the universal access (UACC) for the relevant profile. Depending on how you have set your access levels, the UACC might give the undefined user a wide-ranging access.

For example, if you issue this RACF command from TSO:

```
RDEFINE MQQUEUE Q.AVAILABLE.TO.EVERYONE UACC(UPDATE)
```

you define a profile that enables both OS/390-defined user IDs (that have not been put in the access list) and the RACF undefined user ID to put messages on, and get messages from, that queue.

To protect your MQSeries subsystem from blank user IDs you must plan your access levels carefully, and limit the number of people who can use context and alternate user security. You must prevent people using the RACF undefined user ID from getting access to resources that they should not. However, at the same time, you must allow access to people with defined user IDs. To do this, you can specify a user ID of asterisk (*) in a RACF command PERMIT. For example, these RACF commands prevent the RACF undefined user ID from gaining access to the queue to put or get messages:

```
RDEFINE MQQUEUE Q.AVAILABLE.TO.RACF.DEFINED.USERS.ONLY UACC(NONE)
PERMIT Q.AVAILABLE.TO.RACF.DEFINED.USERS.ONLY CLASS(MQQUEUE) ACCESS(UPDATE) ID(*)
```

Auditing considerations

The normal RACF auditing controls are available for conducting a security audit of a queue manager. The RACF auditing can be based upon:

- User IDs
- Resource classes
- Profiles

For more details, see the *Security Server (RACF) Auditor's Guide*.

Note: Auditing degrades performance; the more auditing you implement, the more performance is degraded. This is also a consideration for the use of the RACF WARNING option.

Auditing RESLEVEL

No normal RACF audit records are taken when the RESLEVEL check is made to see what access an address space user ID has to the ssid.RESLEVEL profile. Instead, MQSeries requests that RACF create a GENERAL audit record (event number 27).

These checks are only carried out at connect time, so the overhead should be minimal.

You can report the MQSeries general audit records using the RACF report writer (RACFRW). You could use the following RACFRW commands to report the RESLEVEL access:

```
RACFRW
SELECT PROCESS
EVENT GENERAL
LIST
END
```

Auditing considerations

A sample report from RACFRW, excluding the *Date*, *Time*, and *SYSID* fields, is shown in Figure 102 on page 448.

```
          RACF REPORT - LISTING OF PROCESS RECORDS                                    PAGE   4
                                    E
                                    V  Q
                                    E  U
*JOB/USER  *STEP/    --TERMINAL--  N  A
   NAME     GROUP       ID    LVL  T  L

     WS21B     MQMGRP   IGJZM000   0 27  0  JOBID=(WS21B 93.111 09:44:57),USERDATA=()
      TRUSTED USER                          AUTH=(NONE),REASON=(NONE)
                                          SESSION=TSOLOGON,TERMINAL=IGJZM000,
                                           LOGSTR='CSQH RESLEVEL CHECK PERFORMED AGAINST PROFILE(QM66.RESLEVEL),
                                          CLASS(MQADMIN), ACCESS EQUATES TO (CONTROL)',RESULT=SUCCESS,MQADMIN
```

Figure 102. Sample output from RACFRW showing RESLEVEL general audit records

From checking the LOGSTR data in the output above, you can see that TSO user WS21B has CONTROL access to QM66.RESLEVEL. This means that all resource security checks will be bypassed when user WS21B access QM66 resources.

For more information about using RACFRW, see the *Security Server (RACF) Auditor's Guide*.

Statistics

MQSeries does not gather any security statistics of its own. The only statistics are those that can be created by auditing.

Chapter 27. MQSeries security implementation

The chapter covers the following subjects:

- "Security implementation checklist"
- "MQSeries security management" on page 451
- "Customizing security" on page 454
- "Security considerations for using MQSeries with CICS" on page 455
- "Security considerations for using MQSeries with IMS" on page 459
- "Security considerations for distributed queuing" on page 463
- "Security considerations for cluster support" on page 465
- "Security installation tasks" on page 466
- "Example security scenario" on page 468
- "Security problem determination" on page 474

Security implementation checklist

This section gives a step-by-step procedure you can use to work out and define the security implementation for each of your MQSeries subsystems. Refer to other sections for details, in particular "Profiles used to protect MQSeries resources" on page 414.

If you require security checking to be implemented on at least one of your MQSeries subsystems, you must first activate the RACF MQADMIN class. Then, for each MQSeries subsystem, you must decide whether you need security checking on that subsystem. If you do *not* require security checking, you must define an ssid.NO.SUBSYS.SECURITY profile in the MQADMIN class.

If you *do* require security checking, follow this checklist to implement it:

- □ Do you need connection security?

  Yes: Define appropriate connection profiles in the MQCONN class and permit the appropriate users or groups access to these profiles.

  Note: Only users of the **MQCONN** API request or CICS or IMS address space user IDs need to have access to the corresponding connection profile.

  No: Define an ssid.NO.CONNECT.CHECKS profile in the MQADMIN class.

- □ Do you need security checking on commands?

  Yes: Activate the MQCMDS class. Define appropriate command profiles in the MQCMDS class and permit the appropriate users or groups access to these profiles.

  No: Define an ssid.NO.CMD.CHECKS profile in the MQADMIN class.

- □ Do you need security on the resources used in commands?

  Yes: Ensure the MQADMIN class is active. Define appropriate profiles for protecting resources on commands in the MQADMIN class and permit the appropriate users or groups access to these profiles. Set the CMDUSER parameter in CSQ6SYSP to the default user ID to be used for command security checks.

© Copyright IBM Corp. 1993,1999

No: Define an ssid.NO.RESC.CMD.CHECKS profile in the MQADMIN class.

- ☐ Do you need queue security?

  Yes: Activate the MQQUEUE class. Define appropriate queue profiles in the MQQUEUE class and permit the appropriate users or groups access to these profiles.

  No: Define an ssid.NO.QUEUE.CHECKS profile in the MQADMIN class.

- ☐ Do you need process security?

  Yes: Activate the MQPROC class. Define appropriate process profiles and permit the appropriate users or groups access to these profiles.

  No: Define an ssid.NO.PROCESS.CHECKS profile in the MQADMIN class.

- ☐ Do you need namelist security?

  Yes: Activate the MQNLIST class. Define appropriate namelist profiles in the MQNLIST class and permit the appropriate users or groups access to these profiles.

  No: Define an ssid.NO.NLIST.CHECKS profile in the MQADMIN class.

- ☐ Do any users need to protect the use of the **MQOPEN** or **MQPUT1** options relating to the use of context?

  Yes: Ensure the MQADMIN class is active. Define an ssid.CONTEXT profile in the MQADMIN class and permit the appropriate users or groups access to this profile.

  No: Define an ssid.NO.CONTEXT.CHECKS profile in the MQADMIN class.

- ☐ Do you need to protect the use of alternate user IDs?

  Yes: Ensure the MQADMIN class is active. Define the appropriate ssid.ALTERNATE.USER.`alternateuserid` profiles and permit the required users or groups access to these profiles.

  No: Define the profile ssid.NO.ALTERNATE.USER.CHECKS in the MQADMIN class.

- ☐ Do you need to tailor which user IDs are to be used for resource security checks through RESLEVEL?

  Yes: Ensure the MQADMIN class is active. Define an ssid.RESLEVEL profile in the MQADMIN class and permit the required users or groups access to the profile.

  No: Ensure that no generic profiles exist in the MQADMIN class that could apply to ssid.RESLEVEL. Define an ssid.RESLEVEL profile and ensure that no users or groups have access to it.

- ☐ Do you need to 'time out' unused user IDs from MQSeries?

  Yes: Determine what timeout values you would like to use and issue the MQSeries command alter security to change the TIMEOUT and INTERVAL parameters.

  No: Issue the MQSeries command ALTER SECURITY to set the INTERVAL value to zero.

Note: Update the CSQINP1 data set used by your subsystem so that the MQSeries command ALTER SECURITY is issued automatically at every MQSeries start up.

- □ Do you use distributed queuing (without CICS)?

  Yes: Determine the appropriate MCAUSER attribute value for each channel, and/or provide suitable channel security exits.

- □ Do you use clients?

  Yes: Determine the appropriate MCAUSER attribute value for each server-connection channel, and/or provide suitable channel security exits.

MQSeries security management

MQSeries uses an in-storage table to hold information relating to each user and the access requests made by each user.

To manage this table efficiently and to reduce the number of requests made from MQSeries to the external security manager (ESM), these controls are available:

- User ID timeouts
- User ID reverification
- Security refreshes
- Displaying security status

These controls are available through both the operations and control panels and MQSC.

User ID timeouts

When a user accesses an MQSeries resource, the queue manager tries to sign this user on to the queue manager—if subsystem security is active. This means that the user is authenticated to RACF. This user remains signed on to MQSeries until either the queue manager is shut down, or until the user ID is “timed out” (the authentication lapses) or reverified (reauthenticated).

When a user is timed out, the user ID is “signed off” within the queue manager and any security related information retained for this user is discarded.

Users are eligible for time out when they have not used any MQSeries resources for a predetermined amount of time. This time period is set by the MQSeries command ALTER SECURITY. For a description of the command syntax, see the *MQSeries Command Reference* manual.

Two values can be specified in the ALTER SECURITY command:

TIMEOUT The time period in minutes that an unused user ID can remain signed on within the MQSeries subsystem.

INTERVAL The time period in minutes between MQSeries checks for user IDs for which the TIMEOUT has expired.

For example, if the TIMEOUT value is 30 and the INTERVAL value is 10, every 10 minutes MQSeries checks for user IDs that have not been used for 30 minutes. If such a user ID is found, that user ID is signed off within the queue manager.

Note: The signing on and off of the user within the queue manager is transparent to the application program and to the end user.

If you do not want to time out user IDs, set the INTERVAL value to zero.

Note: If you use values for INTERVAL or TIMEOUT other than the defaults, you must re-enter the command at every MQSeries startup. You can do this automatically by putting the MQSeries command ALTER SECURITY in the CSQINP1 data set for that queue manager.

User ID reverification

If the RACF definition of a user who is using MQSeries resources has been changed—for example, by connecting the user to a new group—you can tell the queue manager to sign this user on again the next time it tries to access an MQSeries resource. You can do this by using the MQSeries command RVERIFY SECURITY. For example:

- User HX0804 is getting and putting messages to the PAYROLL queues on queue manager PRD1. However HX0804, now requires access to some of the PENSION queues on the same queue manager (PRD1).
- The data security administrator connects user HX0804 to the RACF group that allows access to the PENSION queues.
- So that HX0804 can access the PENSION queues immediately—that is, without shutting down queue manager PRD1, or waiting for HX0804 to time out—you must use the MQSeries command:

  ```
  RVERIFY SECURITY(HX0804)
  ```

Note: If you turn off user ID timeout for long periods of time (days or even weeks), while the queue manager is running, you must remember to perform an RVERIFY SECURITY for any users that have been revoked or deleted in that time.

Security refreshes

Whenever you change a RACF profile that is used by MQSeries security, you must tell the corresponding queue manager to refresh its in-storage list of RACF profiles. You can do this by using the MQSeries command REFRESH SECURITY. For a description of command syntax, see the *MQSeries Command Reference* manual.

You must also issue normal RACF refresh commands if you change generic profiles. For example, SETROPTS GENERIC(classname) REFRESH. You must also issue the MQSeries command, REFRESH SECURITY, if you change a profile in any of these RACF classes:

- MQADMIN
- MQQUEUE
- MQNLIST
- MQPROC

These are the only classes affected by the MQSeries command REFRESH SECURITY. You do *not* need to use REFRESH SECURITY if you change a profile in either the MQCONN or MQCMDS classes.

Note: A refresh of MQADMIN is not required if you change a RESLEVEL security profile.

For performance reasons, use REFRESH SECURITY as infrequently as possible, ideally at off-peak times. You can minimize the number of security refreshes by connecting users to RACF groups that are already in the access list for MQSeries profiles, rather than putting individual users in the access lists. In this way, you change the user rather than the resource profile. You can also RVERIFY SECURITY the appropriate user instead of refreshing security.

As an example of REFRESH SECURITY, suppose you define the new profiles to protect access to queues starting with INSURANCE.LIFE on queue manager PRMQ. You use these RACF commands:

```
RDEFINE MQQUEUE PRMQ.INSURANCE.LIFE.** UACC(NONE)
PERMIT PRMQ.INSURANCE.LIFE.** ID(LIFEGRP) ACCESS(UPDATE)
```

Because these profiles are generic, you must tell RACF to refresh the generic profiles for MQQUEUE. For example:

```
SETROPTS GENERIC(MQQUEUE) REFRESH
```

Then you must use this command to tell queue manager PRMQ that the queue profiles have changed:

```
REFRESH SECURITY(MQQUEUE)
```

If you issue a REFRESH SECURITY(*) or a REFRESH SECURITY(MQADMIN), the status of the security switches in the MQADMIN class are also checked. This means you can activate new security types, or de-activate them without having to restart the queue manager.

Displaying security status

To display the status of the security switches, and other security controls, you can issue the MQSeries command DISPLAY SECURITY. For a description of the command syntax, see the *MQSeries Command Reference* manual.

Figure 103 shows a typical output of the MQSeries command DISPLAY SECURITY ALL. The example shows that the queue manager that replied to the command has all MQSeries security active, except for namelist security. It also shows that user ID timeouts are active, and that every 12 minutes the queue manager checks for user IDs that have not been used in this queue manager for 54 minutes and removes them.

Note: This command shows the current security status. It does not necessarily reflect the current status of the switch profiles defined to RACF, or the status of the RACF classes. For example, the switch profiles might have been changed since the last restart of this queue manager or REFRESH SECURITY command.

```
CSQH015I +cpf SECURITY TIMEOUT = 54 MINUTES
CSQH016I +cpf SECURITY INTERVAL = 12 MINUTES
CSQH002I +cpf CSQHPDTC SUBSYSTEM SECURITY SWITCH SET ON
CSQH002I +cpf CSQHPDTC CONNECTION SECURITY SWITCH SET ON
CSQH002I +cpf CSQHPDTC COMMAND SECURITY SWITCH SET ON
CSQH002I +cpf CSQHPDTC CONTEXT SECURITY SWITCH SET ON
CSQH002I +cpf CSQHPDTC ALTERNATE USER SECURITY SWITCH SET ON
CSQH002I +cpf CSQHPDTC PROCESS SECURITY SWITCH SET ON
CSQH002I +cpf CSQHPDTC NAMELIST SECURITY SWITCH SET OFF
CSQH002I +cpf CSQHPDTC QUEUE SECURITY SWITCH SET ON
CSQH002I +cpf CSQHPDTC COMMAND RESOURCES SECURITY SWITCH SET ON
CSQ9022I +cpf CSQHPDTC ' DISPLAY SECURITY' NORMAL COMPLETION
```

Figure 103. Typical output from the MQSeries command DISPLAY SECURITY

Customizing security

If you want to change the way MQSeries security operates, you must do this via the SAF exit (ICHRFR00), or exits in your external security manager. To find out more about RACF exits, see the *Security Server (RACF) External Security Interface (RACROUTE) Macro Reference* manual.

Note: Because MQSeries optimizes calls to the ESM, RACROUTE requests will not be made on, for example, every open for a particular queue by a particular user.

Security considerations for using MQSeries with CICS

The CICS adapter provides this information to MQSeries specifically for use in MQSeries security:

- Whether CICS resource-level security is active for this transaction—as specified on the RESSEC or RSLC operand of the RDO TRANSACTION definition.
- User IDs.

  For terminal tasks where a user has not signed on, the user ID is the CICS user ID associated with the terminal and is either:

  – The default CICS user ID as specified on the CICS parameter DFLTUSER SIT

  – A preset security user ID specified on the terminal definition

  For non-terminal tasks, the CICS adapter tries to get a user ID with an EXEC CICS ASSIGN command. If this is unsuccessful, the adapter tries to get the user ID using EXEC CICS INQUIRE TASK. If security is active in CICS, and the non-terminal attached transaction is defined with CMDSEC(YES), the CICS adapter passes a user ID of blanks to MQSeries.

For more information about RACF security management in the CICS environment, see the *CICS RACF Security Guide*.

Controlling the security of CICS transactions supplied by MQSeries

The CKTI and CKAM transactions are designed to be run without a terminal; no user should have access to these transactions. These transactions are examples of what the *CICS RACF Security Guide* calls “category 1 transactions”. For information about to set these transactions up in CICS and RACF, see the information about category 1 transactions in the *CICS RACF Security Guide*.

If you want a user to administer the CICS adapter, you must authorize them to these transactions:

Transaction	***What it does***
CKQC	Controls the CICS adapter functions
CKBM	Controls the CICS adapter functions
CKRT	Controls the CICS adapter functions
CKCN	Connect
CKSD	Disconnect
CKRS	Statistics
CKDP	Full screen display
CKDL	Line mode display
CKSQ	CKTI START/STOP

If required, you can restrict access to specific functions of the adapter. For example, if you want to allow users to display the current status of the adapter via the full screen interface, but nothing else, give them access to CKQC, CKBM, CKRT, and CKDP only.

You should define these transactions to CICS with RESSEC(NO) and CMDSEC(NO). For more details, see the *CICS RACF Security Guide*. For information about the security of the CICS transactions supplied by MQSeries for remote queuing, see the *MQSeries Intercommunication* manual.

CICS adapter user IDs

The user ID associated with CICS adapter is that of the MQSeries-supplied task initiator transaction, CKTI. This section describes some of the implications of this.

User ID checking for MQSeries resources during PLTPI and PLTSD

If an MQSeries resource is accessed during the CICS PLTPI phase, the user ID passed to MQSeries is blanks. If an MQSeries resource is accessed during the CICS PLTSD phase, the user ID passed to MQSeries is the user ID associated with the shutdown transaction.

If CKTI is started during the CICS PLTPI phase, the user ID of the CKTI task is the CICS sysidnt. This means that a user ID with the same name as the CICS sysidnt must be defined and given access to the required MQSeries resources, for example, initiation queues.

Terminal user IDs

If CKTI is started from a terminal from the CKQC transaction or a user-written program that links to CSQCSSQ, the user ID that CKTI uses is the same as the user ID of the terminal that started CKTI.

Automating starting of CKTI

To automate the starting of CKTIs under a specific user ID, you can use an automation product, for example, NetView. You can use this to sign on a CICS console and issue the STARTCKTI command.

You can also use preset security sequential terminals, which have been defined to emulate a CRLP terminal, with the sequential terminal input containing the CKQC STARTCKTI command.

However, when the CICS adapter alert monitor reconnects CICS to MQSeries, after, for example, an MQSeries restart, only the CKTI specified at the initial MQSeries connection is restarted. You must automate starting any extra CKTIs yourself.

Propagating the CKTI user ID to other CICS transactions

If CKTI starts other CICS transactions, for example, message channel agents (MCAs) or user-written CICS applications, the user ID of CKTI is propagated to these applications. For example, if CKTI is running under user ID CIC1 and a trigger event occurs which requires the sender MCA transaction, CKSG, to be started, the CKSG transaction also runs under user ID CIC1. Therefore user ID CIC1 must have access to the required transmission queue.

Security considerations for the CICS bridge

When you run the CICS bridge, you can specify the level of authentication you want to take place. If requested, the bridge checks the user ID and password extracted from the MQSeries request message before running the CICS program named in the request message.

Notes:

1. If you have not specified a user ID or password in a message, the bridge task runs with the LOCAL level of authentication, even if you started the bridge monitor with a different authentication option.
2. The options that include password (or passticket) validation require a CICS bridge header (MQCIH) to be provided. See the *MQSeries Application Programming Reference* manual for more information about the MQCIH header.

The level of authentication you can use is described below:

LOCAL This is the default. CICS programs run by the bridge task are started with the CICS DFLTUSER user ID, therefore run with the authority associated with this user ID. There is no checking of user IDs or passwords. If a CICS program is run that tries to access protected resources, it will probably fail.

IDENTIFY When you start the monitor task with the IDENTIFY authentication option, the bridge task is started with the user ID specified in the message (MQMD). CICS programs run by the bridge run with the user ID extracted from the MQMD. There is no password checking, the user ID is treated as trusted.

VERIFY_UOW When you start the monitor task with the VERIFY_UOW authentication option, the monitor task checks the user ID and password by issuing the EXEC CICS VERIFY PASSWORD command before starting the bridge task. CICS programs run by the bridge run with the user ID extracted from the MQMD. If the user ID or password is invalid, the request fails with return code MQCRC_SECURITY_ERROR.

VERIFY_ALL This is the same as VERIFY_UOW except that the bridge task checks the user ID and password in **every** message. This is not applicable for 3270 transactions.

If you have not specified a user ID in a message, or you have not provided a password, the CICS program started by the CICS bridge runs with the user ID set to the CICS DFLTUSER, regardless of the option requested. If you want more than one level of authentication checking performed, run a monitor task for each level you need.

Table 57 and Table 58 on page 458 summarize the level of authority of the bridge monitor and the bridge tasks, and the use of the MQMD user ID.

Table 57 (Page 1 of 2). CICS bridge monitor security

Monitor started by	At a signed on terminal	Monitor authority
From a terminal or EXEC CICS LINK within a program	Yes	Signed on user ID

Table 57 (Page 2 of 2). CICS bridge monitor security		
Monitor started by	**At a signed on terminal**	**Monitor authority**
From a terminal or EXEC CICS LINK within a program	No	CICS default user ID
EXEC CICS START with user ID	–	User ID from START
EXEC CICS START without user ID	–	CICS default user ID
The MQSeries trigger monitor CKTI	–	CICS default user ID

Table 58. CICS bridge task security	
AUTH	**Bridge task authority**
LOCAL	CICS default user ID
IDENTIFY	MQMD UserIdentifier
VERIFY_UOW	MQMD UserIdentifier
VERIFY_ALL	MQMD UserIdentifier

The options IDENTIFY, VERIFY_UOW, and VERIFY_ALL need the user ID of the bridge monitor defined to RACF as a surrogate of all the user IDs used in request messages. This is in addition to the user ID in the message being defined to RACF. (A surrogate user is one who has the authority to start work on behalf of another user, without knowing the other user's password.)

For more information on surrogate user security, see the *CICS RACF Security Guide*.

Note: When IDENTIFY security is being used, you might see abend AICO for CKBP if you try to run with a user ID that has been revoked. The error reply will have return code MQCRC_BRIDGE_ERROR with reason MQFB_CICS_BRIDGE_FAILURE.

Authority

Components of the bridge need authority to either put to or get from the various MQSeries queues. In summary:

- The monitor and all bridge tasks need authority to get messages from the bridge request queue.
- A bridge tasks need authority to put messages to its reply-to queue.
- To ensure any error replies are received, the monitor should have authority to put messages to all reply-to queues.
- Bridge tasks should have authority to put messages to the dead-letter queue.
- The monitor needs authority to put messages to the dead-letter queue, unless you want the bridge to stop if an error occurs.

See Table 57 on page 457 to determine the correlation between user IDs and authority.

Security considerations for using MQSeries with IMS

Using the OPERCMDS class

If you are using RACF to protect resources in the OPERCMDS class, ensure that your MQSeries system has authority to issue the MODIFY command to any IMS system to which it can connect.

Security considerations for the IMS bridge

There are four aspects that you must consider when deciding your security requirements for the IMS bridge, these are:

- What security authorization is needed to connect MQSeries to IMS ("Connecting to IMS")
- How much security checking is performed on applications using the bridge to access IMS ("Application access control" on page 460)
- Which IMS resources these applications are allowed to use ("Security checking on IMS" on page 461)
- What authority is to be used for messages that are put and got by the bridge ("Security checking done by the bridge" on page 462)

When you define your security requirements for the IMS bridge you must consider the following:

- Messages passing across the bridge might have originated from applications on platforms that do not offer strong security features
- Messages passing across the bridge might have originated from applications that are not controlled by the same enterprise or organization

Connecting to IMS

The IMS bridge is an OTMA client. The connection to IMS operates under the user ID of the MQSeries for OS/390 address space. This is normally defined as a member of the started task group. This user ID must be granted access to the OTMA group (unless the /SECURE OTMA setting is NONE). To do this, define the following profile in the FACILITY class:

```
IMSXCF.xcfgname.mqxcfmname
```

Where `xcfgname` is the XCF group name and `mqxcfmname` is the XCF member name of MQSeries.

You must give your MQSeries subsystem user ID read access to this profile.

Notes:

1. If you change the authorities in the FACILITY class, you must issue the RACF command SETROPTS RACLIST(FACILITY) REFRESH to activate the changes.
2. If profile qmgr.NO.SUBSYS.SECURITY exists in the MQADMIN class, no user ID will be passed to IMS and the connection will fail unless the /SECURE OTMA setting is NONE.

Application access control

For each IMS system that the IMS bridge connects to, you can define the following RACF profile in the FACILITY class to determine how much security checking is performed for each message passed to the IMS system.

```
IMSXCF.xcfgname.imsxcfmname
```

Where `xcfgname` is the XCF group name and `imsxcfmname` is the XCF member name for IMS. (You need to define a separate profile for each IMS system.)

The access level you allow for the MQSeries subsystem user ID in this profile is returned to MQSeries when the IMS bridge connects to IMS, and indicates the level of security that is required on subsequent transactions. For subsequent transactions, MQSeries requests the appropriate services from RACF and, where the user ID is authorized, passes the message to IMS.

OTMA does not support the IMS /SIGN command; however, MQSeries allows you to set the access checking for each message to enable implementation of the necessary level of control.

The following access level information can be returned:

NONE or NO PROFILE FOUND

This indicates that maximum security is required, that is, authentication is required for every transaction. A check is made to verify that the user ID specified in the *UserIdentifier* field of the MQMD structure, and the password or passticket in the *Authenticator* field of the MQIIH structure are known to RACF, and are a valid combination. A Utoken is created with a password or passticket, and passed to IMS; the Utoken is not cached.

Note: If profile qmgr.NO.SUBSYS.SECURITY exists in the MQADMIN class, this level of security overrides whatever is defined in the profile.

READ

This indicates that the same authentication is to be performed as above under the following circumstances:

- The first time that a specific user ID is encountered
- When the user ID has been encountered before but the cached Utoken was not created with a password or passticket

MQSeries requests a Utoken if required, and passes it to IMS.

Note: If a request to reverify security has been actioned, all cached information is lost and a Utoken is requested the first time each user ID is subsequently encountered.

UPDATE

A check is made that the user ID in the *UserIdentifier* field of the MQMD structure is known to RACF.

A Utoken is built and passed to IMS; the Utoken is cached.

CONTROL/ALTER

These indicate that no security Utokens need to be provided for any user IDs for this IMS system. (You would probably only use this for development and test systems.)

Notes:

1. This access is defined when MQSeries connects to IMS, and lasts for the duration of the connection. To change the security level, the access to the security profile must be changed and then the bridge stopped and restarted (for example, by stopping and restarting OTMA).
2. If you change the authorities in the FACILITY class, you must issue the RACF command SETROPTS RACLIST(FACILITY) REFRESH to activate the changes.
3. You can use a password or a passticket, but you must remember that the IMS bridge does not encrypt data. For information about using passtickets, see "Using RACF passtickets in the IMS header" on page 462.
4. Some of the above might be affected by security settings in IMS, using the /SECURE OTMA command.
5. Cached Utoken information is held for the duration defined by the INTERVAL and TIMEOUT parameters of the MQSeries ALTER SECURITY command.

Security checking on IMS

Each MQSeries message that passes across the bridge contains the following security information:

- A user ID contained in the *UserIdentifier* field of the MQMD structure
- The security scope contained in the *SecurityScope* field of the MQIIH structure (if the MQIIH structure is present)
- A Utoken (unless the MQSeries sub system has CONTROL or ALTER access to the relevant `IMSXCF.xcfgname.imsxcfmname` profile)

The security checks made depend on the setting by the IMS command /SECURE OTMA, as follows:

/SECURE OTMA NONE
No security checks are made for the transaction.

/SECURE OTMA CHECK
The *UserIdentifier* field of the MQMD structure is passed to IMS for transaction or command authority checking.

An ACEE (Accessor Environment Element) is built in the IMS control region.

/SECURE OTMA FULL
The *UserIdentifier* field of the MQMD structure is passed to IMS for transaction or command authority checking.

An ACEE is built in the IMS dependent region as well as the IMS control region.

/SECURE OTMA PROFILE
The *UserIdentifier* field of the MQMD structure is passed to IMS for transaction or command authority checking

The *SecurityScope* field in the MQIIH structure is used to determine whether to build an ACEE in the IMS dependent region as well as the control region.

Notes:

1. If you change the authorities in the TIMS or CIMS class, or the associated group classes GIMS or DIMS, you must issue the following IMS commands to activate the changes:
   - /MODIFY PREPARE RACF
   - /MODIFY COMMIT
2. If you do not use /SECURE OTMA PROFILE, any value specified in the *SecurityScope* field of the MQIIH structure is ignored.

Security checking done by the bridge

When the bridge puts or gets a message, the following authorities are used:

Getting a message from the bridge queue
No security checks are performed.

Putting an exception, or COA report message
Uses the authority of the user ID in the *UserIdentifier* field of the MQMD structure.

Putting a reply message
Uses the authority of the user ID in the *UserIdentifier* field of the MQMD structure of the original message

Putting a message to the dead-letter queue
No security checks are performed.

Notes:

1. If you change the MQSeries class profiles, you must issue the MQSeries command REFRESH SECURITY(*) to activate the changes.
2. If you change the authority of a user, you must issue the MQSeries command RVERIFY SECURITY to activate the change.

Using RACF passtickets in the IMS header

If you want to use a passticket instead of a password in the IMS header (MQIIH), you should use an application name as if you were creating a passticket for an OS/390 batch job. That is, the APPL field should be of the form `MVSxxxx`, where `xxxx` is the SMFID of the OS/390 system on which the target queue manager runs.

A passticket is built from a user ID, the target application name (APPL), and a secret key. It is an 8-byte value containing uppercase alphabetic and numeric characters. It can be used only once, and is valid for a 20 minute period centered on the time that it was created. For full information about passtickets, see the *Security Server (RACF) Security Administrator's Guide*.

Passtickets in IMS headers are given to RACF by MQSeries, not IMS.

Security considerations for distributed queuing

This section discusses security considerations for the non-CICS mover. If you are using the CICS mover, see “Security considerations for distributed queuing (using CICS ISC)” on page 494. If you are using clustering, you should also read “Security considerations for cluster support” on page 465.

If you are using resource security, you should consider the following if you are using distributed queuing:

- The channel initiator address space needs RACF UPDATE access to these system queues:
  - SYSTEM.CHANNEL.INITQ
  - SYSTEM.CHANNEL.SYNCQ
  - SYSTEM.COMMAND.INPUT
  - SYSTEM.ADMIN.CHANNEL.EVENT

  and to all the user destination queues, and also the dead-letter queue (but see “Dead-letter queue security” on page 421).
- The channel initiator address space (and the user ID specified by MCAUSER on each channel if you have a RESLEVEL profile specifying that two user IDs are to be checked) need ALTER access to all the user transmission queues.
- The channel initiator address space (and the MCA user ID if one has been specified) also need RACF CONTROL access to the ssid.CONTEXT profile in the MQADMIN class, and, depending on the RESLEVEL profile, the network-received user ID might also need CONTROL access to this profile. See “Profiles for context security” on page 427 and “RESLEVEL and channel initiator connections” on page 437 for more information.

  If you are using the CSQINPX input data set, the channel initiator also needs READ access to CSQINPX, and UPDATE access to data set CSQOUTX and dynamic queues SYSTEM.CSQXCMD.*.
- The channel initiator address space connection requests use a connection type of CHIN, for which appropriate access security must be set, see “Connection security profiles for distributed queuing” on page 415.
- The channel initiator address space needs appropriate access to queue manager data sets, see “Authorizing access to data sets” on page 467.
- The distributed queuing commands (for example, DEFINE CHANNEL, START CHINIT, START LISTENER, and so on) should have appropriate command security set, see Table 45 on page 433.
- Channels, particularly receivers and server-connections, need appropriate security to be set up; see “User IDs for security checking” on page 440 for more information. See also the *MQSeries Clients* manual for information about server-connection security.
- The user ID specified by MCAUSER on each channel (and if you have a RESLEVEL profile specifying that two user IDs are to be checked, the network-received user ID if there is one being used), need the following:
  - RACF UPDATE access to the appropriate destination queues and the dead-letter queue
  - RACF CONTROL access to the `ssid.CONTEXT` profile if context checking is performed at the receiver

  - For clients, the appropriate RACF access to the resources to be used.

- Set appropriate APPC security if you are using the LU 6.2 transmission protocol. (Use the APPCLU RACF class for example.) For information about setting up security for APPC, see the following manuals:
  - *MVS Planning: APPC/MVS Management*
  - *APPC Security: MVS/ESA, CICS/ESA, and OS/2* (redbook)

  Outbound transmissions use the "SECURITY(SAME)" APPC option. This means that the user ID of the channel initiator address space and its default profile (RACF GROUP) are flowed across the network to the receiver with an indicator that the user ID has already been verified (ALREADYV).

  If the receiving side is also OS/390, the user ID and profile are verified by APPC and the user ID is presented to the receiver channel and used as the network user ID.

  In an environment where the queue manager is using APPC to communicate with another queue manager on the same or another OS/390 system, you need to ensure that either:

  - The VTAM definition for the communicating LU specifies SETACPT(ALREADYV)
  - There is a RACF APPCLU profile for the connection between LUs that specifies CONVSEC(ALREADYV)

- If the RACF access level that either the channel user ID or network-received user ID has to a destination queue is changed, this change will only take effect for new object handles (that is, new **MQOPEN**s) for the destination queue. The times when MCAs open and close queues is variable; if a channel is already running when such an access change is made, the MCA can continue to put messages on the destination queue using the existing security access of the user ID(s) rather than the updated security access. To avoid this, you should stop and re-start the channels to enforce the updated access level.

Security considerations for cluster support

This section discusses the security considerations for cluster support.

You can use the MCA user ID and security exits to authenticate cluster channels (as with conventional channels). The security exit on the cluster-receiver channel must check that the queue manager is permitted access to the server queue manager's clusters. You can start to use MQSeries cluster support without having to change your existing queue access security, however you must allow other queue managers in the cluster to write to the SYSTEM.CLUSTER.COMMAND.QUEUE if they are to join the cluster.

MQSeries cluster support does not provide a mechanism to limit a member of a cluster to the client role only. As a result, you must be sure that you trust any queue managers that you allow into the cluster. If any queue manager in the cluster creates a queue with a particular name, it will be able to receive messages for that queue, regardless of whether the application putting messages to that queue intended this or not.

To restrict the membership of a cluster, you need to take the same action that you would take to prevent queue managers connecting to receiver channels. You can achieve this by writing a security exit program on the receiver channel or by writing an exit program to prevent unauthorized queue managers from writing to the SYSTEM.CLUSTER.COMMAND.QUEUE.

Note: It is not advisable to permit applications to open the SYSTEM.CLUSTER.TRANSMIT.QUEUE directly, just as it is not advisable to permit an application to open any other transmission queue directly.

If you are using resource security you should consider the following in addition to the considerations discussed in “Security considerations for distributed queuing” on page 463:

- The channel initiator needs RACF ALTER access to the following system queues:
  - SYSTEM.CLUSTER.COMMAND QUEUE
  - SYSTEM.CLUSTER.TRANSMIT.QUEUE.

  and UPDATE access to SYSTEM.CLUSTER.REPOSITORY.QUEUE

  It also needs READ access to any namelists used for clustering.
- The cluster support commands (REFRESH and RESET CLUSTER, SUSPEND and RESUME QMGR) should have appropriate command security set (as described in Table 45 on page 433).

Security installation tasks

When MQSeries is first installed, you must perform these security-related tasks:

1. Set up MQSeries data set and system security by:
   - Authorizing the queue manager started-task procedure xxxxMSTR and the distributed queuing started-task procedure xxxxCHIN to run under RACF.
   - Authorizing access to queue manager data sets.
2. Set up RACF definitions for MQSeries security.

Setting up MQSeries data set and system security

The possible users of MQSeries data sets include:

- The queue manager itself.
- MQSeries administrators who need to create MQSeries data sets, run utility programs, and so on.
- Application programmers, who need to use the MQSeries-supplied copybooks, include data sets, macros, and so on.
- Applications involving one or more of the following:
  - Batch jobs
  - TSO users
  - CICS regions
  - IMS regions

For all of these potential users, protect the MQSeries data sets with RACF.

You must also control access to all your 'CSQINP' data sets.

RACF authorization of started-task procedures

Some MQSeries data sets should be for the exclusive use of the queue manager. If you protect your MQSeries data sets using RACF, you must also authorize the queue manager started-task procedure xxxxMSTR, and the distributed queuing started-task procedure xxxxCHIN, using RACF. To do this, use either:

- The STARTED class.
- The started procedures table (ICHRIN03).

  (Any changes you make to the RACF started procedures table require that you IPL your OS/390 system before the changes can take effect.)

For more information, see the *Security Server (RACF) System Programmer's Guide*.

The RACF user ID identified must have the required access to the data sets in the started-task procedure. For example, if you associate a queue manager started task procedure called CSQ1MSTR with the RACF user ID QMGRCSQ1, the user ID QMGRCSQ1 must have access to the OS/390 resources accessed by the CSQ1 queue manager.

The RACF user IDs associated with the queue manager and channel initiator started task procedures should not have the TRUSTED attribute set.

Authorizing access to data sets

The MQSeries data sets should be protected so that no unauthorized user can run a queue manager instance, or gain access to any queue manager data. To do this, use normal OS/390 RACF data set protection. For more information, see the *Security Server (RACF) Security Administrator's Guide*.

Table 59 summarizes the RACF access that the queue manager started task procedure must have to the different data sets.

Table 59. RACF access to data sets associated with a queue manager

RACF access	Data sets
READ	• thlqual.SCSQAUTH and thlqual.SCSQANLx (where x is the language letter for your national language). • The data sets referred to by CSQINP1, CSQINP2 and CSQXLIB in the queue manager's started task procedure.
UPDATE	• All page sets and log and BSDS data sets.
ALTER	• All archive data sets.

Table 60 summarizes the RACF access that the started task procedure for distributed queuing must have to the different data sets.

Table 60. RACF access to data sets associated with distributed queuing

RACF access	Data sets
READ	• thlqual.SCSQAUTH, thlqual.SCSQANLx (where x is the language letter for your national language), and thlqual.SCSQMVR1 or thlqual.SCSQMVR2. • LE/370 library data sets. • The data sets referred to by CSQXLIB and CSQINPX in the distributed queuing started task procedure.
UPDATE	• Data sets CSQOUTX and CSQSNAP • Dynamic queues SYSTEM.CSQXCMD.*

Example security scenario

This section describes an example security scenario, showing the security settings required. The scenario uses 2 queue managers on OS/390, called QM1 and QM2.

An application uses the **MQPUT1** call to put messages to queues on queue manager QM1. Some of the messages are then forwarded to queues on QM2, using TCP and LU 6.2 channels. The application could be a batch application or a CICS application, and the messages are put using the MQPMO_SET_ALL_CONTEXT option. This is illustrated in Figure 104.



Figure 104. Example security scenario

The following assumptions are made about the queue managers:

- All the required MQSeries definitions have been predefined or have been made through the CSQINP2 data set processed at queue manager startup.

  If they have not, you will need the appropriate access authority to the commands needed to define these objects.

- All the RACF profiles required have been defined and appropriate access authorities have been granted, before the queue manager and channel initiators started.

  If they have not, you will need the appropriate authority to issue the RACF commands required to define all the profiles needed and grant the appropriate access authorities to those profiles. You will also need the appropriate authority to issue the MQSeries security commands to start using the new security profiles.

Security switch settings

The following security switches are set for both queue managers:

- Subsystem security on
- Queue security on
- Alternate user security on
- Context security on
- Process security off
- Namelist security off
- Connection security on

- Command security on
- Command resource security on

The following profiles are defined in the MQADMIN class to turn process and namelist security off:

```
QM1.NO.PROCESS.CHECKS
QM1.NO.NLIST.CHECKS
QM2.NO.PROCESS.CHECKS
QM2.NO.NLIST.CHECKS
```

MQSeries object definitions

The following objects are defined on the two queue managers. The definitions use the defaults supplied with MQSeries, unless otherwise stated.

Queue manager QM1

The following queues are defined on queue manager QM1:

LQ1 A local queue.

RQA A remote queue definition, with the following attributes:

- RNAME(LQA)
- RQMNAME(QM2)
- XMITQ(QM1.TO.QM2.TCP)

RQB A remote queue definition, with the following attributes:

- RNAME(LQB)
- RQMNAME(QM2)
- XMITQ(QM1.TO.QM2.LU62)

QM1.TO.QM2.TCP
A transmission queue.

QM1.TO.QM2.LU62
A transmission queue.

The following channels are defined on QM1:

QM1.TO.QM2.TCP
A sender channel definition, with the following attributes:

- Channel name = QM1.TO.QM2.TCP
- CHLTYPE(SDR)
- TRPTYPE(TCP)
- XMITQ(QM1.TO.QM2.TCP)
- CONNAME(QM2TCP)

QM1.TO.QM2.LU62
A sender channel definition, with the following attributes:

- Channel name = QM1.TO.QM2.LU62
- CHLTYPE(SDR)
- TRPTYPE(LU62)
- XMITQ(QM1.TO.QM2.LU62)
- CONNAME(QM2LU62)

(See “Security considerations for distributed queuing” on page 463 for information about setting up APPC security.)

Queue manager QM2

The following queues have been defined on queue manager QM2:

LQ1 A local queue.
LQB A local queue.
DLQ A local queue that is used as the dead-letter queue.

The following channels have been defined on QM2:

QM1.TO.QM2.TCP

A receiver channel definition, with the following attributes:

- Channel name = QM1.TO.QM2.TCP
- CHLTYPE(RCVR)
- TRPTYPE(TCP)
- PUTAUT(CTX)
- MCAUSER(MCATCP)

QM1.TO.QM2.LU62

A receiver channel definition, with the following attributes:

- Channel name = QM1.TO.QM2.LU62
- CHLTYPE(RCVR)
- TRPTYPE(LU62)
- PUTAUT(CTX)
- MCAUSER(MCALU62)

(See “Security considerations for distributed queuing” on page 463 for information about setting up APPC security.)

User IDs used in scenarios

The following user IDs are used:

BATCHID Batch application (Job or TSO ID)
MSGUSR *UserIdentifier* in MQMD (context user ID)
MOVER1 QM1 channel initiator address space user ID
MOVER2 QM2 channel initiator address space user ID
MCATCP MCAUSER specified on the TCP receiver channel definition
MCALU62 MCAUSER specified on the LU 6.2 receiver channel definition
CICSAD1 CICS address space ID
CICSTX1 CICS task user ID

Security profiles and accesses required

Table 61 through Table 65 on page 473 show the security profiles that are required to enable the scenario to work:

Table 61 (Page 1 of 2). Security profiles for the example scenario

Class	Profile	User ID	Access
MQCONN	QM1.CHIN	MOVER1	READ
MQADMIN	QM1.RESLEVEL	BATCHID	NONE
MQADMIN	QM1.RESLEVEL	CICSAD1	NONE
MQADMIN	QM1.CONTEXT	MOVER1	CONTROL

Table 61 (Page 2 of 2). Security profiles for the example scenario

Class	Profile	User ID	Access
MQQUEUE	QM1.SYSTEM.COMMAND.INPUT	MOVER1	UPDATE
MQQUEUE	QM1.SYSTEM.CHANNEL.SYNCQ	MOVER1	UPDATE
MQQUEUE	QM1.SYSTEM.CHANNEL.INITQ	MOVER1	UPDATE
MQQUEUE	QM1.SYSTEM.COMMAND.REPLY.MODEL	MOVER1	UPDATE
MQQUEUE	QM1.SYSTEM.ADMIN.CHANNEL.EVENT	MOVER1	UPDATE
MQQUEUE	QM1.QM1.TO.QM2.TCP	MOVER1	ALTER
MQQUEUE	QM1.QM1.TO.QM2.LU62	MOVER1	ALTER
MQCONN	QM2.CHIN	MOVER2	READ
MQADMIN	QM2.RESLEVEL	MOVER2	NONE
MQADMIN	QM2.CONTEXT	MOVER2	CONTROL
MQQUEUE	QM2.SYSTEM.COMMAND.INPUT	MOVER2	UPDATE
MQQUEUE	QM2.SYSTEM.CHANNEL.SYNCQ	MOVER2	UPDATE
MQQUEUE	QM2.SYSTEM.CHANNEL.INITQ	MOVER2	UPDATE
MQQUEUE	QM2.SYSTEM.COMMAND.REPLY.MODEL	MOVER2	UPDATE
MQQUEUE	QM2.SYSTEM.ADMIN.CHANNEL.EVENT	MOVER2	UPDATE
MQQUEUE	QM2.DLQ	MOVER2	UPDATE

Security profiles required for a batch application

The batch application runs under user ID BATCHID on QM1. It connects to queue manager QM1 and puts messages to the following queues:

- LQ1
- RQA
- RQB

It uses the MQPMO_SET_ALL_CONTEXT and MQPMO_ALTERNATE_USER_AUTHORITY options. The alternate user ID found in the *UserIdentifier* field of the message descriptor (MQMD) is MSGUSR.

The following profiles are required on queue manager QM1:

Table 62. Sample security profiles for the batch application on queue manager QM1

Class	Profile	User ID	Access
MQCONN	QM1.BATCH	BATCHID	READ
MQADMIN	QM1.CONTEXT	BATCHID	CONTROL
MQQUEUE	QM1.LQ1	BATCHID	UPDATE
MQQUEUE	QM1.RQA	BATCHID	UPDATE
MQQUEUE	QM1.RQB	BATCHID	UPDATE

Example security scenario

The following profiles are required on queue manager QM2 for messages put to queue RQA on queue manager QM1 (for the TCP channel):

Table 63. Sample security profiles for queue manager QM2 using TCP

Class	Profile	User ID	Access
MQADMIN	QM2.ALTERNATE.USER.MSGUSR	MCATCP	UPDATE
MQADMIN	QM2.ALTERNATE.USER.MSGUSR	MOVER2	UPDATE
MQADMIN	QM2.CONTEXT	MCATCP	CONTROL
MQADMIN	QM2.CONTEXT	MOVER2	CONTROL
MQQUEUE	QM2.LQA	MOVER2	UPDATE
MQQUEUE	QM2.LQA	MSGUSR	UPDATE
MQQUEUE	QM2.DLQ	MOVER2	UPDATE
MQQUEUE	QM2.DLQ	MSGUSR	UPDATE

Notes:

1. The user ID passed in the MQMD of the message is used as the user ID for the **MQPUT1** on queue manager QM2 because the receiver channel was defined with PUTAUT=CTX and MCAUSER=MCATCP.
2. The MCAUSER field of the receiver channel definition is set to MCATCP; this user ID is used in addition to the channel initiator address space user ID for the checks carried out against the alternate user ID and context profile.
3. The MOVER2 user ID and the *UserIdentifier* in the message descriptor (MQMD) are used for the resource checks against the queue.
4. The MOVER2 and MSGUSR user IDs both need access to the dead-letter queue so that messages that cannot be put to the destination queue can be sent there.
5. Two user IDs are checked on all three checks performed because RESLEVEL is set to NONE.

The following profiles are required on queue manager QM2 for messages put to queue RQB on queue manager QM1 (for the LU 6.2 channel):

Table 64 (Page 1 of 2). Sample security profiles for queue manager QM2 using LU 6.2

Class	Profile	User ID	Access
MQADMIN	QM2.ALTERNATE.USER.MSGUSR	MCALU62	UPDATE
MQADMIN	QM2.ALTERNATE.USER.MSGUSR	MOVER1	UPDATE
MQADMIN	QM2.CONTEXT	MCALU62	CONTROL
MQADMIN	QM2.CONTEXT	MOVER1	CONTROL
MQQUEUE	QM2.LQB	MOVER1	UPDATE
MQQUEUE	QM2.LQB	MSGUSR	UPDATE
MQQUEUE	QM2.DLQ	MOVER1	UPDATE

Table 64 (Page 2 of 2). Sample security profiles for queue manager QM2 using LU 6.2

Class	Profile	User ID	Access
MQQUEUE	QM2.DLQ	MSGUSR	UPDATE

Notes:

1. The user ID passed in the MQMD of the message is used as the user ID for the **MQPUT1** on queue manager QM2 because the receiver channel was defined with PUTAUT=CTX and MCAUSER=MCALU62.
2. The MCA user ID is set to the value of the MCAUSER field of the receiver channel definition (MCALU62).
3. Because LU 6.2 supports security on the communications system for the channel, the user ID received from the network is used as the channel user ID (MOVER1).
4. Two user IDs are checked on all three checks performed because RESLEVEL is set to NONE.
5. MCALU62 and MOVER1 are used for the checks performed against the alternate user ID and Context profiles, and MOVER1 and MSGUSR are used for the checks against the queue profile.
6. The MOVER1 and MSGUSR user IDs both need access to the dead-letter queue so that messages that cannot be put to the destination queue can be sent there.

Security profiles required for a CICS application

The CICS application uses a CICS address space user ID of CICSAD1 and a CICS task user ID of CICSTX1. The security profiles required on queue manager QM1 are different to those required for the batch application. The profiles required on queue manager QM2 are the same as for the batch application.

The following profiles are required on queue manager QM1:

Table 65. Sample security profiles for the CICS application on queue manager QM1

Class	Profile	User ID	Access
MQCONN	QM1.CICS	CICSAD1	READ
MQADMIN	QM1.CONTEXT	CICSAD1	CONTROL
MQADMIN	QM1.CONTEXT	CICSTX1	CONTROL
MQQUEUE	QM1.LQ1	CICSAD1	UPDATE
MQQUEUE	QM1.LQ1	CICSTX1	UPDATE
MQQUEUE	QM1.RQA	CICSAD1	UPDATE
MQQUEUE	QM1.RQA	CICSTX1	UPDATE
MQQUEUE	QM1.RQB	CICSAD1	UPDATE
MQQUEUE	QM1.RQB	CICSTX1	UPDATE

Security problem determination

This section describes the conditions under which violation messages can be generated in an MQSeries application program and provides a checklist to be implemented if the ESM is not controlling access in the way that you expect.

Violation messages

An MQRC_NOT_AUTHORIZED can be returned to an application program because:

- A user is not allowed to connect to the queue manager. In this case, you get an ICH408I message in the Batch/TSO, CICS, or IMS joblog.
- A user signon to the queue manager has failed because, for example, the job user ID is not valid or appropriate, or the task user ID or alternate user ID is not valid. One or more of these user IDs might not be valid because they have been revoked or deleted. In this case, you get an ICHxxxx message and possibly an IRRxxxx message in the queue manager joblog giving the reason for the signon failure. For example:

```
ICH408I USER(NOTDFND ) GROUP(        ) NAME(???                 )
  LOGON/JOB INITIATION - USER AT TERMINAL          NOT RACF-DEFINED
IRR012I  VERIFICATION FAILED. USER PROFILE NOT FOUND
```

- An alternate user has been requested, but the job or task user ID does not have access to the alternate user ID. For this failure, you get a violation message in the joblog of the relevant queue manager.
- A context option has been used or is implied by opening a transmission queue for output, but the job user ID or, where applicable, the task or alternate user ID does not have access to the context option. In this case, a violation message is put in the joblog of the relevant queue manager.
- An unauthorized user has attempted to access a secured queue manager object, for example, a queue. In this case, an ICH408I message for the violation is put in the joblog of the relevant queue manager. This violation might be due to the job or, when applicable, the task or alternate user ID.

Violation messages for command security and command resource security can also be found in the joblog of the queue manager.

If the ICH408I violation message shows the queue manager jobname rather than a user ID, this is normally the result of a blank alternate user ID being specified. For example:

```
ICH408I JOB(MQS1MSTR) STEP(MQS1MSTR)
          MQS1.PAYROLL.REQUEST CL(MQQUEUE)
          INSUFFICIENT ACCESS AUTHORITY
          ACCESS INTENT(UPDATE )  ACCESS ALLOWED(NONE   )
```

You can find out who is allowed to use blank alternate user IDs by checking the access list of the MQADMIN profile ssid.ALTERNATE.USER.-BLANK-.

An ICH408I violation message can also be generated by:

- A command being sent to the system-command input queue without context. User-written programs that write to the system-command input queue should always use a context option. For more information, see “Profiles for context security” on page 427.
- When the job accessing the MQSeries resource does not have a user ID associated with it, or when an MQSeries adapter cannot extract the user ID from the adapter environment.

What to do if access is allowed or disallowed incorrectly

In addition to the steps detailed in the *Security Server (RACF) Security Administrator's Guide*, use this checklist if access to a resource appears incorrectly controlled:

- Are the switch profiles correctly set?
  - Is RACF active?
  - Are the MQSeries RACF classes installed and active?
    Use the RACF command, SETROPTS LIST, to check this.
  - Use the MQSeries command, DISPLAY SECURITY, to display the current switch status from the queue manager.
  - Check the switch profiles in the MQADMIN class.
    Use the RACF commands, SEARCH and RLIST, for this.
  - Re-check the RACF switch profiles by issuing the MQSeries command, REFRESH SECURITY(MQADMIN).
- Has the RACF resource profile changed? For example, has universal access on the profile changed or has the access list of the profile changed?
  - Is the profile generic?
    If it is, issue the RACF command, SETROPTS GENERIC(classname) REFRESH.
  - Have you refreshed the security on this queue manager?
    If required, issue the MQSeries command, REFRESH SECURITY(*).
- Has the RACF definition of the user changed? For example, has the user been connected to a new group or has the user access authority been revoked?
  - Have you re-verified the user by issuing the MQSeries command, RVERIFY SECURITY(userid)?
- Are security checks being bypassed due to RESLEVEL?
  - Check the connecting user ID's access to the RESLEVEL profile. Use the RACF audit records to determine what the RESLEVEL is set to.
  - If you are running from CICS, check the transaction's RESSEC setting.
  - If RESLEVEL has been changed while a user is connected, they must disconnect and re-connect before the new RESLEVEL setting takes effect.

Security problem determination

Part 9. Appendixes

© Copyright IBM Corp. 1993,1999

Appendix A. Macros intended for customer use

The macros identified in this appendix are provided as programming interfaces for customers by MQSeries.

Note: Do not use as programming interfaces any MQSeries macros other than those identified in this appendix.

General-use programming interface macros

The following macros are provided to enable you to write programs that use the services of MQSeries. The macros are supplied in library thlqual.SCSQMACS.

CMQA
CMQCDA
CMQCFA
CMQCFHA
CMQCFILA
CMQCFINA
CMQCFSLA
CMQCFSTA
CMQCIHA
CMQCXPA
CMQDLHA
CMQDXPA
CMQGMOA
CMQIIHA
CMQMDA
CMQMDEA
CMQODA
CMQPMOA
CMQRMHA
CMQTMA
CMQTMC2A
CMQWCRA
CMQWDRA
CMQWIHA
CMQWPRA
CMQWXPA
CMQXA
CMQXCALA
CMQXCFBA
CMQXCFCA
CMQXCDFA
CMQXCINA
CMQXCVCA
CMQXPA
CMQXQHA
CMQXWDA

© Copyright IBM Corp. 1993,1999

General-use programming interface copy files

The following COBOL copy files are provided to enable you to write programs that use the services of MQSeries. The copy files are supplied in library thlqual.SCSQCOBC.

CMQCDL
CMQCDV
CMQCFHL
CMQCFHV
CMQCFILL
CMQCFILV
CMQCFINL
CMQCFINV
CMQCFSLL
CMQCFSLV
CMQCFSTL
CMQCFSTV
CMQCFV
CMQCIHL
CMQCIHV
CMQCXPL
CMQCXPV
CMQDLHL
CMQDLHV
CMQGMOL
CMQGMOV
CMQIIHL
CMQIIHV
CMQMDEL
CMQMDEV
CMQMDL
CMQMDV
CMQODL
CMQODV
CMQPMOL
CMQPMOV
CMQRMHL
CMQRMHV
CMQTML
CMQTMV
CMQTMC2L
CMQTMC2V
CMQWIHL
CMQWIHV
CMQV
CMQXV
CMQXQHL
CMQXQHV

Product-sensitive programming interface macros

The following macros are provided to enable you to write programs that use the services of MQSeries. The macros are supplied in library thlqual.SCSQMACS.

CSQBDEF
CSQQDEFX
CSQQLITX

General-use programming interface include files

The following C include files are provided to enable you to write programs that use the services of MQSeries. The files are supplied in library thlqual.SCSQC370.

CMQC
CMQXC
CMQCFC

The following PL/I include files are provided to enable you to write programs that use the services of MQSeries. The files are supplied in library thlqual.SCSQPLIC.

CMQP
CMQEPP
CMQXP
CMQCFP

Macros

Appendix B. Using OTMA exits in IMS

If you want to send output from an IMS transaction to MQSeries, and that transaction did not originate in MQSeries, you need to code one or more IMS OTMA exits.

Similarly if you want to send output to a non-OTMA destination, and the transaction did originate in MQSeries, you also need to code one or more IMS OTMA exits.

The following exits are available in IMS to enable you to customize processing between IMS and MQSeries:

- An OTMA pre-routing exit
- A destination resolution user (DRU) exit

Exit names

You must name the pre-routing exit DFSYPRX0. You can name the DRU exit anything, as long as it does not conflict with a module name already in IMS.

Specifying the destination resolution user exit name

You can use the *Druexit* parameter of the OTMACON keyword of the CSQ6SYSP macro to specify the name of the OTMA DRU exit to be run by IMS.

We suggest you adopt a naming convention of DRU0xxxx, where xxxx is the name of your MQSeries system.

If you do not specify the name of a DRU exit in the OTMACON parameter, the default is DFSYDRU0. A sample of this module is supplied by IMS. See the *IMS/ESA Customization Guide* for information about this.

Naming convention for IMS destination

You need a naming convention for the destination to which you send the output from your IMS program. This is the destination that is set in the CHNG call of your IMS application, or that is pre-set in the IMS PSB.

A sample scenario

We suggest the OTMA destination name is synonymous with the MQSeries system name, for example the MQSeries system name repeated. (In this case, if the MQSeries system name is VCPE, the destination set by the CHNG call is VCPEVCPE.)

The pre-routing exit DFSYPRX0

You must first code a pre-routing exit DFSYPRX0. Parameters passed to this routine by IMS are documented in *IMS/ESA Customization Guide*.

This exit tests whether the message is intended for a known OTMA destination (in our example VCPEVCPE). If it is, the exit must check whether the transaction sending the message originated in OTMA. If so, it will already have an OTMA header, so you should exit from DFSYPRX0 with register 15 set to 0.

© Copyright IBM Corp. 1993,1999

- If the transaction sending the message did not originate in OTMA, you must set the client name to be a valid OTMA client. This is the XCF member-name of the MQSeries system to which you want to send the message. The *IMS/ESA Customization Guide* tells you where to set this. We suggest you set your client name (in the OTMACON parameter of the CSQ6SYSP macro) to be the queue manager name. This is the default. You should then exit from DFSYPRX0 setting register 15 to 4.
- If the transaction sending the message originated in OTMA, and the destination is non-OTMA, you should set register 15 to 8 and exit.
- In all other cases, you should set register 15 to 0.

If you set the OTMA client name to one that is not known to IMS, your application CHNG or ISRT call returns an A1 status code.

For an IMS system communicating with more than one MQSeries system, you should repeat the logic above for each MQSeries system.

Sample assembler code to achieve the above is shown in Figure 105:

```
         TITLE 'DFSYPRX0: OTMA PRE-ROUTING USER EXIT'
DFSYPRX0 CSECT
DFSYPRX0 AMODE 31
DFSYPRX0 RMODE ANY
*
         SAVE  (14,12),,DFSYPRX0&SYSDATE&SYSTIME
         SPACE 2
         LR    R12,R15               MODULE ADDRESSABILITY
         USING DFSYPRX0,R12
*
         L     R2,12(,R1)            R2 -> OTMA PREROUTE PARMS
*
         LA    R3,48(,R2)            R3 AT ORIGINAL OTMA CLIENT (IF ANY)
         CLC   0(16,R3),=XL16'00'    OTMA ORIG?
         BNE   OTMAIN                YES, GO TO THAT CODE
*
NOOTMAIN DS 0H                       NOT OTMA INPUT
         LA    R5,8(,R2)             R5 IS AT THE DESTINATION NAME
         CLC   0(8,R5),=C'VCPEVCPE'  IS IT THE OTMA UNSOLICITED DEST?
         BNE   EXIT0                 NO, NORMAL PROCESSING
*
         L     R4,80(,R2)            R4 AT ADDR OF OTMA CLIENT
         MVC   0(16,R4),=CL16'VCPE'  CLIENT OVERRIDE
         B     EXIT4                 AND EXIT
*
OTMAIN   DS 0H                       OTMA INPUT
         LA    R5,8(,R2)             R5 IS AT THE DESTINATION NAME
         CLC   0(8,R5),=C'VCPEVCPE'  IS IT THE OTMA UNSOLICITED DEST?
         BNE   EXIT8                 NO, NORMAL PROCESSING
```

Figure 105 (Part 1 of 2). OTMA pre-routing exit assembler sample

```
*
EXIT0    DS 0H
         LA    R15,0                RC = 0
         B     BYEBYE
*
EXIT4    DS 0H
         LA    R15,4                RC = 4
         B     BYEBYE
*
EXIT8    DS 0H
         LA    R15,8                RC = 8
         B     BYEBYE
*
BYEBYE   DS 0H
         RETURN (14,12),,RC=(15)    RETURN WITH RETURN CODE IN R15
         SPACE 2
         REQUATE
         SPACE 2
         END
```

Figure 105 (Part 2 of 2). OTMA pre-routing exit assembler sample

The destination resolution user exit

If you have set register 15 to 4 in DFSYPRX0, or if the source of the transaction was OTMA ***and*** you set Register 15 to 0, your DRU exit is invoked. In our example, the DRU exit name is DRU0VCPE.

The DRU exit checks if the destination is VCPEVCPE. If it is, it sets the OTMA user data (in the OTMA prefix) as follows:

Offset (decimal)	**OTMA user data**
0	OTMA user data length (in this example, 334)
2	MQMD
326	Reply to format

These offsets are where the MQSeries-IMS bridge expects to find this information.

We suggest that the DRU exit is as simple as possible. Therefore, in this sample, all messages originating in IMS for a particular MQSeries system will be put to the same MQSeries queue.

If the message needs to be persistent, IMS must use a synchronized transaction pipe. To do this, the DRU exit must set the OUTPUT flag. For further details, please refer to the *IMS/ESA Customization Guide*.

You should write an MQSeries application to process this queue, and use information from the MQMD structure, the MQIIH structure (if present), or the user data, to route each message to its destination.

A sample assembler DRU exit is shown in Figure 106 on page 486.

```
         TITLE 'DRU0VCPE: OTMA DESTINATION RESOLUTION USER EXIT'
DRU0VCPE CSECT
DRU0VCPE AMODE 31
DRU0VCPE RMODE ANY
*
         SAVE  (14,12),,DRU0VCPE&SYSDATE&SYSTIME
         SPACE 2
         LR    R12,R15                         MODULE ADDRESSABILITY
         USING DRU0VCPE,R12
*
         L     R2,12(,R1)                      R2 -> OTMA DRU PARMS
*
         L     R5,88(,R2)                      R5 ADDR OF OTMA USERDATA
         LA    R6,2(,R5)                       R6 ADDR OF MQMD
         USING MQMD,R6                         AS A BASE
*
         LA    R4,MQMD_LENGTH+10               SET THE OTMA USERDATA LEN
         STH   R4,0(,R5)                       = LL + MQMD + 8
*                                              CLEAR REST OF USERDATA
         MVI   0(R6),X'00'                     ...NULL FIRST BYTE
         MVC   1(255,R6),0(R6)                 ...AND PROPAGATE IT
         MVC   256(MQMD_LENGTH-256+8,R6),255(R6) ...AND PROPAGATE IT
*
VCPE     DS    0H
         CLC   44(16,R2),=CL16'VCPE'           IS DESTINATION VCPE?
         BNE   EXIT4                           NO, THEN DEST IS NON-OTMA
         MVC   MQMD_REPLYTOQ,=CL48'IMS.BRIDGE.UNSOLICITED.QUEUE'
         MVC   MQMD_REPLYTOQMGR,=CL48'VCPE'    SET QNAME AND QMGRNAME
         MVC   MQMD_FORMAT,MQFMT_IMS           SET MQMD FORMAT NAME
         MVC   MQMD_LENGTH(8,R6),MQFMT_IMS_VAR_STRING
*                                              SET REPLYTO FORMAT NAME
         B     EXIT0
*
EXIT0    DS    0H
         LA    R15,0                           SET RC TO OTMA PROCESS
         B     BYEBYE                          AND EXIT
*
EXIT4    DS    0H
         LA    R15,4                           SET RC TO NON-OTMA
         B     BYEBYE                          AND EXIT
*
BYEBYE   DS    0H
         RETURN (14,12),,RC=(15)               RETURN CODE IN R15
         SPACE 2
         REQUATE
         SPACE 2
         CMQA   EQUONLY=NO
         CMQMDA DSECT=YES
         SPACE 2
         END
```

Figure 106. Sample assembler DRU exit

Appendix C. Upgrading and applying service to TCP/IP, Language Environment, or OS/390 Callable Services

The following tables show you what you need to do to MQSeries for OS/390 if you upgrade your level of, or apply service to, the following products:

- TCP/IP
- Language Environment®
- OS/390 Callable Services (APPC and RRS for example)

Table 66. Service has been applied or the product has been upgraded to a new release

Product	Action if using CALLLIBS	Action if using LINK
TCP/IP	You need to do this only if the TCP/IP module DSPREFIX in the SEZACMTX library has been changed. 1. Run REPORT CALLLIBS for DDDEF SEZACMTX. 2. Run the job generated by REPORT CALLLIBS.	No action required provided that the SMP/E zones were set up for automatic relinking, and the CSQ8LDQM job has been run.
Language Environment	1. Run REPORT CALLLIBS for DDDEFs SCEELKED and SCEESPC. 2. Run the job generated by REPORT CALLLIBS.	No action required provided that the SMP/E zones were set up for automatic relinking, and the CSQ8LDQM job has been run.
Callable Services	1. Run REPORT CALLLIBS for DDDEF CSSLIB. 2. Run the job generated by REPORT CALLLIBS.	No action required provided that the SMP/E zones were set up for automatic relinking, and the CSQ8LDQM job has been run.

Table 67 (Page 1 of 2). One of the products has been updated to a new release in a new SMP/E environment and libraries

Product	Action if using CALLLIBS	Action if using LINK
TCP/IP	1. Change the DDDEF for SEZACMTX to point to the new library. 2. Run REPORT CALLLIBS for DDDEF SEZACMTX. 3. Run the job generated by REPORT CALLLIBS.	1. Delete the XZMOD subentries for the following LMOD entries in the MQSeries for OS/390 target zone: • CSQXRCTL • CSQXSUPR • CSQXTCP 2. Set up the appropriate ZONEINDEXs between the MQSeries zones and the TCP/IP zone. 3. Tailor CSQ8LDQM to refer to the new zone on the FROMZONE parameter of the LINK commands (CSQ8LDQM can be found in the SCSQINST library). 4. Run CSQ8LDQM.

© Copyright IBM Corp. 1993,1999

Table 67 (Page 2 of 2). One of the products has been updated to a new release in a new SMP/E environment and libraries

Product	Action if using CALLLIBS	Action if using LINK
Language Environment	1. Change the DDDEFs for SCEELKED and SCEESPC to point to the new library. 2. Run REPORT CALLLIBS for DDDEF SEZACMTX. 3. Run the job generated by REPORT CALLLIBS.	1. Delete the XZMOD subentries for the following LMOD entries in the MQSeries for OS/390 target zone: CMQXDCST, CMQXRCTL, CMQXSUPR, CSQCBE00, CSQCBP00, CSQCBP10, CSQCBR00, CSQUCVX, CSQVXPCB, CSQVXSPT, CSQXDCST, CSQXRCTL, CSQXSUPR, CSQXTCP, CSQXTNSV, IMQB23IC, IMQB23IM, IMQB23IR, IMQS23IC, IMQS23IM, IMQS23IR 2. Set up the appropriate ZONEINDEXs between the MQSeries zones and the Language Environment zones. 3. Tailor CSQ8LDQM to refer to the new zone on the FROMZONE parameter of the LINK commands. CSQ8LDQM can be found in the SCSQINST library. 4. Run CSQ8LDQM.
Callable services	1. Change the DDDEF for CSSLIB to point to the new library. 2. Run REPORT CALLLIBS for DDDEF CSSLIB. 3. Run the job generated by REPORT CALLLIBS.	1. Delete the XZMOD subentries for the following LMOD entries in the MQSeries for OS/390 target zone: CMQXRCTL, CMQXSUPR, CSQBSRV, CSQILPLM, CSQXJST, CSQXSUPR, CSQ3AMGP, CSQ3EPX, CSQ3REPL, 2. Set up the appropriate ZONEINDEXs between the MQSeries zones and the Callable Services zones. 3. Tailor CSQ8LDQM to refer to the new zone on the FROMZONE parameter of the LINK commands. CSQ8LDQM can be found in the SCSQINST library. 4. Run CSQ8LDQM.

Running a REPORT CALLLIBS job

When running a REPORT CALLLIBS job there is an option that instructs SMP/E to place a user created job card at the front of the output data set. The option (JOBCARD) requires a DDDEF that points to a PDS containing the job card. This DDDEF can be defined to SMP/E using the example job step shown in Figure 107 on page 489.

To run a REPORT CALLLIBS job you need to supply the following:

- The data set names of SMP/E CSI that contains MQSeries for OS/390
- The data set into which the link-edit job is to be placed

In the SMP/E commands you need to provide:

- The DDDEFs of the products that have been upgraded or updated (see Table 66 on page 487 and Table 67 on page 487 for a list of possible DDDEFs)

```
//*****************************************************************
//* DEFINE THE LOCATION TO SMP/E OF THE JOBCARD CALLLIBS IS TO
//* USE WHEN CREATING THE LINK-EDIT JOB.
//*****************************************************************
//DEFJCARD  EXEC PGM=GIMSMP,REGION=4096K
//SMPCSI   DD DSN=your.csi,
//            DISP=SHR
//SYSPRINT DD SYSOUT=*
//SMPCNTL  DD *
  SET BDY(GLOBAL).
  UCLIN .
    REP DDDEF(MQJCARD)
        DA(job.card.data.set) SHR .
  ENDUCL .
/*
//
```

Figure 107. Example SMP/E JOBCARD job step

- The DDDEF of the PDS containing the JOBCARD (MQJCARD in the example below)
- The name of the member containing the JOBCARD

Figure 108 shows an example SMP/E job that can used as a basis for your own job.

```
//*****************************************************************
//* RUN REPORT CALLLIBS.
//*****************************************************************
//CALLLIBS  EXEC PGM=GIMSMP,REGION=4096K
//SMPCSI   DD DSN=your.csi,
//            DISP=SHR
//SMPPUNCH DD DSN=your.callibs.punched.output,
//            DISP=(MOD,CATLG),
//            UNIT=SYSDA,
//            DCB=(RECFM=FB,LRECL=80,BLKSIZE=8800),
//            SPACE=(8800,(10,2))
//SYSPRINT DD SYSOUT=*
//SMPCNTL  DD *
  SET BDY(GLOBAL).
  REPORT CALLLIBS(dddef)
  ZONES(target zone)
  JOBCARD(MQJCARD,jobcard member name).
/*
```

Figure 108. Example SMP/E REPORT CALLLIBS job

Service and upgrade considerations

Appendix D. Enabling distributed queuing using CICS ISC

To enable distributed queuing using CICS ISC (the "CICS mover"), you must do the tasks described in the following sections:

- "Defining MQSeries programs and data sets as CICS resources"
- "Defining the channel definitions" on page 492
- "Defining the CKMQ transient data queue" on page 493
- "Defining MQSeries queues, triggers, and processes" on page 493
- "Defining CICS resources used by distributed queuing" on page 493
- "Security considerations for distributed queuing (using CICS ISC)" on page 494

Note: You must also define access security as described in "Security considerations for distributed queuing (using CICS ISC)" on page 494.

Prerequisites are that you have installed the CICS mover feature, and that the CICS adapter component has already been set up (see "Setting up the CICS adapter" on page 124).

Defining MQSeries programs and data sets as CICS resources

As part of installing the CICS adapter, you might already have updated the CICS system definition (CSD) data set. If you have already done this, go to "Defining the channel definitions" on page 492.

The thlqual.SCSQPROC library includes a member called CSQ4D100. This member contains the resource definition online (RDO) statements required for distributed queuing. These RDO statements must be included in the CSD of both the local CICS system and the remote CICS system to be used by the distributed queuing facility.

Notes:

1. You might have to customize CSQ4D100; in particular, the definition for the channel definition data set might have to be changed to include a data set name. There is a note at the beginning of CSQ4D100 that explains this.
2. The CSQKCDF file definition must specify a variable record format, that is, RECORDFORMAT(V). You must not change this format.

The group created is called CSQKDQ1. This group can be included in a group LIST so that the definitions are available at CICS startup. A cold start of your CICS system is required. Figure 109 shows an example of JCL that can be used to do this using the CICS DFHCSDUP offline utility.

© Copyright IBM Corp. 1993,1999

```
//CSDLOOKC EXEC PGM=DFHCSDUP,REGION=4096K
//STEPLIB  DD DSN=CICS330.SDFHLOAD,DISP=SHR
//DFHCSD   DD DSN=your.cics.csd,DISP=SHR
//SYSUT1   DD UNIT=SYSDA,SPACE=(1024,(100,10))
//SYSPRINT DD SYSOUT=A
//SYSIN    DD DSN=MQM.CSQ1.USER(CSQ4D100),DISP=SHR
//         DD *
  ADD GROUP(CSQKDQ1) LIST(yourlist)
/*
```

Figure 109. Adding the distributed queuing definitions to the CICS CSD. This JCL sample assumes that the group CSQKDQ1 does not already exist on your CICS system.

Defining the channel definitions

You must also define the CSQKCDF data set for the channel definitions to be used by the distributed queuing facility. A data set definition is required on both the local and remote CICS systems.

The member CSQ4CHDF of thlqual.SCSQPROC contains the JCL to define the CSQKCDF data set. You must modify the JCL so that the data set high level qualifier and volume attributes conform to the naming conventions at your installation.

When the data set has been defined this DD statement can be added to your CICS startup procedure:

```
//CSQKCDF  DD DSN=thlqual.CDFILE,DISP=SHR
```

Figure 110. Adding a DD statement to the CICS startup procedure

Alternatively, you can modify the DSNAME field of the CSQKCDF file definition in the CSQKDQ1 group to contain the data set name. CICS then dynamically allocates the data set, removing the need to modify the CICS startup procedure.

Notes:

1. You must not change the supplied values for the RECORDSIZE and KEYS parameters ((400 400) and (20 8) respectively) of the DEFINE CLUSTER functional command in CSQ4CHDF.
2. You should have only one channel definition file for each queue manager. A single CICS system should own the channel definition file; the other CICS systems should define it as a remote file.
3. The channel definitions must be available, via function shipping if necessary, to all CICS regions running distributed queuing programs.

Defining the CKMQ transient data queue

Messages from the MQSeries distributed queue management facility are normally sent to the system console. However, these can be routed to the CKMQ extra-partition transient data queue. CSQ4DCT2 contains a sample DCT entry for CKMQ.

The sample DCT entries, CSQ4DCT1 and CSQ4DCT2, should already be incorporated with those of the existing DCT as part of installing the CICS adapter. See step 2 on page 126. If you have not done this, follow the instructions in "System definition" on page 126. Then add a DD statement for the CKMQ transient data queue to your CICS startup procedure. For example:

```
//MQMMSG  DD SYSOUT=*
```

See also "EXEC CICS LINK interface messages" on page 131.

Defining MQSeries queues, triggers, and processes

You must include the required queue definitions in your MQSeries subsystem. Distributed queuing requires a queue for use with sequence numbers and logical units of work identifiers (LUWID). You must ensure that a queue is available with the name SYSTEM.CHANNEL.SEQNO.

To pass commands to a running channel program, you need to ensure that a channel command queue exists for your system with the name SYSTEM.CHANNEL.COMMAND.

The member CSQ4DISQ in the thlqual.SCSQPROC library contains the queue definitions required for distributed queuing and examples of definitions of your own that you will need. You must customize this sample before you use it, then you can include this member in the CSQINP2 DD concatenation of the MQSeries startup procedure or you can use the COMMAND function in CSQUTIL utility to issue the required DEFINE commands.

Defining CICS resources used by distributed queuing

The distributed queuing facilities on the local and remote CICS system require the definition of certain CICS resources for communication to be established. Before starting a channel, you must define these resources using the CICS RDO facility:

ISC LU 6.2 CONNECTION
This can be one of:

- An LU 6.2 single session terminal
- An LU 6.2 single session connection
- An LU 6.2 parallel session connection

SESSIONS
You must define enough sessions to accommodate all the channels that might be active at the same time.

PROFILE (optional)
Profile definitions can be created so that channels are allocated a session from a specific mode group.

For information about the definition of these CICS resources, see these books:

- *CICS Intercommunication Guide* for defining CICS ISC links.
- *CICS System Definition Guide* for guidance on implementing ISC in a CICS system.
- *CICS Resource Definition Guide* manual for defining resources to CICS.

Defining access security

You need to give the required access to the distributed queuing transactions. See "Security considerations for distributed queuing (using CICS ISC)" for information about this.

Setting up communications

For information on this, and all other aspects of distributed queuing using CICS ISC, see the *MQSeries Intercommunication* manual.

Security considerations for distributed queuing (using CICS ISC)

This section discusses security considerations for the "CICS mover."

When defining and starting channels for distributed queuing, the transactions used require access to certain MQSeries for OS/390 and CICS resources. The list below shows the transactions that are used for distributed queuing and the access requirements that might be needed. Security is not a mandatory requirement and these examples are only relevant where you are using resource security.

CKMC This transaction will require RACF UPDATE access to the following resources:

- The CSQKCDF VSAM file in CICS
- The SYSTEM.CHANNEL.SEQNO local queue in MQSeries for OS/390
- The SYSTEM.CHANNEL.COMMAND local queue in MQSeries for OS/390

The CKMC transaction only needs RACF UPDATE access to the above resources under certain conditions:

- For the CSQKCDF file, only when the following functions are performed:
  - CREATE a channel
  - COPY a channel
  - DELETE a channel
  - ALTER a channel
- For the SYSTEM.CHANNEL.SEQNO local queue, only when the following functions are performed:
  - RESYNC a channel
  - RESET a channel
  - RESOLVE a channel
- For the system.channel.command local queue when requesting stop for a channel.

  All other functions only require RACF READ access.

CKSG This transaction will require RACF READ access to the following resources:

- The CSQKCDF VSAM file in CICS

RACF UPDATE access to the following resources:

- The SYSTEM.CHANNEL.SEQNO local queue in MQSeries for OS/390
- The SYSTEM.CHANNEL.COMMAND local queue in MQSeries for OS/390
- The dead-letter queue (see "Dead-letter queue security" on page 421 for information about how to achieve this)

and RACF ALTER access to the following resources:

- The transmission queue specified in the channel definition in MQSeries for OS/390

CKSV This transaction will require RACF READ access to the following resources:

- The CSQKCDF VSAM file in MQSeries for OS/390

RACF UPDATE access to the following resources:

- The SYSTEM.CHANNEL.SEQNO local queue in MQSeries for OS/390
- The SYSTEM.CHANNEL.COMMAND local queue in MQSeries for OS/390
- The dead-letter queue (see "Dead-letter queue security" on page 421 for information about how to achieve this)

and RACF ALTER access to the following resources:

- The transmission queue specified in the channel definition in MQSeries for OS/390

CKRQ This transaction will require RACF READ access to the following resources:

- The CSQKCDF VSAM file in CICS

and RACF UPDATE access to the following resources:

- The SYSTEM.CHANNEL.SEQNO local queue in MQSeries for OS/390
- In MQSeries for OS/390, either:
  - The object name passed in the *RemoteQname* field of the MQXQH structure, or
  - The transmission queue representing the remote queue manager, if the value in the *RemoteQMgrName* field of the MQXQH structure does not match the local queue manager name.
- In MQSeries for OS/390 the SYSTEM.CHANNEL.COMMAND local queue
- The dead-letter queue (see "Dead-letter queue security" on page 421 for information about how to achieve this)

CKRC This transaction will require RACF READ access to the following resources:

- The CSQKCDF VSAM file in CICS

and RACF UPDATE access to the following resources:

- The SYSTEM.CHANNEL.SEQNO local queue in MQSeries for OS/390
- The SYSTEM.CHANNEL.COMMAND local queue
- In MQSeries for OS/390, either:
  - The object name passed in the *RemoteQName* field of the MQXQH structure, or
  - The transmission queue representing the remote queue manager, if the value in the *RemoteQmgrName* field of the MQXQH structure does not match the local queue manager name
- The dead-letter queue (see "Dead-letter queue security" on page 421 for information about how to achieve this)

Appendix E. Defining your queue manager environment parameters

After installing MQSeries for OS/390, it is important to consider the following configuration options and decide on the most appropriate definitions for your particular queue manager environment. You should consider these options before customizing the queue manager because it might be difficult to change them once the queue manager has been defined.

The following configuration options should be considered:

- Log data set definitions
- Page set definitions
- Buffer pool definitions

This chapter describes the factors that should be taken into account when designing your queue manager environment.

For the latest capacity planning and tuning guidance, see the MQSeries SupportPacs™ at the following Web site:

```
http://www.software.ibm.com/mqseries/txppacs/
```

Log data set definitions

Before setting up the log data sets, review the following section in order to decide on the most appropriate configuration for your system.

Should your archive logs reside on tape or DASD?

When deciding whether to use tape or DASD for your archive logs, there are a number of factors that you should consider:

1. Review your operating procedures before making decisions about tape or disk. For example, if you choose to archive to tape, operators must be available to mount the appropriate tapes when they are required.
2. During recovery, archive logs on tape are available as soon as the tape is mounted. If DASD archives have been used, and the data sets migrated to tape using hierarchical storage manager (HSM), there will be a delay while HSM recalls each data set to disk. You can recall the data sets before the archive log is used. However, it is not always possible to predict the correct order in which they will be required.
3. When using archive logs on DASD, if many logs are required (which might be the case when recovering a page set after restoring from a backup) you might require a significant quantity of DASD in order to hold all the archive logs.
4. In a low usage system or test system, it might be more convenient to have archive logs on DASD in order to eliminate the need for tape mounts.

© Copyright IBM Corp. 1993,1999

Should your installation use single or dual logging?

If your DASD type is 3390 or similar, you are recommended to use dual logging in order to ensure that you have an alternative backup source in the event of losing a data set. You should also use dual BSDSs and dual archiving to ensure adequate provision for data recovery.

If you use devices with in-built data redundancy (for example, Redundant Array of Independent Disks (RAID) devices) you might consider using single active logging. If you use persistent messages, single logging can increase maximum capacity by 10-30% and can also improve response times.

If you use dual archive logs on tape, it is typical for one copy to be held locally, and the other copy to be held off-site for use in disaster recovery.

Dual active logging adds a small performance overhead. You might want to specify it on a test system used for benchmarking, in addition to a production system.

How many active log data sets do you need?

You should have sufficient active logs to ensure that your system is not impacted in the event of an archive being delayed.

In practice, you should have at least three active log data sets but it is preferable to define more. For example, if the time taken to fill a log is likely to approach the time taken to archive a log during peak load, you should define more logs. You are also recommended to define more logs to offset possible delays in log archiving. If you use archive logs on tape, allow for the time required to mount the tape.

How large should the active logs be?

Your logs should be large enough so that it takes at least 30 minutes to fill a single log during the expected peak persistent message load. If you are archiving to tape, you are advised to make the logs large enough to fill one tape cartridge, or a number of tape cartridges. (For example, a log size of 1000 cylinders on 3390 DASD will fit onto a 3490E non-compacted tape with space to spare.)

Note: When archiving to tape, a copy of the BSDS is also written to the tape. When archiving to DASD, a separate data set is created for the BSDS copy.

If the logs are small (for example, 10 cylinders) it is likely that they will fill up frequently, which could result in performance degradation. In addition, you might find that the large number of archive logs required is difficult to manage.

If the logs are very large, and you are archiving to DASD, you will need a corresponding amount of spare space reserved on DASD for SMS retrieval of migrated archive logs, which might cause space management problems. In addition, the time taken to restart might increase because one or more of the logs has to be read sequentially at startup.

Active log placement

Ideally, each of the active logs should be allocated on separate, low-usage DASD volumes. As a minimum, no two adjacent logs should be on the same volume.

When an active log fills, the next log in the ring is used and the previous log data set is copied to the archive data set. If these two active data sets are on the same volume, contention will result, because one data set is read while the other is written to. For example, if you have three active logs and use dual logging, you will need six DASD volumes because each log is adjacent to both of the two other logs. Alternatively, if you have four active logs and you want to conserve DASD space, by allocating logs 1 and 3 on one volume and logs 2 and 4 on another, you will require four DASD volumes only.

In addition, you should ensure that primary and secondary logs are on separate physical units. If you use 3390 DASD, be aware that each head disk assembly contains two logical volumes. The physical layout of other DASD subsystems such as RAMAC arrays should also be taken into account.

Page set definitions

When deciding on the most appropriate settings for page set definitions, there are a number of factors that should be considered. These are discussed in the following sections.

Page set usage

In the case of short-lived messages, few pages are normally used on the page set and there is little or no I/O to the data sets except at startup, during a checkpoint, or at shutdown.

In the case of long-lived messages, those pages containing messages are normally written out to disk. This is performed by the queue manager in order to reduce restart time.

You should separate short-lived messages from long-lived messages by placing them on different page sets and in different buffer pools.

Size of page sets

You should allow enough space in your page sets for the expected peak message capacity. You should also specify a secondary extent to allow for any unexpected peak capacity, such as when a build up of messages develops because a queue server program is not running.

Number of page sets

Using several large page sets can make the role of the MQSeries administrator easier because it means that you need fewer page sets, making the mapping of queues to page sets simpler.

Using multiple, smaller page sets has a number of advantages. For example, they take less time to back up and I/O can be carried out in parallel during backup and restart. However, consider that this adds a significant overhead to the role of the MQSeries administrator, who will be required to map each queue to one of a much greater number of page sets.

The size of the page set also determines the time taken to recover a page set when restoring from a backup, because a large page set takes longer to restore.

Note: Recovery of a page set also depends on the time the queue manager takes to process the log records written since the backup was taken; this is determined by the backup frequency. This is discussed in "Recovering page sets" on page 500.

Recovering page sets

A key factor in recovery strategy concerns the period of time for which you can tolerate a queue manager outage. The total outage time might include the time taken to recover a page set from a backup, or to restart the queue manager after an abnormal termination. Factors affecting restart time include how frequently you back up your page sets, and how much data is written to the log between checkpoints.

In order to minimize the restart time after an abnormal termination, keep units of work short so that, at most, two active logs are used when the system restarts. For example, if you are designing an MQSeries application, avoid placing an **MQGET** call that has a long wait interval between the first in-syncpoint MQI call and the commit point because this might result in a unit of work that has a long duration. Other common causes of long units of work are in-doubt channels in the CICS mover, and batch intervals of more than 5 minutes for the non-CICS mover.

You can use the DISPLAY THREAD command to display the RBA of units of work and to help resolve the old ones. For information about the DISPLAY THREAD command, see the *MQSeries Command Reference* manual.

How often should a page set be backed up?

Frequent page set backup is essential if a reasonably short recovery time is required. This applies even when a page set is very small or there is a small amount of activity on queues in that page set.

If you use persistent messages in a page set, the backup frequency should be in the order of hours rather than days. This is also the case for page set zero.

In order to calculate an approximate backup frequency, start by determining the target total recovery time. This will consist of:

1. The time taken to react to the problem.
2. The time taken to restore the page set backup copy.

   (For example, you can restore approximately 60 cylinders of 3390 data per minute from and to RAMAC Virtual Array 2 Turbo 82 (RVA2-T82) DASD using Access Method Services REPRO.)

   If you use SnapShot backup/restore, the time taken to perform this task is of the order of a few seconds. For further information on SnapShot, see the *DFSMSdss Storage Administration Guide*.
3. The time the queue manager requires to restart, including the additional time needed to recover the page set.

   This depends most significantly on the amount of log data that must be read from active and archive logs since that page set was last backed up. All such

log data must be read, in addition to that directly associated with the damaged page set.

Note: When using fuzzy backup, it might be necessary to read up to three additional checkpoints, and this might result in the need to read one or more additional logs.

When deciding on how long to allow for the recovery of the page set, the factors you need to consider are:

- The rate at which data is written to the active logs during normal processing:
  - An approximation of the amount of data required on the log for a persistent message is 1.3 KB more than the user message length.
  - Approximately 2.5 KB of data is required on the log for each batch of messages sent on a channel.
  - Approximately 1.4 KB of data is required on the log for each batch of messages received on a channel.
  - Nonpersistent messages require no log data. NPMSPEED(FAST) channels require no log data for batches consisting entirely of nonpersistent messages.

  The rate at which data is written to the log depends on how messages arrive in your system, in addition to the message rate. Messages received or sent over a channel result in more data logging than messages generated and retrieved locally.
- The rate at which data can be read from the archive and active logs.

  When reading the logs, the achievable data rate depends on the devices used and the overall load on your particular DASD subsystem. (For example, data rates of approximately 2.7 MB per second have been observed using active and archive logs on RVA2-T82 DASD.)

  With most tape units, it is possible to achieve higher data rates for archived logs with a large block size. However, if an archive log is required for recovery, all the data on the active logs must be read also.

Achieving specific recovery targets

If you have specific recovery targets to achieve, for example, completion of the queue manager recovery and restart processing in addition to the normal startup time within *xx* seconds, you can use the following calculation to estimate your backup frequency (in hours):

```
Formula (A)
                     Required restart time * System recovery log read rate
                           (in secs)                  (in MB/sec)
Backup frequency  = ------------------------------------------------------
   (in hours)               Application log write rate (in MB/hour)
```

For example, consider a system in which MQSeries clients generate an overall load of 100 persistent messages per second. In this case, all messages are generated locally.

If each message is of user length 1 KB, the amount of data logged per hour is of the order:

```
100 * (1 + 1.3 KB) * 3600 seconds = approximately 800 MB

where
      100          = the message rate per second
      (1 + 1.3 KB) = the amount of data logged for
                     each 1 KB of persistent messages
```

Consider an overall target recovery time of 75 minutes. If you have allowed 15 minutes to react to the problem and restore the page set backup copy, queue manager recovery and restart must then complete within 60 minutes applying formula (A). This necessitates a page set backup frequency of at least every:

```
    3600 seconds * 2.7 MB per second / 800 MB per hour  =  12.15 hours
```

Note: This assumes that all required log data is on RVA2-T82 DASD.

If your MQSeries application day lasts approximately 12 hours, one backup each day is appropriate. However, if the application day lasts 24 hours, two backups each day is more appropriate.

Another example might be a production system in which all the messages are for request-reply applications (that is, a persistent message is received on a receiver channel and a persistent reply message is generated and sent down a sender channel).

In this example, the achieved batch size is one, and so there is one batch for every message. If there are 50 request replies per second, the overall load is 100 persistent messages per second. If each message is 1 KB in length, the amount of data logged per hour is of the order:

```
50((2 * (1+1.3 KB)) + 1.4 KB + 2.5 KB) * 3600 = approximately 1500 MB

where
      50                 = the message pair rate per second
      (2 * (1 + 1.3 KB)) = the amount of data logged for each message pair
      1.4 KB             = the overhead for each batch of messages
                           received by each channel
      2.5 KB             = the overhead for each batch of messages
                           sent by each channel
```

In order to achieve the queue manager recovery and restart within 30 minutes (1800 seconds) requires that page set backup is carried out at least every:

```
    1800 seconds * 2.7 MB per second / 1500 MB per hour  =   3.24 hours
```

Note: This assumes that all required log data is on RVA2-T82 DASD.

Periodic review of backup frequency

You are recommended to monitor your MQSeries log usage in terms of MB per hour. You should perform this check periodically and amend your page set backup frequency if necessary.

Buffer pool definitions

The following table shows suggested values for buffer pool definitions that affect the performance of queue manager operation, recovery, and restart. Two sets of values are given; one set is suitable for a test system, the other for a production system or a system that will become a production system eventually.

Table 68. Suggested test and production definitions for buffer pool settings

Definition setting	Test system	Production system
BUFFPOOL 0	1 050 buffers (default)	50 000 buffers The supplied default buffer pool sizes are usually too small for a production system.
BUFFPOOL 1	1 050 buffers (default)	20 000 buffers
BUFFPOOL 2	1 050 buffers (default)	100 000 buffers
BUFFPOOL 3	1 050 buffers (default)	30 000 buffers

You are recommended to reserve buffer pool 0 for object definitions (in page set 0) and performance critical, system related message queues, such as the SYSTEM.CHANNEL.SYNCQ queue and the SYSTEM.CLUSTER.* queues. The remaining three buffer pools can be used for user messages, for example:

- Buffer pool 1 might be used for important long-lived messages.

  Long-lived messages are those that remain in the system for longer than two checkpoints, at which time they are written out to the page set. If you have a large number of long-lived messages, this buffer pool should be relatively small, so that page set I/O is evenly distributed (older messages are written out to DASD each time the buffer pool becomes 85% full).

  If the buffer pool is too large, page set I/O is delayed until checkpoint processing. This might affect response times throughout the system.

  If you expect a small number of long-lived messages only, this buffer pool should be defined so that it is sufficiently large to hold all of these messages.

- Buffer pool 2 might be used for performance-critical, short-lived messages.

  There will normally be a high degree of buffer reuse, using a small number of buffers; however, you are recommended to make this buffer pool large in order to allow for unexpected message accumulation, for example, when a server application fails.

- Buffer pool 3 might be used for all other (usually performance non-critical) messages. Queues such as the dead-letter queue, SYSTEM.COMMAND.* queues and SYSTEM.ADMIN.* queues can also be mapped to buffer pool 3.

  Where virtual storage constraints exist and buffer pools need to be smaller, buffer pool 3 is the first candidate for size reduction.

Initially, you are recommended to define all buffer pools as shown in the table. Usage of buffer pools can be monitored by analysis of buffer pool statistics. In particular, you should ensure that the buffer pools are large enough so that QPSTSOS, QPSTSTLA and QPSTNBUF remain at zero. (These are described in “Buffer manager statistics” on page 384).

Buffer pool definitions

Buffer pool 0 and the buffer pool for short-lived messages (buffer pool 2) should be tuned so that the 15% free threshold is never exceeded (that is, QPSTCBSL divided by QPSTNBUF is always greater than 15%). If more than 15% of buffers remain free, I/O to the page sets using these buffer pools can be largely avoided during normal operation, although messages older than two checkpoints will be written to page sets.

See the MQSeries SupportPac *Capacity planning and tuning for MQSeries for OS/390* (MP16) for more information on buffer pool tuning.

Note: The optimum value for these parameters is dependent on the characteristics of the individual system. The values given are only intended as a guideline and might not be appropriate for your system.

Appendix F. New messages and codes

The following messages and codes have been added since the last version of the *MQSeries for OS/390 Messages and Codes* manual was issued:

- CSQI029I
- CSQI049I
- CSQJ160I
- CSQJ161I
- CSQP021I
- CSQR020I
- CSQR021D
- CSQR022I
- CSQR023I
- CSQR029I
- CSQR030I
- CSQR031I
- CSQR032I
- CSQR033I
- CSQU159E
- CSQU160E
- 00C94503

In order to receive these messages, you need to apply the following APARs:

- PQ24994
- PQ27752
- PQ28083
- PQ28093

CSQI029I *csect-name* **PAGE SET** *psid* **IS AN OLD COPY. MEDIA RECOVERY STARTED**

Explanation: MQSeries for OS/390 has recognized that the media recovery RBA held within the page set is older than the media recovery RBA checkpointed for the page set. This is because MQSeries for OS/390 was started with an old copy of the page set.

Module: CSQIECUR

Severity: 0

System Action: MQSeries for OS/390 applies any updates to the page set that are necessary. Restart processing continues.

CSQI049I Page set *psid* **has media recovery RBA**=*rcvry-rba***, checkpoint RBA**=*chkpt-rba*

Explanation: During restart, the queue manager opened the indicated page set. The media recovery RBA from the page set itself and the checkpointed RBA from the logs are as shown.

If the RBAs differ, it indicates that an old copy of the page set is being used. If the checkpoint RBA and the prior checkpoint RBA shown in message CSQR003I differ, it indicates that the page set has been offline.

Module: CSQIERST

Severity: 0

System Action: Processing continues. Media recovery is performed if necessary to bring the page set up to date.

CSQJ160I LONG-RUNNING UOW FOUND, URID=*urid* **CONNECTION NAME=***name*

Explanation: During active log offload, MQSeries encountered an uncommitted unit of recovery that now has records on the newly created archive log. The unit of recovery identifier *urid* together with the connection name *name* identify the associated thread.

System Action: Processing continues.

System Programmer Response: Consult with the application programmer to determine if there is a problem with the unit of recovery, and to ensure that the application commits work frequently enough. Uncommitted units of recovery can lead to difficulties later.

CSQJ161I UOW UNRESOLVED AFTER *n* **OFFLOADS, URID=***urid* **CONNECTION NAME=***name*

Explanation: During active log offload, MQSeries encountered an uncommitted unit of recovery that now has records spanning several archive logs. The unit of recovery identifier *urid* together with the connection name *name* identify the associated thread.

n is the number of logs archived since the unit of recovery was started. The message is first issued during an offload when *n* exceeds half the MAXARCH system parameter value, and is issued during every offload thereafter while the unit of recovery remains uncommitted.

System Action: Processing continues.

System Programmer Response: Consult with the application programmer to determine if there is a problem with the unit of recovery, and to ensure that the application commits work frequently enough. Uncommitted units of recovery can lead to difficulties later.

© Copyright IBM Corp. 1993,1999

CSQP021I Page set *psid* new media recovery RBA=*rcvry-rba*, checkpoint RBA=*chkpt-rba*

Explanation: During checkpoint processing, buffers have been flushed from the buffer pools to the indicated page set, establishing a new media recovery RBA. This RBA is the point from which log data would be required to perform media recovery for the page set. It should be the same as the checkpoint RBA.

Module: CSQPECKW

Severity: 0

System Action: Processing continues.

System Programmer Response: If the media recovery and checkpoint RBAs differ, contact your IBM support center for assistance.

CSQR020I OLD UOW FOUND

Explanation: During restart, a unit of work was found that predates the oldest active log. Information about the unit of work is displayed in a table in the same format as in message CSQR007I.

Module: CSQRCOLS

System Action: Message CSQR021D is issued and the operator's reply is awaited.

Operator Response: The operator has two options:

- Commit the unit of work, by replying Y.
- Continue, by replying N. The unit of work will be handled by the normal restart recovery processing. Because the unit of work is old, this is likely to involve using the **archive** logs.

CSQR021D REPLY Y TO COMMIT OR N TO CONTINUE

Explanation: An old unit of work was found, as indicated in the preceding CSQR020I message.

Module: CSQRCOLS

System Action: The queue manager waits for the operator's reply.

Operator Response: See message CSQR020I.

CSQR022I OLD UOW COMMITTED, URID=*urid*

Explanation: This message is sent if the operator answers Y to message CSQR021D.

Module: CSQRCOLS

System Action: The indicated unit of work is committed.

CSQR023I OLD UOW UNCHANGED, URID=*urid*

Explanation: This message is sent if the operator answers N to message CSQR021D.

Module: CSQRCOLS

System Action: The indicated unit of work is left for handling by the normal restart recovery process.

CSQR029I INVALID RESPONSE – NOT Y OR N

Explanation: The operator did not respond correctly to the reply message CSQR021D. Either 'Y' or 'N' must be entered.

Module: CSQRCOLS

System Action: The original message is repeated.

Operator Response: Reply as indicated in the repeated message.

CSQR030I Forward recovery log range from RBA=*from-rba* to RBA=*to-rba*

Explanation: This indicates the log range that must be read to perform forward recovery during restart.

Module: CSQRRPRC

System Action: Restart processing continues.

CSQR031I Reading log forwards, RBA=*rba*

Explanation: This is issued periodically during restart recovery processing to show the progress of the forward recovery phase. The log range that needs to be read is shown in the preceding CSQR030I message.

Module: CSQRPULS

System Action: Restart processing continues.

Operator Response: If this message is issued repeatedly with the same RBA value, investigate the cause; for example, MQSeries for OS/390 might be waiting for a tape with an archive log data set to be mounted.

CSQR032I Backward recovery log range from RBA=*from-rba* to RBA=*to-rba*

Explanation: This indicates the log range that must be read to perform backward recovery during restart.

Module: CSQRRPRC

System Action: Restart processing continues.

CSQR033I Reading log backwards, RBA=*rba*

Explanation: This is issued periodically during restart recovery processing to show the progress of the backward recovery phase. The log range that needs to be read is shown in the preceding CSQR032I message.

Module: CSQRPULS

System Action: Restart processing continues.

Operator Response: If this message is issued repeatedly with the same RBA value, investigate the cause; for example, MQSeries for OS/390 might be waiting for a tape with an archive log data set to be mounted.

CSQU159E *csect-name* **Source data set** *ddname1* **is not a page set**

Explanation: The COPYPAGE and RESETPAGE functions can only be used with an MQSeries for OS/390 page set.

Module: CSQUCOPY

Severity: 4

System Action: Processing continues with the next page set.

System Programmer Response: Specify a valid source page set, and resubmit the job.

CSQU160E *csect-name* **Source data set** *ddname1* **is not suitable for use with RESETPAGE**

Explanation: The RESETPAGE function should only be used with page sets for a queue manager that terminated normally.

Module: CSQUCOPY

Severity: 4

System Action: Processing continues with the next page set.

System Programmer Response: Specify a valid source page set, and resubmit the job.

00C94503

Explanation: A page set that has been the subject of the RESETPAGE function had not previously been through a clean shutdown of MQSeries. Using this page set for subsequent MQSeries processing would lead to data integrity problems.

Module: CSQIECUR

System Action: The current execution unit terminates with abend code X'5C6', and a dump is produced.

System Programmer Response: The problem determination section might help you diagnose the problem.

Contact your IBM support center if you need help.

Problem Determination: Check the page sets that are defined to the MQSeries system. One or more of the page sets has been the subject of a RESETPAGE operation. The RESETPAGE operation should not be run against page sets that are either of the following:

- Fuzzy page set backups
- From an MQSeries system that has terminated abnormally

If you are unable to solve the problem, collect the following diagnostic items and contact your IBM support center:

- MQSeries job log
- System dump resulting from the abend
- Any output from the RESETPAGE job that was previously run
- The MQSeries, CICS, IMS, and OS/390 service levels

00C94503

Appendix G. Notices

This information was developed for products and services offered in the United States. IBM may not offer the products, services, or features discussed in this information in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this information. The furnishing of this information does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:
INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the information. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this information at any time without notice.

Any references in this information to non-IBM documentation or non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those documents or Web sites. The materials for those documents or Web sites are not part of the materials for this IBM product and use of those documents or Web sites is at your own risk.

© Copyright IBM Corp. 1993,1999

Notices

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM United Kingdom Laboratories,
Mail Point 151,
Hursley Park,
Winchester,
Hampshire,
England
SO21 2JN.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Programming License Agreement, or any equivalent agreement between us.

Programming interface information

This book is intended to help you to administer and operate MQSeries for OS/390.

This book also documents General-use Programming Interface and Associated Guidance Information and Product-sensitive Programming Interface and Associated Guidance Information provided by MQSeries for OS/390.

General-use programming interfaces allow the customer to write programs that obtain the services of MQSeries for OS/390.

General-use Programming Interface and Associated Guidance Information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

General-use programming interface

General-use Programming Interface and Associated Guidance Information...

End of General-use programming interface

Product-sensitive programming interfaces allow the customer installation to perform tasks such as diagnosing, modifying, monitoring, repairing, tailoring, or tuning of MQSeries for OS/390. Use of such interfaces creates dependencies on the detailed design or implementation of the IBM software product. Product-sensitive programming interfaces should be used only for these specialized purposes. Because of their dependencies on detailed design and implementation, it is to be expected that programs written to such interfaces may need to be changed in order to run with new product releases or versions, or as a result of service.

Product-sensitive Programming Interface and Associated Guidance Information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

Product-sensitive programming interface

Product-sensitive Programming Interface and Associated Guidance Information...

End of Product-sensitive programming interface

Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, or other countries, or both:

AIX	AS/400	BookManager
C/370	CICS	CICS/ESA
CUA	DB2	DFSMS
DFSMSdss	DFSMS/MVS	IBM
IMS	IMS/ESA	Language Environment
MQ	MQSeries	MVS/DFP
MVS/ESA	NetView	OpenEdition
OS/2	OS/390	OS/400
RACF	RAMQC	RMF
SupportPac	VSE/ESA	VTAM

Lotus, Freelance, and Word Pro are trademarks of Lotus Development Corporation in the United States, or other countries, or both.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and/or other countries.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States and/or other countries.

UNIX is a registered trademark in the United States and/or other countries licensed exclusively through X/Open Company Limited.

Other company, product, or service names, may be the trademarks or service marks of others.

Part 10. Glossary and index

© Copyright IBM Corp. 1993,1999

Glossary of terms and abbreviations

This glossary defines MQSeries terms and abbreviations used in this book. If you do not find the term you are looking for, see the Index or the *IBM Dictionary of Computing*, New York: McGraw-Hill, 1994.

This glossary includes terms and definitions from the *American National Dictionary for Information Systems*, ANSI X3.172-1990, copyright 1990 by the American National Standards Institute (ANSI). Copies may be purchased from the American National Standards Institute, 11 West 42 Street, New York, New York 10036. Definitions are identified by the symbol (A) after the definition.

A

abend reason code. A 4-byte hexadecimal code that uniquely identifies a problem with MQSeries for OS/390. A complete list of MQSeries for OS/390 abend reason codes and their explanations is contained in the *MQSeries for OS/390 Messages and Codes* manual.

active log. See *recovery log*.

adapter. An interface between MQSeries for OS/390 and TSO, IMS, CICS, or batch address spaces. An adapter is an attachment facility that enables applications to access MQSeries services.

address space. The area of virtual storage available for a particular job.

address space identifier (ASID). A unique, system-assigned identifier for an address space.

administrator commands. MQSeries commands used to manage MQSeries objects, such as queues, processes, and namelists.

affinity. An association between objects that have some relationship or dependency upon each other.

alert. A message sent to a management services focal point in a network to identify a problem or an impending problem.

alert monitor. In MQSeries for OS/390, a component of the CICS adapter that handles unscheduled events occurring as a result of connection requests to MQSeries for OS/390.

alias queue object. An MQSeries object, the name of which is an alias for a base queue defined to the local queue manager. When an application or a queue manager uses an alias queue, the alias name is resolved and the requested operation is performed on the associated base queue.

allied address space. See *ally*.

ally. An OS/390 address space that is connected to MQSeries for OS/390.

alternate user security. A security feature in which the authority of one user ID can be used by another user ID; for example, to open an MQSeries object.

APAR. Authorized program analysis report.

application environment. The software facilities that are accessible by an application program. On the OS/390 platform, CICS and IMS are examples of application environments.

application queue. A queue used by an application.

archive log. See *recovery log*.

ARM. Automatic Restart Management

ASID. Address space identifier.

asynchronous messaging. A method of communication between programs in which programs place messages on message queues. With asynchronous messaging, the sending program proceeds with its own processing without waiting for a reply to its message. Contrast with *synchronous messaging*.

attribute. One of a set of properties that defines the characteristics of an MQSeries object.

authorization checks. Security checks that are performed when a user tries to issue administration commands against an object, for example to open a queue or connect to a queue manager.

authorized program analysis report (APAR). A report of a problem caused by a suspected defect in a current, unaltered release of a program.

Automatic Restart Management (ARM). An OS/390 recovery function that can improve the availability of specific batch jobs or started tasks, and therefore result in faster resumption of productive work.

© Copyright IBM Corp. 1993,1999

B

backout. An operation that reverses all the changes made during the current unit of recovery or unit of work. After the operation is complete, a new unit of recovery or unit of work begins. Contrast with *commit*.

basic mapping support (BMS). An interface between CICS and application programs that formats input and output display data and routes multiple-page output messages without regard for control characters used by various terminals.

BMS. Basic mapping support.

bootstrap data set (BSDS). A VSAM data set that contains:

- An inventory of all active and archived log data sets known to MQSeries for OS/390
- A wrap-around inventory of all recent MQSeries for OS/390 activity

The BSDS is required if the MQSeries for OS/390 subsystem has to be restarted.

browse. In message queuing, to use the MQGET call to copy a message without removing it from the queue. See also *get*.

browse cursor. In message queuing, an indicator used when browsing a queue to identify the message that is next in sequence.

BSDS. Bootstrap data set.

buffer pool. An area of main storage used for MQSeries for OS/390 queues, messages, and object definitions. See also *page set*.

C

call back. In MQSeries, a requester message channel initiates a transfer from a sender channel by first calling the sender, then closing down and awaiting a call back.

CCF. Channel control function.

CCSID. Coded character set identifier.

CDF. Channel definition file.

channel. See *message channel*.

channel control function (CCF). In MQSeries, a program to move messages from a transmission queue to a communication link, and from a communication link to a local queue, together with an operator panel interface to allow the setup and control of channels.

channel definition file (CDF). In MQSeries, a file containing communication channel definitions that associate transmission queues with communication links.

channel event. An event indicating that a channel instance has become available or unavailable. Channel events are generated on the queue managers at both ends of the channel.

checkpoint. A time when significant information is written on the log. Contrast with *syncpoint*.

CI. Control interval.

CL. Control Language.

client. A run-time component that provides access to queuing services on a server for local user applications. The queues used by the applications reside on the server. See also *MQSeries client*.

client application. An application, running on a workstation and linked to a client, that gives the application access to queuing services on a server.

client connection channel type. The type of MQI channel definition associated with an MQSeries client. See also *server connection channel type*.

cluster. A network of queue managers that are logically associated in some way.

cluster queue. A queue that is hosted by a cluster queue manager and made available to other queue managers in the cluster.

cluster queue manager. A queue manager that is a member of a cluster. A queue manager may be a member of more than one cluster.

cluster transmission queue. A transmission queue that transmits all messages from a queue manager to any other queue manager that is in the same cluster. The queue is called SYSTEM.CLUSTER.TRANSMIT.QUEUE.

coded character set identifier (CCSID). The name of a coded set of characters and their code point assignments.

command. In MQSeries, an administration instruction that can be carried out by the queue manager.

command prefix (CPF). In MQSeries for OS/390, a character string that identifies the queue manager to which MQSeries for OS/390 commands are directed, and from which MQSeries for OS/390 operator messages are received.

command processor. The MQSeries component that processes commands.

command server. The MQSeries component that reads commands from the system-command input queue, verifies them, and passes valid commands to the command processor.

commit. An operation that applies all the changes made during the current unit of recovery or unit of work. After the operation is complete, a new unit of recovery or unit of work begins. Contrast with *backout*.

completion code. A return code indicating how an MQI call has ended.

connect. To provide a queue manager connection handle, which an application uses on subsequent MQI calls. The connection is made either by the MQCONN call, or automatically by the MQOPEN call.

connection handle. The identifier or token by which a program accesses the queue manager to which it is connected.

context. Information about the origin of a message.

context security. In MQSeries, a method of allowing security to be handled such that messages are obliged to carry details of their origins in the message descriptor.

control interval (CI). A fixed-length area of direct access storage in which VSAM stores records and creates distributed free spaces. The control interval is the unit of information that VSAM transmits to or from direct access storage.

controlled shutdown. See *quiesced shutdown*.

CPF. Command prefix.

Cross Systems Coupling Facility (XCF). Provides the OS/390 coupling services that allow authorized programs in a multisystem environment to communicate with programs on the same or different OS/390 systems.

D

datagram. The simplest message that MQSeries supports. This type of message does not require a reply.

DCI. Data conversion interface.

dead-letter queue (DLQ). A queue to which a queue manager or application sends messages that it cannot deliver to their correct destination.

default object. A definition of an object (for example, a queue) with all attributes defined. If a user defines an object but does not specify all possible attributes for that object, the queue manager uses default attributes in place of any that were not specified.

deferred connection. A pending event that is activated when a CICS subsystem tries to connect to MQSeries for OS/390 before MQSeries for OS/390 has been started.

dequeue. To remove a message from a queue. Contrast with *enqueue*.

distributed application. In message queuing, a set of application programs that can each be connected to a different queue manager, but that collectively constitute a single application.

distributed queue management (DQM). In message queuing, the setup and control of message channels to queue managers on other systems.

DLQ. Dead-letter queue.

DQM. Distributed queue management.

dual logging. A method of recording MQSeries for OS/390 activity, where each change is recorded on two data sets, so that if a restart is necessary and one data set is unreadable, the other can be used. Contrast with *single logging*.

dual mode. See *dual logging*.

dynamic queue. A local queue created when a program opens a model queue object. See also *permanent dynamic queue* and *temporary dynamic queue*.

E

enqueue. To put a message on a queue. Contrast with *dequeue*.

environment. See *application environment*.

ESM. External security manager.

event. See *channel event*, *instrumentation event*, *performance event*, and *queue manager event*.

event data. In an event message, the part of the message data that contains information about the event (such as the queue manager name, and the application that gave rise to the event). See also *event header*.

event header. In an event message, the part of the message data that identifies the event type of the reason code for the event.

event message. Contains information (such as the category of event, the name of the application that caused the event, and queue manager statistics) relating to the origin of an instrumentation event in a network of MQSeries systems.

event queue. The queue onto which the queue manager puts an event message after it detects an event. Each category of event (queue manager, performance, or channel event) has its own event queue.

external security manager (ESM). A security product that is invoked by the OS/390 System Authorization Facility. RACF is an example of an ESM.

F

FIFO. First-in-first-out.

first-in-first-out (FIFO). A queuing technique in which the next item to be retrieved is the item that has been in the queue for the longest time. (A)

forced shutdown. A type of shutdown of the CICS adapter where the adapter immediately disconnects from MQSeries for OS/390, regardless of the state of any currently active tasks. Contrast with *quiesced shutdown*.

G

GCPC. Generalized command preprocessor.

generalized command preprocessor (GCPC). An MQSeries for OS/390 component that processes MQSeries commands and runs them.

Generalized Trace Facility (GTF). An OS/390 service program that records significant system events, such as supervisor calls and start I/O operations, for the purpose of problem determination.

get. In message queuing, to use the MQGET call to remove a message from a queue. See also *browse*.

global trace. An MQSeries for OS/390 trace option where the trace data comes from the entire MQSeries for OS/390 subsystem.

GTF. Generalized Trace Facility.

H

handle. See *connection handle* and *object handle*.

hardened message. A message that is written to auxiliary (disk) storage so that the message will not be lost in the event of a system failure. See also *persistent message*.

I

immediate shutdown. In MQSeries, a shutdown of a queue manager that does not wait for applications to disconnect. Current MQI calls are allowed to complete, but new MQI calls fail after an immediate shutdown has been requested. Contrast with *quiesced shutdown* and *preemptive shutdown*.

in-doubt unit of recovery. In MQSeries, the status of a unit of recovery for which a syncpoint has been requested but not yet confirmed.

initialization input data sets. Data sets used by MQSeries for OS/390 when it starts up.

initiation queue. A local queue on which the queue manager puts trigger messages.

input/output parameter. A parameter of an MQI call in which you supply information when you make the call, and in which the queue manager changes the information when the call completes or fails.

input parameter. A parameter of an MQI call in which you supply information when you make the call.

instrumentation event. A facility that can be used to monitor the operation of queue managers in a network of MQSeries systems. MQSeries provides instrumentation events for monitoring queue manager resource definitions, performance conditions, and channel conditions. Instrumentation events can be used by a user-written reporting mechanism in an administration application that displays the events to a system operator. They also allow applications acting as agents for other administration networks to monitor reports and create the appropriate alerts.

Interactive Problem Control System (IPCS). A component of OS/390 that permits online problem management, interactive problem diagnosis, online debugging for disk-resident abend dumps, problem tracking, and problem reporting.

Interactive System Productivity Facility (ISPF). An IBM licensed program that serves as a full-screen editor and dialog manager. It is used for writing application programs, and provides a means of generating standard

screen panels and interactive dialogues between the application programmer and terminal user.

IPCS. Interactive Problem Control System.

ISPF. Interactive System Productivity Facility.

L

listener. In MQSeries distributed queuing, a program that monitors for incoming network connections.

local definition. An MQSeries object belonging to a local queue manager.

local definition of a remote queue. An MQSeries object belonging to a local queue manager. This object defines the attributes of a queue that is owned by another queue manager. In addition, it is used for queue-manager aliasing and reply-to-queue aliasing.

local queue. A queue that belongs to the local queue manager. A local queue can contain a list of messages waiting to be processed. Contrast with *remote queue*.

local queue manager. The queue manager to which a program is connected and that provides message queuing services to the program. Queue managers to which a program is not connected are called *remote queue managers*, even if they are running on the same system as the program.

log. In MQSeries, a file recording the work done by queue managers while they receive, transmit, and deliver messages, to enable them to recover in the event of failure.

logical unit of work (LUW). See *unit of work*.

M

machine check interrupt. An interruption that occurs as a result of an equipment malfunction or error. A machine check interrupt can be either hardware recoverable, software recoverable, or nonrecoverable.

MCA. Message channel agent.

MCI. Message channel interface.

message. (1) In message queuing applications, a communication sent between programs. See also *persistent message* and *nonpersistent message*. (2) In system programming, information intended for the terminal operator or system administrator.

message channel. In distributed message queuing, a mechanism for moving messages from one queue manager to another. A message channel comprises two message channel agents (a sender at one end and a receiver at the other end) and a communication link. Contrast with *MQI channel*.

message channel agent (MCA). A program that transmits prepared messages from a transmission queue to a communication link, or from a communication link to a destination queue. See also *message queue interface*.

message channel interface (MCI). The MQSeries interface to which customer- or vendor-written programs that transmit messages between an MQSeries queue manager and another messaging system must conform. A part of the MQSeries Framework.

message descriptor. Control information describing the message format and presentation that is carried as part of an MQSeries message. The format of the message descriptor is defined by the MQMD structure.

message priority. In MQSeries, an attribute of a message that can affect the order in which messages on a queue are retrieved, and whether a trigger event is generated.

message queue. Synonym for *queue*.

message queue interface (MQI). The programming interface provided by the MQSeries queue managers. This programming interface allows application programs to access message queuing services.

message queuing. A programming technique in which each program within an application communicates with the other programs by putting messages on queues.

message sequence numbering. A programming technique in which messages are given unique numbers during transmission over a communication link. This enables the receiving process to check whether all messages are received, to place them in a queue in the original order, and to discard duplicate messages.

messaging. See *synchronous messaging* and *asynchronous messaging*.

model queue object. A set of queue attributes that act as a template when a program creates a dynamic queue.

MQI. Message queue interface.

MQI channel. Connects an MQSeries client to a queue manager on a server system, and transfers only MQI calls and responses in a bidirectional manner. Contrast with *message channel*.

MQSC. MQSeries commands.

MQSeries. A family of IBM licensed programs that provides message queuing services.

N

namelist. An MQSeries object that contains a list of names, for example, queue names.

nonpersistent message. A message that does not survive a restart of the queue manager. Contrast with *persistent message*.

null character. The character that is represented by X'00'.

O

object. In MQSeries, an object is a queue manager, a queue, a process definition, a channel, a namelist, or a storage class (OS/390 only).

object descriptor. A data structure that identifies a particular MQSeries object. Included in the descriptor are the name of the object and the object type.

object handle. The identifier or token by which a program accesses the MQSeries object with which it is working.

off-loading. In MQSeries for OS/390, an automatic process whereby a queue manager's active log is transferred to its archive log.

Open Transaction Manager Access (OTMA). A transaction-based, connectionless client/server protocol. It functions as an interface for host-based communications servers accessing IMS TM applications through the OS/390 Cross Systems Coupling Facility (XCF). OTMA is implemented in an OS/390 sysplex environment. Therefore, the domain of OTMA is restricted to the domain of XCF.

OTMA. Open Transaction Manager Access.

output log-buffer. In MQSeries for OS/390, a buffer that holds recovery log records before they are written to the archive log.

output parameter. A parameter of an MQI call in which the queue manager returns information when the call completes or fails.

P

page set. A VSAM data set used when MQSeries for OS/390 moves data (for example, queues and messages) from buffers in main storage to permanent backing storage (DASD).

pending event. An unscheduled event that occurs as a result of a connect request from a CICS adapter.

percolation. In error recovery, the passing along a preestablished path of control from a recovery routine to a higher-level recovery routine.

performance event. A category of event indicating that a limit condition has occurred.

performance trace. An MQSeries trace option where the trace data is to be used for performance analysis and tuning.

permanent dynamic queue. A dynamic queue that is deleted when it is closed only if deletion is explicitly requested. Permanent dynamic queues are recovered if the queue manager fails, so they can contain persistent messages. Contrast with *temporary dynamic queue*.

persistent message. A message that survives a restart of the queue manager. Contrast with *nonpersistent message*.

ping. In distributed queuing, a diagnostic aid that uses the exchange of a test message to confirm that a message channel or a TCP/IP connection is functioning.

platform. In MQSeries, the operating system under which a queue manager is running.

point of recovery. In MQSeries for OS/390, the term used to describe a set of backup copies of MQSeries for OS/390 page sets and the corresponding log data sets required to recover these page sets. These backup copies provide a potential restart point in the event of page set loss (for example, page set I/O error).

preemptive shutdown. In MQSeries, a shutdown of a queue manager that does not wait for connected applications to disconnect, nor for current MQI calls to complete. Contrast with *immediate shutdown* and *quiesced shutdown*.

process definition object. An MQSeries object that contains the definition of an MQSeries application. For example, a queue manager uses the definition when it works with trigger messages.

Q

queue. An MQSeries object. Message queuing applications can put messages on, and get messages from, a queue. A queue is owned and maintained by a queue manager. Local queues can contain a list of messages waiting to be processed. Queues of other types cannot contain messages—they point to other queues, or can be used as models for dynamic queues.

queue manager. (1) A system program that provides queuing services to applications. It provides an application programming interface so that programs can access messages on the queues that the queue manager owns. See also *local queue manager* and *remote queue manager*. (2) An MQSeries object that defines the attributes of a particular queue manager.

queue manager event. An event that indicates:

- An error condition has occurred in relation to the resources used by a queue manager. For example, a queue is unavailable.
- A significant change has occurred in the queue manager. For example, a queue manager has stopped or started.

queuing. See *message queuing*.

quiesced shutdown. (1) In MQSeries, a shutdown of a queue manager that allows all connected applications to disconnect. Contrast with *immediate shutdown* and *preemptive shutdown*. (2) A type of shutdown of the CICS adapter where the adapter disconnects from MQSeries, but only after all the currently active tasks have been completed. Contrast with *forced shutdown*.

quiescing. In MQSeries, the state of a queue manager prior to it being stopped. In this state, programs are allowed to finish processing, but no new programs are allowed to start.

R

RBA. Relative byte address.

reason code. A return code that describes the reason for the failure or partial success of an MQI call.

receiver channel. In message queuing, a channel that responds to a sender channel, takes messages from a communication link, and puts them on a local queue.

recovery log. In MQSeries for OS/390, data sets containing information needed to recover messages, queues, and the MQSeries subsystem. MQSeries for OS/390 writes each record to a data set called the *active log*. When the active log is full, its contents are off-loaded to a DASD or tape data set called the *archive log*. Synonymous with *log*.

relative byte address (RBA). The displacement in bytes of a stored record or control interval from the beginning of the storage space allocated to the data set to which it belongs.

remote queue. A queue belonging to a remote queue manager. Programs can put messages on remote queues, but they cannot get messages from remote queues. Contrast with *local queue*.

remote queue manager. To a program, a queue manager that is not the one to which the program is connected.

remote queue object. See *local definition of a remote queue*.

remote queuing. In message queuing, the provision of services to enable applications to put messages on queues belonging to other queue managers.

reply message. A type of message used for replies to request messages. Contrast with *request message* and *report message*.

reply-to queue. The name of a queue to which the program that issued an MQPUT call wants a reply message or report message sent.

report message. A type of message that gives information about another message. A report message can indicate that a message has been delivered, has arrived at its destination, has expired, or could not be processed for some reason. Contrast with *reply message* and *request message*.

repository. A collection of information about the queue managers that are members of a cluster. This information includes queue manager names, their locations, their channels, what queues they host, and so on.

requester channel. In message queuing, a channel that may be started remotely by a sender channel. The requester channel accepts messages from the sender channel over a communication link and puts the messages on the local queue designated in the message. See also *server channel*.

request message. A type of message used to request a reply from another program. Contrast with *reply message* and *report message*.

RESLEVEL. In MQSeries for OS/390, an option that controls the number of CICS user IDs checked for API-resource security in MQSeries for OS/390.

resolution path. The set of queues that are opened when an application specifies an alias or a remote queue on input to an MQOPEN call.

resource. Any facility of the computing system or operating system required by a job or task. In MQSeries for OS/390, examples of resources are buffer pools, page sets, log data sets, queues, and messages.

resource manager. An application, program, or transaction that manages and controls access to shared resources such as memory buffers and data sets. MQSeries, CICS, and IMS are resource managers.

Resource Recovery Services (RRS). An OS/390 facility that provides 2-phase syncpoint support across participating resource managers.

responder. In distributed queuing, a program that replies to network connection requests from another system.

resynch. In MQSeries, an option to direct a channel to start up and resolve any in-doubt status messages, but without restarting message transfer.

return codes. The collective name for completion codes and reason codes.

rollback. Synonym for *back out*.

RRS. Resource Recovery Services.

S

SAF. System Authorization Facility.

security enabling interface (SEI). The MQSeries interface to which customer- or vendor-written programs that check authorization, supply a user identifier, or perform authentication must conform. A part of the MQSeries Framework.

SEI. Security enabling interface.

sender channel. In message queuing, a channel that initiates transfers, removes messages from a transmission queue, and moves them over a communication link to a receiver or requester channel.

sequential delivery. In MQSeries, a method of transmitting messages with a sequence number so that the receiving channel can reestablish the message sequence when storing the messages. This is required where messages must be delivered only once, and in the correct order.

sequential number wrap value. In MQSeries, a method of ensuring that both ends of a communication link reset their current message sequence numbers at the same time. Transmitting messages with a sequence number ensures that the receiving channel can reestablish the message sequence when storing the messages.

server. (1) In MQSeries, a queue manager that provides queue services to client applications running on a remote workstation. (2) The program that responds to requests for information in the particular two-program, information-flow model of client/server. See also *client*.

server channel. In message queuing, a channel that responds to a requester channel, removes messages from a transmission queue, and moves them over a communication link to the requester channel.

server connection channel type. The type of MQI channel definition associated with the server that runs a queue manager. See also *client connection channel type*.

service interval. A time interval, against which the elapsed time between a put or a get and a subsequent get is compared by the queue manager in deciding whether the conditions for a service interval event have been met. The service interval for a queue is specified by a queue attribute.

service interval event. An event related to the service interval.

session ID. In MQSeries for OS/390, the CICS-unique identifier that defines the communication link to be used by a message channel agent when moving messages from a transmission queue to a link.

shutdown. See *immediate shutdown*, *preemptive shutdown*, and *quiesced shutdown*.

signaling. In MQSeries for OS/390 and MQSeries for Windows 2.1, a feature that allows the operating system to notify a program when an expected message arrives on a queue.

single logging. A method of recording MQSeries for OS/390 activity where each change is recorded on one data set only. Contrast with *dual logging*.

single-phase backout. A method in which an action in progress must not be allowed to finish, and all changes that are part of that action must be undone.

single-phase commit. A method in which a program can commit updates to a queue without coordinating those updates with updates the program has made to resources controlled by another resource manager. Contrast with *two-phase commit*.

SIT. System initialization table.

storage class. In MQSeries for OS/390, a storage class defines the page set that is to hold the messages for a particular queue. The storage class is specified when the queue is defined.

store and forward. The temporary storing of packets, messages, or frames in a data network before they are retransmitted toward their destination.

subsystem. In OS/390, a group of modules that provides function that is dependent on OS/390. For example, MQSeries for OS/390 is an OS/390 subsystem.

supervisor call (SVC). An OS/390 instruction that interrupts a running program and passes control to the supervisor so that it can perform the specific service indicated by the instruction.

SVC. Supervisor call.

switch profile. In MQSeries for OS/390, a RACF profile used when MQSeries starts up or when a refresh security command is issued. Each switch profile that MQSeries detects turns off checking for the specified resource.

synchronous messaging. A method of communication between programs in which programs place messages on message queues. With synchronous messaging, the sending program waits for a reply to its message before resuming its own processing. Contrast with *asynchronous messaging*.

syncpoint. An intermediate or end point during processing of a transaction at which the transaction's protected resources are consistent. At a syncpoint, changes to the resources can safely be committed, or they can be backed out to the previous syncpoint.

sysplex. A multiple OS/390-system environment that allows multiple-console support (MCS) consoles to receive console messages and send operator commands across systems.

System Authorization Facility (SAF). An OS/390 facility through which MQSeries for OS/390 communicates with an external security manager such as RACF.

system.command.input queue. A local queue on which application programs can put MQSeries commands. The commands are retrieved from the queue by the command server, which validates them and passes them to the command processor to be run.

system control commands. Commands used to manipulate platform-specific entities such as buffer pools, storage classes, and page sets.

system initialization table (SIT). A table containing parameters used by CICS on start up.

T

target library high-level qualifier (thlqual). High-level qualifier for OS/390 target data set names.

task control block (TCB). An OS/390 control block used to communicate information about tasks within an address space that are connected to an OS/390 subsystem such as MQSeries for OS/390 or CICS.

task switching. The overlapping of I/O operations and processing between several tasks. In MQSeries for OS/390, the task switcher optimizes performance by allowing some MQI calls to be executed under subtasks rather than under the main CICS TCB.

TCB. Task control block.

temporary dynamic queue. A dynamic queue that is deleted when it is closed. Temporary dynamic queues are not recovered if the queue manager fails, so they can contain nonpersistent messages only. Contrast with *permanent dynamic queue*.

termination notification. A pending event that is activated when a CICS subsystem successfully connects to MQSeries for OS/390.

thlqual. Target library high-level qualifier.

thread. In MQSeries, the lowest level of parallel execution available on an operating system platform.

time-independent messaging. See *asynchronous messaging*.

TMI. Trigger monitor interface.

trace. In MQSeries, a facility for recording MQSeries activity. The destinations for trace entries can include GTF and the system management facility (SMF). See also *global trace* and *performance trace*.

tranid. See *transaction identifier*.

transaction identifier. In CICS, a name that is specified when the transaction is defined, and that is used to invoke the transaction.

transmission program. See *message channel agent*.

transmission queue. A local queue on which prepared messages destined for a remote queue manager are temporarily stored.

trigger event. An event (such as a message arriving on a queue) that causes a queue manager to create a trigger message on an initiation queue.

triggering. In MQSeries, a facility allowing a queue manager to start an application automatically when predetermined conditions on a queue are satisfied.

trigger message. A message containing information about the program that a trigger monitor is to start.

trigger monitor. A continuously-running application serving one or more initiation queues. When a trigger message arrives on an initiation queue, the trigger monitor retrieves the message. It uses the information in the trigger message to start a process that serves the queue on which a trigger event occurred.

trigger monitor interface (TMI). The MQSeries interface to which customer- or vendor-written trigger monitor programs must conform. A part of the MQSeries Framework.

two-phase commit. A protocol for the coordination of changes to recoverable resources when more than one resource manager is used by a single transaction. Contrast with *single-phase commit*.

U

undo/redo record. A log record used in recovery. The redo part of the record describes a change to be made to an MQSeries object. The undo part describes how to back out the change if the work is not committed.

unit of recovery. A recoverable sequence of operations within a single resource manager. Contrast with *unit of work*.

unit of work. A recoverable sequence of operations performed by an application between two points of consistency. A unit of work begins when a transaction starts or after a user-requested syncpoint. It ends either at a user-requested syncpoint or at the end of a transaction. Contrast with *unit of recovery*.

utility. In MQSeries, a supplied set of programs that provide the system operator or system administrator with facilities in addition to those provided by the MQSeries commands. Some utilities invoke more than one function.

X

XCF. Cross Systems Coupling Facility.

MQSeries publications

This section describes the documentation available for all current MQSeries products.

MQSeries cross-platform publications

Most of these publications, which are sometimes referred to as the MQSeries "family" books, apply to all MQSeries Level 2 products. The latest MQSeries Level 2 products are:

- MQSeries for AIX V5.1
- MQSeries for AS/400 V4R2M1
- MQSeries for AT&T GIS UNIX V2.2
- MQSeries for Digital OpenVMS V2.2
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for SINIX and DC/OSx V2.2
- MQSeries for Sun Solaris V5.1
- MQSeries for Tandem NonStop Kernel V2.2
- MQSeries for VSE/ESA V2.1
- MQSeries for Windows V2.0
- MQSeries for Windows V2.1
- MQSeries for Windows NT V5.1

Any exceptions to this general rule are indicated. (Publications that support the MQSeries Level 1 products are listed in "MQSeries Level 1 product publications" on page 529. For a functional comparison of the Level 1 and Level 2 MQSeries products, see the *MQSeries Planning Guide*.)

MQSeries Brochure
The *MQSeries Brochure*, G511-1908, gives a brief introduction to the benefits of MQSeries. It is intended to support the purchasing decision, and describes some authentic customer use of MQSeries.

MQSeries: An Introduction to Messaging and Queuing
MQSeries: An Introduction to Messaging and Queuing, GC33-0805, describes briefly what MQSeries is, how it works, and how it can solve some classic interoperability problems. This book is intended for a more technical audience than the *MQSeries Brochure*.

MQSeries Planning Guide
The *MQSeries Planning Guide*, GC33-1349, describes some key MQSeries concepts, identifies items that need to be considered before MQSeries is installed, including storage requirements, backup and recovery, security, and migration from earlier releases, and specifies hardware and software requirements for every MQSeries platform.

MQSeries Intercommunication
The *MQSeries Intercommunication* book, SC33-1872, defines the concepts of distributed queuing and explains how to set up a distributed queuing network in a variety of MQSeries environments. In particular, it demonstrates how to (1) configure communications to and from a representative sample of MQSeries products, (2) create required MQSeries objects, and (3) create and configure MQSeries channels. The use of channel exits is also described.

MQSeries Clients
The *MQSeries Clients* book, GC33-1632, describes how to install, configure, use, and manage MQSeries client systems.

MQSeries System Administration
The *MQSeries System Administration* book, SC33-1873, supports day-to-day management of local and remote MQSeries objects. It includes topics such as security, recovery and restart, transactional support, problem determination, and the dead-letter queue handler. It also includes the syntax of the MQSeries control commands.

This book applies to the following MQSeries products only:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

MQSeries Command Reference
The *MQSeries Command Reference*, SC33-1369, contains the syntax of the MQSC commands, which are used by MQSeries system operators and administrators to manage MQSeries objects.

MQSeries Programmable System Management
The *MQSeries Programmable System Management* book, SC33-1482, provides both reference and guidance information for users of MQSeries events, Programmable Command Format (PCF) messages, and installable services.

MQSeries Messages
The *MQSeries Messages* book, GC33-1876, which describes "AMQ" messages issued by MQSeries, applies to these MQSeries products only:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1
- MQSeries for Windows V2.0
- MQSeries for Windows V2.1

© Copyright IBM Corp. 1993,1999

This book is available in softcopy only.

MQSeries Application Programming Guide
The *MQSeries Application Programming Guide*, SC33-0807, provides guidance information for users of the message queue interface (MQI). It describes how to design, write, and build an MQSeries application. It also includes full descriptions of the sample programs supplied with MQSeries.

MQSeries Application Programming Reference
The *MQSeries Application Programming Reference*, SC33-1673, provides comprehensive reference information for users of the MQI. It includes: data-type descriptions; MQI call syntax; attributes of MQSeries objects; return codes; constants; and code-page conversion tables.

MQSeries Application Programming Reference Summary
The *MQSeries Application Programming Reference Summary*, SX33-6095, summarizes the information in the *MQSeries Application Programming Reference* manual.

MQSeries Using C++
MQSeries Using C++, SC33-1877, provides both guidance and reference information for users of the MQSeries C++ programming-language binding to the MQI. MQSeries C++ is supported by these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for AS/400 V4R2M1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for OS/390 V2.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

MQSeries C++ is also supported by MQSeries clients supplied with these products and installed in the following environments:

- AIX®
- HP-UX
- OS/2®
- Sun Solaris
- Windows NT®
- Windows® 3.1
- Windows 95 and Windows 98

MQSeries Using Java®
MQSeries Using Java, SC34-5456, provides both guidance and reference information for users of the MQSeries Bindings for Java and the MQSeries Client for Java. MQSeries Java is supported by these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1

MQSeries Administration Interface Programming Guide and Reference
The *MQSeries Administration Interface Programming Guide and Reference*, SC34-5390, provides information for users of the MQAI. The MQAI is a programming interface that simplifies the way in which applications manipulate Programmable Command Format (PCF) messages and their associated data structures.

This book applies to the following MQSeries products only:

MQSeries for AIX V5.1
MQSeries for HP-UX V5.1
MQSeries for OS/2 Warp V5.1
MQSeries for Sun Solaris V5.1
MQSeries for Windows NT V5.1

MQSeries Queue Manager Clusters
MQSeries Queue Manager Clusters, SC34-5349, describes MQSeries clustering. It explains the concepts and terminology and shows how you can benefit by taking advantage of clustering. It details changes to the MQI, and summarizes the syntax of new and changed MQSeries commands. It shows a number of examples of tasks you can perform to set up and maintain clusters of queue managers.

This book applies to the following MQSeries products only:

MQSeries for AIX V5.1
MQSeries for HP-UX V5.1
MQSeries for OS/2 Warp V5.1
MQSeries for OS/390 V2.1
MQSeries for Sun Solaris V5.1
MQSeries for Windows NT V5.1

MQSeries platform-specific publications

Each MQSeries product is documented in at least one platform-specific publication, in addition to the MQSeries family books.

MQSeries for AIX

MQSeries for AIX Version 5 Release 1 Quick Beginnings, GC33-1867

MQSeries for AS/400®

MQSeries for AS/400 Version 4 Release 2.1 Administration Guide, GC33-1956

MQSeries for AS/400 Version 4 Release 2 Application Programming Reference (RPG), SC33-1957

MQSeries for AT&T GIS UNIX®

MQSeries for AT&T GIS UNIX Version 2 Release 2 System Management Guide, SC33-1642

MQSeries for Digital OpenVMS

MQSeries for Digital OpenVMS Version 2 Release 2 System Management Guide, GC33-1791

MQSeries for Digital UNIX

MQSeries for Digital UNIX Version 2 Release 2.1 System Management Guide, GC34-5483

MQSeries for HP-UX

MQSeries for HP-UX Version 5 Release 1 Quick Beginnings, GC33-1869

MQSeries for OS/2 Warp

MQSeries for OS/2 Warp Version 5 Release 1 Quick Beginnings, GC33-1868

MQSeries for OS/390

MQSeries for OS/390 Version 2 Release 1 Licensed Program Specifications, GC34-5377

MQSeries for OS/390 Version 2 Release 1 Program Directory

MQSeries for OS/390 Version 2 Release 1 System Management Guide, SC34-5374

MQSeries for OS/390 Version 2 Release 1 Messages and Codes, GC34-5375

MQSeries for OS/390 Version 2 Release 1 Problem Determination Guide, GC34-5376

MQSeries link for R/3

MQSeries link for R/3 Version 1 Release 2 User's Guide, GC33-1934

MQSeries for SINIX and DC/OSx

MQSeries for SINIX and DC/OSx Version 2 Release 2 System Management Guide, GC33-1768

MQSeries for Sun Solaris

MQSeries for Sun Solaris Version 5 Release 1 Quick Beginnings, GC33-1870

MQSeries for Tandem NonStop Kernel

MQSeries for Tandem NonStop Kernel Version 2 Release 2 System Management Guide, GC33-1893

MQSeries for VSE/ESA™

MQSeries for VSE/ESA Version 2 Release 1 Licensed Program Specifications, GC34-5365

MQSeries for VSE/ESA Version 2 Release 1 System Management Guide, GC34-5364

MQSeries for Windows

MQSeries for Windows Version 2 Release 0 User's Guide, GC33-1822
MQSeries for Windows Version 2 Release 1 User's Guide, GC33-1965

MQSeries for Windows NT

MQSeries for Windows NT Version 5 Release 1 Quick Beginnings, GC34-5389

MQSeries for Windows NT Using the Component Object Model Interface, SC34-5387

MQSeries LotusScript Extension, SC34-5404

MQSeries Level 1 product publications

For information about the MQSeries Level 1 products, see the following publications:

MQSeries: Concepts and Architecture, GC33-1141

MQSeries Version 1 Products for UNIX Operating Systems Messages and Codes, SC33-1754

MQSeries for UnixWare Version 1 Release 4.1 User's Guide, SC33-1379

Softcopy books

Most of the MQSeries books are supplied in both hardcopy and softcopy formats.

BookManager® format: The MQSeries library is supplied in IBM BookManager format on a variety of online library collection kits, including the *Transaction Processing and Data* collection kit, SK2T-0730. You can view the softcopy books in IBM BookManager format using the following IBM licensed programs:

BookManager READ/2
BookManager READ/6000
BookManager READ/DOS
BookManager READ/MVS
BookManager READ/VM
BookManager READ for Windows

HTML format: Relevant MQSeries documentation is provided in HTML format with these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1 (compiled HTML)
- MQSeries link for R/3 V1.2

The MQSeries books are also available in HTML format from the MQSeries product family Web site at:

`http://www.software.ibm.com/ts/mqseries/`

Portable Document Format (PDF): PDF files can be viewed and printed using the Adobe Acrobat Reader.

If you need to obtain the Adobe Acrobat Reader, or would like up-to-date information about the platforms on which the Acrobat Reader is supported, visit the Adobe Systems Inc. Web site at:

```
http://www.adobe.com/
```

PDF versions of relevant MQSeries books are supplied with these MQSeries products:

- MQSeries for AIX V5.1
- MQSeries for HP-UX V5.1
- MQSeries for OS/2 Warp V5.1
- MQSeries for Sun Solaris V5.1
- MQSeries for Windows NT V5.1
- MQSeries link for R/3 V1.2

PDF versions of all current MQSeries books are also available from the MQSeries product family Web site at:

```
http://www.software.ibm.com/ts/mqseries/
```

PostScript format: The MQSeries library is provided in PostScript (.PS) format with many MQSeries Version 2 products. Books in PostScript format can be printed on a PostScript printer or viewed with a suitable viewer.

Windows Help format: The *MQSeries for Windows User's Guide* is provided in Windows Help format with MQSeries for Windows Version 2.0 and MQSeries for Windows Version 2.1.

MQSeries information available on the Internet

MQSeries Web site

The MQSeries product family Web site is at:

```
http://www.software.ibm.com/ts/mqseries/
```

By following links from this Web site you can:

- Obtain latest information about the MQSeries product family.
- Access the MQSeries books in HTML and PDF formats.
- Download MQSeries SupportPacs.

Related publications

For information about other products that are referred to in this book, see the following books:

OS/390

- *MVS IPCS Customization*, GC28-1755
- *MVS Initialization and Tuning Reference*, SC28-1752
- *MVS Planning: Workload Management*, GC28-1761
- *MVS Programming: Callable Services for High Level Languages*, GC28-1768
- *MVS Routing and Descriptor Codes*, GC28-1778
- *MVS Setting up a Sysplex* GC28-1779
- *MVS System Commands*, GC28-1781
- *MVS System Management Facilities (SMF)*, GC28-1783
- *MVS Diagnosis: Tools and Service Aids*, LY28-1085
- *OpenEdition Planning*, SC28-1890
- *MVS Resource Measurement Facility User's Guide*, SC28-1916
- *MVS Planning: APPC/MVS Management*, GC28-1807

CICS Transaction Server for OS/390

- *XRF Guide*, SC33-0661
- *Migration Guide*, GC33-1571
- *System Definition Guide*, SC33-1682
- *Customization Guide*, SC33-1683
- *Resource Definition Guide*, SC33-1684
- *Operations and Utilities Guide*, SC33-1685
- *CICS-Supplied Transactions*, SC33-1686
- *Application Programming Guide*, SC33-1687
- *Messages and Codes*, GC33-1694
- *Intercommunication Guide*, SC33-1695
- *Recovery and Restart Guide*, SC33-1698
- *Performance Guide*, SC33-1699
- *RACF Security Guide*, SC33-1701
- *Internet and External Interfaces Guide*, SC33-1944

CICS for MVS/ESA Version 4

- *XRF Guide*, SC33-0661
- *Migration Guide*, GC33-1162
- *System Definition Guide*, SC33-1164
- *Customization Guide*, SC33-1165
- *Resource Definition Guide*, SC33-1166
- *Operations and Utilities Guide*, SC33-1167
- *CICS-Supplied Transactions*, SC33-1168
- *Application Programming Guide*, SC33-1169
- *Messages and Codes*, SC33-1177
- *Intercommunication Guide*, SC33-1181
- *Recovery and Restart Guide*, SC33-1182
- *Performance Guide*, SC33-1183
- *CICS-RACF Security Guide*, SC33-1185

IMS

- *Customization Guide*, SC26-8020
- *Operator's Reference*, SC26-8030
- *Administration Guide: System*, SC26-8013
- *Open Transaction Manager Access Guide*, SC26-8026
- *Messages and Codes*, SC26-8028
- *Failure Analysis Structure Tables (FAST) for Dump Analysis*, LY27-9621

DFSMS/MVS

- *Access Method Services for VTAM*, SC26-4905
- *Access Method Services for the Integrated Catalog Facility*, SC26-4906
- *DFSMSdds Storage Administration Guide*,SC26-4930
- *Macro Instructions for Data Sets*, SC26-4913

Security Server

- *Security Server (RACF) Security Administrator's Guide*, SC28-1915
- *Security Server (RACF) Auditor's Guide*, SC28-1916
- *Security Server (RACF) System Programmer's Guide*, SC28-1913
- *Security Server (RACF) External Security Interface (RACROUTE) Macro Reference*, GC28-1922

Other products

- *Data Facility Data Set Services: Reference*, SC26-4389
- *DFP Storage Administration Reference*, SC26-4566
- *ISPF Dialog Developer's Guide and Reference*, SC28-1273
- *TCP/IP OpenEdition: Planning and Release Guide*, SC31-8303
- *MQSeries Workflow for OS/390: Customization and Administration*, SC33-7030
- *MQSeries Workflow: Concepts and Architecture*, GH12-6285
- *Performance Reporter for OS/390 Administration Guide*, SH19-6816-03
- *Data Facility Hierarchical Storage Manager User's Guide*, SH35-0093
- *APPC Security: MVS/ESA, CICS/ESA, and OS/2*, GG24-3960 (redbook)

Related publications

Index

Special Characters

&ZSEL 94
% character in RACF profiles 411

Numerics

00C94503 code 507

A

abend
  application option of SSM entry 180
  CICS transaction disconnecting 151
  starting after 201
  states 286
  U3042 183
abnormal termination 283, 286
access
  if incorrect 475
  restricting by using alias queues 418
access method services (AMS)
  BSDS definition 312
  defining page sets 63
  deleting damaged BSDS 359
  new active log definition 327
  renaming damaged BSDS 359
  REPRO 340
accounting
  eye catcher string 398
  introduction 371
  message manager 398
  rules for data collection 376
  sample SMF records 400
  SMF trace 374
  starting automatically 74
ACS user-exit filter, archive log data sets 317
ACTCHL parameter of CSQ6CHIP 87
active log
  copy to archive 20
  CSQJU003, change log inventory utility 262
  data set
    copying 327
    copying with AMS REPRO statement 340
    off-loaded to archive log 308
    VSAM linear 307
  defining in BSDS 327
  delays in off-loading 351
  deleting from BSDS 328
  description 305
  dual logging 309
  enlarging 328
  input buffer size (INBUFF) 76
active log *(continued)*
  log print utility (CSQ1LOGP) 272
  number of buffers per write 78
  off-loading 309
  out of space 351
  output buffer
    number filled (WRTHRSH) 78
    size (OUTBUFF) 77
  printing (CSQ1LOGP) 272
  recording existing in BSDS 328
  recovery plan, problems 346
  single or dual (TWOACTV) 77
  space allocation
    primary (PRIQTY) 82
    secondary (SECQTY) 84
    units (ALCUNIT) 79
  status 326
  stopped data set effect 347, 351
  truncation 310
  writing 309
active log problem
  both copies are damaged 348
  delays in off-loading 351
  dual logging lost 346
  log stopped 347
  one copy is damaged 348
  out of space 351
  read I/O errors 349
  write I/O errors 349
ADAPS parameter of CSQ6CHIP 88
adapter
  CICS 115—161
  illustration 8
  IMS 165—167, 186
  introduction 8, 22
adapter subtasks, number to use for channel initiator 88
adapters and dispatchers, total number 90
address space
  abend 198
  canceling for MQSeries 202
  CICS adapter 117
  CICS, user ID 442
  connection security 449
  for MQSeries 22
  IMS adapter 165
  IMS control region 171
  IMS, user ID 442
  user ID 439, 440
administering
  by writing programs 217
  introduction 28

© Copyright IBM Corp. 1993,1999

Index

administration programs 217, 220
administrator commands 19
age, specifying for OTMA 73
ALCUNIT parameter of CSQ6ARVP 79
alert monitor 118
alias queue 10
  system default 55
alias queues
  command resource checking 432
  restricting access using 418
  security 417, 421
  undelivered messages 421
ALL, attribute of DISPLAY SECURITY 453
ALTER commands, security 433
alter queue attributes, security 433
ALTER SECURITY command 451
alternate user ID 441
alternate user ID, distributed queuing 439
alternate user security 406, 425
AMS (access method services)
  BSDS definition 312
  defining page sets 63
  deleting damaged BSDS 359
  new active log definition 327
  renaming damaged BSDS 359
  REPRO 340
AMS REPRO, backing up and recovering page sets 340
APF authorization of load libraries 47
API-crossing exit
  defining 120
  enable or disable 138
  including the load module 127
API-resource security 405
  quick reference 429
  RESLEVEL 435
APPC
  LU name 89
  LUADD 89
  maximum number of current channels 89
  restart interval after failure 88
APPC, applying service 487
APPCPMxx 89
application
  data 4
  environments 4
  in MQSeries 14
  program 23, 305
    batch adapter 23
    CICS adapter 24
    command format 130
    CQKC DISPLAY 148
    IMS adapter 25
    issuing commands from 217
    recovery 305
  starting automatically 14
application *(continued)*
  time-independent 3
  types 14
application access control 460
application stubs, coexistence with earlier versions 104
applid node name 127
archive initialization parameters, setting 69
archive log
  ACS user-exit filter 317
  adding information to BSDS (NEWLOG) 264, 329
  BSDS copies 312
  cataloging (CATALOG) 82
  compacting (COMPACT) 82
  create 20
  CSQJU003, change log inventory utility 262
  data set
    name prefix 80
    off-loading 308
    password 267
    password protection (PROTECT) 83
    time stamp (TSTAMP) 84
  deleting 323
  deleting information from the BSDS 266, 329
  device type (UNIT) 84
  discarding records 323
  dual copies 312
  dynamic allocation of data sets 316
  information in BSDS 311
  input buffer size (INBUFF) 76
  maximum number in BSDS (MAXARCH) 76
  maximum number of volumes (MAXALLC) 76
  mounting, WTOR (ARCWTOR) 81
  output buffer size (OUTBUFF) 77
  password, changing 329
  printing (CSQ1LOGP) 272
  quiesce time (QUIESCE) 84
  recording in BSDS 329
  recovery plan 353
  retention period (ARCRETN) 80
  route codes (ARCWRTC) 80
  single or dual (TWOARCH) 78
  space allocation
    block size (BLKSIZE) 81
    primary (PRIQTY) 82
    secondary (SECQTY) 84
    units (ALCUNIT) 79
ARCHIVE LOG command
  security 433
archive log problem
  allocation problems 353
  insufficient DASD for off-load 354
  read I/O errors during restart 355
  write I/O errors during off-load 353
ARCHIVE LOG, command 321

archive parameter
  default 79
  setting 79
ARCHIVE, utility function (CSQJU003) 267
archiving 305, 316, 321
  See also archive log
  controlling, OFFLOAD parameter of CSQ6LOGP 77
  log data sets 310, 316
  SMS 317
ARCPFX1 parameter of CSQ6ARVP 80
ARCPFX2 parameter of CSQ6ARVP 80
ARCRETN parameter of CSQ6ARVP 80
ARCWRTC parameter of CSQ6ARVP 80
ARCWTOR parameter of CSQ6ARVP 81
ARM
  activating a policy 302
  couple data sets 300
  defining a policy 301
  introduction 300
  network considerations 302
  policy sample 301
  registering with 302
ARM (automatic restart manager)
  coexistence 97
  introduction 26
  LUADD for channel initiator 89
  migration 97
  subsystem name table 45
attributes of queues 9
audit, security 447
auditing RESLEVEL 447
authority, alternate user 406
auto-reconnect, CICS adapter 119
Automatic Restart Manager
  See ARM
automatic restart manager (ARM)
  coexistence 97
  introduction 26
  LUADD for channel initiator 89
  migration 97
  subsystem name table 45
automating starting of CKTI 456
availability, recovery planning 313

B

back out 280
backing up
  logs, frequency 314
  object definitions 315
  page sets 339, 340
  queues 313
base function 33
batch
  example security scenario 468
Batch adapter
  See Batch/TSO adapter
batch application, improving portability 92
batch assembler, IVP 105
batch message program (BMP)
  See BMP (batch message program)
batch utility
  See MQSeries utility program (CSQUTIL)
batch, testing customization 105
Batch/TSO adapter 23
  connection security 414
  CSQBSTUB stub program 23
  installing 92
  maximum number of connections
    background (IDBACK) 71
    foreground (IDFORE) 71
    total (CTHREAD) 70
  OS/390 SNAP dump 92
  RESLEVEL 435
  security checking 435
  user IDs, security checking 441
Batch/TSO RRS adapter
  See RRS adapter
bibliography 527
blank fields in operations and control panels 215
blank user IDs 446
BLKSIZE parameter of CSQ6ARVP 81
BLSCECTX SYS1.PARMLIB member 95
BMP (batch message program) 180
BookManager 529
bootstrap data set (BSDS)
  introduction 18
BSDS (bootstrap data set) 305
  changing log inventory utility (CSQJU003) 329
  defining 311
  dual copies 311
  errors 356
  introduction 18
  managing 321, 329
  print log map utility (CSQJU004) 271
  recovery 330
  registers log data 311
  time stamps 325
  what it is for 311
BSDS problem
  both copies are damaged 357
  does not agree with log 357
  error while opening 356
  I/O error 359
  out of synchronization 359
  unequal time stamps 358
buffer
  illustration 17
  input buffer size (INBUFF) 76
  maximum number 17
  number filled before write to log 78

buffer *(continued)*
output buffer size (OUTBUFF) 77
output log 308
setting up 17
size 17
what they are 17
buffer manager
suppressing console messages 96
buffer manager statistics 384
interpretation 385
buffer pool
defining 17, 20, 54
illustration 17
performance implications 17
buffer pools
management 385
size 386
statistics 386
building messages 222
bypass of syncpoint 281

C

C and C++, testing customization 108
callable services, applying service 487
canceling MQSeries address space 202
CARTs 196
CATALOG parameter of CSQ6ARVP 82
catalog, archive log (CATALOG) 82
CCSID (coded character set identifier)
queue manager (QMCCSID) 73
CCSID, keyword of COMMAND function 245
change log inventory utility (CSQJU003) 262—270
adding new active log 327, 352
BSDS preparation 61
change BSDS 325, 327
changes for active logs 327
changes for archive logs 328
functions
ARCHIVE 267, 331
CHECKPT 269
conditional restart 268
CRESTART 268
DELETE 266
HIGHRBA 270
NEWLOG 264, 327, 329
setting checkpoint records 269
updating the highest written log RBA 270
invoking 262
log data set preparation 61
managing log data sets 311
multiple statement operation 263
time stamp in BSDS 359
CHANGE SUBSYS, command of IMS 175, 179
channel
controlling 21
channel *(continued)*
introduction 13
maximum number active 87
maximum number current 88
maximum number of current LU 6.2 89
maximum number of current TCP/IP 89
queues 56
sample definitions 58
storage requirement 29
suppressing console messages 96
system default 55
user ID 439
channel definitions (CICS mover) 492
channel file definition (CSQKCDF) 491
channel initiator
controlling 21
CSQ6CHIP 87
defining the procedure 50
installation verification program 108
maximum number of connections (CTHREAD) 70
migration considerations 99
restarting with ARM 302
sample definitions 60
tailoring the parameter module 86
channel initiator parameter module, invoking 87
channel initiator parameters
default 87
displaying settings 86
migration considerations 97
channel listener, controlling
channel reply information queue 11
channel sequence number queue 493
channel synchronization queue 11
channel-initiation queue 11
checkpoint
number of log records (LOGLOAD) 72
records 307
checkpoint records, setting 269
CHECKPT, utility function (CSQJU003) 269
Chinese language feature 39, 233
CI (control interval), description 308
description 316
CICS
address space user ID, security checking 440
CICS mover
See distributed queuing using CICS ISC
completing the connection 127
connection ID 289
definition of term xv
example security scenario 468
in-doubt units of recovery 289
monitoring facility 375
MQSeries-CICS bridge 25
recovery considerations when using MQSeries 318
related publications 531
resources for distributed queuing 491

CICS *(continued)*
system administration and operation 25
system definition (CSD) data set 124
terminating 151
testing customization 108
units of recovery 292
user IDs, security checking 442
CICS adapter 57, 115—161
address space 117
administrative functions 115
alert monitor 118
API-crossing exit 120
application programming 24
auto-reconnect 119
CKTI task initiator 119
commands 129
components 117
connect program (CSQCQCON) 135
connection security 414
consistency with MQSeries 281
control panels 132—148
conventions 123
CSQ4INYG object sample 57
CSQCSTUB stub program 117, 127
customizing 128
deferred connection 118
disconnect program 137
displaying CICS tasks 141
displaying connection details 141
displaying status 148
forced shutdown 150, 151
initiation queue, defining 58
installing 124
introduction 24
maximum number of connections (CTHREAD) 70
MQI support 116
object sample 57
operation of
control functions 115
control panels 132
displaying current tasks 147
displaying instances of CKTI 146
lowercase queue names 134
modifying a connection 138
starting a connection 133
starting CKTI 142
stopping CKTI 144
orderly shutdown 151
overview 115
passing parameters 130
pending events 118
performance 121
connection statistics 122
multi-tasking 120
PLTPI program, writing 128
quiesced shutdown 150
CICS adapter *(continued)*
recovery 289
RESLEVEL 435
resource definition 124
restart, what happens 297
restrictions 119
security 456
authorization 455
checking 435
for transactions 455
PLTPI 456
PLTSD 456
terminal user IDs 456
shutting down a connection 150
starting a connection 133
statistics 372
system definition 126
task initiation program (CSQCSSQ) 143
terminating 151
testing customization 108
transaction authority 455
transaction services
security support 455
syncpoint support 281
two-phase commit 122, 282
user IDs for security 435, 440, 456
VTAM node name, connection ID in system initialization tables 127
CICS bridge
customizing 158
definition 153
migration considerations 97
prerequisite APARs 158
security 457
starting 160
stopping 161
system configuration 154
tuning considerations 160
when to use 153
CICS mover
See distributed queuing using CICS ISC
CICS system definition data set (CSD)
updating for CICS 124
CICS Transaction Server for OS/390
See CICS
CKBM, security 455
CKCN, security 455
CKDL, security 455
CKDP, security 455
CKMQ, transient data queue 493
CKQC
authorization 455
CICS adapter transaction 115
DISPLAY command 148
MODIFY command 139
security 455

Index

CKQC *(continued)*
  START command 134
  STARTCKTI command 143
  STOP command 137
  STOPCKTI command 144
CKQQ, transient data queue 131
CKRS, security 455
CKRT, security 455
CKSD, security 455
CKSG, MCA transaction 456
CKSQ, security 455
CKTI transaction 119
  automating starting of 456
  displaying 146
  propagating user IDs 456
  security 455, 456
  starting 142
  stopping 144, 145
class of service 26
client
  channels 13
  sample definitions 58
client attachment feature 33
client channel definition file, generating 245
close options, dynamic queues 420
cluster
  coexistence 98
  command queue 11
  commands 21
  introduction 6
  joining 21
  leaving 21
  migration 98
  queues 10, 57
  queues required 11
  repository queue 11
  sample definitions 59
  transmission queue 12
cluster support
  security considerations 465
clusters and ARM 303
CMDUSER parameter of CSQ6SYSP 70
COBOL, testing customization 108
coded character set identifier (CCSID)
  queue manager (QMCCSID) 73
coded character set identifier, queue manager (QMCCSID) 73
cold start 368
command
  administrator 19
  for the CICS adapter 129
  introduction 19
  issuing
    from initialization input data sets 52
  methods of issuing 19
  processor 12, 219
command *(continued)*
  queue manager 8
  queues required 12
  resource checking summary table 433
  resource security 407
  resource security profiles 432
  security 407
  security profiles 431
  summary table 19
  system control, summary 20
command and response tokens 196
command prefix (CPF)
  displaying existing 43
  naming convention 43
  valid characters 43
command prefix string
  See CPF (command prefix)
command queue, clustering 11
command server 12, 219—232
  controlling 20
  restart 219
  sending commands to 222
  starting 219
  stopping 219
COMMAND, CSQUTIL function 244
  MAKECLNT keyword 247
  MAKEDEF keyword 246
commands
  See also MQSeries, commands
  DISPLAY 372
  examples of 226
  in request messages 222
  issuing 195, 196
    from CSQUTIL 197, 244
    from system-command input queue 217
    from the OS/390 console 196
    from TSO panels 197
  no reply to 232
  operator 197
  remote queue manager 220
  STOP QMGR 202
  user messages
    from DEFINE 227
    from DEFINE QLOCAL 229
    from DEFINE THREAD 228
    from DELETE 227
    from DISPLAY 227
    from DISPLAY commands 228
commit 281
commit point
  See point of consistency
communication protocol, choosing 40
COMPACT parameter of CSQ6ARVP 82
compacting archive logs (COMPACT) 82
conditional restart 268

connection parameters, setting 69
connection security 405, 449, 459
connections
  controlling CICS 128
  controlling IMS 175
  displaying details of
    CICS 141
    IMS 180
  maximum number
    Batch/TSO, background (IDBACK) 71
    Batch/TSO, foreground (IDFORE) 71
    total (CTHREAD) 70
  monitoring the activity on 180
  profiles for security 414
  starting from
    CICS adapter control panel 133
    CICS application program 135
    CICS command line 134
    IMS 176
    PLTPI program 125
  statistics for CICS adapter 122
  stopping from
    CICS adapter control panel 136
    CICS application program 137
    CICS command line 137
    IMS 175
  to IMS, monitoring activity 180—181
consistency of data, abnormal termination 283
consistency with batch, CICS, IMS, and TSO 281
console messages, suppressing 96
context security 406, 427
continuous operation, recovery planning 313
control functions, CICS adapter 115
control interval
  See CI (control interval), description
control panels for the CICS adapter 132
control region
  See CTL (IMS control region)
controlling application connections 128
controls and options, security 404
coordinator, recovery 281
copy files
  general-use programming interface 480
COPY, CSQUTIL function 252
copying
  messages from a queue (COPY) 251
  page sets
    COPYPAGE function 239
    RESETPAGE function 241
  queues to a data set (COPY) 252
  queues to a data set (SCOPY) 255
COPYPAGE, CSQUTIL function 239
CorrelId field, administration programs 224
COUNT field, user messages 226
couple data sets, ARM 300
CPF (command prefix)
  displaying existing 43
  establishing 41
  issuing commands 196
  naming convention 43
  registering 44
  registration 44
  running in a sysplex 44
  scope 44
  valid characters 42, 43
CRESTART, utility function (CSQJU003) 268
CSA storage requirement 28
CSD (CICS system definition data set) 124
CSQ1LOGP
  See log print utility (CSQ1LOGP)
CSQ2020E message 190
CSQ4BSDS, sample 330, 360
CSQ4D100, customization 491
CSQ4DISP, display sample 54, 59
CSQ4DISQ, distributed queuing sample 54
CSQ4DISQ, distributed queuing using CICS ISC sample 59
CSQ4INP1 sample initialization data set 54
CSQ4INPX sample initialization data set 54
CSQ4INSG sample initialization data set 54
CSQ4INSX sample initialization data set 54
CSQ4INSX system object sample 56
CSQ4INYC sample initialization data set 54
CSQ4INYD sample initialization data set 54
CSQ4INYG sample initialization data set 54
CSQ4IVP, installation verification program 54, 59
CSQ4IVP1
  RACF commands 106, 109
CSQ4IVP1 installation verification program 105
CSQ4IVPX 108
  example output 111
CSQ4MPFL information message suppression sample 96
CSQ4MSTR sample startup procedure 49
CSQ4PAGE page set sample 63
CSQ6ARVP macro 68, 79
CSQ6ARVP, macro 316
CSQ6CHIP 87
CSQ6LOGP macro 68, 76
CSQ6SYSP macro 68, 69
CSQ6SYSP, macro 376
CSQBDEFV 92
CSQBSTUB for Batch/TSO adapter 23
CSQBSTUB for IMS adapter 25
CSQCAPX sample API-crossing exit program 120
CSQCCODF sample PLTPI program 125
CSQCDSC CICS adapter disconnect program 137
CSQCQCON CICS adapter connect program 135
CSQCRST CICS adapter reset program 140
CSQCSSQ CICS adapter task initiation program 143, 145

CSQCSTUB for CICS adapter 24, 117, 127
CSQI029I message 505
CSQI049I message 505
CSQINP1
  commands 52
  sample data set 54
  security 407, 441
CSQINP2
  commands 52
  security 407, 441
  updating 127
  using 55
CSQINPX
  security 407, 463
  specifying a response time 53
CSQINPx data sets, issuing commands from 52
CSQJ004I message 345, 346
CSQJ030E message 345, 347
CSQJ100E message 345, 356
CSQJ102E message 345, 348, 357
CSQJ103E message 345, 353
CSQJ105E message 345, 349
CSQJ106E message 345, 349
CSQJ107E message 345, 359
CSQJ108E message 359
CSQJ110E message 345, 351
CSQJ111A message 345, 351
CSQJ114I message 354
CSQJ115E message 353
CSQJ117E message 345
CSQJ119E message 345
CSQJ120E message 345, 358
CSQJ122E message 345, 359
CSQJ124E message 349
CSQJ126E message 346, 359
CSQJ128E message 346, 354
CSQJ160I 505
CSQJ161I 505
CSQJ232E message 345
CSQJU003
  See change log inventory utility (CSQJU003)
CSQJU004
  See print log map utility (CSQJU004)
CSQKCDF, channel file definition 491
CSQOREXX 94
CSQP004E message 346, 361
CSQP018I message 198
CSQP019I message 198
CSQP021I message 505
CSQQ001I message 346
CSQQ002E message 346
CSQQ003E message 346
CSQQ004E message 346
CSQQ005E message 346
CSQQ006E message 346
CSQQ007E message 346
CSQQDEFV, subsystem definition table 167—172
CSQQDEFX, macro 171
CSQQSTUB for IMS adapter 25
CSQQSTUB, for IMS adapter 165
CSQQTRMN program
  starting 183
CSQQTRMN transaction 166
  stopping 184
CSQQxxx messages 364
CSQR020I message 346, 506
CSQR021D message 506
CSQR022I message 506
CSQR023I message 506
CSQR029I message 506
CSQR030I message 506
CSQR031I message 506
CSQR032I message 506
CSQR033I message 506
CSQSNAP 92, 116, 165
CSQU159E message 507
CSQUTIL
  See also MQSeries utility program (CSQUTIL)
  RESLEVEL 435
  security checking 435
CSQWDMP 95
CSQWDPRD 95
CSQXPARM
  description 86
  displaying settings 86
CSQZPARM
  creating 68
  displaying settings 68
  specifying an alternate 200
CTHREAD parameter of CSQ6SYSP 70
CTL (IMS control region) 176, 180
CURRCHL parameter of CSQ6CHIP 88
customizing 33
  before you start 37
  CICS adapter 128
  CICS bridge 158
  IMS bridge 187
  initialization input data sets 52
  introduction 27, 37
  IPL 37
  overview 33
  planning 33
  security 454
  tasks 37
  testing 105
  when migrating from previous versions 97

D

DASD 17, 308, 316
  performance 385

Data Facility Hierarchical Storage Manager
  See DFHSM (Data Facility Hierarchical Storage Manager)
data integrity 4
data manager statistics 383
data set
  See also page set
  multivolume 67
  space management 15
data sets
  See also active log
  See also archive log
  active log 327
  archive log 316
  bootstrap, creating 61
  copying messages from queues 252
  copying messages from queues (offline) 255
  dump and restore 341
  initialization 52
  log, creating 61
  page set I/O error 361
  restart on losing 368
  restoring messages from 260
datagram, message 5
dead-letter queue 12, 58
  finding out its name 230
  security 421
DEAD.QUEUE
  See dead-letter queue
default
  archive parameters 79
  CCSID 73
  channel definition 13
  channel initiator parameters 87
  CSQ6ARVP macro 79
  CSQ6LOGP macro 76
  CSQ6SYSP macro 69
  logging parameters 76
  namelist definition 13
  process definition 14
  queue definitions 13
  routing code 74
  system queues 13
  user ID 70
DEFAULT storage class 57
default transmission queue 58
deferred connection for CICS 118
DEFINE commands, security 433
defining
  buffer pools 17
  CICS resources for MQSeries 124
  MQSeries to IMS 168
  storage class 15
  subsystems 41
defining queues 9
  defaults 13
definitions
  storing 15
DELETE commands, security 433
DELETE, utility function (CSQJU003) 266
deleting
  active information log from BSDS 328
  archive logs 323, 324
  log information from BSDS 266
  messages from a queue 258
dependent region, IMS 180, 181
  disconnecting from 181
  user ID 442
DEQUEUE TMEMBER, command of IMS 189
descriptor, message 4
DEST option, trace data destination 377
destination resolution exit
  sample 485
  specifying name 73
destination resolution exit, writing 483
device type for logs (UNIT) 84
DFHSM (Data Facility Hierarchical Storage Manager)
  in backup and recovery 317—318
DFS3611 message 364
DFS555I message 346, 364
DFSMS
  related publications 531
DFSYDRU0 sample module 483
DFSYPRX0 483
disaster recovery 318
discarded messages 225
disconnecting
  from CICS 136
  from IMS 182
dispatchers and adapters, total number 90
dispatchers, number to use for channel initiator 88
display
  channel initiator parameters 86
  CKQC transaction 148
  system settings 68
DISPLAY commands, security 433
DISPLAY OASN command of IMS 179
display sample 59
DISPLAY THREAD 286
displaying
  function key settings 207
  units of recovery in CICS 292
  units of recovery in IMS 178, 294
DISPS parameter of CSQ6CHIP 88
distributed queuing
  choosing facility 40
  connection security 415
  CSQINPX 53
  defining the data sets 50
  definition of term xv
  initialization input data sets 53
  installation verification program 108

distributed queuing *(continued)*
LE runtime library 46
MCA user ID 443
queues required 11
RESLEVEL 437
sample definitions 58
SCEERUN 46
security 51
security checking 437
security considerations 463
setting the CCSID 73
testing customization 108
distributed queuing using CICS ISC
channel definitions 492
channel file definition 491
channel sequence number queue 493
defining CICS resources 491, 493
defining queues, triggers, and processes 493
LU 6.2 connections 493
sample, CSQ4DISQ 59
security 494
transient data queue 493
DRU exit
specifying name 73
DRU exit sample
sample 485
DRU exit, writing 483
druexit name, specifying for OTMA 73
dual BSDS (TWOBSDS) 78
dual logging 306
establishing 315
losing 346
specifying for active log (TWOACTV) 77
specifying for archive log (TWOARCH) 78
dump formatting member 95
dynamic calls, IMS 168
dynamic expansion of page sets 66
dynamic queue
specifying a name 10
template 10
dynamic queues 5
close options 420
security 419

E

early code library 46
early code, multiple versions 103
ECSA storage requirement 28
editing namelists 214
EMCS 196
EMPTY, utility function (CSQUTIL) 258
English language feature 39
ENQUEUE names, CICS 123
environments, for applications 4
error symptoms
OS/390 error recovery program message 355
errors, hardware 366
euro currency support 99
event
introduction 18
event queues 12
event reporting sample, CSQ4INSG 55
event-driven processing 4
example
ARM policy 301
output from CSQ4IVPX 111
security scenario 468
SMP/E JOBCARD job step 489
SMP/E REPORT CALLLIBS job 489
example recovery scenarios
active log problems
both copies are damaged 348
delays in off-loading 351
dual logging lost 346
log stopped 347
one copy is damaged 348
out of space 351
read I/O errors 349
write I/O errors 349
archive log problems
allocation problems 353
insufficient DASD for off-load 354
read I/O errors during restart 355
write I/O errors during off-load 353
BSDS problems
both copies are damaged 357
BSDS recovery 330
does not agree with log 357
error while opening 356
I/O error 359
out of synchronization 359
unequal time stamps 358
hardware problems 366
IMS problems
application terminates 364
IMS not operational 365
unable to connect to MQSeries 364
page set problems
I/O error 361
page set full 362
EXEC CICS LINK
COMMAREA option 128
INPUTMSG option 130
linking to the CICS adapter 128, 135
exit program
CICS adapter 120
number of TCBs 71
time allowed per invocation 71
EXITLIM parameter of CSQ6SYSP 71

EXITTCB parameter of CSQ6SYSP 71
expanding page sets 239
extended console support 196
Extended Recovery Facility (XRF) 318
external security manager (ESM) 403
eye catcher strings 391, 398
  SMF type 115 records 391
  SMF type 116 records 398

F

F keys
  See function keys
FAILURE, keyword of COMMAND function 245
features, installable 33
finding archive log data sets to be deleted 324
FORCE 285
  parameter, table of effects 285
FORCE keyword of FORMAT 237
FORCE option of STOP QMGR command 286
FORCE parameter or RESETPAGE 242
format
  type 115 SMF records 379
  type 116 SMF records 395
FORMAT, utility function (CSQUTIL) 237
formatting dumps 95
frequency backing up logs 314
function keys
  changing namelists 214
  operations and control panels 207
  showing 207
  updating 94
  using 207
functions
  See change log inventory utility (CSQJU003)
  See MQSeries utility program (CSQUTIL)
functions, return codes from CSQUTIL 236

G

global trace
  initial setting 74
  start automatically 74
glossary 515
GMQADMIN, security class 410, 411
GMQNLIST, security class 410
GMQPROC, security class 410
GMQQUEUE, security class 410
group class, security 410
group name, specifying for OTMA 72
GRPLIST system initialization parameter 126

H

hardware errors 366
header
  SMF type 115 record 379
  SMF type 116 record 395
help
  CICS adapter 132
  operations and control panels 208
HIGHRBA, utility function (CSQJU003) 270
HTML (Hypertext Markup Language) 529
Hypertext Markup Language (HTML) 529

I

I/O error
  marks active log as TRUNCATED 326
  occurrence 311
  queues 361
ICHRIN03, started-task procedure table 466
IDBACK parameter of CSQ6SYSP 71
IDFORE parameter of CSQ6SYSP 72
IEFSSNss, SYS1.PARMLIB member 41
IFASMFDP, reporting program for SMF 374
IMS
  abend U3042 183
  adapter 180
  application programming 25
  commands
    CHANGE SUBSYS 175, 179
    DEQEUUE TMEMBER 189
    DISPLAY OASN 179
    DISPLAY OASN SUBSYS 175
    DISPLAY SUBSYS 181
    START REGION 181
    START SUBSYS 175
    START TMEMBER 189
    STOP REGION 181
    STOP SUBSYS 175, 182
    STOP TMEMBER 189
    TRACE 175
  connection status 181
  connections to MQSeries 175
  control region 176
  controlling dependent region connections 180
  CSQQTRMN transaction 166
  definition of term xv
  disconnecting from dependent region 181
  dynamic call stub, linking 168
  in-doubt units of recovery 290, 294
  initializing 176
  log record 290
  MQSeries-IMS bridge 25
  recovery considerations when using MQSeries 318
  related problems 364
  related publications 531
  reset Tpipe 21
  resynchronizing the bridge 190
  second user ID, determining 442

Index

IMS *(continued)*
  system administration and operation 25, 26
  thread 177
  trigger monitor 166
  user IDs, security checking 442
IMS adapter 167, 186
  address space user ID 405
  connection security 415
  connection status 181
  CSQBSTUB stub program 25
  CSQQDEFV, subsystem definition table 171
  CSQQDEFX, macro 171, 172
  CSQQSTUB stub program 25
  CSQQSTUB, stub program 165
  CSQQTRMN transaction 166
  defining MQSeries to it 171
  dependent regions of IMS 180
  displaying in-doubt units of recovery 178
  IMSID option 176
  installing 167
  language interface token (LIT) 172
  logical terminal (LTERM) 176
  maximum number of connections (CTHREAD) 70
  residual recovery entry (RRE) 179
  RESLEVEL 436
  restart, what happens 299
  second user ID 436, 442
  security checking 436
  SSM EXEC parameter 170
  SSM specification options 171
  starting CSQQTRMN 183
  stopping CSQQTRMN 184
  subsystem member entry in IMS.PROCLIB 168
  threads, displaying 178
  trigger monitor 166
IMS bridge
  age, specifying for OTMA 73
  Commit mode, synchronization 190
  controlling queues 189
  customizing 187
  deleting messages 189
  description 185
  druexit name, specifying for OTMA 73
  group name, specifying for OTMA 72
  illustration 185
  member name, specifying for OTMA 73
  OTMA parameters 72
  persistent messages 485
  resynchronizing 190
  security 459
  starting 185
  stopping 185
  storage class 187
  suppressing console messages 96
  Tpipe name 73
IMS problem
  application terminates 364
  IMS not operational 365
  unable to connect to MQSeries 364
IMS transactions, submitting 186
IMS.PROCLIB library 168, 176, 180
in-doubt units of recovery 289, 291, 297, 299
  causing inconsistent state 286
  resolution 295
  resolving, in CICS 289
  resolving, in IMS 290
  resolving, in RRS 291
INBUFF parameter of CSQ6LOGP 76
include files
  general-use programming interface 481
incorrect access 475
indexed queues, effect on restart time 288
information messages, suppressing 96
initialization input data sets
  customizing 52
  editing 53
  formats 53
  migration considerations 98
  MQSeries-supplied samples 54
initiation queue 11
  defining for CICS 58
INITPARM system initialization parameter 126
input buffer size (INBUFF) 76
installable features 33
installation verification program (IVP) 59
  distributed queuing 108
    sample output 111
  queue manager 105
installing
  See also customizing
  CICS adapter 124
  IMS adapter 167
  introduction 27
  security 466
Internet Gateway feature 34
interpreting
  buffer manager statistics 385
  log manager statistics 390
  replies to messages 226
intersystem connection (ISC) links 119
INTERVAL, attribute of ALTER SECURITY 55, 451
introduction to MQSeries 3
investigating performance 373
IPCS job, formatting dumps 95
IPCS list, updating 95
IPCS VERBEXIT 95
IPL (initial program load)
  when required for MQSeries 37
IRC and the CICS adapter 126
ISC LU 6.2 connection 493

ISPF
See also operations and control panels
effect of split screen 72
installing panels permanently 93
menu, updating 94
operations and control panels, setting up 93
panel 22
showing keys 207
ISPLLIB, concatenation 93
ISPMLIB, concatenation 93
ISPPLIB, concatenation 93
ISPSLIB, concatenation 93
ISPTLIB, concatenation 93
issuing commands 195, 244
IUCV
migration considerations 98
IUCV interface to TCP/IP 90
IVP
See installation verification program (IVP)
IVP (installation verification program)
distributed queuing 108
sample output 111
queue manager 105

J

Japanese language feature 39, 233
Japanese language letter 33

K

KEEPALIVE value, TCP/IP 89
KEYLIST, ISPF command 207

L

Language Environment, applying service 487
language interface token (LIT) 169
language letter 33
language, national 39
layout
type 115 SMF records 379
type 116 SMF records 395
libraries, after installation 34
link list, updating 46
listener
controlling 21
restarting with ARM 302
listener restart time 88
LIT (language interface token) 169
load balancing on page sets 335
load libraries, APF authorization of 47
load management 15
LOAD, utility function 260
local queue 10
system default 55
locating archive log data sets to be deleted 324
log
active 305
archive 305
changing log inventory utility (CSQJU003) 262
copy active to archive 20
determining inventory contents 325
dual logging 306
active 306, 312
archive 306, 312
synchronization 310
error recovery procedures 346
introduction 17
log print utility (CSQ1LOGP) 272
managing 305
number of buffers per write 78
print log map utility (CSQJU004) 271
records 290
logical 308
physical 308
types 307
recovering from problems
active log 346
archive log 353
recovery 332
structure 307
log data sets
creating 61
restart on losing 367
single or dual 76
storage required 61
log initialization parameters, setting 69
log manager statistics 389, 390
log print utility (CSQ1LOGP) 272—274
extract log records 272
invoking 272
output 274
print log records 272, 325
time stamp 325
what it does 272
log RBA value, modifying 262
log RBA, updating the highest written 270
log records
number between checkpoints 72
logging parameters
default 76
setting 76
logging process 308
logging, single and dual 76, 306
LOGLOAD parameter of CSQ6SYSP 72
logs and recovery 17
lowercase queue names
CICS adapter 134
operations and control panels 215
LSTRTMR parameter of CSQ6CHIP 88

LU 6.2
  LU name 89
  LUADD 89
  maximum number of current channels 89
  restart interval after failure 88
LU 6.2 and ARM 303
LU 6.2 connections (CICS mover) 493
LU name for outbound transmissions 89
LU62ARM parameter of CSQ6CHIP 89
LU62CHL parameter of CSQ6CHIP 89
LUNAME parameter of CSQ6CHIP 89

M

macros
  CSQ6ARVP 68
  CSQ6LOGP 68, 76
  CSQ6SYSP 68
  general-use programming interface 479
  product-sensitive programming interface 481
maintaining consistency after errors 283
MAKECLNT, keyword of COMMAND function 245, 247
MAKEDEF, keyword of COMMAND function 244, 246
managing
  BSDS 312, 327
  MQSeries log 321
  page sets 333
MAXALLC parameter of CSQ6LOGP 76
MAXARCH parameter of CSQ6LOGP 76
MAXFILEPROC 89
maximum number of uncommitted messages 54, 251
maximum page set extents 67
MAXSMSGS 54, 251
MCA user ID, distributed queuing 443
media recovery 366
member class, security 410
member name, specifying for OTMA 73
message
  calculating the space required 64
  channels 13
  illustration 4
  maximum length 5
  retrieval algorithms 6
  storing 15
  types 5
  what they are 4
message channel 13
message descriptor 4
message manager accounting 398
message manager statistics 382
message processing program (MPP) 180
message queue interface (MQI) 3
  calls 8
message queuing, what it is 3
message routing code (ROUTCDE) 73
message-driven processing 3
messages
  CICS adapter 131
  discarded 225
  incorporating MQSeries commands 222
  information, suppressing 96
  interpreting replies to MQSeries commands 226
  maximum number of uncommitted 54, 251
  on the system-command input queue 223
  suppressing 96
  undelivered, security 421
  user 207, 218
  violation, security 474
  waiting for replies to 224
MGCR 441
MGCR and MGCRE 195
migration
  testing 105
migration considerations
  ARM 97
  changes to installation process 97
  channel initiator 99
  channel initiator parameters 97
  channel initiator security 99
  CICS bridge 97
  clusters 98
  coexistence with earlier versions 103
  euro currency support 99
  initialization input data sets 98
  IUCV 98
  OpenEdition sockets 98
  operations and control panels 99
  queue objects 99
  RRS 98
  software levels 97
  storage classes 98
  system parameters 97
  TCP/IP 98
model queue 10
  system default 55
model queues
  security 419
modifying an MQSeries-CICS connection 138
monitoring
  CICS connection activity 141
  DISPLAY commands 372
  IMS connection activity 180
  performance 371
  resource usage 371
  tools 371
mounting, archive log (ARCWTOR) 81
mover
  CICS
    See distributed queuing using CICS ISC

moving queues 336
MPP (message processing program) connection control 180
MQADMIN, security class 410, 411
MQCLOSE options, security 429
MQCMDS, security class 410
MQCONN, security class 410, 414
MQGET
  in administration programs 220
  security 418
MQI (message queue interface)
  calls 8
  support, CICS adapter 116
  what it is 3
MQI channel 13
MQNLIST, security class 410
MQOPEN/MQPUT1 options, security 416, 429
MQPROC, security class 410
MQPUT
  in administration programs 220
  security 418
MQQUEUE, security class 410
MQRC_PAGESET_FULL reason code 346
MQSC command
  introduction 19
MQSeries commands
  ARCHIVE LOG 309, 321
  DEFINE PSID 333
  DISPLAY SECURITY 413
  DISPLAY THREAD 292
  issuing from TSO panels 197
  REFRESH SECURITY 413
  remote queue manager 220
  RESOLVE INDOUBT 292
  resource security profiles 432
  security 433
  security profiles 431
  START TRACE 376
  STOP TRACE 376
MQSeries publications 527
MQSeries subsystems
  running different versions 103
MQSeries utility program (CSQUTIL) 235—262
  COMMAND function 244
  COPY function 252
  COPYPAGE function 239
  EMPTY function 258
  FORMAT function 237
  introduction 235
  invoking 235
  issuing commands from 197
  LOAD function 260
  monitoring the progress of 236
  moving queues 336
  page set management 237, 336
  queue management functions 251
MQSeries utility program (CSQUTIL) *(continued)*
  RESETPAGE function 241
  return codes 236
  SCOPY function 255
  SDEFS function 249
  security 441
  syntax checking 236
MQSeries-IMS bridge
  See IMS bridge
MsgId field, administration programs 224
multi-region operation (MRO) restrictions 119
multi-tasking, CICS adapter 120
multi-volume archive log data sets 310
MVS
  See OS/390

N

name of LU to use 89
namelist 13
  system default 55
namelists 214
  security 406, 424
names of objects 7
national language feature 33
network considerations for ARM 302
network ID (NID)
  See NID (network ID)
NEWLOG, utility function (CSQJU003) 264, 327, 329
NID (network ID) 292, 295
NODEFINE storage class 57
nonpersistent messages 219
NSYSLX, value of 45

O

object
  channel 13
  namelist 13
  names 7
  process definition 14
  queue 10
  queue manager 8
  storage class 15
  types 7
object definition
  storing 15
objects
  backing up definitions 315
  defining 213
  operations and control panels 213
  supplied samples 55
  system default 55
off-loading
  active log 309
  description 308, 310

off-loading *(continued)*
diagram of process 309
errors during 310, 326
messages issued during 310
process description 308
relationship to other logging events 309
OFFLOAD parameter of CSQ6LOGP 77
OpenEdition 22
OpenEdition sockets
migration considerations 98
security 51
OpenEdition sockets interface to TCP/IP 90
opening the system-command input queue 220
operating
basic operations 195
introduction 27
operations and control panels
changing function keys 94
changing the subsystem ID 208
coexistence with earlier versions 104
example of 208
function keys 207
installing permanently 93
introduction 22
invoking 204
libraries 93
migration considerations 99
performance 16
queue manager default 207
RESLEVEL 435
rules for using 215
security checking 435
setting up 93
system command objects 56
user messages 207
using 203
working with object definitions 213
operator commands
CICS adapter 149
IMS adapter 175
issuing 195
operations and control panels 203
orderly shutdown
CICS adapter 151
MQSeries 285
OS/390
APF authorized libraries 47
console, connecting from 196
environment 22
issuing MQSeries commands 198
link list, updating 46
MQSeries considerations 22
parmlibs, updating 41
program properties table, updating 48
related publications 531
SNAP dump 92, 116, 165
OS/390 *(continued)*
subsystem name table, updating 41
WLM 26
workload manager 26
OS/390 Automatic Restart Manager
See ARM
OS/390 OpenEdition 22
OTMA 185
DRU exit sample 485
pre-routing exit sample 483
OTMA exit 483
OTMACON parameter of CSQ6SYSP 72
out of space on active log 351
OUTBUFF parameter of CSQ6LOGP 77
output buffer, logs (OUTBUFF) 77, 308

P

page set
backing up 340
define 20
display current state 20
dynamic expansion 66
maximum limit 67
how messages are stored 65
illustration 16, 17
number used 66
problems 361
reducing the size 338
sample 63
storage management 15
what they are 15
page set identifier (PSID)
specifying 15
page set problem
I/O error 361
page set full 362
page set zero 15
managing 16
performance 16
storage requirements 64
page set zero, migration 99
page sets
adding 63, 333
AMS REPRO 340
backing up 314, 339
control records 307
copying 239, 241
COPYPAGE 239
creating a point of recovery 339
defining 63
dynamic expansion 63
expanding 239, 334
formatting 237
full 333, 362
initialization input data sets 54

page sets *(continued)*
load balancing 335
managing 333
performance 386
recovery 314, 341
RESETPAGE 241
resetting the log 241
storage requirements 64
utility functions 237
PAGES keyword of FORMAT 237
panels
blank fields in 215
coexistence with earlier versions 104
installing 94
issuing commands from 197
operations and control 203, 208
rules for using 215
PARM option, START QMGR command 200
parmlibs, updating 41
passwords
archive log data set 329
data sets 264
supply for archive log 267
PDF (Portable Document Format) 530
pending events
deferred connection 118
termination notification 118, 127
performance
buffer pool management 385
buffer pools 17
compacting archive log 82
DASD operations 385
DISPLAY commands 372
effect of indexed queues 288
effect of MQSeries trace 377
monitoring 371
of CICS adapter 121
operations and control panels 16
page set zero 16
problems 372, 373
sample SMF records 391
SMF trace 374
snapshots 372
symptoms of reduced 373
Performance Reporter 375
permanent dynamic queues, problems 16
permanent queue 10
permanent queues 5
PF keys
See function keys
PFSHOW, ISPF command 207
PING CHANNEL command
security 433
PL/I, testing customization 108
PLTPI (program list table post initialization) 125
starting the CICS adapter 128
point of consistency
CICS 281
description 279
IMS 281
point of recovery 314
creating 339
Portable Document Format (PDF) 530
PostScript format 530
PPT (program properties table)
example 48
updating 48
pre-routing exit 483
predefined queues 5
previous versions
migrating from
coexistence with earlier versions 103
print log map utility (CSQJU004) 271
invoking 271
PRIQTY parameter of CSQ6ARVP 82
problem determination
IMS 364
performance 372
security 474
problems
operations and control panels 16
permanent dynamic queues 16
procedures
channel initiator 50
queue manager subsystem 49
process
definitions 14
security 405
security profile 423
system default 55
proclibs 49
profile, RACF 411
for alternate user security 425
for command resources 432
for command security 431
for connection security
batch/TSO adapter 414
CICS adapter 414
distributed queuing 415
IMS adapter 415
RRS adapter 414
for context security 427
for namelists 424
for process security 423
for queue security 416
RESLEVEL 438
switch 411
used to protect MQSeries resources 414
program list table (PLT) 125
program properties table
See PPT (program properties table)

program, administration 217
PROTECT parameter of CSQ6ARVP 83
PSID (page set identifier)
  specifying 15
publications
  MQSeries 527
  related 531

Q

QIST, data manager statistics record 383
QJST, log manager statistics record 389
QMAC, message manager accounting record 398
QMCCSID (queue manager coded character set identifier) 73
QMCCSID parameter of CSQ6SYSP 73
QMST, message manager statistics record 382
QPST, buffer manager statistics record 384
queue
  alias 10
  attributes 9
  channel 11
  channel initiation 11
  channel reply information 11
  channel sequence number (CICS mover) 493
  channel synchronization 11
  cluster 10
  cluster command 11
  cluster repository 11
  cluster transmission 12
  dead-letter 12
  defining 9
  dynamic 5
  event 12
  illustration 8
  initiation 11
  local 10
  mapping to page sets 15
  model 10
  permanent 5, 10
  predefined 5
  remote 10
  required for clusters 11
  required for commands 12
  required for distributed queuing 11
  required for events 12
  required for triggering 11
  system default 13
  system-command
    input 12
  temporary 10
  transmission 11
  used with MQSeries 10
  what they are 5
  where they reside 6
  WLM-managed 26
queue management utility functions 251
queue manager
  commands 8
  display cluster information 21
  illustration 8
  installation verification program 105
  relationship to queues 6
  running multiple versions 103
  starting 21, 198
  stopping 21, 201
  what it is 8
queue manager cluster
  See cluster
queue manager coded character set identifier (QMCCSID) 73
queue manager environment
  parameters 497
  settings 497
queue manager environment parameters 497
queue manager event
  introduction 18
queue object
  types 10
  using 10
queue objects
  migration considerations 99
queues 123
  alter attributes, security 433
  backup 313
  channel 56
  cluster 57
  copying 239, 252
  copying (offline) 255
  dead-letter 58
  defining local 209
  emptying 258
  indexed, effect on restart time 288
  LOAD function 260
  moving them 336
  profiles for security 416
  recommended, sample 57
  recovery 313
  reply-to model 220
  reserved names 123
  restoring messages 260
  security 405, 416
  supplied samples 55
  system-administration 56
  system-command 220
    input 220
    reply-to model 220
  transmission, default 58
QUIESCE 201, 285, 286
  option of STOP QMGR command 286
  parameter, table of effects 285
  stop mode 201

QUIESCE MODE, of ARCHIVE LOG utility
function 321
QUIESCE parameter of CSQ6ARVP 84
QWHS, message manager accounting record 398

R

RACF
See also profile, RACF
See also security
authority, dead-letter queue 422
authorization
ICHRIN03 466
STARTED class 466
started-task procedure table 466
to MQSeries data sets 467
commands for CSQ4IVP1 106, 109
profiles 411
related publications 531
security classes 410
RACF profiles 460
railroad diagrams, how to read 234
RBA (relative byte address)
description 306
range shown in messages 310
range specified in active log 327
RDO (resource definition online) 124
recommended queues sample, CSQ4INYG 57
record subtypes, SMF type 115 records 380
records
type 115 (SMF) 374
type 116 (SMF) 374
RECOVER BSDS command
security 433
recovery 343
active log problems 346
application program 305
basic operations 195
BSDS
errors 356
log inventory 323
CICS
manually recovering units of recovery 292
resolving in-doubt units of recovery 289
COPY 343
creating a point of 339
data with DFHSM 317
description 341
example scenarios 345
IMS
manually recovering units of recovery 294
resolving in-doubt units of recovery 178, 290
resynchronizing the bridge 190
introduction 17, 28
logs 332
long-running UOW 363
recovery *(continued)*
MQSeries-related problems
active log problems 346
archive log problems 353—355
BSDS 332, 356
page set problems 361
object definitions, backing up 315
page sets 340
point of 339
procedure, IMS units of recovery 294
restart 287
RRS
manually recovering units of recovery 296
resolving in-doubt units of recovery 291
single BSDS 330
starting 197—201
subsystem 305
system procedures 313
tokens 292
redo records 307
reduced performance, symptoms of 373
reducing the size of a page set 338
REFRESH SECURITY command 413
security 433
using 452
region error options (REO) 169, 180
region size 29
registering with ARM 302
relative byte address (RBA) 306
See also RBA (relative byte address)
remote queue
system default 55
remote queues 10
command resource checking 432
security 420
REMOTE storage class 57
REO (region error options) 169, 180
replies, examples 226
reply message descriptor 225
reply messages 5, 224
reply-to queue
attributes 220
defining 220
opening 221
system-command 56
REPORT CALLLIBS 488
report message 5
repository queue, clustering 11
REPRO command of access method services 340
request message 5, 223
RESET CHANNEL command
security 433
RESETPAGE, utility function (CSQUTIL) 241
resetting page sets 241
residual recovery entry (RRE)
See RRE (residual recovery entry)

RESLEVEL
  auditing 440, 447
  checking CICS user IDs 435
  distributed queuing 437
  IMS adapter 436
  security profile 404
  usage notes 440
  user IDs associated with 438
  using 435
RESOLVE commands
  security 433
RESOLVE INDOUBT command
  free locked resources 292
resolving
  in-doubt units of recovery 178
  units of recovery 292, 296
resource definition online (RDO) 124
Resource Measurement Facility (RMF) 375
resource protection 4, 405
resource recovery services (RRS)
  adapter 23
  introduction 23
  migration considerations 98
resource security
  alias queues 432
  API 405, 429
  commands 407, 432
  remote queues 432
resource-level security checking by CICS adapter 455
RESOURCE_TYPE, CICS adapter 123
RESPTIME, keyword of COMMAND function 245
restart 285
  See also recovery
  after abnormal termination 283
  after losing data sets 368
  after losing logs 367
  CICS adapter 289, 297
  cold start 368
  conditional 268
  distributed recovery environment 283
  effect of indexed queues 288
  effect of lost connections 289
  IMS 290
  IMS adapter 299
  long-running UOW 363
  MQSeries 290
    phase 281
  normal 287
  OS/390 Automatic Restart Manager 300
  parameter, table of effects 285
  process 279, 285, 287
  RRS adapter 291
  user messages 298
  with ARM 300
RESTART option of STOP QMGR command 286
restart timer, listener 88
restoring
  messages to a queue 251
restricting access using alias queues 418, 421
resynchronization of CICS and MQSeries
  resources 289
resynchronization of IMS and MQSeries resources 290
resynchronization of RRS and MQSeries
  resources 291
retention period, archive logs (ARCRETN) 80, 323
retrieval algorithms, for messages 6
return codes, from utility functions 236
RMF (Resource Measurement Facility) 375
ROUTCDE parameter of CSQ6SYSP 73
route codes, archive log (ARCWRTC) 80
routing code, message (ROUTCDE) 73
routing commands
  in a sysplex 44
  using CPFs 42
RRE (residual recovery entry) 179
  logged at IMS checkpoint 290
  not resolved 290
RRS
  applying service 487
  units of recovery 296
RRS (resource recovery services)
  adapter 23
  introduction 23
  migration considerations 98
RRS adapter 23
  connection security 414
  installing 92
  recovery 291
rules for using the operations and control panels 215
RVERIFY SECURITY command
  security 433
  using 452

S

sample
  ARM policy 301
  channel definitions (CICS mover) 492
  defining page sets 63
  destination resolution exit 485
  initialization input data set members 54
  linking the IMS dynamic call stub 168
  OTMA pre-routing exit 483
  output from CSQ4IVPX 111
  security scenario 468
  SMF accounting record 400
  SMF statistics records 391
  SMP/E JOBCARD job step 489
  SMP/E REPORT CALLLIBS job 489
  startup procedure 49

sample data set members 37
SCOPY, CSQUTIL function 255
SCSQxxxx contents 34
SDEFS, CSQUTIL function 249
second user ID, IMS adapter 436, 439, 442
SECQTY parameter of CSQ6ARVP 84
security
  See also profile, RACF
  See also RACF
  alternate user 406
  API quick-reference table 429
  archive log 83
  auditing considerations 447
  automating starting of CKTI 456
  blank user IDs 446
  CICS adapter 455
    transactions 455
    user IDs 456
  CICS bridge 457
  CKSG user IDs 456
  CKTI 456
  clustering 465
  command 407
    summary table 433
  command resource 407
  connection 405, 414, 440
  context 406
  controlling 20
  controls and options 404
  customizing 454
  data sets 466
  default user ID 70, 440
  displaying status 453
  distributed queuing 463
  distributed queuing (using CICS ISC) 494
  example scenario 468
  implementation 404
  implementation checklist 449
  IMS 459
  installation tasks 51, 466
  installation verification program
    distributed queuing 109
    queue manager 106
  INTERVAL attribute 55, 451
  introduction 51
  management 403, 451
  migration considerations 99
  MQCLOSE/MQOPEN/MQPUT1 options 429
  namelist 406
  OTMA 459
  problem determination 474
  process 405
  profile, RESLEVEL 404, 435
  propagating CKTI user IDs 456
  queues 405
    alias 417, 432
    dead-letter 421
security *(continued)*
  queues *(continued)*
    dynamic 420
    model 419
    profiles 416, 433
    remote 420, 432
    transmission 427, 429, 432
  refreshes 452
  subsystem 404
  terminal user IDs 456
  TIMEOUT attribute 55, 451
  undelivered messages 421
  universal access (UACC) levels 446
  user ID timeouts 451
  user IDs 440
  using RACF classes 410
  utilities 441
Security Server
  See also RACF
  related publications 531
self-defining section
  SMF type 115 records 379, 381
  SMF type 116 records 395, 397
service considerations 487
service goal 26
SETSSI command 41
shutdown
  See terminating
shutting down
  CICS bridge 161
Simplified Chinese language feature 39
Simplified Chinese language letter 33
single BSDS (TWOBSDS) 78
single logging 306
  establishing 315
  specifying for active log (TWOACTV) 77
  specifying for archive log (TWOARCH) 78
single phase commit 281
SIT (system initialization table) 127
  GRPLIST parameter 126
  INITPARM parameter 126
  PLTPI parameter 126
SMF (System Management Facility) 374
  accounting record sample 400
  buffers 374
  CSQ6SYSP, specifying parameters 69
  data records
    type 115 379
    type 116 395
  gathering (STATIME) 74
  processing type 115 records 380
  processing type 116 records 396
  recording trace data for 374
  reporting data in (IFASMFDP) 374
  self-defining section
    type 115 records 379
    type 116 records 395, 397

Index

SMF (System Management Facility) *(continued)*
  starting automatically (SMFSTAT) 74
  statistics records sample 391
  type 115 header 379
  type 115 record layout 379
  type 115 record subtypes 380
  type 115 self-defining section 381
  type 116 header 395
  type 116 record layout 395
SMFACCT parameter of CSQ6SYSP 74
SMFSTAT parameter of CSQ6SYSP 74
SMS (Storage Management Subsystem)
  See Storage Management Subsystem (SMS)
SNAP dump
  Batch/TSO adapter 92
  CICS adapter 116
  IMS adapter 165
snapshots, performance 372
sockets
  security 51
sockets interface to TCP/IP 90
softcopy books 529
software levels 97
space allocation
  archive logs, block size (BLKSIZE) 81
  logs, primary (PRIQTY) 82
  logs, secondary (SECQTY) 84
  units, logs (ALCUNIT) 79
SPT (started-task procedure table) 466
ssid.DEAD.QUEUE
  See dead-letter queue
SSM (subsystem member)
  contains control information 176
  entry in IMS.PROCLIB 168
  error options 180
  EXEC parameter 170
  specification options 171
  specified on EXEC parameter 180
START CMDSERV command 219
START commands
  security 433
start options for MQSeries 200
START QMGR command
  from OS/390 console 197
  options 200
START REGION, command of IMS 181
START SUBSYS, command of IMS 175
START TMEMBER, command of IMS 189
START TRACE command 376
start-up messages (MQSeries) 198
STARTED RACF class 466
  authorization to data sets 467
started task procedure
  authorization 466
  creating for channel initiator 50
  creating for queue manager 49
started task procedure *(continued)*
  security 49
starting
  after an abend 201
  CICS bridge 160
  CICS-MQSeries connection
    from a CICS program 135
    from the command line 134
    using the CICS adapter control panels 133
  command server 219
  IMS-MQSeries connection 176
  MQSeries 197, 198, 201
  MQSeries trace 376
  OS/390 Automatic Restart Manager 300
  with ARM 300
startup procedure, CSQ4MSTR 49
STATIME parameter of CSQ6SYSP 74
statistics
  buffer manager 384
  buffer pool 386
  CICS adapter 122, 372
  data manager 383
  eye catcher strings 391
  gathering time interval 74
  log manager 389, 390
  message manager 382
  sample SMF records 391
  security 448
  starting automatically 74
STOP CMDSERV command 219
STOP commands
  security 433
STOP QMGR command
  MODE(FORCE) 202, 285
  MODE(QUIESCE) 202, 285
  MODE(RESTART) 201, 285
STOP REGION, command of IMS 181
STOP SUBSYS, command of IMS 175, 182
STOP TMEMBER, command of IMS 189
STOP TRACE command 376
stopping
  See also terminating
  CICS bridge 161
storage class
  errors 58
  illustration 16
  migration considerations 98
  sample 57
  storage management 15
  system default 55
  when to change 58
storage class sample, CSQ4INYG 57
storage class, defining 15
storage class, IMS bridge 187
storage management 15

Storage Management Subsystem (SMS) 26, 323
  archive log data sets 317
storage requirement
  BSDS 61
  CSA 28
  messages 64
  page set 64
  trace table 75
storage, archive planning 316
stub program
  CSQBRRSI, for Batch/TSO RRS adapter 23
  CSQBRRSI, for RRS adapter 23
  CSQBRSTB, for Batch/TSO RRS adapter 23
  CSQBRSTB, for RRS adapter 23
  CSQBSTUB for Batch/TSO adapter 23
  CSQBSTUB for IMS adapter 25
  CSQCSTUB for CICS adapter 24
  CSQQSTUB for IMS adapter 25
stub programs
  coexistence with earlier versions 104
  CSQCSTUB for CICS adapter 117, 127
  CSQQSTUB, for IMS adapter 165
subsystem ID, changing 208
subsystem member (SSM)
  See SSM (subsystem member)
subsystem name table, updating 41
subsystem recovery 305
  See also recovery
subsystem security 404
  See also security
subsystems, defining
successful collection, accounting data 376
suppressing information messages 96
switches, security 411
syncpoint
  See point of consistency
syncpoint protocols 281
syncpoint-bypassing, CICS adapter 122
syntax diagrams, how to read 234
SYS1.PARMLIB member
  APPCPMxx 89
SYS1.PARMLIB members
  IEFSSNss 41
SYSEXEC, concatenation 93
sysplex
  routing commands 44
SYSPROC, concatenation 93
system administration
  CICS 25
  IMS 26
  MQSC commands 19
  MQSeries commands 195, 197
  using application programs 217
system command sample, CSQ4INSG 55
system control command
  summary 20
system control commands
  for starting MQSeries 197
system default
  objects 55
  queues 13
  sample, CSQ4INPX 60
  sample, CSQ4INSG 55, 57
  sample, CSQ4INYC 59
  sample, CSQ4INYG 58
system initialization table (SIT)
  See SIT (system initialization table)
system linkage index, reviewing the number 45
System Management Facility (SMF)
  See SMF (System Management Facility)
system monitoring, DISPLAY commands 372
system object sample, CSQ4INSG 55
system parameter module
  CSQZPARM 200
  displaying settings 68
  invoking 68
  tailoring 68
system parameters
  migration considerations 97
  setting 69
system security 466
SYSTEM storage class 57
  migration considerations 98
system-administration
  objects 56
system-command
  input queue 12, 56, 197
    default attributes 56
    defining 220
    opening 220
    putting messages on 223
  objects 56
  reply-to model queue 12, 56, 220
SYSTEM.ADMIN.CHANNEL.EVENT queue 12
SYSTEM.ADMIN.PERFM.EVENT queue 12
SYSTEM.ADMIN.QMGR queue 12
SYSTEM.CHANNEL.COMMAND queue 493
SYSTEM.CHANNEL.INITQ queue 11
SYSTEM.CHANNEL.REPLY.INFO queue 11
SYSTEM.CHANNEL.SEQNO queue 493
SYSTEM.CHANNEL.SYNCQ queue 11
SYSTEM.CLUSTER.COMMAND.QUEUE 12
SYSTEM.CLUSTER.REPOSITORY.QUEUE 11
SYSTEM.CLUSTER.TRANSMIT.QUEUE 12
SYSTEM.COMMAND.INPUT queue 12
SYSTEM.COMMAND.REPLY.MODEL queue 12

T

target library high-level qualifier (thlqual) 34
task initiator (CKTI)
  See CKTI transaction

Index

tasks, displaying CICS 147
TCB
  CICS adapter 120
  number for exit programs 71
TCP/IP
  address space name 89
  interface type 90
  KEEPALIVE value 89
  MAXFILEPROC 89
  maximum number of current channels 89
  migration considerations 98
  number of dispatchers 88
  restart interval after failure 88
  settings 90
TCP/IP and ARM 303
TCP/IP, applying service 487
TCPCHL parameter of CSQ6CHIP 89
TCPKEEP parameter of CSQ6CHIP 89
TCPNAME parameter of CSQ6CHIP 89
TCPTYPE parameter of CSQ6CHIP 90
temporary queues
  See dynamic queues
terminal user IDs, CICS adapter 456
terminating
  MQSeries 201, 285
  MQSeries-CICS connection 150
    from a CICS program 137
    from the CICS adapter control panels 136
    from the CICS command line 137
  MQSeries-IMS connection 182
  using QUIESCE, FORCE, and RESTART, table of effects 285
termination notification, CICS adapter 118
terminology used in this book 515
testing your queue manager 105
TGTQMGR, keyword of COMMAND function 245
thlqual
  definition of term xv
thlqual (target library high-level qualifier) 34
thlqual.SCSQxxxx contents 34
thread cross reference 286
thread, display information 20
threads
  attachment in IMS 177
  CICS adapter termination 151, 285
  displaying, IMS adapter 178
  ID for CICS transactions 128
  IMS termination 182
  maximum number (CTHREAD) 70
  stopping MQSeries 201
time stamps 288, 325
  archive log (TSTAMP) 84
  from BSDS 325
  unequal in BSDS 358
time-independent applications 3
TIMEOUT, security attribute 55, 451
Tpipe
  name 73
  reset 21
trace
  controlling 20
  controlling MQSeries 376
  effect on performance 377
  specifying destinations 377
  specifying keywords 376
  starting automatically (TRACSTR) 74
  trace table size (TRACTBL) 75
TRACE, command of IMS 175
trace, size of data space for channel initiator 90
trace, start automatically for channel initiator 90
tracing parameters, setting 69
TRACSTR parameter of CSQ6SYSP 74
TRACTBL parameter of CSQ6SYSP 75
transaction pipe
  See Tpipe
transient data queue (TDQ), CKMQ 493
transient data queue (TDQ), CKQQ 131
transmission queue 11
  See also security
  default 58
transmission queue, clustering 12
TRAXSTR parameter of CSQ6CHIP 90
TRAXTBL parameter of CSQ6CHIP 90
trigger monitor 14
  See also CKTI transaction
  See also CSQQTRMN transaction
triggering
  queues required 11
truncation, active log 310
TSO
  See also Batch/TSO adapter
  formatting dumps 95
  issuing MQSeries commands from 197
  starting MQSeries from 197
TSO applications
  improving portability 92
TSTAMP parameter of CSQ6ARVP 84
tuning
  CICS bridge 160
tuning MQSeries 371
tuning, introduction 28
two-phase commit 281
TWOACTV parameter of CSQ6LOGP 77
TWOARCH parameter of CSQ6LOGP 78
TWOBSDS parameter of CSQ6LOGP 78
type 115 SMF records 374
type 116 SMF records 374
types of objects 7

U

U.S. English language letter 33
U3042 abend (IMS) 183
unauthorized access, protecting from 403
uncommitted messages, maximum number 20, 54, 251
undelivered messages, security 421
undelivered-message queue
  See dead-letter queue
undo records 307
unit of recovery
  maximum number of messages in 54, 251
unit of work
  CICS adapter 297
  long running 363
UNIT parameter of CSQ6ARVP 84
units of recovery 279
  CICS
    in-doubt resolution 289
    recovering manually 292
  IMS
    in-doubt resolution 178, 290
    recovering manually 294
  in-doubt
    displaying in IMS 178
    how they are resolved 289
    recovering in IMS 178
  log records 307
  RRS
    in-doubt resolution 291
    recovering manually 296
universal access (UACC) levels 446
UNIX system services sockets interface to TCP/IP
  See OpenEdition sockets interface to TCP/IP
UOW 297
updating
  CSQINP2 127
  OS/390 link list 46
  OS/390 parmlibs 41
  OS/390 subsystem name table 41
  RACF security 403
upgrade considerations 487
upgrading from previous versions
  coexistence with earlier versions 103
US English language features 233
user exits 120
user ID
  maximum age in OTMA 73
user ID security
  alternate user 438
  Batch/TSO adapter
    connection 414, 435, 440
    RESLEVEL 435, 438
  blank 446
  checking 441
user ID security *(continued)*
  CICS adapter 455
    address space 442
    connection 414, 435, 440
    RESLEVEL 435, 438
    task 442
    transactions 442
  CKTI 456
  CSQUTIL 435
  default 70
  distributed queuing 439
    connection 415, 437
    RESLEVEL 437
  IMS adapter
    address space 442
    connection 415, 436, 440
    RESLEVEL 436, 438
    second user ID 436, 439, 442
  number checked 435
  operations and control panels 435
  RESLEVEL profile 404, 435, 438
  reverification 452
  RRS adapter
    connection 414
  timeouts 451
user messages 218
  at start up 198
  COUNT field 226
  displaying from panels 207
  from MQSeries commands, replies 226
utilities
  CSQ1LOGP
    See log print utility (CSQ1LOGP)
  CSQJU003
    See change log inventory utility (CSQJU003)
  CSQJU004
    See print log map utility (CSQJU004)
  CSQUTIL
    See MQSeries utility program (CSQUTIL)
  functions
    ARCHIVE 267
    CHECKPT 269
    COMMAND 244
    conditional restart 268
    COPY 252
    COPYPAGE 239
    CRESTART 268
    DELETE 266
    EMPTY 258
    FORMAT 237
    HIGHRBA 270
    LOAD 260
    NEWLOG 264
    RESETPAGE 241
    SCOPY 255
    SDEFS 249
    setting checkpoint records 269

utilities *(continued)*
functions *(continued)*
updating the highest written log RBA 270
summary table 233
time stamp 325
unit of recovery, maximum number of messages 251
utility program
See MQSeries utility program (CSQUTIL)
Utoken 441

V

VERBEXIT, IPCS 95
violation messages, security 474
virtual storage access method (VSAM)
See VSAM (virtual storage access method)
volume dump and restore 341
volume serial number 312
VSAM (virtual storage access method) 264, 306, 308
control interval, block size 316

W

WAIT option, CICS adapter 123
waiting for replies to messages 224
Windows Help 530
WLM 26
WLMTIME parameter of CSQ6SYSP 75
work, units of 292
Workflow 26
workload manager 26
queue scan interval 75
writing
programs to administer MQSeries 217
to the active log 309
to the archive log 309
WRTHRSH parameter of CSQ6LOGP 78
WTOR, MQSeries-related 201

X

XCF
group name, specifying for OTMA 72
member name, specifying for OTMA 73
XRF (Extended Recovery Facility) 318

Sending your comments to IBM

System Management Guide

SC34-5374-01

If you especially like or dislike anything about this book, please use one of the methods listed below to send your comments to IBM.

Feel free to comment on what you regard as specific errors or omissions, and on the accuracy, organization, subject matter, or completeness of this book. Please limit your comments to the information in this book and the way in which the information is presented.

To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate, without incurring any obligation to you.

You can send your comments to IBM in any of the following ways:

- By mail, use the Readers' Comment Form.
- By fax:
  - From outside the U.K., after your international access code use 44 1962 870229
  - From within the U.K., use 01962 870229
- Electronically, use the appropriate network ID:
  - IBM Mail Exchange: GBIBM2Q9 at IBMMAIL
  - IBMLink: HURSLEY(IDRCF)
  - Internet: idrcf@hursley.ibm.com

Whichever you use, ensure that you include:

- The publication number and title
- The page number or topic to which your comment applies
- Your name and address/telephone number/fax number/network ID.

Readers' Comments

System Management Guide

SC34-5374-01

Use this form to tell us what you think about this manual. If you have found errors in it, or if you want to express your opinion about it (such as organization, subject matter, appearance) or make suggestions for improvement, this is the form to use.

To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer. This form is provided for comments about the information in this manual and the way it is presented.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Be sure to print your name and address below if you would like a reply.

Name	Address
Company or Organization	
Telephone	Email

System Management Guide
SC34-5374-01

IBM

1 Cut along this line

You can send your comments POST FREE on this form from any one of these countries:

Australia	Finland	Iceland	Netherlands	Singapore	United States
Belgium	France	Israel	New Zealand	Spain	of America
Bermuda	Germany	Italy	Norway	Sweden	
Cyprus	Greece	Luxembourg	Portugal	Switzerland	
Denmark	Hong Kong	Monaco	Republic of Ireland	United Arab Emirates	

If your country is not listed here, your local IBM representative will be pleased to forward your comments to us. Or you can pay the postage and send the form direct to IBM (this includes mailing in the U.K.).

2 Fold along this line

By air mail
Par avion

IBRS/CCRI NUMBER: PHQ - D/1348/SO

NE PAS AFFRANCHIR

NO STAMP REQUIRED

IBM

REPONSE PAYEE
GRANDE-BRETAGNE

IBM United Kingdom Laboratories
Information Development Department (MP095)
Hursley Park,
WINCHESTER, Hants
SO21 2ZZ United Kingdom

3 Fold along this line

From: Name _____

Company or Organization _____

Address _____

_____

EMAIL _____

Telephone _____

1 Cut along this line

4 Fasten here with adhesive tape

Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

SC34-5374-01