


DB2 Version 9.5  
for Linux, UNIX, and Windows



**Getting Started with DB2 installation and administration on Linux and  
Windows**  
**Updated March, 2008**





**Note**

Before using this information and the product it supports, read the general information under Appendix E, "Notices," on page 47.

**Edition Notice**

This document contains proprietary information of IBM. It is provided under a license agreement and is protected by copyright law. The information contained in this publication does not include any product warranties, and any statements provided in this manual should not be interpreted as such.

You can order IBM publications online or through your local IBM representative.

- To order publications online, go to the IBM Publications Center at [www.ibm.com/shop/publications/order](http://www.ibm.com/shop/publications/order)
- To find your local IBM representative, go to the IBM Directory of Worldwide Contacts at [www.ibm.com/planetwide](http://www.ibm.com/planetwide)

To order DB2 publications from DB2 Marketing and Sales in the United States or Canada, call 1-800-IBM-4YOU (426-4968).

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1993, 2008. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>Chapter 1. Installation prerequisites. . . . .</b>	<b>1</b>	Response file considerations . . . . .	25
Disk and memory requirements . . . . .	1	Creating a response file using the DB2 Setup wizard	26
Windows installation prerequisites . . . . .	1	<b>Appendix B. Applying DB2 fix packs . . . . .</b>	<b>29</b>
Installation requirements for DB2 servers and IBM data server clients (Windows). . . . .	1	Applying fix packs . . . . .	29
Setting up Windows elevated privileges prior to installing a DB2 product (Windows) . . . . .	3	<b>Appendix C. Uninstalling your DB2 product . . . . .</b>	<b>31</b>
Granting user rights (Windows) . . . . .	5	Uninstalling your DB2 product (Windows) . . . . .	31
DB2 system administrator group considerations (Windows) . . . . .	5	Uninstalling your DB2 product (Linux and UNIX)	32
Linux installation prerequisites . . . . .	6	Stopping the DB2 administration server (Linux and UNIX) . . . . .	32
Installation requirements for DB2 servers and IBM data server clients (Linux) . . . . .	8	Removing the DB2 administration server (Linux and UNIX) . . . . .	32
Centralized user-management considerations (Linux and UNIX) . . . . .	10	Stopping root instances (Linux and UNIX) . . . . .	33
<b>Chapter 2. Installing your DB2 product . . . . .</b>	<b>11</b>	Removing DB2 instances (Linux and UNIX) . . . . .	33
Installing DB2 servers (Windows) . . . . .	11	Removing DB2 products using the db2_deinstall or doce_deinstall command (Linux and UNIX) . . . . .	34
Installing DB2 servers using the DB2 Setup wizard (Linux and UNIX) . . . . .	13	<b>Appendix D. Overview of the DB2 technical information . . . . .</b>	<b>37</b>
<b>Chapter 3. Verifying your installation . . . . .</b>	<b>17</b>	DB2 technical library in hardcopy or PDF format . . . . .	37
Verifying the installation of DB2 servers using First Steps (Linux and Windows) . . . . .	17	Ordering printed DB2 books. . . . .	40
Verifying the installation using the command line processor (CLP) . . . . .	18	Displaying SQL state help from the command line processor . . . . .	40
Creating your own database using the Create Database with the Automatic Maintenance wizard . . . . .	18	Accessing different versions of the DB2 Information Center . . . . .	41
<b>Chapter 4. DB2 product licensing . . . . .</b>	<b>21</b>	Displaying topics in your preferred language in the DB2 Information Center . . . . .	41
DB2 license files . . . . .	21	Updating the DB2 Information Center installed on your computer or intranet server . . . . .	42
Registering a DB2 product or feature license key using the License Center . . . . .	22	DB2 tutorials . . . . .	43
Checking DB2 license compliance . . . . .	22	DB2 troubleshooting information . . . . .	44
Upgrading a Trial license . . . . .	23	Terms and Conditions . . . . .	44
<b>Appendix A. Installing DB2 products using response files . . . . .</b>	<b>25</b>	<b>Appendix E. Notices . . . . .</b>	<b>47</b>
Response file installation basics. . . . .	25	<b>Index . . . . .</b>	<b>51</b>



---

## Chapter 1. Installation prerequisites

---

### Disk and memory requirements

#### Disk requirements

The disk space required for your product depends on the type of installation you choose and the type of file system you have. The DB2® Setup wizard provides dynamic size estimates based on the components selected during a typical, compact, or custom installation.

Remember to include disk space for required databases, software and communication products.

On Linux® and UNIX® operating systems, 2 GB of free space in the /tmp directory is recommended.

#### Memory requirements

At a minimum, a DB2 database system requires 256 MB of RAM. For a system running just a DB2 product and the DB2 GUI tools, a minimum of 512 MB of RAM is required. However, 1 GB of RAM is recommended for improved performance. These requirements do not include any additional memory requirements for other software that is running on your system.

When determining memory requirements, be aware of the following:

- DB2 products that run on HP-UX Version 11i for Itanium-based systems require 512 MB of RAM at a minimum.
- For IBM® data server client support, these memory requirements are for a base of five concurrent client connections. You will need an additional 16 MB of RAM per five client connections.
- Memory requirements are affected by the size and complexity of your database system, as well as by the extent of database activity and the number of clients accessing your system.

For DB2 server products, the self-tuning memory feature simplifies the task of memory configuration by automatically setting values for several memory configuration parameters. When enabled, the memory tuner dynamically distributes available memory resources among several memory consumers including sort, the package cache, the lock list and buffer pools.

- On Linux operating system, SWAP space at least twice as large as RAM is recommended.

---

### Windows installation prerequisites

#### Installation requirements for DB2 servers and IBM data server clients (Windows)

To install a DB2 product, the following operating system, software, and hardware requirements must be met:

Table 1. Windows workstation platforms

Operating System	Prerequisites	Hardware
Windows® XP Professional (32-bit and x64)	Windows XP Service Pack 2 or later	All Intel® and AMD processors capable of running the supported Windows operating systems (32-bit and x64 based systems)
Windows Vista Ultimate (32-bit and x64)	IBM Data Server Provider for .NET client applications and CLR server-side procedures require .NET 1.1 SP1 or .NET 2.0 framework runtime	
Windows Vista Business (32-bit and x64)		
Windows Vista Enterprise (32-bit and x64)		
	64-bit IBM data server provider for .NET applications are supported	

Table 2. Windows server platforms

Operating System	Prerequisites	Hardware
Windows 2003 Standard Edition (32-bit and x64)	Service Pack 1 or later.	All Intel and AMD processors capable of running the supported Windows operating systems
Windows 2003 Enterprise Edition (32-bit and x64)	R2 is also supported	
Windows 2003 Datacenter Edition (32-bit and x64)	IBM data server provider for .NET client applications and CLR server-side procedures require .NET 1.1 SP1 or .NET 2.0 framework runtime	
	64-bit IBM data server provider for .NET applications are supported	

#### Additional software considerations

- Windows Installer 3.0 is required. It will be installed by the installer if it is not detected.
- IBM Data Server Provider for .NET client applications and CLR server-side procedures require .NET 1.1 SP1 or .NET 2.0 framework runtime. In an x64 environment, 32-bit IBM data server provider for .NET applications will run in the WOW64 emulation mode.
- MDAC 2.8 is required. The DB2 Setup wizard will install MDAC 2.8 if it is not already installed.

**Note:** If a previous version of MDAC (for example, 2.7) is already installed, DB2 install will upgrade MDAC to 2.8. For a typical install, MDAC 2.8 is installed. For a custom install, MDAC 2.8 is installed but only if you have not deselected the default which is to install it. If you deselect MDAC as part of a custom install, it will not be installed.

- If you plan to use LDAP (Lightweight Directory Access Protocol), you should use either a Microsoft® LDAP client or the IBM Tivoli® Directory Server v6 client (also known as the IBM LDAP client which is included with DB2 products). Prior to installation of the Microsoft Active



Directory, you will need to extend your directory schema using the db2schex utility, which can be found on the installation media under the db2\Windows\utilities directory.

The Microsoft LDAP client is included with Windows operating systems.

- One of the following browsers is required to view online help, run the DB2 install launchpad (setup.exe), and to run First Steps (db2fs):
  - Internet Explorer 6 and up
  - Mozilla 1.4 and up
  - Firefox 1.0 and up
  - Netscape 7.0 and up

## Setting up Windows elevated privileges prior to installing a DB2 product (Windows)

The usual method to install a DB2 product on Windows is to use an Administrator user account. However, DB2 products can be installed using a non-administrator account. To do so, a Windows Administrator must configure the elevated privileges feature in Windows.

This task explains how a Windows Administrator can set up a computer with elevated privileges to allow installation using a non-Administrator user account. The related task of granting DB2 administration authorities to non-Administrator users is also covered.

Typically a Windows Administrator would perform this task to enable another person who does not have an Administrator account to install a DB2 product. The role of this person might be only to install DB2 products or to also administer DB2 products once installed.

Prior to initiating this procedure, note the following restrictions on non-Administrator installation using elevated privileges:

- Non-Administrator users can only install fix packs, add-on products, or upgrade DB2 as long as prior installations or upgrades were also performed by the same non-Administrator user.
- Non-Administrator users cannot uninstall a DB2 product. Those non-Administrator users on a Windows Vista (and later) operating system **can** uninstall a DB2 product.

This procedure uses the Windows Group Policy Editor.

1. Click **Start** -> **Run** and type gpedit.msc. The **Group Policy** window opens.
2. Click on Computer Configuration -> Administrative Templates -> Windows Components -> Windows Installer.
3. Enable the following Group Policy settings:
  - Always install with elevated privileges (mandatory)
  - Enable user control over installs (mandatory)
  - Disable Windows Installer. Then set it to *Never*.
  - Enable user to patch elevated products (optional)
  - Enable user to use media source while elevated (optional)
  - Enable user to browse for source while elevated (optional)
4. Enable elevated privileges for the user account that will be performing the installation.

- a. Click **User Configuration** → **Administrative Templates** → **Windows Components** → **Windows Installer**.
  - b. Enable the **Always install with elevated privileges (mandatory)** Group Policy setting.
5. Perform setup related to the user account that will install the DB2 product.
    - Identify the user account that will install the DB2 product. If necessary, create that account.
    - Give that account write permission for the drive on which an installation is planned.
  6. Optional: Complete additional steps applicable to installing fix packs:
    - Provide *read* access to the `sqllib\cfg` directory.
    - Ensure that *allowlockdownpatch* is enabled (as described in the Windows Installer SDK documentation) because fix pack installations are considered minor upgrades to the product.
  7. Refresh the computer's security policy in any one of the following ways:
    - Reboot the PC.
    - At the command line, enter `gpupdate.exe`.

By following this procedure you will have set up the computer with elevated privileges and set up a user account that will be able to install DB2 server products, clients and fix packs.

After DB2 installation is complete:

- Any user in the system administrative (SYSADM) or system control (SYSCTRL) authority group defined in the database manager configuration for the instance can create and use DB2 databases within the DB2 instance.
- Only a user with local Administrator authority can run DB2 instance utilities, such as `db2icrt`, `db2idrop`, `db2iupdt`, or `db2imigr`.
- The authorization requirements for running the `db2start` or `db2stop` command is defined in the topics `START DATABASE MANAGER` command, and `STOP DATABASE MANAGER` command.

### Using regedit instead of the Windows Group Policy Editor

An alternative to using the Windows Group Policy Editor is to use `regedit`.

1. In the registry branch `HKEY_LOCAL_MACHINE\SOFTWARE\Policies\Microsoft\Windows`, add the key `installer`
2. Edit the key `installer` with the following values:
  - For `AlwaysInstallElevated`, enter `REG_DWORD=1`
  - For `AllowLockdownBrowse`, enter `REG_DWORD=1`
  - For `AllowLockdownMedia`, enter `REG_DWORD=1`
  - For `AllowLockdownPatch`, enter `REG_DWORD=1`
  - For `DisableMSI`, enter `REG_DWORD=0`
  - For `EnableUserControl`, enter `REG_DWORD=1`
3. In the registry branch `HKEY_CURRENT_USER\SOFTWARE\Policies\Microsoft\Windows`, add the key `installer`
4. Edit the key `installer` with the following values:
  - For `AlwaysInstallElevated`, enter `REG_DWORD=1`

### Removing elevated privileges

After you have given elevated privileges, you can reverse this action. To do so, remove the registry key `Installer` under `HKEY_LOCAL_MACHINE\SOFTWARE\Policies\Microsoft\Windows`.

### **Granting a non-administrator user DB2 administration authorities**

At this point, only members of the Windows Administrators group will have DB2 administration authorities. The Windows Administrator has the option to grant one or more DB2 authorities, such as `SYSADM`, `SYSMAINT`, or `SYSCTRL` to the non-Administrator user who installed the DB2 product.

## **Granting user rights (Windows)**

This topic describes the steps required to grant user rights on Windows operating systems. Specific user rights are recommended for user accounts required to install and set up DB2.

To grant advanced user rights on Windows you must be logged on as a local Administrator.

1. Click **Start** -> **Run** and type `secpol.msc`. On Windows Vista, click **Start** and type `secpol.msc` in the search bar. Click **OK**.
2. Select **Local Security Policy**.
3. In the left window pane, expand the **Local Policies** object, then select **User Rights Assignment**.
4. In the right window pane, select the user right that you want to assign.
5. From the menu, select **Action** —> **Security...**
6. Click **Add**, then select a user or group to assign the right to, and click **Add**.
7. Click **OK**.

If your computer belongs to a Windows domain, the domain user rights may override your local settings. In this case, your Network Administrator will have to make the changes to the user rights.

## **DB2 system administrator group considerations (Windows)**

By default, system administrative (`SYSADM`) authority is granted to any valid DB2 user account that belongs to the Administrators group on the computer where the account is defined. If the account is a local account, then it must belong to the local Administrators group. If the account is a domain account, then it must belong to the Administrators group at the domain controller or the local Administrators group. You can force the DB2 database server to always perform group lookup on the local computer by setting the registry variable `DB2_GRP_LOOKUP=local` and adding the domain accounts (or global groups) to the local group.

For example, if a user logs on to a domain account and tries to access a DB2 database, the DB2 database server goes to a domain controller to enumerate groups (including the Administrators group).

For a domain user to have `SYSADM` authority, they must belong to the local Administrators group or the Administrators group at the domain controller. Since the DB2 database server always performs authorization at the machine where the account is defined, adding a domain user to the local Administrators group on the server does not grant the domain user `SYSADM` authority to this group, unless `DB2_GRP_LOOKUP=local` is set.

To avoid adding a domain user to the Administrators group at the domain controller, create a global group and add the domain users to which you want to grant SYSADM authority to it. Then update the DB2 configuration parameter SYSADM\_GROUP with the name of the global group.

To update the DB2 configuration parameter, enter the following commands:

```
db2 update dbm cfg using sysadm_group global_group
db2stop
db2start
```

---

## Linux installation prerequisites

### Installation requirements for DB2 servers and IBM data server clients (Linux)

For the latest information on supported Linux distributions, point your browser to <http://www.ibm.com/software/data/db2/linux/validate/>.

To install DB2 products, the distribution requirements, hardware, and communications prerequisites must be met.

DB2 products are supported on the following hardware:

- x86 (Intel Pentium®, Intel Xeon®, and AMD) 32-bit Intel and AMD processors
- x64 (64-bit AMD64 and Intel EM64T processors)
- POWER™ (IBM eServer™ OpenPower™, System i™ or pSeries® systems that support Linux)
- eServer System z™ or System z9™

The supported operating systems for Linux include:

- Red Hat Enterprise Linux (RHEL) 4 Update 4
- Red Hat Enterprise Linux (RHEL) 5
- SUSE Linux Enterprise Server (SLES) 9 Service Pack 3
- SUSE Linux Enterprise Server (SLES) 10 Service Pack 1

**Note:** POWER requires a minimum of SLES 10 Service Pack 1 or RHEL 5

### Multithreaded architecture limitations

If you are installing a DB2 Version 9.5 32-bit database product on a Linux operating system, consider upgrading to a 64-bit operating system and installing the DB2 Version 9.5 64-bit database product instead. The multithreaded architecture generally simplifies memory configuration. However, this could affect the memory configuration of 32-bit DB2 servers. For example:

- Private memory for agent threads is allocated within a single process. The aggregate of all private memory allocations for database agents might not fit in a single process memory space.
- Support for multiple databases is limited because all database shared memory segments for all databases are allocated in a single process. You might need to reduce the memory usage for some databases in order to activate all databases successfully at the same time. However, the database manager performance might be impacted. Another alternative is to create multiple instances and

catalog the databases across the instances. However, sufficient system resources is required to support this configuration.

## Distribution Requirements

You should update your kernel configuration parameters in preparation for your Linux distribution. The default values for particular kernel parameters might not be sufficient when running a DB2 database system.

You might also have other products or applications that require Linux system resources. You should modify the kernel configuration parameters based on the needs of your Linux system working environment.

The kernel configuration parameters are set in `/etc/sysctl.conf`.

Refer to your operating system manual for information on setting and activating these parameters using the `sysctl` command.

## Package requirements

The following tables list the package requirements for SLES and RHEL distributions for DB2 Version 9.5:

- `libaio.so.1` is required for DB2 servers using asynchronous i/o.
- `libstdc++so.5` is required for DB2 servers and clients.

Package requirements for SLES and RHEL

Package name	Description
<code>libaio</code>	contains the asynchronous library required for DB2 servers.
<code>compat-libstdc++</code>	contains <code>libstdc++so.5</code> (not required for Linux on POWER)

The following tables list the package requirements for SUSE Linux and Red Hat distributions for DB2 Version 9.5 partitioned servers.

- The `pdksh` Korn Shell package is required for all DB2 systems.
- A remote shell utility is required for partitioned database systems. DB2 supports the following remote shell utilities:
  - `rsh`
  - `ssh`

By default, DB2 uses `rsh` when executing commands on remote DB2 nodes, for example, when starting a remote DB2 database partition. To use the DB2 default, the `rsh-server` package must be installed (see table below). More information on `rsh` and `ssh` is available in the DB2 Information Center.

If you choose to use the `rsh` remote shell utility, `inetd` (or `xinetd`) must be installed and running as well. If you choose to use the `ssh` remote shell utility, you need to set the `DB2RSHCMD` communication variable immediately after the DB2 installation is complete. If this registry variable is not set, `rsh` is used.

- The `nfs-utils` Network File System support package is required for partitioned database systems.

All required packages should be installed and configured before continuing with the DB2 setup. For general Linux information, see your Linux distribution documentation.

#### Package requirements for SUSE Linux

Package name	Description
pdksh	Korn Shell. This package is required for partitioned database environments.
openssh	This package contains a set of server programs which allow users to run commands on (and from) remote computers via a secure shell. This package is not required if you use the default configuration of DB2 with rsh.
rsh-server	This package contains a set of server programs which allow users to run commands on remote computers, login in to other computers, and copy files between computers (rsh, rexec, rlogin, and rcp). This package is not required if you configure DB2 to use ssh.
nfs-utils	Network File System support package. It allows access to local files from remote computers.

#### Package requirements for Red Hat

Directory	Package name	Description
/System Environment/Shell	pdksh	Korn Shell. This package is required for partitioned database environments.
/Applications/Internet	openssh	This package contains a set of client programs which allow users to run commands on a remote computer via a secure shell. This package is not required if you use the default configuration of DB2 with rsh.
/System Environment/Daemons	openssh-server	This package contains a set of server programs which allow users to run commands from a remote computer via a secure shell. This package is not required if you use the default configuration of DB2 with rsh.
/System Environment/Daemons	rsh-server	This package contains a set of programs which allow users to run commands on a remote computer. Required for partitioned database environments. This package is not required if you configure DB2 to use ssh.
/System Environment/Daemons	nfs-utils	Network File System support package. It allows access to local files from remote computers.

### Software considerations

- (Clients only) If you plan to use Kerberos Authentication, you require IBM Network Authentication Service client v1.4 or later. The NAS client can be downloaded from <https://www6.software.ibm.com/dl/dm/dm-nas-p>.
- One of the following browsers is required to view online help and to run First Steps (db2fs):
  - Mozilla 1.4 and up
  - Firefox 1.0 and up
  - Netscape 7.0 and up

- An X Window System software capable of rendering a graphical user interface is required if:
  - you want to use the DB2 Setup wizard to install a DB2 product on Linux or UNIX operating systems, or
  - you want to use any DB2 graphical tools on Linux for x86 and Linux on AMD 64/EM64T.

## DB2 product installation on NFS (Network File System)

The installation of DB2 products on NFS (Network File System) is not recommended. Running DB2 products on NFS (for example, NFS mounting /opt/IBM/db2/V9.5 and then running off code that was physically installed on a remote system) requires several manual setup steps. There are also a number of potential issues with setting up NFS for DB2. These include possible problems that involve:

- Performance (impacted by network performance)
- Availability (you are allowing a single point of failure)
- Licensing (there is no checking done across machines)
- Diagnosing NFS errors can be difficult

As mentioned, the setup for NFS will require several manual actions including:

- Ensuring that the mount point preserve the install path
- Permission must be controlled (for example, write permission should not be given to the mounting machine)
- DB2 registries have to be set up manually and maintained across all mounting machines
- The db2ls command, which lists installed DB2 products and features, must be set up and maintained properly if you need to detect DB2 products and features
- More care is required when updating your DB2 product environment
- More steps are required when cleaning up on the exporting machine and the mounting machine

For detailed instructions, see the “Setting up DB2 for UNIX and Linux on NFS mounted file systems” white paper in <http://www.ibm.com/developerworks/db2/library/long/dm-0609lee>.

## Security-enhanced Linux considerations

On RHEL 4 and RHEL 5 systems, if Security-enhanced Linux (SELinux) is enabled and in enforcing mode, the installer might fail due to SELinux restrictions.

To determine if SELinux is installed and in enforcing mode, you can do one of the following:

- check the /etc/sysconfig/selinux file
- run the **sestatus** command
- check the /var/log/messages file for SELinux notices (Notice format might differ between RHEL 4 and RHEL 5.)

To disable SELinux, you can do one of the following:

- set it in permissive mode and run the **setenforce 0** command as a superuser
- modify /etc/sysconfig/selinux and reboot the machine.

If your DB2 product installs successfully on a RHEL 4 or RHEL 5 system, DB2 processes will run in the unconfined domain. To assign DB2 processes to their own domains, modify the policy. A sample SELinux policy is provided in the `sqlib/samples` directory.

## Centralized user-management considerations (Linux and UNIX)

In environments that include security software, there are some installation considerations.

**Note:** The DB2 installation cannot update or create users and groups if they are controlled outside of the operating system. For example, LDAP can be used to control users and groups outside of the operating system.

**Note:** Network Information Services (NIS) and Network Information Services Plus (NIS+) features are deprecated starting with DB2 Version 9.1 Fix Pack 2. Support for these features might be removed in a future release. Lightweight Directory Access Protocol (LDAP) is the recommended solution for centralized user-management services.

At instance creation, without a security component present, the instance owner's group list is modified to include that of the database administrative server (DAS) user's primary group, if the DAS is created. If the instance creation program is unable to modify these properties, it reports that it could not. The warning message provides the necessary information to manually make the changes.

These considerations hold true for any environment in which an external security program does not allow the DB2 installation or instance creation programs to modify user characteristics.



---

## Chapter 2. Installing your DB2 product

---

### Installing DB2 servers (Windows)

This task describes how to start the DB2 Setup wizard on Windows. You will use the DB2 Setup wizard to define your installation and install your DB2 product on your system.

#### Prerequisites

Before you start the DB2 Setup wizard:

- If you are planning on setting up a partitioned database environment, see the "Setting up a partitioned database environment" topic.
- Ensure that your system meets installation, memory, and disk requirements.
- If you are planning to use LDAP on Windows to register the DB2 server in Active Directory, you should extend the directory schema before you install.
- You must have a local *Administrator* user account with the recommended user rights to perform the installation. In DB2 servers where LocalSystem can be used as the DAS and DB2 instance user and you are not using the database partitioning feature, a non-administrator user with elevated privileges can perform the installation.

**Note:** If a non-Administrator user account is going to do the product installation, then the VS2005 runtime library must be installed before attempting to install a DB2 product. The VS2005 runtime library is needed on the operating system before the DB2 product can be installed. The VS2005 runtime library is available from the Microsoft runtime library download web site. There are two choices: choose `vcredist_x86.exe` for 32-bit systems or `vcredist_x64.exe` for 64-bit systems.

- Although not mandatory, it is recommended that you close all programs so that the installation program can update any files on the computer without requiring a reboot.

#### Restrictions

- The DB2 copy name and the instance name cannot start with a numeric value.
- The DB2 copy name and the instance name must be unique among all DB2 copies.
- The use of XML features is restricted to a database that has only one database partition.
- No other DB2 product can be installed in the same path if one of the following is already installed:
  - IBM Data Server Runtime Client
  - IBM Data Server Driver for ODBC, CLI, and .NET
  - DB2 Information Center.
- The DB2 Setup wizard fields do not accept non-English characters.
- If you enable extended security on Windows Vista, users must belong to the DB2ADMNS or DB2USERS group to run local DB2 commands and applications because of an extra security feature (User Access Control) that limits the privileges that local administrators have by default. If

users do not belong to one of these groups, they will not have read access to local DB2 configuration or application data.

To start the DB2 Setup wizard:

1. Log on to the system with the local Administrator account that you have defined for the DB2 installation.
2. If you the DB2 product DVD, insert it into the drive. If enabled, the auto-run feature automatically starts the DB2 Setup Launchpad. If the auto-run does not work, use Windows Explorer to browse the DB2 product DVD and double-click on the setup icon to start the DB2 Setup Launchpad.
3. If you downloaded the DB2 product from passport advantage, run the executable file to extract the DB2 product installation files. Use Windows Explorer to browse the DB2 installation files and double-click on the setup icon to start the DB2 Setup Launchpad.
4. From the DB2 Setup Launchpad, you can view installation prerequisites and the release notes, or you can proceed directly to the installation. You may want to review the installation prerequisites and release notes for late-breaking information.
5. Click **Install a Product** and the **Install a Product** window will display the products available for installation.  
If you have no existing DB2 products installed on your computer, launch the installation by clicking **Install New**. Proceed through the installation following the DB2 Setup wizard's prompts.  
If you have at least one existing DB2 product installed on your computer, you can:
  - Click **Install New** to create a new DB2 copy.
  - Click **Work with Existing** to upgrade an existing DB2 copy, to add functionality to an existing DB2 copy, migrate an existing DB2 Version 8 or Version 9.1 copy, or to install an add-on product.
6. The DB2 Setup wizard will determine the system language, and launch the setup program for that language. Online help is available to guide you through the remaining steps. To invoke the online help, click **Help** or press **F1**. You can click **Cancel** at any time to end the installation.

Your DB2 product will be installed, by default, in the <Program Files>\IBM\sqllib directory, where <Program Files> represents the location of the Program Files directory.

If you are installing on a system where this directory is already being used, the DB2 product installation path will have `_xx` added to it, where `_xx` are digits, starting at 01 and increasing depending on how many DB2 copies you have installed.

You can also specify your own DB2 product installation path.

For information on errors encountered during installation, review the installation log file located in the My Documents\DB2LOG\ directory. The log file uses the following format: DB2-ProductAbrev-DateTime.log, for example, DB2-ESE-Tue Apr 04 17\_04\_45 2006.log.

If you want your DB2 product to have access to DB2 documentation either on your local computer or on another computer on your network, then you must install the DB2 Information Center. The DB2 Information Center contains documentation for

the DB2 database system and DB2 related products. By default, DB2 information will be accessed from the web if the DB2 Information Center is not locally installed.

#### **DB2 Express and DB2 Workgroup Server Edition memory limits**

If you are installing DB2 Express Edition, the maximum allowed memory for the instance is 4GB.

If you are installing DB2 Workgroup Server Edition, the maximum allowed memory for the instance is 16GB.

The amount of memory allocated to the instance is determined by the `INSTANCE_MEMORY` database manager configuration parameter.

#### **Important notes when migrating from Version 9.1:**

- If the memory configuration for your Version 9.1 DB2 product exceeds the allowed limit, the DB2 product might not start after migrating to the current version.
- The self tuning memory manager will not increase your overall instance memory limit beyond the license limits.

---

## **Installing DB2 servers using the DB2 Setup wizard (Linux and UNIX)**

This task describes how to start the DB2 Setup wizard on Linux and UNIX systems. The DB2 Setup wizard is used to define your installation preferences and to install your DB2 product on your system.

Before you start the DB2 Setup wizard:

- If you are planning on setting up a partitioned database environment, see how to do this by following the related link at the bottom of this topic.
- Ensure that your system meets installation, memory, and disk requirements.
- You can install a DB2 server using either root or non-root authority. For more information on non-root installation, see the related links.
- The DB2 product image must be available. You can obtain a DB2 installation image either by purchasing a physical DB2 product DVD, or by downloading an installation image from Passport Advantage.
- If you are installing a non-English version of a DB2 database product, you must have the appropriate National Language Packages.
- The DB2 Setup wizard is a graphical installer. You must have X windows software capable of rendering a graphical user interface for the DB2 Setup wizard to run on your machine. Ensure that the X windows server is running. Ensure that you have properly exported your display. For example, export `DISPLAY=9.26.163.144:0`.
- If you are using security software in your environment, you must manually create required DB2 users before you start the DB2 Setup wizard.

#### **Note:**

- The use of XML features is restricted to a database that is defined with the code set UTF-8 and has only one database partition.
- The DB2 Setup wizard fields do not accept non-English characters.

To start the DB2 Setup wizard:

1. If you have a physical DB2 product DVD, change to the directory where the DB2 product DVD is mounted by entering the following command:

```
cd /dvdrom
```

where */dvdrom* represents mount point of the DB2 product DVD.

2. If you downloaded the DB2 product image, you must decompress and untar the product file.
  - a. Decompress the product file:  

```
gzip -d product.tar.gz
```

where *product* is the name of the product that you downloaded.

- b. Untar the product file:

**On Linux operating systems**

```
tar -xvf product.tar
```

**On AIX®, HP-UX, and Solaris operating systems**

```
guntar -xvf product.tar
```

where *product* is the name of the product that you downloaded.

- c. Change directory:

```
cd ./product
```

where *product* is the name of the product that you downloaded.

**Note:** If you downloaded a National Language Package, untar it into the same directory. This will create the subdirectories (for example *./nlpack/disk1*) in the same directory, and allows the installer to automatically find the installation images without prompting.

3. Enter the *./db2setup* command from the directory where the product image resides to start the DB2 Setup wizard.
4. The IBM DB2 Setup Launchpad opens. From this window, you can view installation prerequisites and the release notes, or you can proceed directly to the installation. You may want to review the installation prerequisites and release notes for late-breaking information.
5. Click **Install a Product** and the **Install a Product** window will display the products available for installation.

Launch the installation by clicking **Install New**. Proceed through the installation following the DB2 Setup wizard's prompts.

Once you have initiated the installation, proceed through the DB2 Setup wizard installation panels and make your selections. Installation help is available to guide you through the remaining steps. To invoke the installation help, click **Help** or press F1. You can click **Cancel** at any time to end the installation.

For non-root installations, DB2 products are always installed in the *\$HOME/sqllib* directory, where *\$HOME* represents the non-root user's home directory.

For root installations, DB2 products are installed, by default, in one of the following directories:

**AIX, HP-UX, and Solaris**

```
/opt/IBM/db2/V9.5
```

**Linux** /opt/ibm/db2/V9.5

If you are installing on a system where this directory is already being used, the DB2 product installation path will have *\_xx* added to it, where *\_xx* are digits, starting at 01 and increasing depending on how many DB2 copies you have installed.

You can also specify your own DB2 product installation path.

DB2 installation paths have the following rules:

- Can include lowercase letters (a–z), uppercase letters (A–Z), and the underscore character ( \_ )
- Cannot exceed 128 characters
- Cannot contain spaces
- Cannot contain non-English characters

National Language Packs can also be installed by running the `./db2setup` command from the directory where the National Language Pack resides, after a DB2 database product has been installed.

The installation log files are:

- The DB2 setup log file. This file captures all DB2 installation information including errors.
  - For root installations, the DB2 setup log file name is `db2setup.log`.
  - For non-root installations, the DB2 setup log file name is `db2setup_username.log`, where *username* is the non-root user ID under which the installation was performed.
- The DB2 error log file. This file captures any error output that is returned by Java™ (for example, exceptions and trap information).
  - For root installations, the DB2 error log file name is `db2setup.err`.
  - For non-root installations, the DB2 error log file name is `db2setup_username.err`, where *username* is the non-root user ID under which the installation was performed.

By default, these log files are located in the `/tmp` directory. You can specify the location of the log files.

There is no longer a `db2setup.his` file. Instead, the DB2 installer saves a copy of the DB2 setup log file in the `DB2_DIR/install/logs/` directory, and renames it `db2install.history`. If the name already exists, then the DB2 installer renames it `db2install.history.xxxx`, where `xxxx` is 0000-9999, depending on the number of installations you have on that machine.

Each installation copy has a separate list of history files. If an installation copy is removed, the history files under this install path will be removed as well. This copying action is done near the end of the installation and if the program is stopped or aborted before completion, then the history file will not be created.

On Linux x86, if you want your DB2 product to have access to DB2 documentation either on your local computer or on another computer on your network, then you must install the DB2 Information Center. The DB2 Information Center contains documentation for the DB2 database system and DB2 related products.

### **DB2 Express and DB2 Workgroup Server Edition memory limits**

If you are installing DB2 Express Edition, the maximum allowed memory for the instance is 4GB.

If you are installing DB2 Workgroup Server Edition, the maximum allowed memory for the instance is 16GB.

The amount of memory allocated to the instance is determined by the `INSTANCE_MEMORY` database manager configuration parameter.

### **Important notes when migrating from Version 9.1:**

- If the memory configuration for your Version 9.1 DB2 product exceeds the allowed limit, the DB2 product might not start after migrating to the current version.
- The self tuning memory manager will not increase your overall instance memory limit beyond the license limits.

---

## Chapter 3. Verifying your installation

---

### Verifying the installation of DB2 servers using First Steps (Linux and Windows)

You should verify that the DB2 server installation has completed successfully by accessing data from the SAMPLE database.

You must have the Control Center and the First Steps component installed to perform this task.

First Steps is listed as a getting started component in the feature selection window in the DB2 Setup wizard. It is installed as part of a Typical installation or may be selected when performing a Custom installation.

The Control Center component is only available on Linux (x86 and AMD64/EM64T only) and Windows (x86 and AMD64/EM64T only).

1. On Linux, log on to the system as the instance owner.
2. Start First Steps:
  - On Windows operating systems, click **Start** and, select **Programs -> IBM DB2 -> [DB2 Copy Name] -> Set-up Tools > First Steps**
  - On Linux and Windows operating systems, you can start First Steps by typing the **db2fs** command.
3. Select **Database Creation** in the First Steps launchpad. On the Database Creation page, you will see links to the DB2 Information Center for creating the SAMPLE database and the **Create SAMPLE Database** button. Click **Create SAMPLE Database** to launch the Create SAMPLE Database window.
4. You have the options to choose the type of database objects to create and the database location. You can choose the drive on which to create the SAMPLE database on Windows, and the directory in which to create the SAMPLE database on Linux.
5. This command may take a few minutes to process. When the SAMPLE database has been created, you will receive a completion message. Click **OK**.
6. Launch the Control Center. On Windows, click **Start** and, select **Programs -> IBM DB2 -> [DB2 Copy Name] -> General Administration Tools -> Control Center**. On Linux systems, type the **db2cc** command.
7. In the left pane of the Control Center screen, expand the object tree to view the SAMPLE database and SAMPLE database objects. Select the Tables object to view the SAMPLE database tables in the right pane of the Control Center screen. Right-click on the table name staff and select Query. In the command editor window, click the run button to execute the query and see the result set.

After you have verified the installation, you can remove the SAMPLE database to free up disk space. However, you will need to keep the SAMPLE database if you plan to make use of the sample applications.

Enter the **db2 drop database sample** command to drop the SAMPLE database.

---

## Verifying the installation using the command line processor (CLP)

You can verify the installation by creating the SAMPLE database and running SQL commands to retrieve sample data.

### Prerequisites

- The SAMPLE database component, found in the features selection, must be installed on your system and is included in a typical installation.
- You require a user with SYSADM authority.

To verify the installation:

1. Log on to the system as a user with SYSADM authority.
2. Start the database manager by entering the db2start command.
3. Enter the db2sampl command to create the SAMPLE database.

This command may take a few minutes to process. There is no completion message; when the command prompt returns, the process is complete.

The SAMPLE database is automatically cataloged with the database alias SAMPLE when it is created.

4. Connect to the SAMPLE database, retrieve a list of all the employees that work in department 20, and reset the database connection. Enter the following commands from the command line processor (CLP):

```
connect to sample
"select * from staff where dept = 20"
connect reset
```

The output should be similar to the following:

ID	NAME	DEPT	JOB	YEARS	SALARY	COMM
10	Sanders	20	Mgr	7	98357.50	-
20	Pernal	20	Sales	8	78171.25	612.45
80	James	20	Clerk	-	43504.60	128.20
190	Sneider	20	Clerk	8	34252.75	126.50

4 record(s) selected.

After you have verified the installation, you can remove the SAMPLE database to free up disk space. Enter the db2 drop database sample command to drop the SAMPLE database.

---

## Creating your own database using the Create Database with the Automatic Maintenance wizard

The Create Database with Automatic Maintenance wizard is the quickest way to set up your own database. Based on basic information that you provide, the wizard:

- creates a new database on the disk or directory of your choice
- assigns disk space for your data
- configures the new database for optimal performance
- turns on automatic maintenance
- configures notification by e-mail or pager if the database needs attention

The Create Database with Automatic Maintenance wizard can be started from First Steps or directly from within the Control Center.



### Prerequisites

- If you wish to start the wizard from First Steps, you must also have the First Steps component installed. First Steps is part of the Getting started component grouping in the DB2 Setup wizard. It is installed as part of a Typical installation or may be selected when performing a Custom installation.
  - You must have SYSADM or SYSCTRL authority to perform this task.
  - For Linux, you must have Xwindow software capable of rendering a graphical user interface for First Steps and the Control Center to run on your machine. Ensure that you have properly exported your display. For example, export `DISPLAY=9.26.163.144:0`.
  - On Linux, ensure that you are logged on as the instance owner, `db2inst1` by default. An instance is a logical database manager environment where you catalog databases and set configuration parameters.
1. Log on to the system with the user account that you want to use to create the database.
  2. Start the Create Database with Automatic Maintenance in the one of the following ways:
    - From First Steps: Click **Create Your Own Database**.
    - From the Control Center: Click the **All Databases** folder. Click **Create New Database** in the **All Databases** pane.
  3. Follow the steps of the wizard. You will have to provide some details and preferences about your new database, including such things as its name and the contacts who can be notified under various conditions.

If you created your own database from First Steps, you will now want to start the Control Center to begin exploring and working with your database. To do this, click **Work With Databases** in First Steps.



---

## Chapter 4. DB2 product licensing

---

### DB2 license files

Your DB2 product will run without registering the license key. However, registering the license key is recommended as a mechanism for you to keep track of, and differentiate, the DB2 products and features you have installed on your system. You can find the DB2 product license terms at Software license agreements.

Installing a DB2 data server does not include registering a license key. You should register the license key before using the DB2 product or feature.

Registering the license key (also referred to as a license entitlement certificate) lets the DB2 license manager know which license keys you plan to use on each machine. This is also referred to as applying the license key.

Each DB2 product and DB2 feature comes with a license key. If you downloaded the DB2 product or feature image from Passport Advantage®, the license key is included in the Activation CD image. When using Passport Advantage, you must download the Activation CD image for *each* product and feature separately. If you receive your DB2 product or feature on a physical media pack from IBM, the license key is on the Activation CD.

If you purchased a base DB2 product, as well as, separately priced features, you will need to apply more than one license key. Each DB2 product and DB2 feature has its own license key. You should ensure that you have the correct license entitlements for the DB2 products and features you installed. For more information, see DB2 packaging or DB2 features and benefits.

DB2 Personal Edition and DB2 Connect™ Personal Edition are exceptions. If you installed DB2 Personal Edition or DB2 Connect Personal Edition, the license key is applied automatically as part of the base installation.

The management of licenses for DB2 products or features is done through either:

- the License Center within the Control Center, or,
- the db2licm license management tool command.

To assist you in managing your licenses, a compliance report lists the compliance or noncompliance of DB2 features with your current product entitlement. To be in compliance with your license agreement, you should apply the license key. However, even without applying a license key, your DB2 product will continue to operate without interruption or restriction, unless you installed a DB2 product trial image, or, installed a DB2 fix pack installation image. A trial DB2 product will stop working after a 90 day trial period. If you installed a DB2 fix pack installation image over an existing DB2 product acquired from Passport Advantage, the fix pack installation image will continue to operate uninterrupted.

DB2 product trial images include access to all features available in the edition you are using. You can download a DB2 try and buy image from Trials and demos.

If you installed a DB2 product with a trial license and now want to upgrade to a full license, you do not need to reinstall the DB2 product. You simply upgrade your license. For details see *Upgrading your DB2 license*.

**Note:** The trial license for DB2 Enterprise Server Edition on 32-bit Linux cannot be upgraded to a full production license.

**Note:** Under the processor Value Unit (PVU) licensing structure, each processor core will be assigned a specific number of Value Units. You must acquire the total number of processor Value Units for each processor core on which the software programs are deployed. IBM continues to define a processor to be each processor core on a chip. For example, a dual-core chip contains two processor cores. Each software program has a unique price per Value Unit. To determine the total cost of deploying an individual software program, you multiply the program price per Value Unit by the total number of processor Value Units required. The PVU calculator calculates the total number of PVU in your environment.

---

## Registering a DB2 product or feature license key using the License Center

The license key is available from either the DB2 product or feature image you downloaded from Passport Advantage, or from the Activation CD you received in the physical media pack from IBM.

On Linux or Windows operating systems, you can register license key using the License Center. On UNIX operating systems, use the `db2licm` command to register a license key.

On Linux operating systems, the instance owner must have read and write privileges on the directory where the license files are located.

To register a DB2 license key:

1. Start the DB2 Control Center and select **License Center** from the **Tools** menu.
2. Select the system for which you are installing a license. Select an instance on the system you selected. Select the product from installed products. The **Installed Products** field will display the name of the product that you have installed.
3. Select **Add** from the **License** menu.
4. In the Add License window, select the license file:
  - On Windows servers: `x:\db2\license\license_filename.lic`
  - On Linux servers: `/cd/db2/license/license_filename.lic`where `x:` or `/cd` represents the drive or mount point containing the Activation CD for the DB2 product or feature.
5. Click **Apply** to add the license key.

---

## Checking DB2 license compliance

Each DB2 product and feature has a license key associated with it. The license key should be registered before using the DB2 product or feature. The License Center lists product information on the main panel. DB2 products that do not have the license registered show the License Type as not registered.

To verify license compliance of DB2 features, you can generate a compliance report. The compliance report lists DB2 features out of compliance with your current product entitlement. Each DB2 feature status is listed as either:

- In compliance: indicating the feature has been used and is properly licensed
- Violation: indicating the feature is not licensed and has been used
- Not used: indicating the feature is properly licensed but has not been used.

**Note:** Some DB2 functionality is only available under license when purchased as part of a DB2 feature.

If you installed a DB2 product trial image, the image includes access to all features available in the edition you are using.

**Note:** The trial license for DB2 Enterprise Server Edition for 32-bit Linux cannot be upgraded to a full production license.

You can generate a compliance report using the License Center or the `db2licm` command.

- To generate the compliance report from the License Center, select License>Generate Compliance Report.
- To generate compliance report using the `db2licm` command, enter the following command from the command line:

– For Linux and UNIX operating systems:

```
db2instance_path/adm/db2licm -g filename
```

– For Windows operating systems:

```
db2instance_path\bin\db2licm -g filename
```

where

- *db2instance\_path* is where the DB2 instance was created.
- *filename* specifies the file name where output is to be stored.

DB2 features showing a violation should have the license key registered using either the License Center or the `db2licm` command. The License Center or the `db2licm` command can also be used to reset the license usage information. See the related links for details.

---

## Upgrading a Trial license

If you installed a DB2 product with a trial license and now want to upgrade to a full license you need to upgrade the product license key.

You cannot use this method to upgrade from one DB2 product to another.

If a previously licensed copy of a DB2 server product does not already exist on the machine, a single server fix pack image can be used to install any of the DB2 database server products. In this case, the DB2 product installed is treated as a trial license.

To upgrade your DB2 license:

1. Get the license key. The license key is available from either:
  - the activation key that you downloaded from Passport Advantage, or
  - the Activation CD that you received in the physical media pack from IBM.
2. Register the license key using the License Center or the `db2licm` command.

**Note:** The trial license for DB2 Enterprise Server Edition on 32-bit Linux cannot be upgraded to a production license.

---

## Appendix A. Installing DB2 products using response files

---

### Response file installation basics

Unlike the DB2 Setup wizard, a DB2 response file installation lets you install DB2 products without any user interaction.

A *response file* is an English-only text file that contains setup and configuration information. A response file specifies configuration and setup parameters and the products and components to install.

This method is useful not only for large-scale deployments of DB2 products, but also for embedding the DB2 installation process transparently inside your customized installation and configuration procedure.

You can create a response file by any of the following methods:

- Modifying one of the sample response files that are provided. Sample response files are located in the DB2 product DVD under the directory:  
`db2/platform/samples`

where *platform* refers to the appropriate hardware platform.

- Using the DB2 Setup wizard to save the setup and configuration data according to the input you provided. If you choose the option to create a response file in the DB2 Setup wizard, the response files (one for the server, and one for the partition, if you are setting up a multi-partitioned environment) will be saved by default at this location. The default names of the files are *name1* and *name2*.
- Using the response file generator to create a response file from an existing installed and configured DB2 product (Windows platforms only).

A response file installation can also be referred to as a silent installation or an unattended installation.

---

### Response file considerations

You should understand the following considerations before proceeding with a response file installation:

- Although response files created in Version 8 and response files created in Version 9 have similar formats, there are version limitations as to where response files can be used. For example, any response file generated in DB2 Version 9 can only be used to install a DB2 Version 9 (or Version 9.5) product; it cannot be used to install DB2 Version 8. The opposite is also true, where response files generated in DB2 Version 8 cannot be used to install DB2 Version 9. This is primarily caused by mandatory keywords that are new in Version 9.
- On Linux or UNIX platforms, a response file created for a root installation might not be usable for a non-root installation. Some response file keywords are valid for root installation only. For details, see the response file keywords.
- If you are using the DB2 Setup wizard:
  - You can save your settings in a response file during the installation in the **Select the installation action** panel of the DB2 Setup wizard.

- You are creating a response file based on just the installation you are performing. This method is recommended if you have either a fairly simple configuration or if you want to create a response file that you plan to later customize.
- A response file is only generated if you allow the installation process to complete, and it completes successfully. If you cancel the installation, or if the installation fails, the response file is not created.
- You can use a response file to install an identical configuration across every workstation on your network or to install multiple configurations of a DB2 product. You can then distribute this file to every workstation where you want this product to be installed.
- If you use the response file generator (Windows platforms only), you are creating the response file based on an existing installation. This method is recommended when you have a more complex configuration, one that you manually configured. If you are using the response file generator after generating the response file, you might need to input user names and passwords

---

## Creating a response file using the DB2 Setup wizard

You can create a response file using the DB2 Setup wizard based on the installation you are performing. This response file will be generated based on your DB2 Setup wizard selections. You can then use the response file to perform an unattended installation using the same settings.

To create a response file using the DB2 Setup wizard:

1. From the DB2 Setup launchpad, select **Install New** for the product you want to install, or, select **Work with Existing** to select the DB2 copy you want to work with.
2. Select the product or DB2 copy you want to install and click **Next** to launch the DB2 Setup wizard.
3. Click **Next** on the Welcome page and accept the license agreement terms.
4. In the **Select the installation type** window, select from Typical, Compact or Custom installation.
5. In the **Select the installation, response file creation, or both** window, select either the **Save my installation setting in a response file** option or the **Install product on this computer and save my settings in a response file** option. Then, in the **Response file name** field type the path where you want the DB2 Setup wizard to place the generated response file. By default, the response file name is *name1*, and is saved in *directory1*.

**Note:**

- a. If you select the **Save my installation setting in a response file** option, no software is installed on the computer, only the response file is created with the name specified in the **Response file name** field.
- b. If you select a partitioned database installation, two response files will be generated, one for the instance-owning computer and one for the participating computers. The participating computer response file name is generated based on the name of the instance-owning computer. By default, the partition response file name is *name2*, and is saved in *directory2*.
6. Proceed through the rest of the installation panels selecting the options you want.
7. In the **Start copying files and create response file** window, review the settings you selected.



8. To install the product, click **Finish**.
9. When the installation has completed, the DB2 Setup wizard will have placed the generated response file in the path you specified. When the DB2 Setup wizard is used to create the response file, a special keyword ENCRYPTED is added to the response file. For example:

```
DAS_PASSWORD = 07774020164457377565346654170244883126985535505156353  
ENCRYPTED = DAS_PASSWORD
```

The keyword ENCRYPTED indicates the actual value of the password is not the sequence of numbers shown.



---

## Appendix B. Applying DB2 fix packs

---

### Applying fix packs

It is recommended that you keep your DB2 environment running at the latest fix pack level to ensure problem-free operation. To install a fix pack successfully, perform all of the necessary pre-installation and post-installation tasks.

A DB2 fix pack contains updates and fixes for problems (Authorized Program Analysis Reports, or "APARs") found during testing at IBM, as well as fixes for problems reported by customers. Each fix pack contains an APARLIST.TXT file, which describes the fixes it contains.

Fix packs are cumulative. This means that the latest fix pack for any given version of DB2 contains all of the updates from previous fix packs for the same version of DB2.

The fix pack images available are:

- A single server image.

The single server image contains the new and updated code required for all DB2 server products and the IBM Data Server Client. If more than one DB2 server product is installed in a single location, the DB2 server fix pack applies maintenance code updates to all the installed DB2 server products. The Data Server Client fix pack is contained within the one DB2 server fix pack (namely the fix pack that can service any one of the following server products: Enterprise Server Edition, Workgroup Server Edition, Express Edition, Personal Edition, Connect Enterprise Edition, Connect Application Server Edition, Connect Unlimited Edition for zSeries®, and Connect Unlimited Edition for i5/OS®). You can use the DB2 server fix pack to upgrade a Data Server Client.

A single server image can also be used to install any of the DB2 database server products, at a particular fix pack level, with a DB2 try and buy license by default.

- A fix pack for each of the other DB2 database products.

Use this fix pack only if you only have non-server database products or add-on products installed. For example, IBM Data Server Runtime Client or Query Patroller.

Do not use this type of fix pack if the installed DB2 products are only DB2 server products or a Data Server Client. Instead, use the single server image fix pack.

For Windows platforms, if you have more than one DB2 database product (which includes at least one product that is not a Data Server Client or a DB2 server) installed in a single DB2 copy, you must download and uncompress all of the corresponding product-specific fix packs before starting the fix pack installation process.

- A universal fix pack (on Linux or UNIX platforms only).

The universal fix pack services installations where more than one DB2 database product has been installed.

The universal fix pack is not needed if the installed DB2 products are only DB2 server products or a Data Server Client. In this case, the single server image fix pack should be used.

## Restrictions

- A DB2 Version 9.5 fix pack can only be applied to DB2 Version 9.5 general availability (GA) or fix pack level copies.
- All DB2 instances, DAS, and applications related to the DB2 copy being updated must be stopped before installing a fix pack.
- If you are using the database partitioning feature (DPF), prior to installing the fix pack, you must stop the database manager on all nodes. You must install the fix pack on the instance owning node and all other partitioned nodes. All computers participating in the instance must be upgraded to the same fix pack level.
- On Linux or UNIX operating systems:
  - If you have DB2 products on a Network File System (NFS), you must ensure the following are stopped completely before installing the fix pack: all instances, the DB2 administration server (DAS), interprocess communications (IPC), and applications on other machines using the same NFS mounted installation.
  - If the system commands `fuser` or `lsof` are not available, the `installFixPack` command cannot detect loaded DB2 files. You must ensure no DB2 files are loaded and provide an override option to install the fix pack. On UNIX, the `fuser` command is required to check for loaded files. On Linux, either the `fuser` command or `lsof` command is required.  
For details on the override option, see the `installFixPack` command.
- On client applications, after a fix pack has been applied, to perform autobind of applications, the user must have bind authority.
- Installation of a DB2 fix pack will not service IBM Data Studio Administration Console or IBM Data Studio.

For non-root installations on Linux or UNIX, root-based features (such as High Availability and operating system-based authentication) can be enabled using the `db2rfe` command. If root-based features were enabled after installing your DB2 product, you must rerun the `db2rfe` command each time a fix pack is applied in order to re-enable those features. For details, see the non-root related links below.

On Linux or UNIX operating systems, if national languages have been installed, you also require a separate national language fix pack. The national language fix pack can not be installed alone. A universal or product-specific fix pack must be applied at the same time and they must both be at the same fix pack level. For example, if you are applying a universal fix pack to non-English DB2 database products on Linux or UNIX, you must apply both the universal fix pack and the national language fix pack to update the DB2 database products.

If you have multiple DB2 copies on the same system, those copies can be at different version and fix pack levels. If you want to apply a fix pack to one or more DB2 copies, you must install the fix pack on those DB2 copies one by one.

---

## Appendix C. Uninstalling your DB2 product

---

### Uninstalling your DB2 product (Windows)

This task provides steps for completely removing your DB2 product from your Windows operating system. You should only perform this task if you no longer require existing your DB2 instances and databases.

If you are uninstalling the DB2 default copy, and you have other DB2 copies on your system, you should use the `db2swtch` command to choose a new default copy before you proceed with the uninstallation. Also, if your database administration server (DAS) is running under the copy being removed, you should move your DAS to a copy that is not being removed. Otherwise, you will have to recreate the DAS using `db2admin create` command after the uninstall and you might have to reconfigure the DAS for some functionality to work.

To remove your DB2 product from Windows:

1. (Optional) Drop all databases using the Control Center or drop database command. Be sure that you no longer need these databases. If you drop your databases, all of your data will be gone.
2. Stop all DB2 processes and services. This can be done through the Windows Services panel or by issuing the `db2stop` command. If DB2 services and processes are not stopped before attempting to remove your DB2 product, you will receive a warning containing a list of processes and services that are holding DB2 DLLs in memory.
3. You have two options for removing your DB2 product:

#### **Add/Remove Programs**

Accessible through the Windows Control Panel, use the Add/Remove Programs window to remove your DB2 product. Refer to your operating system's help for more information about removing software products from your Windows operating system.

#### **db2unins command**

You can run the `db2unins` command to remove your DB2 product. Using this command, you can uninstall multiple DB2 products at the same time using the `/p` parameter. You can also silently uninstall DB2 products by using `/u` parameter which will remove the DB2 products specified in the response file. For more information, see the `db2unins` command topic.

Unfortunately, your DB2 product cannot always be removed by using the Control Panel - Add/Remove Programs facility or using the `db2unins /p` command or the `db2unins /u` command. The following uninstallation option should ONLY be attempted if the above method fails.

To forcefully remove all DB2 copies from your Windows system, run the `db2unins /f` command. This command will perform a brute force uninstallation of ALL DB2 copies on the system. Everything except user data, such as DB2 databases, will be forcefully deleted.

---

## Uninstalling your DB2 product (Linux and UNIX)

This task provides steps for removing a DB2 product from your Linux or UNIX operating system.

This task is not required to install a new version of a DB2 product. Each version of a DB2 product on Linux or UNIX has a different installation path and can therefore coexist on the same computer.

**Note:** This task applies to DB2 products that were installed with root authority. A separate topic explains how to uninstall DB2 products that were installed as a non-root user.

To remove your DB2 product:

1. Optional: Drop all databases. You can drop databases using the Control Center or the drop database command. Database files remain intact on your file systems when you drop an instance without dropping databases first.
2. Stop the DB2 Administration Server. Refer to the *Quick Beginnings for DB2 Servers* manual.
3. Remove the DB2 Administration Server, or run the `dasupdt` command to update the DB2 Administration Server to another installation path. To remove the DB2 Administration Server, refer to the *Quick Beginnings for DB2 Servers* manual.
4. Stop all DB2 instances. Refer to the *Quick Beginnings for DB2 Servers* manual.
5. Remove the DB2 instances, or run the `db2iupdt` command to update the instances another installation path. To remove the DB2 instances, refer to the *Quick Beginnings for DB2 Servers* manual.
6. Remove the DB2 products. Refer to the *Quick Beginnings for DB2 Servers* manual.

## Stopping the DB2 administration server (Linux and UNIX)

You must stop the DB2 administration server (DAS) before you remove your DB2 product.

When uninstalling a DB2 product, you must drop the DAS if you are removing your last DB2 Version 9.5 copy. If you have other DB2 Version 9.5 copies, it is recommended that you run the `dasupdt` command to associate the DAS with another DB2 copy. If you decide to drop the DAS, you must stop the DAS first.

**Note:** This task does not apply to non-root installations of DB2 products.

To stop the DB2 administration server:

1. Log in as the DB2 administration server owner.
2. Stop the DB2 administration server by entering the `db2admin stop` command.

## Removing the DB2 administration server (Linux and UNIX)

If you are removing your last DB2 Version 9 copy, you must remove the DB2 administration server (DAS) before you remove your DB2 product.

If you removing a DB2 Version 9 copy, but have other DB2 Version 9 copies, you should run the `dasupdt` command from the DB2 copy that you would like to have the DB2 DAS associated with.

**Note:** This task applies only to DB2 products that were installed with root authority.

To remove the DAS:

1. Log in as a user with root authority.
2. Stop the DAS:  
`db2admin stop`
3. Remove the DAS by entering the following command:  
`DB2DIR/instance/dasdrop`

where *DB2DIR* is the location you specified during the DB2 installation. The default installation path for UNIX is */opt/IBM/db2/V9.5*. The default installation path for Linux is */opt/ibm/db2/V9.5*.

## Stopping root instances (Linux and UNIX)

You must stop all DB2 instances associated with the DB2 copy you are uninstalling. Instances associated with other DB2 copies should not be affected by uninstalling the current copy.

**Note:** This task applies to DB2 products that were installed with root authority.

To stop a DB2 instance:

1. Log in as a user with root authority.
2. Obtain a list of the names of all DB2 instances associated with your current DB2 copy by entering the following command:  
`DB2DIR/bin/db2ilist`

where *DB2DIR* is the location you specified during the DB2 Version 9 installation. The default installation path for UNIX is */opt/IBM/db2/V9.5*. The default installation path for Linux is */opt/ibm/db2/V9.5*.

3. Run the start up script if it is not included in `.profile`.  
`. INSTHOME/sqllib/db2profile` (bash, Bourne, or Korn shells)  
`source INSTHOME/sqllib/db2cshrc` (C shell)

where *INSTHOME* is the home directory of the instance.

4. It is recommended that you save the following files:
  - The database manager configuration file, `$HOME/sqllib/db2system`
  - The node configuration file, `$HOME/sqllib/db2nodes.cfg`
  - User defined functions or fenced stored procedure applications in `$HOME/sqllib/function`
5. Stop the DB2 database manager by entering the `db2stop force` command.
6. Confirm that the instance is stopped by entering the `db2 terminate` command.
7. Repeat these steps for each instance.

## Removing DB2 instances (Linux and UNIX)

This task explains how to remove some or all of the root instances on your system.

**Note:** This task does not apply to non-root installations. To remove a non-root instance, you must uninstall your DB2 product.

If you are removing your last DB2 Version 9 copy, you can remove the DB2 instances before you remove your DB2 product. If you removing a DB2 Version 9 copy, but have other DB2 Version 9 copies, you can run the `db2iupdt` command from the DB2 copy that you would like to have the DB2 instances associated with.

Once an instance is removed, you can use the DB2 databases owned by the instance if you catalog them under another instance of the same release. Even though you remove the instance, the databases are still intact and can be reused unless the database files are expressly deleted.

Remove DB2 instances only if you are not planning to use your DB2 products, or if you do not want to migrate existing instances to a later version of the DB2 product. Migration requires that both the new and old DB2 versions are still installed. You cannot migrate an instance if the DB2 copy it is associated with has been removed.

To remove an instance:

1. Log in as a user with root authority.
2. Optional: If you are certain you no longer need the data in the associated databases, you can remove the database files from the systems or drop the databases before dropping the instance.
3. Remove the instance by entering the following command:

```
DB2DIR/instance/db2idrop InstName
```

where *DB2DIR* is the location you specified during the DB2 installation. The default installation path for UNIX is `/opt/IBM/db2/V9.5`. The default installation path for Linux is `/opt/ibm/db2/V9.5`.

The `db2idrop` command removes the instance entry from the list of instances and removes the *INSTHOME*/`sqllib` directory, where *INSTHOME* is the home directory of the instance and where *InstName* is the login name of the instance. If you are storing any files in `/sqllib` directory, these files will be removed by this action. If you still need these files, you must make a copy of them before dropping the instance.

4. Optional: As a user with root authority, remove the instance owner's user ID and group (if used only for that instance). Do not remove these if you are planning to re-create the instance.

**Note:** This step is optional since the instance owner and the instance owner group might be used for other purposes.

## Removing DB2 products using the `db2_deinstall` or `doce_deinstall` command (Linux and UNIX)

This task provides steps for removing DB2 products or DB2 components using the `db2_deinstall` command. The `db2_deinstall` command removes all DB2 products from your system. The `doce_deinstall` command removes the DB2 Information Center that is in the same install path as the `doce_deinstall` tool. This command is only available on the Linux operating systems.

Before you remove DB2 products from your system, ensure that you have performed all steps outlined in "Uninstalling your DB2 product (Linux and UNIX)" on page 32

**Note:**



- This task applies to DB2 products that were installed with root authority.
- You cannot remove DB2 products using a native operating system utility, such as rpm or SMIT.
- The doce\_deinstall command is available only on Linux x32 and x64.

To remove ALL DB2 products from a specific path:

1. Log in as the root user.
2. Access the path where the DB2 products are located.
3. Run one of the following commands:
  - To remove a feature from an installed DB2 product in the current location, run the `db2_deinstall -F` command from the `DB2DIR/install` directory
  - To remove all installed DB2 products in the current location, run the `db2_deinstall -a` command from the `DB2DIR/install` directory
  - To remove the DB2 Information Center in the current location, run the `doce_deinstall -a` from the `DB2DIR/doc/install` directory

where DB2DIR is the location that you specified when you installed your DB2 product.



---

## Appendix D. Overview of the DB2 technical information

DB2 technical information is available through the following tools and methods:

- DB2 Information Center
  - Topics (Task, concept and reference topics)
  - Help for DB2 tools
  - Sample programs
  - Tutorials
- DB2 books
  - PDF files (downloadable)
  - PDF files (from the DB2 PDF DVD)
  - printed books
- Command line help
  - Command help
  - Message help

**Note:** The DB2 Information Center topics are updated more frequently than either the PDF or the hard-copy books. To get the most current information, install the documentation updates as they become available, or refer to the DB2 Information Center at [ibm.com](http://ibm.com)<sup>®</sup>.

You can access additional DB2 technical information such as technotes, white papers, and IBM Redbooks<sup>®</sup> publications online at [ibm.com](http://www.ibm.com). Access the DB2 Information Management software library site at <http://www.ibm.com/software/data/sw-library/>.

### Documentation feedback

We value your feedback on the DB2 documentation. If you have suggestions for how to improve the DB2 documentation, send an email to [db2docs@ca.ibm.com](mailto:db2docs@ca.ibm.com). The DB2 documentation team reads all of your feedback, but cannot respond to you directly. Provide specific examples wherever possible so that we can better understand your concerns. If you are providing feedback on a specific topic or help file, include the topic title and URL.

Do not use this email address to contact DB2 Customer Support. If you have a DB2 technical issue that the documentation does not resolve, contact your local IBM service center for assistance.

---

## DB2 technical library in hardcopy or PDF format

The following tables describe the DB2 library available from the IBM Publications Center at [www.ibm.com/shop/publications/order](http://www.ibm.com/shop/publications/order). English DB2 Version 9.5 manuals in PDF format and translated versions can be downloaded from [www.ibm.com/support/docview.wss?rs=71&uid=swg2700947](http://www.ibm.com/support/docview.wss?rs=71&uid=swg2700947).

Although the tables identify books available in print, the books might not be available in your country or region.

The form number increases each time a manual is updated. Ensure that you are reading the most recent version of the manuals, as listed below.

**Note:** The DB2 Information Center is updated more frequently than either the PDF or the hard-copy books.

*Table 3. DB2 technical information*

<b>Name</b>	<b>Form Number</b>	<b>Available in print</b>
<i>Administrative API Reference</i>	SC23-5842-01	Yes
<i>Administrative Routines and Views</i>	SC23-5843-01	No
<i>Call Level Interface Guide and Reference, Volume 1</i>	SC23-5844-01	Yes
<i>Call Level Interface Guide and Reference, Volume 2</i>	SC23-5845-01	Yes
<i>Command Reference</i>	SC23-5846-01	Yes
<i>Data Movement Utilities Guide and Reference</i>	SC23-5847-01	Yes
<i>Data Recovery and High Availability Guide and Reference</i>	SC23-5848-01	Yes
<i>Data Servers, Databases, and Database Objects Guide</i>	SC23-5849-01	Yes
<i>Database Security Guide</i>	SC23-5850-01	Yes
<i>Developing ADO.NET and OLE DB Applications</i>	SC23-5851-01	Yes
<i>Developing Embedded SQL Applications</i>	SC23-5852-01	Yes
<i>Developing Java Applications</i>	SC23-5853-01	Yes
<i>Developing Perl and PHP Applications</i>	SC23-5854-01	No
<i>Developing User-defined Routines (SQL and External)</i>	SC23-5855-01	Yes
<i>Getting Started with Database Application Development</i>	GC23-5856-01	Yes
<i>Getting Started with DB2 installation and administration on Linux and Windows</i>	GC23-5857-01	Yes
<i>Internationalization Guide</i>	SC23-5858-01	Yes
<i>Message Reference, Volume 1</i>	GI11-7855-00	No
<i>Message Reference, Volume 2</i>	GI11-7856-00	No
<i>Migration Guide</i>	GC23-5859-01	Yes
<i>Net Search Extender Administration and User's Guide</i>	SC23-8509-01	Yes
<i>Partitioning and Clustering Guide</i>	SC23-5860-01	Yes
<i>Query Patroller Administration and User's Guide</i>	SC23-8507-00	Yes
<i>Quick Beginnings for IBM Data Server Clients</i>	GC23-5863-01	No

*Table 3. DB2 technical information (continued)*

<b>Name</b>	<b>Form Number</b>	<b>Available in print</b>
<i>Quick Beginnings for DB2 Servers</i>	GC23-5864-01	Yes
<i>Spatial Extender and Geodetic Data Management Feature User's Guide and Reference</i>	SC23-8508-01	Yes
<i>SQL Reference, Volume 1</i>	SC23-5861-01	Yes
<i>SQL Reference, Volume 2</i>	SC23-5862-01	Yes
<i>System Monitor Guide and Reference</i>	SC23-5865-01	Yes
<i>Troubleshooting Guide</i>	GI11-7857-01	No
<i>Tuning Database Performance</i>	SC23-5867-01	Yes
<i>Visual Explain Tutorial</i>	SC23-5868-00	No
<i>What's New</i>	SC23-5869-01	Yes
<i>Workload Manager Guide and Reference</i>	SC23-5870-01	Yes
<i>pureXML Guide</i>	SC23-5871-01	Yes
<i>XQuery Reference</i>	SC23-5872-01	No

*Table 4. DB2 Connect-specific technical information*

<b>Name</b>	<b>Form Number</b>	<b>Available in print</b>
<i>Quick Beginnings for DB2 Connect Personal Edition</i>	GC23-5839-01	Yes
<i>Quick Beginnings for DB2 Connect Servers</i>	GC23-5840-01	Yes
<i>DB2 Connect User's Guide</i>	SC23-5841-01	Yes

*Table 5. Information Integration technical information*

<b>Name</b>	<b>Form Number</b>	<b>Available in print</b>
<i>Information Integration: Administration Guide for Federated Systems</i>	SC19-1020-01	Yes
<i>Information Integration: ASNCLP Program Reference for Replication and Event Publishing</i>	SC19-1018-02	Yes
<i>Information Integration: Configuration Guide for Federated Data Sources</i>	SC19-1034-01	No
<i>Information Integration: SQL Replication Guide and Reference</i>	SC19-1030-01	Yes
<i>Information Integration: Introduction to Replication and Event Publishing</i>	SC19-1028-01	Yes

---

## Ordering printed DB2 books

If you require printed DB2 books, you can buy them online in many but not all countries or regions. You can always order printed DB2 books from your local IBM representative. Keep in mind that some softcopy books on the *DB2 PDF Documentation DVD* are unavailable in print. For example, neither volume of the *DB2 Message Reference* is available as a printed book.

Printed versions of many of the DB2 books available on the *DB2 PDF Documentation DVD* can be ordered for a fee from IBM. Depending on where you are placing your order from, you may be able to order books online, from the IBM Publications Center. If online ordering is not available in your country or region, you can always order printed DB2 books from your local IBM representative. Note that not all books on the *DB2 PDF Documentation DVD* are available in print.

**Note:** The most up-to-date and complete DB2 documentation is maintained in the DB2 Information Center at <http://publib.boulder.ibm.com/infocenter/db2luw/v9r5>.

To order printed DB2 books:

- To find out whether you can order printed DB2 books online in your country or region, check the IBM Publications Center at <http://www.ibm.com/shop/publications/order>. You must select a country, region, or language to access publication ordering information and then follow the ordering instructions for your location.
- To order printed DB2 books from your local IBM representative:
  1. Locate the contact information for your local representative from one of the following Web sites:
    - The IBM directory of world wide contacts at [www.ibm.com/planetwide](http://www.ibm.com/planetwide)
    - The IBM Publications Web site at <http://www.ibm.com/shop/publications/order>. You will need to select your country, region, or language to the access appropriate publications home page for your location. From this page, follow the "About this site" link.
  2. When you call, specify that you want to order a DB2 publication.
  3. Provide your representative with the titles and form numbers of the books that you want to order. For titles and form numbers, see "DB2 technical library in hardcopy or PDF format" on page 37.

---

## Displaying SQL state help from the command line processor

DB2 returns an `SQLSTATE` value for conditions that could be the result of an SQL statement. `SQLSTATE` help explains the meanings of SQL states and SQL state class codes.

To invoke SQL state help, open the command line processor and enter:

```
? sqlstate or ? class code
```

where *sqlstate* represents a valid five-digit SQL state and *class code* represents the first two digits of the SQL state.

For example, `? 08003` displays help for the 08003 SQL state, and `? 08` displays help for the 08 class code.

---

## Accessing different versions of the DB2 Information Center

For DB2 Version 9.5 topics, the DB2 Information Center URL is <http://publib.boulder.ibm.com/infocenter/db2luw/v9r5/>

For DB2 Version 9 topics, the DB2 Information Center URL is <http://publib.boulder.ibm.com/infocenter/db2luw/v9/>

For DB2 Version 8 topics, go to the Version 8 Information Center URL at: <http://publib.boulder.ibm.com/infocenter/db2luw/v8/>

---

## Displaying topics in your preferred language in the DB2 Information Center

The DB2 Information Center attempts to display topics in the language specified in your browser preferences. If a topic has not been translated into your preferred language, the DB2 Information Center displays the topic in English.

- To display topics in your preferred language in the Internet Explorer browser:
  1. In Internet Explorer, click the **Tools** → **Internet Options** → **Languages...** button. The Language Preferences window opens.
  2. Ensure your preferred language is specified as the first entry in the list of languages.
    - To add a new language to the list, click the **Add...** button.

**Note:** Adding a language does not guarantee that the computer has the fonts required to display the topics in the preferred language.
    - To move a language to the top of the list, select the language and click the **Move Up** button until the language is first in the list of languages.
  3. Clear the browser cache and then refresh the page to display the DB2 Information Center in your preferred language.
- To display topics in your preferred language in a Firefox or Mozilla browser:
  1. Select the button in the **Languages** section of the **Tools** → **Options** → **Advanced** dialog. The Languages panel is displayed in the Preferences window.
  2. Ensure your preferred language is specified as the first entry in the list of languages.
    - To add a new language to the list, click the **Add...** button to select a language from the Add Languages window.
    - To move a language to the top of the list, select the language and click the **Move Up** button until the language is first in the list of languages.
  3. Clear the browser cache and then refresh the page to display the DB2 Information Center in your preferred language.

On some browser and operating system combinations, you might have to also change the regional settings of your operating system to the locale and language of your choice.

---

## Updating the DB2 Information Center installed on your computer or intranet server

If you have installed the DB2 Information Center locally, you can obtain and install documentation updates from IBM.

Updating your locally-installed DB2 Information Center requires that you:

1. Stop the DB2 Information Center on your computer, and restart the Information Center in stand-alone mode. Running the Information Center in stand-alone mode prevents other users on your network from accessing the Information Center, and allows you to apply updates. Non-Administrative and Non-Root DB2 Information Centers always run in stand-alone mode. .
2. Use the Update feature to see what updates are available. If there are updates that you would like to install, you can use the Update feature to obtain and install them

**Note:** If your environment requires installing the DB2 Information Center updates on a machine that is not connected to the internet, you have to mirror the update site to a local file system using a machine that is connected to the internet and has the DB2 Information Center installed. If many users on your network will be installing the documentation updates, you can reduce the time required for individuals to perform the updates by also mirroring the update site locally and creating a proxy for the update site.

If update packages are available, use the Update feature to get the packages. However, the Update feature is only available in stand-alone mode.

3. Stop the stand-alone Information Center, and restart the DB2 Information Center on your computer.

**Note:** On Windows Vista, the commands listed below must be run as an administrator. To launch a command prompt or graphical tool with full administrator privileges, right-click on the shortcut and then select **Run as administrator**.

To update the DB2 Information Center installed on your computer or intranet server:

1. Stop the DB2 Information Center.
  - On Windows, click **Start** → **Control Panel** → **Administrative Tools** → **Services**. Then right-click on **DB2 Information Center** service and select **Stop**.
  - On Linux, enter the following command:  

```
/etc/init.d/db2icdv95 stop
```
2. Start the Information Center in stand-alone mode.
  - On Windows:
    - a. Open a command window.
    - b. Navigate to the path where the Information Center is installed. By default, the DB2 Information Center is installed in the <Program Files>\IBM\DB2 Information Center\Version 9.5 directory, where <Program Files> represents the location of the Program Files directory.
    - c. Navigate from the installation directory to the doc\bin directory.
    - d. Run the help\_start.bat file:  

```
help_start.bat
```
  - On Linux:



- a. Navigate to the path where the Information Center is installed. By default, the DB2 Information Center is installed in the /opt/ibm/db2ic/V9.5 directory.
- b. Navigate from the installation directory to the doc/bin directory.
- c. Run the help\_start script:
 

```
help_start
```

The systems default Web browser launches to display the stand-alone Information Center.

3. Click the **Update** button (🔧). On the right hand panel of the Information Center, click **Find Updates**. A list of updates for existing documentation displays.
4. To initiate the installation process, check the selections you want to install, then click **Install Updates**.
5. After the installation process has completed, click **Finish**.
6. Stop the stand-alone Information Center:

- On Windows, navigate to the installation directory's doc\bin directory, and run the help\_end.bat file:

```
help_end.bat
```

**Note:** The help\_end batch file contains the commands required to safely terminate the processes that were started with the help\_start batch file. Do not use Ctrl-C or any other method to terminate help\_start.bat.

- On Linux, navigate to the installation directory's doc/bin directory, and run the help\_end script:

```
help_end
```

**Note:** The help\_end script contains the commands required to safely terminate the processes that were started with the help\_start script. Do not use any other method to terminate the help\_start script.

7. Restart the DB2 Information Center.
  - On Windows, click **Start** → **Control Panel** → **Administrative Tools** → **Services**. Then right-click on **DB2 Information Center** service and select **Start**.
  - On Linux, enter the following command:
 

```
/etc/init.d/db2icdv95 start
```

The updated DB2 Information Center displays the new and updated topics.

---

## DB2 tutorials

The DB2 tutorials help you learn about various aspects of DB2 products. Lessons provide step-by-step instructions.

### Before you begin

You can view the XHTML version of the tutorial from the Information Center at <http://publib.boulder.ibm.com/infocenter/db2help/>.

Some lessons use sample data or code. See the tutorial for a description of any prerequisites for its specific tasks.

## DB2 tutorials

To view the tutorial, click on the title.

**“pureXML™” in *pureXML Guide***

Set up a DB2 database to store XML data and to perform basic operations with the native XML data store.

**“Visual Explain” in *Visual Explain Tutorial***

Analyze, optimize, and tune SQL statements for better performance using Visual Explain.

---

## DB2 troubleshooting information

A wide variety of troubleshooting and problem determination information is available to assist you in using DB2 products.

### DB2 documentation

Troubleshooting information can be found in the DB2 Troubleshooting Guide or the Support and Troubleshooting section of the DB2 Information Center. There you will find information on how to isolate and identify problems using DB2 diagnostic tools and utilities, solutions to some of the most common problems, and other advice on how to solve problems you might encounter with your DB2 products.

### DB2 Technical Support Web site

Refer to the DB2 Technical Support Web site if you are experiencing problems and want help finding possible causes and solutions. The Technical Support site has links to the latest DB2 publications, TechNotes, Authorized Program Analysis Reports (APARs or bug fixes), fix packs, and other resources. You can search through this knowledge base to find possible solutions to your problems.

Access the DB2 Technical Support Web site at <http://www.ibm.com/software/data/db2/udb/support.html>

---

## Terms and Conditions

Permissions for the use of these publications is granted subject to the following terms and conditions.

**Personal use:** You may reproduce these Publications for your personal, non commercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these Publications, or any portion thereof, without the express consent of IBM.

**Commercial use:** You may reproduce, distribute and display these Publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these Publications, or reproduce, distribute or display these Publications or any portion thereof outside your enterprise, without the express consent of IBM.

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the Publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the Publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.



---

## Appendix E. Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10504-1785  
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country/region or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106, Japan

**The following paragraph does not apply to the United Kingdom or any other country/region where such provisions are inconsistent with local law:**

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions; therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

This document may provide links or references to non-IBM Web sites and resources. IBM makes no representations, warranties, or other commitments whatsoever about any non-IBM Web sites or third-party resources that may be referenced, accessible from, or linked from this document. A link to a non-IBM Web site does not mean that IBM endorses the content or use of such Web site or

its owner. In addition, IBM is not a party to or responsible for any transactions you may enter into with third parties, even if you learn of such parties (or use a link to such parties) from an IBM site. Accordingly, you acknowledge and agree that IBM is not responsible for the availability of such external sites or resources, and is not responsible or liable for any content, services, products, or other materials on or available from those sites or resources. Any software provided by third parties is subject to the terms and conditions of the license that accompanies that software.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information that has been exchanged, should contact:

IBM Canada Limited  
Office of the Lab Director  
8200 Warden Avenue  
Markham, Ontario  
L6G 1C7  
CANADA

Such information may be available, subject to appropriate terms and conditions, including in some cases payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems, and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements, or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility, or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information may contain examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious, and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information may contain sample application programs, in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as follows:

© (*your company name*) (*year*). Portions of this code are derived from IBM Corp. Sample Programs. © Copyright IBM Corp. *\_enter the year or years\_*. All rights reserved.

## Trademarks

The following terms are trademarks or registered trademarks of the International Business Machines Corporation in the United States, other countries, or both.

pureXML	Passport Advantage
OpenPower	Redbooks
System i	IBM
DB2	zSeries
System z9	AIX
Tivoli	System z
eServer	ibm.com
i5/OS	pSeries
POWER	

The following terms are trademarks or registered trademarks of other companies

- Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.
- Java and all Java-based trademarks are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.
- UNIX is a registered trademark of The Open Group in the United States and other countries.
- Intel Xeon, and Pentium, and Intel are trademarks of Intel Corporation or its subsidiaries in the United States and other countries.
- Microsoft, and Windows are trademarks of Microsoft Corporation in the United States, other countries, or both.

Other company, product, or service names may be trademarks or service marks of others.





---

# Index

## A

- administration server
  - stopping 32
- automatic maintenance wizard
  - creating databases 18

## B

- books
  - printed
    - ordering 40

## C

- command line processor (CLP)
  - verifying the installation 18
- commands
  - db2\_deinstall 34
  - db2idrop 33
  - db2ilist 33
  - db2sampl 18
  - db2start 5
  - db2stop 33
  - doce\_deinstall 34
  - force application 33
- creating
  - database
    - automatic maintenance wizard 18
    - response files using DB2 Setup wizard 26
    - sample databases 17

## D

- databases
  - Create Database with Automatic Maintenance wizard 18
  - creating
    - Create Database with Automatic Maintenance wizard 18
- DB2 administration server (DAS)
  - removing 32
  - stopping 32
- DB2 Information Center
  - languages 41
  - updating 42
  - versions 41
  - viewing in different languages 41
- DB2 servers
  - installing
    - Windows 11
- DB2 Setup wizard
  - creating response files 26
  - installing DB2 servers
    - Linux 13
    - UNIX 13
  - installing DB2 servers on UNIX 13
- db2\_deinstall command
  - removing DB2 products 34
- db2licm command
  - checking compliance 23

- db2licm command (*continued*)
  - managing licenses 21
- disk space requirements 1
- doce\_deinstall command
  - procedure 34
- documentation
  - overview 37
  - PDF 37
  - printed 37
  - terms and conditions of use 44
- dropping
  - root instances 33

## F

- First Steps
  - verifying
    - DB2 installation 17
- fix packs
  - applying 29

## H

- hardware
  - requirements
    - Linux 6
    - Windows 1
- help
  - configuring language 41
  - SQL statements 40

## I

- installing
  - requirements
    - Linux 6
    - Windows 1
  - response files
    - types 25
  - security considerations 10
  - using response files 25
  - verifying using CLP 18
  - verifying using First Steps 17
  - Windows elevated privileges 3
- instances
  - dropping 33
  - removing 33
  - root
    - removing 33
  - stopping root 33

## L

- License Center
  - checking compliance 23
  - managing licenses 21
  - registering licenses 22
  - upgrading a trial license 23

- licenses
  - checking compliance 23
  - overview 21
  - registering
    - License Center 22
  - upgrading a trial license 23
- Linux
  - installation requirements 6
  - installing
    - DB2 Setup wizard 13
  - removing
    - DB2 (root) 32
    - DB2 root instances 33
- Linux library
  - libaio.so.1 6
  - libstdc++so.5 6

## M

- memory requirements 1

## N

- Network File System (NFS) installation
  - on Linux 6
- notices 47

## O

- operating system requirements
  - Linux 6
  - Windows 1
- ordering DB2 books 40

## P

- problem determination
  - information available 44
  - tutorials 44

## R

- removing
  - DAS 32
  - DB2 (root)
    - Linux 32
    - UNIX 32
  - DB2 database
    - Windows 31
  - root instances 33
- requirements
  - disk 1
  - memory 1
- response files
  - creating
    - DB2 Setup wizard 26
  - installation
    - types 25
    - location 25, 26
    - overview 25
- root instances
  - dropping 33
  - removing 33

## S

- SAMPLE database
  - verifying installation 17
  - warehousing 17
- silent installation
  - using response files 25
- software requirements
  - Linux 6
  - Windows 1
- SQL statements
  - displaying help 40
- stopping
  - Administration Server 32
  - root instances 33
- SYSADM
  - Windows 5
- sysadm\_group configuration parameter 5
- system administrator group
  - DB2 database
    - Windows 5

## T

- terms and conditions
  - use of publications 44
- troubleshooting
  - online information 44
  - tutorials 44
- tutorials
  - problem determination 44
  - troubleshooting 44
  - Visual Explain 43

## U

- uninstalling
  - DB2 database
    - Windows 31
  - db2\_deinstall command 34
  - doce\_deinstall command 34
  - root installations 32
- UNIX
  - installing
    - using the DB2 Setup wizard 13
  - removing
    - DB2 (root) 32
    - DB2 products 34
    - removing DB2 root instances 33
- updates
  - DB2 Information Center 42
- user privileges
  - Windows 5

## V

- verifying
  - DB2 installation
    - using First Steps 17
- Visual Explain
  - tutorial 43

## W

- Windows operating systems
  - granting user rights 5

Windows operating systems *(continued)*  
installation using a non-Administrator user account  
    setting up elevated privileges 3  
installing  
    DB2 servers (requirements) 1  
    DB2 servers (with DB2 Setup wizard) 11  
    IBM data server clients (requirements) 1  
system administrator authority 5  
uninstalling DB2 31







Printed in USA

GC23-5857-01



Spine information:

DB2 Version 9.5 for Linux, UNIX, and Windows

Getting Started with DB2 installation and administration on Linux and Windows

