



**Program Directory for
WebSphere eXtreme Scale V7.1 for z/OS**

Version 7 Release 1 Modification 0

Program Number 5655-V66, 5655-P28

HEJD710, JEJD266, JEJD228

for Use with
WebSphere Application Server for z/OS V6.1 or V7.0

Document Date: July 2010

GI11-4333-02

Note!

Before using this information and the product it supports, be sure to read the general information under Appendix A, "Notices" on page 26.

A form for reader's comments is at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 2010. All rights reserved.**

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

1.0 Introduction	1
1.1 WebSphere eXtreme Scale V7.1 for z/OS Description	2
1.2 WebSphere eXtreme Scale V7.1 for z/OS FMIDs	2
2.0 Program Materials	3
2.1 Basic Machine-Readable Material	3
2.2 Optional Machine-Readable Material	3
2.3 Program Publications	3
2.3.1 Basic Program Publications	3
2.3.2 Optional Program Publications	4
2.4 Program Source Materials	4
2.5 Publications Useful During Installation	4
3.0 Program Support	6
3.1 Program Services	6
3.2 Preventive Service Planning	6
3.3 Statement of Support Procedures	6
4.0 Program and Service Level Information	8
4.1 Program Level Information	8
4.2 Service Level Information	8
5.0 Installation Requirements and Considerations	9
5.1 Driving System Requirements	9
5.1.1 Machine Requirements	9
5.1.2 Programming Requirements	9
5.2 Target System Requirements	10
5.2.1 Machine Requirements	10
5.2.2 Programming Requirements	10
5.2.2.1 Installation Requisites	10
5.2.2.2 Operational Requisites	11
5.2.2.3 Toleration/Coexistence Requisites	11
5.2.2.4 Incompatibility (Negative) Requisites	11
5.2.3 DASD Storage Requirements	12
5.3 FMIDs Deleted	15
5.4 Special Considerations	15
5.4.1 Driving System Mountpoint	16
5.4.2 Target System Mountpoint	16
6.0 Installation Instructions	17
6.1 Installing WebSphere eXtreme Scale V7.1 for z/OS	17
6.1.1 SMP/E Considerations for Installing WebSphere eXtreme Scale V7.1 for z/OS	17

6.1.2	Sample Jobs	18
6.1.3	Allocate SMP/E CSI (Optional)	19
6.1.4	Define New SMP/E TARGET and DLIB Zones (Optional)	20
6.1.5	Perform SMP/E RECEIVE	20
6.1.6	Allocate SMP/E Target and Distribution Libraries	20
6.1.7	Allocate HFS Paths	20
6.1.8	Create DDDEF Entries	21
6.1.9	Add Target Zones for Cross-Zone Prerequisite Checking	21
6.1.10	Special Case - Updating The Registration FMID	21
6.1.11	Perform SMP/E APPLY	22
6.1.12	Perform SMP/E ACCEPT	24
6.2	Activating WebSphere eXtreme Scale V7.1 for z/OS	25
6.2.1	HFS Execution	25
6.2.2	Mount the HFS Data Set on the Target System	25
Appendix A. Notices		26
A.1	Trademarks	27
Reader's Comments		28

Figures

1.	Basic Material: Unlicensed Publications	4
2.	Basic Material: Other Unlicensed or Licensed Publications	4
3.	Publications Useful During Installation	4
4.	PSP Upgrade and Subset ID	6
5.	Component IDs for WebSphere eXtreme Scale V7.1 for z/OS	7
6.	Driving System Software Requirements	9
7.	Mandatory Installation Requisites	10
8.	Mandatory Operational Requisites	11
9.	Total DASD Space Required by WebSphere eXtreme Scale V7.1 for z/OS	12
10.	Storage Requirements for SMP/E Work Data Sets	13
11.	Storage Requirements for SMP/E Data Sets	14
12.	Storage Requirements for WebSphere eXtreme Scale V7.1 for z/OS Target Libraries	14
13.	WebSphere eXtreme Scale V7.1 for z/OS HFS Paths	14
14.	Storage Requirements for WebSphere eXtreme Scale V7.1 for z/OS Distribution Libraries	15
15.	Sample Installation Jobs	18

1.0 Introduction

This Program Directory is intended for the system programmer responsible for program installation and maintenance. It contains information concerning the material and procedures associated with the installation of WebSphere eXtreme Scale for z/OS V7.1 whether it is purchased alone under program number 5655-V66 or whether it was purchased as a part of the WebSphere Extended Deployment V6.1.1 for z/OS suite of products using program number 5655-P28.

The Program Directory contains the following sections:

- 2.0, “Program Materials” on page 3 identifies the basic and optional program materials and documentation for WebSphere eXtreme Scale V7.1 for z/OS.
- 3.0, “Program Support” on page 6 describes the IBM support available for WebSphere eXtreme Scale V7.1 for z/OS.
- 4.0, “Program and Service Level Information” on page 8 lists the PTF (service level) incorporated into WebSphere eXtreme Scale V7.1 for z/OS.
- 5.0, “Installation Requirements and Considerations” on page 9 identifies the resources and considerations required for installing and using WebSphere eXtreme Scale V7.1 for z/OS.
- 6.0, “Installation Instructions” on page 17 provides detailed installation instructions for WebSphere eXtreme Scale V7.1 for z/OS. It also describes the procedures for activating the functions of WebSphere eXtreme Scale V7.1 for z/OS, or refers to appropriate publications.

WebSphere eXtreme Scale V7.1 for z/OS is an elastic, highly available and linearly scalable data grid that integrates with WebSphere Application Server V6.1 for z/OS or WebSphere Application Server V7.0 for z/OS plus the enabling service level, which will extend its capabilities and manageability.

This product is shipped alone through CBPDO and as an additional feature to the WebSphere ServerPac, or WebSphere z/OS ServerPac. When shipped through CBPDO, it must be installed into an SMPE environment that already contains WebSphere Application Server V6.1 for z/OS or WebSphere Application Server V7.0 for z/OS.

Prerequisite WebSphere Application Server V6.1 for z/OS or WebSphere Application Server V7.0 for z/OS provides the entire runtime environment needed for WebSphere eXtreme Scale V7.1 for z/OS. There are no additional CDs or products shipped with WebSphere eXtreme Scale V7.1 for z/OS.

Before installing WebSphere eXtreme Scale V7.1 for z/OS, read the Memo to Users Extension that is supplied with this program in softcopy form as well as this Program Directory. Consider keeping them for future reference. Section 3.2, “Preventive Service Planning” on page 6 tells you how to find any updates to the information and procedures in this Program Directory.

When WebSphere eXtreme Scale V7.1 for z/OS is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3), the Program Directory is provided in softcopy form on the CBPDO tape that is identical to the hardcopy form provided with your order. Your CBPDO contains a softcopy preventive

service planning (PSP) upgrade for this product. All service and HOLDDATA for WebSphere eXtreme Scale V7.1 for z/OS are included on the CBPDO tape.

1.1 WebSphere eXtreme Scale V7.1 for z/OS Description

WebSphere eXtreme Scale V7.1 for z/OS provides Extreme Transaction Processing (XTP) capabilities that ensure a smarter application infrastructure to support your most demanding business-critical applications. You can overcome traditional IT performance limitations to generate the levels of global scale, process efficiencies, and business intelligence needed for smarter outcomes and for sustainable competitive advantage for your business. WebSphere eXtreme Scale V7.1 for z/OS provides client support access to the following new capabilities:

- Improved ease of use with automated handling of common retry and exception logic.

Enhanced XTP capabilities:

- Further simplification in building multi-tenant applications
- Improved memory density through the implementation of byte array maps.
- Query optimization and simplification of index usage with enhancements to the built-in HashIndex plug-in.

1.2 WebSphere eXtreme Scale V7.1 for z/OS FMIDs

WebSphere eXtreme Scale V7.1 for z/OS consists of the following FMIDs:

HEJD710 - WebSphere eXtreme Scale V7.1 for z/OS

JEJD266 - WebSphere eXtreme Scale V66 for z/OS Registration, provided by 5655-V66

JEJD228 - WebSphere eXtreme Scale P28 for z/OS Registration, provided by 5655-P28

2.0 Program Materials

An IBM program is identified by a program number. The program number for WebSphere eXtreme Scale V7.1 for z/OS is 5655-V66.

Basic Machine-Readable Materials are materials that are supplied under the base license and feature numbers, and are required for the use of the product. Optional Machine-Readable Materials are orderable under separate feature numbers, and are not required for the product to function.

The program announcement material describes the features supported by WebSphere eXtreme Scale V7.1 for z/OS. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is magnetic tape or downloadable files. It is installed using SMP/E, and is in SMP/E RELFILE format. See 6.0, "Installation Instructions" on page 17 for more information about how to install the program.

Information about the physical tape for the Basic Machine-Readable Materials for WebSphere eXtreme Scale V7.1 for z/OS can be found in the *CBPDO Memo To Users Extension*.

2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for WebSphere eXtreme Scale V7.1 for z/OS.

2.3 Program Publications

The following sections identify the basic and optional publications for WebSphere eXtreme Scale V7.1 for z/OS. Note the main documentation distribution medium for WebSphere eXtreme Scale V7.1 for z/OS is the Information Center, which can be accessed via the WebSphere eXtreme Scale Library page at <http://www.ibm.com/software/webservers/appserv/extremescale/library/>

In addition to the Information Center, other WebSphere eXtreme Scale V7.1 for z/OS articles are available in PDF format at the same URL.

2.3.1 Basic Program Publications

Figure 1 identifies the basic unlicensed program publications for WebSphere eXtreme Scale V7.1 for z/OS. Downloadable copies of these publications are available on the WebSphere eXtreme Scale Library page. To access the documentation, see <http://www.ibm.com/software/webservers/appserv/extremescale/library/>

Figure 1. Basic Material: Unlicensed Publications

Publication Title	Form Number
Program Directory for WebSphere eXtreme Scale V7.1 for z/OS	GI11-4333-02
License Information WebSphere eXtreme Scale V7.1 for z/OS	GC27-2265-00

Figure 2 identifies the basic unlicensed or licensed publications that are not available in hardcopy form, but are available through the internet or other media for WebSphere eXtreme Scale V7.1 for z/OS.

Figure 2. Basic Material: Other Unlicensed or Licensed Publications

Publication Title	Form Number	How Available
WebSphere eXtreme Scale V7.1 for z/OS Customization Guide	GI10-0775-03	Library page

2.3.2 Optional Program Publications

No optional publications are provided for WebSphere eXtreme Scale V7.1 for z/OS.

2.4 Program Source Materials

No program source materials or viewable program listings are provided for WebSphere eXtreme Scale V7.1 for z/OS.

2.5 Publications Useful During Installation

The publications listed in Figure 3 may be useful during the installation of WebSphere eXtreme Scale V7.1 for z/OS. To order copies, contact your IBM representative or visit the IBM Publications Center on the World Wide Web at <http://www.ibm.com/shop/publications/order>.

You can also access these publications online at:

<http://www-1.ibm.com/servers/eserver/zseries/zos/bkserv/>

Figure 3 (Page 1 of 2). Publications Useful During Installation

Publication Title	Form Number
IBM SMP/E for z/OS and OS/390 User's Guide	SA22-7773
IBM SMP/E for z/OS and OS/390 Commands	SA22-7771

Figure 3 (Page 2 of 2). Publications Useful During Installation

Publication Title	Form Number
<i>IBM SMP/E for z/OS and OS/390 Reference</i>	SA22-7772
<i>IBM SMP/E for z/OS and OS/390 Messages, Codes, and Diagnosis</i>	GA22-7770
<i>z/OS MVS JCL Reference</i>	SA22-7597
<i>z/OS System Codes</i>	SA22-7626

3.0 Program Support

This section describes the IBM support available for WebSphere eXtreme Scale V7.1 for z/OS.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before installing WebSphere eXtreme Scale V7.1 for z/OS, you should review the current Preventive Service Planning (PSP) information. If you obtained WebSphere eXtreme Scale V7.1 for z/OS as part of a CBPDO, there is HOLDDATA and PSP information included on the CBPDO.

If the CBPDO for WebSphere eXtreme Scale V7.1 for z/OS is more than two weeks old when you install it, you should contact the IBM Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

For program support, access the Software Support at the following Web site:

<http://www-3.ibm.com/software/support/>

PSP Buckets are identified by UPGRADEs, which specify product levels, and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for WebSphere eXtreme Scale V7.1 for z/OS are:

UPGRADE	SUBSET	Description
WASXS710	HEJD710	WebSphere eXtreme Scale V7.1 for z/OS
WASXS710	JEJD266	Registration FMID for 5655-V66, provided by 5655-V66
WASXS710	JEJD228	Registration FMID for 5655-P28, provided by 5655-P28

3.3 Statement of Support Procedures

Report any difficulties you have using this program to your IBM Support Center. For technical support assistance visit

<http://www.ibm.com/support>

and perform a search on the symptoms you are experiencing with this program. For additional assistance, contact your IBM software support center at 1-800-IBM-SERV (800-426-7378), selecting option #2 for

software assistance. If an APAR is required, the Support Center will provide the address to which any needed documentation can be sent.

Figure 5 identifies the component IDs (COMPID) for WebSphere eXtreme Scale V7.1 for z/OS.

<i>Figure 5. Component IDs for WebSphere eXtreme Scale V7.1 for z/OS</i>			
FMID	COMPID	Component Name	RETAIN Release
HEJD710	5655V6602	WebSphere eXtreme Scale V7.1 for z/OS	710
JEJD266	5655V6666	WebSphere eXtreme Scale V66 for z/OS Registration	710
JEJD228	5655P2878	WebSphere eXtreme Scale P28 for z/OS Registration	710

Note: FMID JEJD266 is provided by 5655-V66, and FMID JEJD228 is provided by 5655-P28.

4.0 Program and Service Level Information

This section identifies the program and any relevant service levels of WebSphere eXtreme Scale V7.1 for z/OS. The program level refers to the APAR fixes incorporated into the program. The service level refers to the PTFs incorporated into the program.

4.1 Program Level Information

This is first release of WebSphere eXtreme Scale V7.1 for z/OS.

4.2 Service Level Information

This is the first release of WebSphere eXtreme Scale V7.1 for z/OS.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating WebSphere eXtreme Scale V7.1 for z/OS. The following terminology is used:

- *Driving system*: the system used to install the program.
- *Target system*: the system on which the program is installed.

In many cases, the same system can be used as both a driving system and a target system. However, you may want to set up a clone of your system to use as a target system by making a separate IPL-able copy of the running system. The clone should include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Some cases where two systems should be used include the following:

- When installing a new level of a product that is already installed, the new product will delete the old one. By installing onto a separate target system, you can test the new product while still keeping the old one in production.
- When installing a product that shares libraries or load modules with other products, the installation can disrupt the other products. Installing onto a test system or clone will allow you to assess these impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install WebSphere eXtreme Scale V7.1 for z/OS.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

<i>Figure 6. Driving System Software Requirements</i>	
Program Number	Product Name and Minimum VRM/Service Level
5655-I56	Java 2 Technology Edition SDK 1.4 or later
Any one of the following:	
5694-A01	z/OS V1.7 or later

Note: WebSphere eXtreme Scale V7.1 for z/OS installs in the z/OS (Z038) SREL.

- UNIX must be up in full function mode on your driving system so that the utilities are available for the Shell Script support.
- Before installing WebSphere eXtreme Scale V7.1 for z/OS, you must ensure that the target system's HFS is available (OMVS active and the target file systems mounted) for processing.

5.2 Target System Requirements

This section describes the environment of the target system required to customize and use WebSphere eXtreme Scale V7.1 for z/OS.

5.2.1 Machine Requirements

The target system can run in any hardware environment that supports WebSphere Application Server for z/OS V6.1 plus service associated with PTF 6.1.0.31 for z/OS. Consider using binary floating point hardware, such as S/390 Parallel Enterprise Server Generation 5 systems, and later.

5.2.2 Programming Requirements

5.2.2.1 Installation Requisites

An installation requisite is defined as a product that is required and **must** be present or one that is not required but **should** be present on the system for the successful installation of this product.

A mandatory installation requisite identifies products that are required, without exception, or this product **will not install** on your system. This includes products specified as PREs or REQs.

Figure 7. Mandatory Installation Requisites

Program Number	Product Name and Minimum VRM/Service Level
5694-A01	z/OS V1.7 or later

A conditional installation requisite identifies products that are **not** required for successful install but may resolve such things as certain warning messages at installation time. They include products that are specified as IF REQs.

WebSphere eXtreme Scale V7.1 for z/OS has no conditional installation requisites.

5.2.2.2 Operational Requisites

An operational requisite is defined as a product that is required and **must** be present or a product that is not required but **should** be present on the system in order for this product to operate all or some of its functions.

A mandatory operational requisite identifies products that are required, without exception, or this product **will not operate** its basic function unless the requisite is met. This includes products specified as PREs or REQs.

<i>Figure 8. Mandatory Operational Requisites</i>	
Program Number	Product Name and Minimum VRM/Service Level
Any one of the following:	
5655-N01	WebSphere Application Server V6.1 for z/OS Fix Pack V6.1.0.31 with PTFs UK56467, UK56466, UK56455, UK56464, UK56463, UK56457, UK56456, UK56454 and UK56378.
5655-N02	WebSphere Application Server V7.0 for z/OS with Fix Pack 7009 with PTFs UK55166, UK55165, UK55164, UK55163, UK55162, UK55161, UK55159 and UK55155.

A conditional operational requisite identifies products that are **not required** for the basic function but are needed at run time for this product to utilize specific functions. They may include products specified as IF REQs.

WebSphere eXtreme Scale V7.1 for z/OS has no conditional operational requisites.

5.2.2.3 Toleration/Coexistence Requisites

A toleration/coexistence requisite is defined as a product which must be present on a sharing system. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD at different time intervals.

WebSphere eXtreme Scale V7.1 for z/OS has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites

A negative requisite identifies products which must *not* be installed on the same system as this product.

WebSphere eXtreme Scale V7.1 for z/OS has no negative requisites.

5.2.3 DASD Storage Requirements

WebSphere eXtreme Scale V7.1 for z/OS libraries can reside on all z/OS or z/OS.e supported DASD types.

Figure 9 on page 12 lists the total space required for each type of library.

Library Type	Total Space Required (3390 Tracks)	Component
Target	20	WebSphere eXtreme Scale V7.1 for z/OS
Distribution	1288	WebSphere eXtreme Scale V7.1 for z/OS
HFS	2250	WebSphere eXtreme Scale V7.1 for z/OS

Notes:

1. IBM recommends use of system determined block sizes for efficient DASD utilization for all non-RECFM U data sets. For RECFM U data sets, IBM recommends a block size of 32760, which is the most efficient from a performance and DASD utilization perspective.
2. Abbreviations used for the data set type are:

- U** Unique data set, allocated by this product and used only by this product. To determine the correct storage needed for this data set, this table provides all required information; no other tables (or Program Directories) need to be referenced for the data set size.
- S** Shared data set, allocated by this product and used by this product and others. To determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other Program Directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
- E** Existing shared data set, used by this product and others. This data set is NOT allocated by this product. To determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other program directories). This existing data set must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old one and reclaim the space used by the old release and any service that had been installed. You can determine whether or not these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information on the names and sizes of the required data sets, refer to 6.1.6, "Allocate SMP/E Target and Distribution Libraries" on page 20.

3. Abbreviations used for the HFS Path type are:

- N** New path, created by this product.
- X** Path created by this product, but may already exist from a previous release.

P Previously existing path, created by another product.

4. All target and distribution libraries listed have the following attributes:

- The default name of the data set may be changed.
- The default block size of the data set may be changed.
- The data set may be a PDS or PDSE, unless PDSE is explicitly specified.

5. All target libraries listed have the following attributes:

- The data set may be SMS-managed.
- It is not required for the data set to be SMS-managed.
- It is not required for the data set to reside on the IPL volume.
- The values in the "Member Type" column are not necessarily the actual SMP/E element types identified in the SMPMCS.

6. Some target libraries must be APF-authorized; some target libraries or library members must be placed in the LPA or LINKLST. See the customization instructions for details.

Figure 10. Storage Requirements for SMP/E Work Data Sets

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SMPWRK1	E	PDS	FB	80	120	10
SMPWRK2	E	PDS	FB	80	30	10
SMPWRK3	E	PDS	FB	80	9500	150
SMPWRK4	E	PDS	FB	80	80	10
SMPWRK6	E	PDS	FB	80	9999	100
SYSUT1	E	SEQ	--	--	7500	0
SYSUT2	E	SEQ	--	--	30	0
SYSUT3	E	SEQ	--	--	30	0
SYSUT4	E	SEQ	--	--	30	0

If the table indicates that the SMPLTS data set must be a PDSE, but your existing SMPLTS is a PDS, you will need to allocate a new PDSE and copy your existing SMPLTS into it and then change the SMPLTS DDDEF entry to indicate the new PDSE data set.

Figure 11. Storage Requirements for SMP/E Data Sets

Library DDNAME	T Y P E	O R G A N I Z A T I O N	R E C O R D S	L E N G T H	No. of 3390 Trks	No. of DIR Blks
SMPLTS	E	PDSE	U	0	6535	-
SMPMTS	E	PDS	FB	80	15	80
SMPPTS	E	PDS	FB	80	8000	80
SMPSCDS	E	PDS	FB	80	15	80
SMPSTS	E	PDS	FB	80	15	80

The following figures describe the target and distribution libraries and HFS paths required to install WebSphere eXtreme Scale V7.1 for z/OS. The storage requirements of WebSphere eXtreme Scale V7.1 for z/OS must be added to the storage required by other programs having data in the same library or path.

Note: The data in these tables should be used when determining which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

Figure 12. Storage Requirements for WebSphere eXtreme Scale V7.1 for z/OS Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G A N I Z A T I O N	R E C O R D S	L E N G T H	No. of 3390 Trks	No. of DIR Blks
SEJDEXEC	EXEC	TVOL1	U	PDS	VB	255	10	15
SEJDJCL	Sample	TVOL2	U	PDS	FB	80	10	15

Figure 13. WebSphere eXtreme Scale V7.1 for z/OS HFS Paths

DDNAME	T Y P E	Path Name
SEJDEBCD	N	/usr/lpp/zWebSphereXS/V7R1/IBM
SEJDANT	N	/usr/lpp/zWebSphereXS/V7R1/IBM

Figure 14. Storage Requirements for WebSphere eXtreme Scale V7.1 for z/OS Distribution Libraries

Library DDNAME	T Y P E	O R G A N I Z A T I O N	R E C O R D S	L E N G T H	No. of 3390 Trks	No. of DIR Blks
AEJDEXEC	U	PDS	VB	255	10	15
AEJDANT	U	PDS	VB	255	1253	120
AEJDEBCD	U	PDS	VB	31000	15	15
AEJDJCL	U	PDS	FB	80	10	15

Notes:

1. WebSphere eXtreme Scale V7.1 for z/OS will require several thousand additional tracks (3390) for run-time data sets; the amount of space depends on the application server structure to be used, the applications to be run and the amount of data storage the applications will require.
2. WebSphere eXtreme Scale V7.1 for z/OS requires significantly larger amounts of HFS storage for downloadable Application Server Client code. See 6.1.6, "Allocate SMP/E Target and Distribution Libraries" on page 20 for more information.

5.3 FMIDs Deleted

Installing WebSphere eXtreme Scale V7.1 for z/OS may result in the deletion of other FMIDs. To see what FMIDs will be deleted, examine the ++VER statement in the product's SMPMCS.

If you do not want to delete these FMIDs at this time, you must install WebSphere eXtreme Scale V7.1 for z/OS into separate SMP/E target and distribution zones.

Note: These FMIDs will not automatically be deleted from the Global Zone. Consult the SMP/E manuals for instructions on how to do this.

5.4 Special Considerations

You may install WebSphere eXtreme Scale V7.1 for z/OS into a new set of SMP/E zones, including SMPCSI, target, distribution, and HFS data sets. This program directory provides sample jobs and instructions to create such an SMP/E environment as well as a sample to implement cross zone checking for prerequisite service should you choose this option.

5.4.1 Driving System Mountpoint

During installation of WebSphere eXtreme Scale V7.1 for z/OS on the driving system, the target filesystem must be mounted at the following mountpoint:

`-PathPrefix-/usr/lpp/zWebSphereXS/V7R1`

where `-PathPrefix-` is a filesystem path prefix such as `/SERVICE` or `/WXD61`. Use of a filesystem path prefix allows maintenance to be applied to a copy of the WebSphere filesystem data sets without disturbing the production filesystem. For more information on the use of an filesystem path prefix during product maintenance, see the Unix System Services Planning book for your release of z/OS.

Care must be taken that maintenance is applied to the proper filesystem. Be sure to verify that the correct filesystem is mounted at your service mountpoint(s) whenever maintenance is applied.

5.4.2 Target System Mountpoint

During customization and operation of WebSphere eXtreme Scale V7.1 for z/OS on the target system, the target filesystem must be mounted at the following mountpoint:

- A WebSphere eXtreme Scale V7.1 for z/OS mountpoint, normally `/usr/lpp/zWebSphereXS/V7R1`

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and activate the functions of WebSphere eXtreme Scale V7.1 for z/OS.

Please note the following:

- If you received WebSphere eXtreme Scale V7.1 for z/OS. through CBPDO or ServerPac, follow the instructions in the Program Directory for that package.
- If you want to install WebSphere eXtreme Scale V7.1 for z/OS. into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMPCSI and the SMP/E control data sets.
- Sample jobs have been provided to help perform some or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries required for SMP/E execution have been defined in the appropriate zones.
- The SMP/E dialogs may be used instead of the sample jobs to accomplish the SMP/E installation tasks.

Note: WebSphere eXtreme Scale V7.1 for z/OS can be installed into new or existing SMP/E zones.

6.1 Installing WebSphere eXtreme Scale V7.1 for z/OS

Run all installation steps from a user ID that is defined to Unix Systems Services, and has the following attributes:

- UID(0) or READ access or higher to the BPX.SUPERUSER facility class.
- READ access or higher to the BPX.FILEATTR.PROGCTL and BPX.FILEATTR.APF and BPX.FILEATTR.SHARELIB facility classes.

6.1.1 SMP/E Considerations for Installing WebSphere eXtreme Scale V7.1 for z/OS

This release of WebSphere eXtreme Scale V7.1 for z/OS is installed using the SMP/E RECEIVE, APPLY, and ACCEPT commands. The SMP/E dialogs may be used to accomplish CBPDO or ServerPac, follow the instructions in the Program Directory the SMP/E installation steps.

The previous release of this product was a feature of WebSphere Extended Deployment V6.1 for z/OS. If WebSphere eXtreme Scale V7.1 for z/OS is installed into the same SMP/E zones as WebSphere Extended Deployment V6.1 it will delete V6.1 of WebSphere eXtreme Scale, formerly known as WebSphere Extended Deployment Data Grid.

We recommend that you install WebSphere eXtreme Scale V7.1 for z/OS into a separate set of SMP/E zones from WebSphere Extended Deployment V6.1.0 for z/OS if you intend to continue using that product.

WebSphere eXtreme Scale V7.1 for z/OS is not compatible with the eXtreme Scale (Data Grid) product shipped with WebSphere Extended Deployment 6.1.0 and should not be configured in the same WebSphere Application Server. WebSphere Extended Deployment V6.1.1 for z/OS includes WebSphere eXtreme Scale V7.1 for z/OS and may use the same SMP/E zones. You can customize sample jobs EJDCSICR and EJDZNCRT for your system and use these to create a new CSI and SMP/E TARGET and DLIB zones. You can find these jobs in the product relfile IBM.HEJD710.F3 which is loaded during SMP/E processing; see Figure 15 for a list of sample jobs.

Note: If you choose to install WebSphere eXtreme Scale V7.1 for z/OS into existing SMP/E target and distribution zones, be sure to completely remove any previous versions of WebSphere eXtreme Scale from the zones and remove the previous version's DDDEFs **before** installing the new version. See 5.4, “Special Considerations” on page 15 for more information.

6.1.2 Sample Jobs

Sample jobs to allocate the target and distribution libraries, set up HFS directories, and create DDDEF entries for the WebSphere eXtreme Scale V7.1 for z/OS elements have been provided.

Figure 15 lists the sample jobs for WebSphere eXtreme Scale V7.1 for z/OS.

<i>Figure 15. Sample Installation Jobs</i>			
Job Name	Job Type	Description	RELFILE
EJDCSICR	Setup	Creates an SMP/E global zone	IBM.HEJD710.F3
EJDZNCRT	Setup	Creates SMP/E target and distribution zones	IBM.HEJD710.F3
EJDZXDEF	Setup	Add additional target zone definitions for cross-zone prerequisite checking	IBM.HEJD710.F3
EJDALLOC	ALLOCATE	Allocates target and distribution libraries for WebSphere eXtreme Scale.	IBM.HEJD710.F3
EJDISMKD	MKDIR	Invokes the supplied EEXMKDIR EXEC to create HFS paths for WebSphere eXtreme Scale.	IBM.HEJD710.F3
EJDDDEF	DDDEF	Defines SMP/E DDDEFs for WebSphere eXtreme Scale.	IBM.HEJD710.F3
EJDAPPLY	APPLY	Applies ordered FMIDs and maintenance	IBM.HEJD710.F3
EJDACCEP	ACCEPT	Accepts ordered FMIDs and maintenance	IBM.HEJD710.F3
EJDRECEV	RECEIVE	Receives ordered FMIDs and maintenance	IBM.HEJD710.F3
EJDREREG	DELETE	Cleans up 5655-V66 Reg FMID	IBM.HEJD710.F3
EJDREGRR	RECEIVE	Receive Registration FMID	IBM.HEJD710.F3

You can access the sample installation jobs by performing an SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 15 to find the appropriate relfile data set.

Each sample job contains comments with specific instructions for customization.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.HEJD710.F3,UNIT=tunit,
// VOL=SER=volser,LABEL=(x,SL),
// DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.HEJD710.F3,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,
// DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,
// SPACE=(TRK,(30,20,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the previous sample, update the statements as noted in the following description:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.HEJD710.F3 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.3 Allocate SMP/E CSI (Optional)

If you are using an existing CSI, do not execute this job.

If you are allocating a new SMP/E CSI data set for this install, edit and submit sample job EJDICSICR to allocate the SMP/E CSI data set for WebSphere eXtreme Scale V7.1 for z/OS. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.4 Define New SMP/E TARGET and DLIB Zones (Optional)

Edit and submit sample job EJDZNCRT to define new SMP/E Target and Distribution zones. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.5 Perform SMP/E RECEIVE

Receive function SYSMODs and service for the WebSphere eXtreme Scale V7.1 for z/OS elements by running the RCVPDO job. For more information, refer to *MVS CBPDO Memo to User Extension* included with the CBPDO.

The CBPDO contains all non-integrated PTFs for every WebSphere eXtreme Scale V7.1 for z/OS FMID. (Cumulative service is included in CBPDO orders, so there is no separate cumulative service tape.) Depending on the options selected when you ordered the CBPDO, your order may contain service for other products in your profile.

To receive service for WebSphere eXtreme Scale V7.1 for z/OS select the FMIDs for the components you purchased based on the list in section 1.2.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.6 Allocate SMP/E Target and Distribution Libraries

Edit and submit sample job EJDALLOC to allocate the SMP/E target and distribution libraries for WebSphere eXtreme Scale V7.1 for z/OS. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.7 Allocate HFS Paths

Edit and submit sample job EJDISMKD to allocate the HFS paths for WebSphere eXtreme Scale V7.1 for z/OS. Consult the instructions in the sample job for more information.

If you plan to create a new HFS for this product, you should consider updating the BPXPRMxxx PARMLIB member to mount the new HFS at IPL time. This may be helpful if an IPL occurs before the installation is complete.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

Important!

- The EJDISMKD and EJDDDDDEF jobs use `-PathPrefix-` to represent a service directory on your driving system. It is assumed that you will be mounting WebSphere eXtreme Scale V7.1 for z/OS HFS data sets under a service directory that already contains the `/usr` and `/usr/lpp` directories. If you specify a `-PathPrefix-` directory which does not contain `/usr` and `usr/lpp` subdirectories, you must manually create these subdirectories before running the EJDISMKD job. If `-PathPrefix-/usr/lpp` is not a read/write HFS, you will need to manually create some additional subdirectories as well. See the comments in the EJDISMKD job for further information.

Check the job output to verify that all directories have been created.

Verify that the product filesystem is mounted at

`-PathPrefix-/usr/lpp/zWebSphereXS/V7R1`

6.1.8 Create DDDEF Entries

Edit and submit sample job EJDDDDDEF to create DDDEF entries for the SMP/E target and distribution libraries for WebSphere eXtreme Scale V7.1 for z/OS. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.9 Add Target Zones for Cross-Zone Prerequisite Checking

Because the WebSphere eXtreme Scale component has a number of maintenance requirements for the target z/OS systems, we recommend that you add the appropriate SMP/E target zones (z/OS, DB2, CICS, and IMS for z/OS) to the WebSphere eXtreme Scale SMP/E global zone. This will allow SMP/E to check each zone for maintenance required by WebSphere eXtreme Scale V7.1 for z/OS.

Customize and run the EJDZXDEF job to add target zones to the global zone which will be used for the SMP/E APPLY and ACCEPT steps in the following section.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.10 Special Case - Updating The Registration FMID

If this is your first install of all of the products in this suite at this release you should skip this section.

If you previously purchased the stand alone offering of any of the software included in this suite then you will have installed a registration FMID with that product. If you do not wish to do a full install of the product you will need to replace the installed registration FMID with the one which reflects that you now own the suite. This does not impact operation of the products and does not require reconfiguration.

Edit and submit the following sample job as needed.

EJDREREG - If you previously installed:
WebSphere eXtreme Scale V7.0

Expected Return Codes and Messages from these jobs:: You may receive a return code of 4 if this job runs correctly because you may not have any HOLDDATA to REJECT.

Once you have removed the old registration FMID you may use the install samples included in this package to install **only the new registration FMID.** Use job EJDREGRR to RECEIVE the new FMID or FMIDs and the APPLY and ACCEPT samples listed for the product or products that you are updating.

6.1.11 Perform SMP/E APPLY

SMP/E apply processing for WebSphere eXtreme Scale V7.1 for z/OS uses the Java SDK JAR command to extract certain HFS files. In order for the JAR command to run correctly, SMP/E must be running with a fix for APAR IR54653. If either SMP/E APAR IO04924 or IO05943 is installed, then SMP/E will NOT run /etc/profile or \$HOME/.profile and the PATH environment variable will not be set. A new DDDEF entry named SMPJHOME in the target zone is required. For example: //SMPJHOME DD
PATH='/usr/lpp/java/J5.0'

Test the availability of the JAR command by logging into the OMVS Shell with the user ID that will be used to run the EJDAPPLY job and entering the following command: /usr/lpp/java/J5.0/jar

The JAR command should print its usage information.

If neither SMP/E APAR IO04924 nor IO05943 is installed, then SMP/E will run /etc/profile or \$HOME/.profile and the PATH environment variable will be set. The DDDEF entry named SMPJHOME in the target zone (set in samples job EJDZNCRT) is not required and can be removed if you choose. The user ID used to run the EJDAPPLY job must have the SDK bin directory in its Unix System Services PATH. This can be accomplished in one of two ways:

1. Add an SDK bin directory containing the JAR command (such as /usr/lpp/java/IBM/J5.0/bin) to the PATH variable in /etc/profile before running the EJDAPPLY job. For example:

```
PATH=/usr/lpp/java/IBM/J5.0/bin:<rest of PATH>
```

2. Add an SDK bin directory to the PATH variable in a file named .profile in the HOME directory for the user ID used in running the EJDAPPLY job.

Test the availability of the JAR command by logging in to the OMVS shell with the user ID that will be used to run the EJDAPPLY job and entering the command "jar"; the JAR command should print its usage information. See the z/OS Unix System Services User's Guide for information about using /etc/profile and &HOME/.profile scripts.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the following on the APPLY CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of **ERRORS** and not of **WARNINGS** (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

Enhanced HOLDDATA introduced ERROR HOLDS against FMIDs for HIPER APARS. Prior to installing, you should ensure you have the latest enhanced HOLDDATA (available at url <http://service.software.ibm.com/holdata/390holddata.html>). The FMID(s) should be installed regardless of the status of unresolved HIPERS, however, the software should not be deployed until the unresolved HIPERs have been analyzed to determine applicability.

There are two methods to complete an FMID installation where ++HOLDS for HIPERs exist for the FMID(s) being installed:

1. To ensure that all recommended and critical service is installed with the FMID(s), add the SOURCEIDs of PRP, HIPER, and RSU* to the APPLY command. There may be PE or HIPER APARS that do not have resolving PTFs available yet. You need to analyze the symptom flags to determine if you want to BYPASS the specific ERROR HOLDS and continue the FMID installation.

```
APPLY S(fmid,fmid,...)
FORFMID(fmid,fmid,...)
SOURCEID(PRP,HIPER,RSU*,...)
GROUPEXTEND .
```

This method requires more initial research, but will provide resolution for all HIPERs that have fixes available and are not in a PE chain. There may still be unresolved PEs or HIPERs which will require the use of BYPASS.

2. To install the FMID(s) as it would have been installed prior to Enhanced HOLDDATA, you can add a BYPASS(HOLDCLASS(HIPER)) operand to the APPLY command. This will allow the FMID to be installed even though there are HIPER ERROR HOLDS against it. Note that not all ERROR HOLDS were bypassed, only the HIPER ERROR HOLDS. After the FMID(s) are installed, the SMP/E REPORT ERRSYSMODS command should be run to identify any missing HIPER maintenance.

```
APPLY S(fmid,fmid,...)
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER)) .
other parameters documented in the program directory...
```

This method is the quicker of the two, but requires subsequent review of the REPORT ERRSYSMODS to investigate any HIPERs.

If you bypass any HOLDS during the installation of the FMID(s) because fixing PTFs were not yet available you can use the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink to be notified when the fixing PTF is available.

Edit and submit EJDAPPLY.

Once you have taken any actions indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Expected Return Codes and Messages from APPLY CHECK: You will receive a return code of 0 if this job runs correctly.

Expected Return Codes and Messages from APPLY: You will receive a return code of 0 if this job runs correctly.

Note!

Using GROUPEXTEND in APPLY with maintenance with HOLDDATA may cause a return code other than 0.

6.1.12 Perform SMP/E ACCEPT

Perform an SMP/E ACCEPT CHECK for WebSphere eXtreme Scale V7.1 for z/OS.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the following on the ACCEPT CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of **ERRORS** and not of **WARNINGS** (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

Before using SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. This will cause entries produced from JCLIN to be saved in the distribution zone whenever a SYSMOD containing inline JCLIN is ACCEPTed. For more information on the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E manuals.

Edit and submit EJDACCEP.

Once you have taken any actions indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accept all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK: You will receive a return code of 0 if this job runs correctly.

If PTFs containing replacement modules are being ACCEPTed, SMP/E ACCEPT processing will link-edit/bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder may issue messages documenting unresolved external references, resulting in a return code of 4 from the ACCEPT step. These messages can be ignored, because the distribution libraries are not executable and the unresolved external references will not affect the executable system libraries.

Note: The GROUPEXTEND operand indicates that SMP/E should ACCEPT all requisite SYSMODS. The requisite SYSMODS may be part of other products; review the ACCEPT CHECK output carefully before proceeding.

Expected Return Codes and Messages from ACCEPT: You will receive a return code of 0 if this job runs correctly.

6.2 Activating WebSphere eXtreme Scale V7.1 for z/OS

WebSphere eXtreme Scale V7.1 for z/OS must be configured after SMP/E installation is complete. See the WebSphere eXtreme Scale V7.1 for z/OS Customization Guide for more information at: <http://www.ibm.com/software/webservers/appserv/extend/library>

6.2.1 HFS Execution

If you choose to have the HFS in which you have installed WebSphere eXtreme Scale V7.1 for z/OS mounted in read-only mode during execution, see the following section.

6.2.2 Mount the HFS Data Set on the Target System

Before proceeding with activation, unmount WebSphere eXtreme Scale V7.1 for z/OS datasets on the driving system and mount them on the target system at the target system mount points. See 5.4.2, “Target System Mountpoint” on page 16, for assistance in selecting the mountpoint.

If you have selected the default mountpoints, you can use the following TSO command on your target system to mount the HFS data set:

```
MOUNT FILESYSTEM('hlq.SEJDHFS')  
MOUNTPOINT('/usr/lpp/zWebSphereXS/V7R1') TYPE(HFS) MODE(READ)
```

You will probably want to add this mount to your BPXPRMxx members in parmlib to ensure that these data sets are always mounted. When, at a later date, you need to perform service on the WebSphere eXtreme Scale V7.1 for z/OS product:

- Temporarily unmount the HFS data sets.
- Mount HFS data sets to be serviced at the service (-PathPrefix-) mountpoint you created for installation.
- Apply the service.
- Unmount the HFS data sets from the service mountpoint.
- Remount at the production mountpoint.

Appendix A. Notices

References in this document to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe on any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, New York 10504-1785
USA

For online versions of this book, we authorize you to:

- Copy, modify, and print the documentation contained on the media, for use within your enterprise, provided you reproduce the copyright notice, all warning statements, and other required statements on each copy or partial copy.
- Transfer the original unaltered copy of the documentation when you transfer the related IBM product (which may be either machines you own, or programs, if the program's license terms permit a transfer). You must, at the same time, destroy all other copies of the documentation.

You are responsible for payment of any taxes, including personal property taxes, resulting from this authorization.

THERE ARE NO WARRANTIES, EXPRESS OR IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Some jurisdictions do not allow the exclusion of implied warranties, so the above exclusion may not apply to you.

Your failure to comply with the terms above terminates this authorization. Upon termination, you must destroy your machine readable documentation.

A.1 Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

CBPDO	OS/390	VTAM
DB2	RACF	WebSphere
IBM	RETAIN	z/OS
IBMLink	S/390	z/VM
Language Environment	SP	z/Architecture
MQSeries	SystemPac	zSeries
MVS/ESA		

The following terms are trademarks of other companies as follows:

JAVA	Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and/or other countries.
UNIX	UNIX is a registered trademark of The Open Group in the United States and other countries.

Reader's Comments

Program Directory for WebSphere eXtreme Scale V7.1 for z/OS, July 2010

You may use this form to comment about this document, its organization, or subject matter with the understanding that IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

For each of the topics below, indicate your satisfaction level by circling your choice from the rating scale. If a statement does not apply, circle N.

RATING SCALE						
very satisfied	<=====>			very dissatisfied	not applicable	
1	2	3	4	5	N	

	Satisfaction					
Ease of product installation	1	2	3	4	5	N
Contents of Program Directory	1	2	3	4	5	N
Installation Verification Programs	1	2	3	4	5	N
Time to install the product	1	2	3	4	5	N
Readability and organization of Program Directory tasks	1	2	3	4	5	N
Necessity of all installation tasks	1	2	3	4	5	N
Accuracy of the definition of the installation tasks	1	2	3	4	5	N
Technical level of the installation tasks	1	2	3	4	5	N
Ease of getting the system into production after installation	1	2	3	4	5	N

How did you order this product?

- CBPDO
- CustomPac
- ServerPac
- Independent
- Other

Is this the first time your organization has installed this product?

- Yes
- No

Were the people who did the installation experienced with the installation of z/OS products?

- Yes

___ No

If yes, how many years? ___

If you have any comments to make about your ratings above, or any other aspect of the product installation, list them below:

Provide the following contact information:

Name and Job Title

Organization

Address

Telephone

Thank you for your participation.

Send the completed form to (or give to your IBM representative who will forward it to the WebSphere eXtreme Scale V7.1 for z/OS Development group):

International Business Machines Corporation
Department 55JA, Mail Station P384
2455 South Road
Poughkeepsie, NY 12601-5400
United States of America

FAX Number: (United States & Canada) 1+845+432+9405

FAX Number: (Other Countries):

Your International Access Code +1+845+432+9405

Internet e-mail: wasdoc@us.ibm.com



Printed in U.S.A.

GI11-4333-02

