



System i

プログラミング

分散アプリケーション開発に Sun TI-RPC の使用

バージョン 6 リリース 1







System i

プログラミング

分散アプリケーション開発に Sun TI-RPC の使用

バージョン 6 リリース 1

### ご注意

本書および本書で紹介する製品をご使用になる前に、39ページの『特記事項』に記載されている情報をお読みください。

本書は、IBM i5/OS (プロダクト番号 5761-SS1) バージョン 6、リリース 1、モディフィケーション 0 に適用されます。また、改訂版で断りがない限り、それ以降のすべてのリリースおよびモディフィケーションに適用されます。このバージョンは、すべての RISC モデルで稼働するとは限りません。また CISC モデルでは稼働しません。

IBM 発行のマニュアルに関する情報のページ

<http://www.ibm.com/jp/manuals/>

こちらから、日本語版および英語版のオンライン・ライブラリーをご利用いただけます。また、マニュアルに関するご意見やご感想を、上記ページよりお送りください。今後の参考にさせていただきます。

(URL は、変更になる場合があります)

お客様の環境によっては、資料中の円記号がバックスラッシュと表示されたり、バックスラッシュが円記号と表示されたりする場合があります。

原典： System i

Programming

Using Sun TI-RPC to develop distributed applications

Version 6 Release 1

発行： 日本アイ・ビー・エム株式会社

担当： ナショナル・ランゲージ・サポート

第1刷 2008.2

この文書では、平成明朝体™W3、平成明朝体™W7、平成明朝体™W9、平成角ゴシック体™W3、平成角ゴシック体™W5、および平成角ゴシック体™W7を使用しています。この(書体\*)は、(財)日本規格協会と使用契約を締結し使用しているものです。フォントとして無断複製することは禁止されています。

注\* 平成明朝体™W3、平成明朝体™W7、平成明朝体™W9、平成角ゴシック体™W3、  
平成角ゴシック体™W5、平成角ゴシック体™W7

© Copyright International Business Machines Corporation 1998, 2008. All rights reserved.

© Copyright IBM Japan 2008

---

## 目次

<b>分散アプリケーション開発に Sun TI-RPC の使用</b>	<b>1</b>
「分散アプリケーション開発に Sun TI-RPC の使用」の PDF ファイル	1
rpcbind デーモンの使用	2
rpcbind デーモンが i5/OS で実行しているかを確認する	2
i5/OS で rpcbind デーモンを開始および終了する	2
rpcgen コンパイラの使用	3
ネットワーク選択メカニズムの使用	3
データ変換サポートの使用	3
例: TI-RPC コードに基づいてサービス・アプリケーションを開発する	4
例: TI-RPC 簡易レベル・サービス API	4
例: TI-RPC トップレベル・サービス API	7
例: TI-RPC 中間レベル・サービス API	14
例: TI-RPC エキスパート・レベル・サービス API	15
例: TI-RPC サービスへの認証の追加	16
例: TI-RPC コードに基づいてクライアント・アプリケーションを開発する	17
例: TI-RPC 簡易レベル・クライアント API	17
例: TI-RPC トップレベル・クライアント API	22
例: TI-RPC 中間レベル・クライアント API	26
例: TI-RPC エキスパート・レベル・クライアント API	31
例: TI-RPC クライアントへの認証の追加	36
<b>付録. 特記事項</b>	<b>39</b>
プログラミング・インターフェース情報	40
商標	41
使用条件	41



---

## 分散アプリケーション開発に Sun TI-RPC の使用

リモート・プロシージャ・コール (RPC) は高水準のパラダイムを提供しており、分散アプリケーションを相互に通信させることができます。

Sun Microsystems 社が開発したオープン・ネットワーク・コンピューティング (ONC) RPC を使用すると、クライアント・アプリケーションをサーバー・メカニズムから容易に分離して分散することができます。トランスポート層に依存しないリモート・プロシージャ・コール (TI-RPC) または ONC+ RPC は、リリースされている RPC の最新バージョンです。 TI-RPC では、ネットワーク層で使用される、基礎となるプロトコルを抽出する方法を提供することにより、プロトコル同士でより途切れの少ない伝送を行うことができます。

TI-RPC を使用して分散アプリケーションを設計、インプリメント、および保守する方法についての詳細は、Sun Microsystems Documentation の Web サイト  にある「ONC+ 開発ガイド」(Sun Microsystems, Inc. 著) を参照してください。

注：コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

---

### 「分散アプリケーション開発に Sun TI-RPC の使用」の PDF ファイル

この情報の PDF ファイルを表示および印刷することができます。

この文書の PDF 版を表示またはダウンロードするには、「分散アプリケーション開発に Sun TI-RPC の使用」を選択します。

### その他の情報

TI-RPC を使用して分散アプリケーションを設計、インプリメント、および保守する方法についての詳細は、Sun Microsystems Documentation の Web サイト  にある「ONC+ 開発ガイド」(Sun Microsystems, Inc. 著) を参照してください。

TI-RPC サービスのアプリケーション・プログラミング・インターフェース (API) についての詳細は、「アプリケーション・プログラミング・インターフェース」を参照してください。

### PDF ファイルの保存

表示用または印刷用の PDF ファイルをワークステーションに保存するには、次のようにします。

1. ご使用のブラウザーで PDF のリンクを右クリックする。
2. ローカルに PDF を保存するオプションをクリックする。
3. PDF を保存したいディレクトリーに進む。
4. 「保存」をクリックする。

## Adobe Reader のダウンロード

これらの PDF を表示または印刷するには、Adobe® Reader がシステムにインストールされている必要があります。Adobe Reader は、Adobe の Web サイト ([www.adobe.com/products/acrobat/readstep.html](http://www.adobe.com/products/acrobat/readstep.html))  から無償でダウンロードすることができます。

---

## rpcbind デーモンの使用

クライアントがリモート・プロシージャ・コール (RPC) サービスへの接続を望む場合、RPC は rpcbind デーモンと連絡を取り、サービスのアドレスを要求します。このようにして、アドレッシングが動的にできるため、クライアントはサービスが待機しているポートを知る必要がありません。

サービスを利用するためには、rpcbind デーモンを使用して登録することが必要です。 rpcbind デーモンが非活動状態である場合、サービスは起動できず、クライアントもサービスを見つけることができません。

## rpcbind デーモンが i5/OS で実行しているかを確認する

トランスポート層に依存しないリモート・プロシージャ・コール (TI-RPC) のアプリケーション・プログラミング・インターフェース (API) を使用するには、rpcbind デーモン・ジョブ (QNFSRPCD) が i5/OS® オペレーティング・システムで実行していることを確認する必要があります。

rpcbind デーモンが実行しているかを確認するには、以下のタスクを完了します。

1. i5/OS コマンド行で、WRKACTJOB と入力します。
2. サブシステム QSYSWRK で、次のジョブがあるかどうかを検索します。

QNFSRPCD The rpcbind daemon

## i5/OS で rpcbind デーモンを開始および終了する

rpcbind デーモンを i5/OS オペレーティング・システムで開始します (まだ実行していない場合)。 rpcbind デーモン (RPCBIND) コマンドは、rpcbind デーモン・ジョブ (QNFSRPCD) を開始します。

### rpcbind デーモン・ジョブを開始する

rpcbind デーモン・ジョブを開始するには、次のコマンドを入力します。

RPCBIND RTVRPCREG(\*YES)

注: このコマンドのオプション・パラメーターは RTVRPCREG で、rpcbind デーモンの開始時に、前に記録された登録情報を検索するかどうかを指定します。このパラメーターのデフォルトは \*NO です。 rpcbind デーモンが開始時に登録情報を検索するようにしたい場合は \*YES を選択します。このコマンドのパラメーターおよび値の説明についての詳細は、オンライン・ヘルプ・テキストを参照してください。

### rpcbind デーモン・ジョブを終了する

rpcbind デーモン・ジョブ (QNFSRPCD) を終了するには、次のコマンドを入力します。

ENDRPCBIND

## rpcgen コンパイラーの使用

RPCGEN コマンドは、リモート・プロシージャ・コール言語 (RPCL) で書かれた入力ファイルから C コードを生成します。生成された C コードを使用して、RPC プロトコルをインプリメントします。

i5/OS オペレーティング・システムで rpcgen コンパイラーを使用するには、以下のタスクを完了します。

1. RPCL にソース入力ファイルを作成します。

rpcgen コンパイラーの使用法について詳しくは、Sun Microsystems Documentation の Web サイト を参照してください。

2. 次のコマンドを入力して、rpcgen コンパイラーを i5/OS オペレーティング・システム上で実行します。

RPCGEN

注: このコマンドのパラメーターおよび値の説明については、オンライン・ヘルプ・テキストを参照してください。

3. i5/OS オペレーティング・システムで C 言語コンパイラーを使用し、rpcgen コンパイラーからの出力をコンパイルします。

注: i5/OS オペレーティング・システムで Integrated Language Environment® (ILE) C コンパイラーを使用している場合は、出力ファイルをソース・メンバーとして保管する必要があります。

## ネットワーク選択メカニズムの使用

ネットワーク選択メカニズムにより、アプリケーションが実行する際のトランスポートを選択することができます。

/etc/netconfig ファイルは、ホストに対して使用可能なトランスポートをリストし、タイプによって識別するデータベースです。トランスポートは、/etc/netconfig ファイルに示された指定の順序で使用できます。

i5/OS オペレーティング・システムの /etc/netconfig ファイルにアクセスするには、以下のステップを完了します。

1. System i<sup>TM</sup> ナビゲーターを開きます。
2. 「ネットワーク (Network)」 → 「サーバー (Servers)」と展開します。
3. 「i5/OS サーバー」を選択します。
4. メニューで「RPC」を右クリックして、「プロパティー」を選択します。
5. 「RPC トранスポート」タブを選択します。

注: この情報を見るには、\*IOSYSCFG 権限が必要です。

### 関連資料

アプリケーション・プログラミング・インターフェース

## データ変換サポートの使用

i5/OS オペレーティング・システム上で、トランスポート層に依存しないリモート・プロシージャ・コール (TI-RPC) のアプリケーション・プログラミング・インターフェース (API) はすべて各国語サポート (NLS) に対応しています。

このサポートは、外部データ表示 (XDR) 関数のリストに追加されています。これらの関数を使用して、異なるコード・ページにあるクライアントとサービスの間でデータの通信を行うことができます。システム管理者は、コード・ページをリモート・クライアントと関連付けるために、/etc/rpcnls ファイルを保持します。XDR 関数は、/etc/rpcnls ファイルの情報を使って暗黙のデータ変換を行います。次の XDR 関数は、暗黙のデータ変換ルーチンを組み込みます。

- `xdr_char()` (1 バイトのみ)
- `xdr_u_char()` (1 バイトのみ)
- `xdr_double_char` (1 バイトおよび 2 バイト)
- `xdr_string()` (1 バイトおよび 2 バイト)
- `xdr_wrapstring ()` (1 バイトおよび 2 バイト)

System i ナビゲーター で i5/OS オペレーティング・システムの /etc/rpcnls ファイルにアクセスするには、以下のステップを完了します。

1. System i ナビゲーター を開きます。
2. 「ネットワーク (Network)」 → 「サーバー (Servers)」と展開します。
3. 「i5/OS サーバー」を選択します。
4. メニューで「RPC」を右クリックして、「プロパティー」を選択します。
5. 「データ変換」タブを選択します。

注: この情報を見るには、\*IOSYSCFG 権限が必要です。

#### 関連資料

アプリケーション・プログラミング・インターフェース

---

## 例: TI-RPC コードに基づいてサービス・アプリケーションを開発する

トランスポート層に依存しないリモート・プロシージャ・コール (TI-RPC) プログラミングは、i5/OS オペレーティング・システム上でクライアント/サーバー・ベースの分散アプリケーションを開発するための効率的な方法を提供します。

#### 関連資料

17 ページの『例: TI-RPC コードに基づいてクライアント・アプリケーションを開発する』  
i5/OS オペレーティング・システムでクライアント・アプリケーションを開発するには、ガイドラインとしてこのコード例を使用します。

## 例: TI-RPC 簡易レベル・サービス API

このコード例では、TI-RPC サービスの開発で使用される簡易レベル・サービス API の 1 つを説明します。

このコード例では、各プロシージャーが、他のプロシージャーから独立して登録される方法に注目してください。簡易レベルでは、サービスに複数のプロシージャーがある場合でも、それぞれを個別に登録しなければなりません。サービスが登録抹消される場合は、すべてのプロシージャーが一度に抹消されます。他のプロシージャーをそのままにしておいて、個々のプロシージャーを登録抹消するという方法はありません。

このレベルは、プロシージャーの数が少ないサービスに適しています。また、限られた数の最終プロシージャーを使って、かなり大きなサービスのプロトタイプを作成するのにも役立ちます。どのサービス・レベルでも、サービスの最終コールは、`svc_run()` でなければなりません。このコールで、Select Wait (クライアントからの接続を待機する) 状態になります。

注: コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

```
#include <stdio.h>
#include <netconfig.h>
#include <rpc/rpc.h>
#include <errno.h>
#include "myapp.h"
int main(int argc, char *argv[]) {

    bool_t rs1t; /* return value for rpc_call() */

    /* unregister any existing copy of this service */
    /* (void)svc_unreg(program, version) */
    svc_unreg(PROGNUM, VERSNUM);

    /* (bool_t)rpc_reg(prognum, versnum, procnum, procname, */
    /*                  xdr_in, xdr_out, nettype) */
    rs1t = rpc_reg(PROGNUM, VERSNUM, GET_UID, myapp_get_uid,
                   xdr_wrapstring, xdr_u_int, NETTYPE);

    /* check for errors calling rpc_reg() */
    if (rs1t == FALSE) {
        /* print error messages and exit */
        fprintf(stderr, "Error calling rpc_reg for %s\n", "GET_UID");
        fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
                PROGNUM, VERSNUM, NETTYPE);
        /* clean up before exiting */
        svc_unreg(PROGNUM, VERSNUM);
        return 1;
    }

    /* (bool_t)rpc_reg(prognum, versnum, procnum, procname, */
    /*                  xdr_in, xdr_out, nettype) */
    rs1t = rpc_reg(PROGNUM, VERSNUM, GET_UID_STRING, myapp_get_uid_string,
                   xdr_wrapstring, xdr_wrapstring, NETTYPE);

    /* check for errors calling rpc_reg() */
    if (rs1t == FALSE) {
        /* print error messages and exit */
        fprintf(stderr, "Error calling rpc_reg for %s\n", "GET_UID_STRING");
        fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
                PROGNUM, VERSNUM, NETTYPE);
        /* clean up before exiting */
        svc_unreg(PROGNUM, VERSNUM);
        return 1;
    }

    /* (bool_t)rpc_reg(prognum, versnum, procnum, procname, */
    /*                  xdr_in, xdr_out, nettype) */
    rs1t = rpc_reg(PROGNUM, VERSNUM, GET_SIZE, myapp_get_size,
                   xdr_wrapstring, xdr_int, NETTYPE);

    /* check for errors calling rpc_reg() */
    if (rs1t == FALSE) {
        /* print error messages and exit */
        fprintf(stderr, "Error calling rpc_reg for %s\n", "GET_SIZE");
        fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
                PROGNUM, VERSNUM, NETTYPE);
        /* clean up before exiting */
        svc_unreg(PROGNUM, VERSNUM);
        return 1;
    }

    /* (bool_t)rpc_reg(prognum, versnum, procnum, procname, */
    /*                  xdr_in, xdr_out, nettype) */
    rs1t = rpc_reg(PROGNUM, VERSNUM, GET_MTIME, myapp_get_mtime,
```

```

xdr_wrapstring, xdr_long, NETTYPE);

/* check for errors calling rpc_reg() */
if (rslt == FALSE) {
    /* print error messages and exit */
    fprintf(stderr, "Error calling rpc_reg for %s\n", "GET_MTIME");
    fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
        PROGNUM, VERSNUM, NETTYPE);
    /* clean up before exiting */
    svc_unreg(PROGNUM, VERSNUM);
    return 1;
}

/* (bool_t)rpc_reg(prognum, versnum, procnum, procname, */
/*                  xdr_in, xdr_out, nettype)           */
rslt = rpc_reg(PROGNUM, VERSNUM, GET_MTIME_STRING, myapp_get_mtime_string,
    xdr_wrapstring, xdr_wrapstring, NETTYPE);

/* check for errors calling rpc_reg() */
if (rslt == FALSE) {
    /* print error messages and exit */
    fprintf(stderr, "Error calling rpc_reg for %s\n", "GET_MTIME_STRING");
    fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
        PROGNUM, VERSNUM, NETTYPE);
    /* clean up before exiting */
    svc_unreg(PROGNUM, VERSNUM);
    return 1;
}

/* (bool_t)rpc_reg(prognum, versnum, procnum, procname, */
/*                  xdr_in, xdr_out, nettype)           */
rslt = rpc_reg(PROGNUM, VERSNUM, GET_CODEPAGE, myapp_get_codepage,
    xdr_wrapstring, xdr_u_short, NETTYPE);

/* check for errors calling rpc_reg() */
if (rslt == FALSE) {
    /* print error messages and exit */
    fprintf(stderr, "Error calling rpc_reg for %s\n", "GET_CODEPAGE");
    fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
        PROGNUM, VERSNUM, NETTYPE);
    /* clean up before exiting */
    svc_unreg(PROGNUM, VERSNUM);
    return 1;
}

/* (bool_t)rpc_reg(prognum, versnum, procnum, procname, */
/*                  xdr_in, xdr_out, nettype)           */
rslt = rpc_reg(PROGNUM, VERSNUM, GET_OBJTYPE, myapp_get_objtype,
    xdr_wrapstring, xdr_wrapstring, NETTYPE);

/* check for errors calling rpc_reg() */
if (rslt == FALSE) {
    /* print error messages and exit */
    fprintf(stderr, "Error calling rpc_reg for %s\n", "GET_OBJTYPE");
    fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
        PROGNUM, VERSNUM, NETTYPE);
    /* clean up before exiting */
    svc_unreg(PROGNUM, VERSNUM);
    return 1;
}

/* (bool_t)rpc_reg(prognum, versnum, procnum, procname, */
/*                  xdr_in, xdr_out, nettype)           */
rslt = rpc_reg(PROGNUM, VERSNUM, GET_FILETYPE, myapp_get_filetype,
    xdr_wrapstring, xdr_wrapstring, NETTYPE);

/* check for errors calling rpc_reg() */

```

```

if (rslt == FALSE) {
    /* print error messages and exit */
    fprintf(stderr, "Error calling rpc_reg for %s\n", "GET_FILETYPE");
    fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
            PROGNUM, VERSNUM, NETTYPE);
    /* clean up before exiting */
    svc_unreg(PROGNUM, VERSNUM);
    return 1;
}

/* (bool_t)rpc_reg(prognum, versnum, procnum, procname, */
/*                  xdr_in, xdr_out, nettype) */
rslt = rpc_reg(PROGNUM, VERSNUM, END_SERVER, myapp_end_server,
               (xdrproc_t)xdr_void, (xdrproc_t)xdr_void, NETTYPE);

/* check for errors calling rpc_reg() */
if (rslt == FALSE) {
    /* print error messages and exit */
    fprintf(stderr, "Error calling rpc_reg for %s\n", "END_SERVER");
    fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
            PROGNUM, VERSNUM, NETTYPE);
    /* clean up before exiting */
    svc_unreg(PROGNUM, VERSNUM);
    return 1;
}

/* this should loop indefinitely waiting for client connections */
svc_run();

/* if we get here, svc_run() returned */
fprintf(stderr, "svc_run() returned. ERROR has occurred.\n");
fprintf(stderr, "errno: %d\n", errno);

/* clean up by unregistering. then, exit */
svc_unreg(PROGNUM, VERSNUM);

return 1;
} /* end of main() */

```

## 例: TI-RPC トップレベル・サービス API

以下のコード例では、TI-RPC サービスの開発で使用する、トップレベル・サービス API について説明します。

トップレベルでサービスを開発するには、開発者がディスパッチ・ルーチンを作成する必要があるため、より複雑な作業になります。このレベルでは、サービス要求が入ってくるとディスパッチ・ルーチンが呼び出されます。ディスパッチ・ルーチンは引き数を収集して正しいローカル・プロシージャを呼び出し、すべてのエラーと結果を捕らえ、その情報をクライアントに戻す必要があります。ディスパッチ関数がいったん作成されると、わずかな変更だけで他のサービスでコピーしたり使ったりすることが容易になります。

トップ、中間、およびエキスパート層は、変更せずに同じディスパッチ関数を使用することができます。次の例では、ディスパッチ関数は、このファイルの他のローカル関数と組み込まれています。両方のファイルを、サービスの実行前にコンパイルし、一緒にリンクすることが必要です。他の層の上にトップレベルをもつてることにより、ネットワーク選択 API を使用しないで、ネット・タイプをストリングとして指定できるという利点があります。トップレベル API を呼び出した後、rpcbind デーモンを使用してサービスを作成し、ディスパッチ関数に結合し登録します。

注: コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

```

#include <stdio.h>
#include <netconfig.h>
#include <rpc/rpc.h>
#include <errno.h>
#include "myapp.h"
int main(int argc, char *argv[]) {

    int num_svc; /* return value for the svc_create() API */

    /* unregister any existing copy of this service */
    /* (void)svc_unreg(program, version) */
    svc_unreg(PROGNUM, VERSNUM);

    /* (int)svc_create(dispatch, progrnum, versnum, nettype); */
    num_svc = svc_create(myapp_dispatch, PROGNUM, VERSNUM, NETTYPE);

    /* check for errors calling svc_create() */
    if (num_svc == 0) {
        /* print error messages and exit */
        fprintf(stderr, "Error calling %s.\n", "svc_create");
        fprintf(stderr, "PROG: %lu\nVERS: %lu\nNET: %s\n",
            PROGNUM, VERSNUM, NETTYPE);
        fprintf(stderr, "errno: %d\n", errno);
        return 1;
    }

    /* this should loop indefinitely waiting for client connections */
    svc_run();

    /* if we get here, svc_run() returned */
    fprintf(stderr, "svc_run() returned. ERROR has occurred.\n");
    fprintf(stderr, "errno: %d\n", errno);

    /* clean up by unregistering. then, exit */
    svc_unreg(PROGNUM, VERSNUM);

    return 1;
} /* end of main() */

/* This is an example of the dispatch function */

#include <stdio.h>
#include <stdlib.h>
#include <sys/stat.h>
#include <pwd.h>
#include <rpc/rpc.h>
#include <time.h>
#include "myapp.h"

char * myapp_get_uid(char *in) {

    u_int retval;           /* return value for this procedure() */
    struct stat sbuf;       /* data storage area for stat() */
    int stat_ret;           /* return value for stat() */
    char *file = *(char **)in; /* input value for stat() */

    /* (int)stat(filename, struct stat *) */
    stat_ret = stat(file, &sbuf);

    if (stat_ret == -1) {
        retval = (u_int)-1;
    }
    else {
        retval = (u_int)(sbuf.st_uid);
    }

    return (char *)&retval;
}

```

```

}

char *myapp_get_uid_string(char *in) {

    char *retval;           /* return value for this procedure() */
    struct passwd *pbuf;    /* return value for getpwuid() */
    struct stat sbuf;      /* data storage area for stat() */
    int stat_ret;          /* return value for stat() */
    char *file = *(char **)in; /* input value for stat() */

    /* (int)stat(filename, struct stat *) */
    stat_ret = stat(file, &sbuf);

    if (stat_ret == -1) {
        retval = (char *)NULL;
    }
    else {

        pbuf = (struct passwd *)getpwuid((uid_t)(sbuf.st_uid));

        if (pbuf == NULL) {
            retval = (char *)NULL;
        }
        else {
            retval = (char *)(pbuf->pw_name);
        }
    }

    return (char *)&retval;
}

char * myapp_get_size(char *in) {

    int retval;           /* return value for this procedure() */
    struct stat sbuf;    /* data storage area for stat() */
    int stat_ret;          /* return value for stat() */
    char *file = *(char **)in; /* input value for stat() */

    /* (int)stat(filename, struct stat *) */
    stat_ret = stat(file, &sbuf);

    if (stat_ret == -1) {
        retval = (int)-1;
    }
    else {
        retval = (int)(sbuf.st_size);
    }

    return (char *)&retval;
}

char * myapp_get_mtime(char *in) {

    long retval;           /* return value for this procedure() */
    struct stat sbuf;    /* data storage area for stat() */
    int stat_ret;          /* return value for stat() */
    char *file = *(char **)in; /* input value for stat() */

    /* (int)stat(filename, struct stat *) */
    stat_ret = stat(file, &sbuf);

    if (stat_ret == -1) {
        retval = (long)-1;
    }
    else {
        retval = (long)(sbuf.st_mtime);
    }
}

```

```

return (char *)&retval;
}

char *myapp_get_mtime_string(char *in) {

char *retval;           /* return value for this procedure() */
struct stat sbuf;       /* data storage area for stat() */
int stat_ret;           /* return value for stat() */
char *file = *(char **)in; /* input value for stat() */

/* (int)stat(filename, struct stat *) */
stat_ret = stat(file, &sbuf);

if (stat_ret == -1) {
    retval = (char *)NULL;
}

else {
    retval = (char *)ctime((time_t *)&(sbuf.st_mtime));
}

return (char *)&retval;
}

char * myapp_get_codepage(char *in) {

u_short retval;           /* return value for this procedure() */
struct stat sbuf;         /* data storage area for stat() */
int stat_ret;             /* return value for stat() */
char *file = *(char **)in; /* input value for stat() */

stat_ret = stat(file, &sbuf);

if (stat_ret == -1) {
    retval = (u_short)-1;
}

else {
    retval = (u_short)(sbuf.st_codepage);
}

return (char *)&retval;
}

char *myapp_get_objtype(char *in) {

char *retval;           /* return value for this procedure() */
struct stat sbuf;         /* data storage area for stat() */
int stat_ret;             /* return value for stat() */
char *file = *(char **)in; /* input value for stat() */

/* (int)stat(filename, struct stat *) */
stat_ret = stat(file, &sbuf);

if (stat_ret == -1) {
    retval = (char *)NULL;
}

else {
    retval = (char *)(sbuf.st_objtype);
}

return (char *)&retval;
}

```

```

}

char *myapp_get_filetype(char *in) {
    char *result = NULL;          /* return value for this procedure() */
    struct stat sbuf;            /* data storage area for stat() */
    int stat_ret;                /* return value for stat() */
    char *file = *(char **)in;   /* input value for stat() */

    /* (int)stat(filename, struct stat *) */
    stat_ret = stat(file, &sbuf);

    if (stat_ret == -1) {
        return (char *)NULL;
    }

    if (S_ISDIR(sbuf.st_mode)) {
        result = "Directory";
    }

    if (S_ISREG(sbuf.st_mode)) {
        result = "Regular File";
    }

    if (S_ISLNK(sbuf.st_mode)) {
        result = "Symbolic Link";
    }

    if (S_ISSOCK(sbuf.st_mode)) {
        result = "Socket";
    }

    if (S_ISNATIVE(sbuf.st_mode)) {
        result = "System i Native Object";
    }

    if (S_ISFIFO(sbuf.st_mode)) {
        result = "FIFO";
    }

    if (S_ISCHR(sbuf.st_mode)) {
        result = "Character Special";
    }

    if (S_ISBLK(sbuf.st_mode)) {
        result = "Block Special";
    }

    return (char *)&result;
}

char * myapp_end_server(char *empty) {
    /* char *empty is not used      */
    /* function always returns NULL */

    svc_unreg(PROGNUM, VERSNUM);

    return (char *)NULL;
}

void myapp_dispatch(struct svc_req *request, SVCXPRT *svc) {
    union {
        /* all of the procedures take a string */

```

```

/* if there were other procedures, it */
/* might look like this:           */
/* int set_codepage_arg           */
char * filename_arg;
} argument;

char *result;          /* pointer to returned data from proc */
xdrproc_t xdr_argument; /* decodes data from client call */
xdrproc_t xdr_result;  /* encodes data to return to client */
char *(*proc)(char *); /* pointer to local procedure to call */

switch (request->rq_proc) {

case NULLPROC:
    /* a special case. always return void */
    (void)svc_sendreply((SVCXPRT *)svc,
                        (xdrproc_t)xdr_void,
                        (char *)NULL);
    return;

case GET_UID:
    /* takes a string argument (filename) */
    /* returns an u_int (uid of file owner) */
    xdr_argument = xdr_wrapstring;
    xdr_result = xdr_u_int;
    proc = (char *(*)(char *))myapp_get_uid;
    break;

case GET_UID_STRING:
    /* takes a string argument (filename) */
    /* returns a string (owner's name in string format) */
    xdr_argument = xdr_wrapstring;
    xdr_result = xdr_wrapstring;
    proc = (char *(*)(char *))myapp_get_uid_string;
    break;

case GET_SIZE:
    /* takes a string argument (filename) */
    /* returns an int (size of file in bytes) */
    xdr_argument = xdr_wrapstring;
    xdr_result = xdr_int;
    proc = (char *(*)(char *))myapp_get_size;
    break;

case GET_MTIME:
    /* takes a string argument (filename) */
    /* returns a long (time last modified) */
    xdr_argument = xdr_wrapstring;
    xdr_result = xdr_long;
    proc = (char *(*)(char *))myapp_get_mtime;
    break;

case GET_MTIME_STRING:
    /* takes a string argument (filename) */
    /* returns a string (time last modified, string format) */
    xdr_argument = xdr_wrapstring;
    xdr_result = xdr_wrapstring;
    proc = (char *(*)(char *))myapp_get_mtime_string;
    break;

case GET_CODEPAGE:
    /* takes a string argument (filename) */
    /* returns an u_short (codepage of file) */
    xdr_argument = xdr_wrapstring;
    xdr_result = xdr_u_short;
    proc = (char *(*)(char *))myapp_get_codepage;
    break;
}

```

```

case GET_OBJTYPE:
/* takes a string argument (filename) */
/* returns a string (object type) */
xdr_argument = xdr_wrapstring;
xdr_result = xdr_wrapstring;
proc = (char *(*)(char *))myapp_get_objtype;
break;

case GET_FILETYPE:
/* takes a string argument (filename) */
/* returns a string (file type) */
xdr_argument = xdr_wrapstring;
xdr_result = xdr_wrapstring;
proc = (char *(*)(char *))myapp_get_filetype;
break;

case END_SERVER:
/* takes no arguments */
/* returns no data */
/* unregisters service with local rpcbind daemon */
xdr_argument = (xdrproc_t)xdr_void;
xdr_result = (xdrproc_t)xdr_void;
proc = (char *(*)(char *))myapp_end_server;
break;

default:
/* fall through case. return error to client */
svcerr_noproc(svc);
return;

} /* end switch(request->rq_proc) */

/* clear the argument */
memset((char *)&argument, (int)0, sizeof(argument));

/* decode argument from client using xdr_argument() */
if (svc_getargs(svc, xdr_argument, (char *)&argument) == FALSE) {
/* if svc_getargs() fails, return RPC_CANTDECODEARGS to client */
svcerr_decode(svc);
return;
}

/* call local procedure, passing in pointer to argument */
result = (char *)(*proc)((char *)&argument);

/* check first that result isn't NULL */
/* try to send results back to client. check for failure */
if ((result != NULL) && (svc_sendreply(svc, xdr_result, result) == FALSE))
{
/* send error message back to client */
svcerr_systemerr(svc);
}

/* free the decoded argument's space */
if (svc_freeargs(svc, xdr_argument, (char *)&argument) == FALSE) {
/* if unable to free, print error and exit */
(void)fprintf(stderr, "unable to free arguments\n");
exit(1);
}

} /* end of myapp_dispatch() */

```

## 例: TI-RPC 中間レベル・サービス API

以下のコード例では、TI-RPC サービスの開発で使用する、中間レベル・サービス API について説明します。

ディスパッチ関数は、変更なしで再利用することができます。トップレベルと中間レベルの間の相違点は、ネットワーク選択 API を使用するかどうかということだけです。中間レベルでも rpcbind デーモンを使用してサービスを作成し、結合し登録します。

注: コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

```
#include <stdio.h>
#include <netconfig.h>
#include <rpc/rpc.h>
#include <errno.h>
#include "myapp.h"

int main(int argc, char *argv[]) {
    struct netconfig *nconf; /* pointer to nettype data */
    SVCXPRT *svc;           /* pointer to service handle */

    /* unregister any existing copy of this service */
    /* (void)svc_unreg(program, version) */
    svc_unreg(PROGNUM, VERSNUM);

    /* (struct netconfig *)getnetconfigent(nettype) */
    nconf = getnetconfigent(NETTYPE);
    if (nconf == (struct netconfig *)NULL) {
        fprintf(stderr, "Error calling getnetconfigent(%s)\n", NETTYPE);
        fprintf(stderr, "errno: %d\n", errno);
        return 1;
    }

    /* (SVCXPRT *)svc_tp_create(dispatch, progrnum, versnum, netconf) */
    svc = svc_tp_create(myapp_dispatch, PROGNUM, VERSNUM, nconf);

    /* check for errors calling svc_tp_create() */
    if (svc == (SVCXPRT *)NULL) {
        /* print error messages and exit */
        fprintf(stderr, "Error calling %s.\n", "svc_tp_create");
        fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
                PROGNUM, VERSNUM, NETTYPE);
        fprintf(stderr, "errno: %d\n", errno);
        return 1;
    }

    /* this should loop indefinitely waiting for client connections */
    svc_run();

    /* if we get here, svc_run() returned */
    fprintf(stderr, "svc_run() returned. ERROR has occurred.\n");
    fprintf(stderr, "errno: %d\n", errno);

    /* clean up by unregistering. then, exit */
    svc_unreg(PROGNUM, VERSNUM);

    return 1;
} /* end of main() */
```

## 例: TI-RPC エキスパート・レベル・サービス API

以下のコード例では、TI-RPC サービスの開発で使用する、エキスパート・レベル・サービス API について説明します。

エキスパート・レベルでは、プログラマーはサービスの送受信バッファー・サイズを指定することができます。 `svc_tli_create()` を呼び出すと、サービス・ハンドルが作成されますが、サービスを `rpcbind` デーモンを使用して登録したり結合したりすることはありません。プログラマーはサービスが適切に作動する前に、`svc_reg()` を呼び出す必要があります。中間レベルと同じように、ネットワーク選択 API を使用して、サービスに関するトランスポート情報を検索するオプションがあります。

注: コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

```
#include <stdio.h>
#include <netconfig.h>
#include <rpc/rpc.h>
#include <errno.h>
#include "myapp.h"

int main(int argc, char *argv[]) {

    struct netconfig *nconf; /* pointer to nettype data */
    SVCXPRT *svc;           /* pointer to service handle */
    bool_t rslt;             /* return value for svc_reg() */

    /* unregister any existing copy of this service */
    /* (void)svc_unreg(program, version) */
    svc_unreg(PROGNUM, VERSNUM);

    /* (struct netconfig *)getnetconfigent(nettype) */
    nconf = getnetconfigent(NETTYPE);

    /* check for errors calling getnetconfigent() */
    if (nconf == (struct netconfig *)NULL) {
        /* print error messages and exit */
        fprintf(stderr, "Error calling getnetconfigent(%s)\n", NETTYPE);
        fprintf(stderr, "errno: %d\n", errno);
        return 1;
    }

    /* (SVCXPRT *)svc_tli_create(filedes, netconfig, bindaddr, sendsz, recvsz) */
    svc = svc_tli_create(RPC_ANYFD, nconf, NULL, 0, 0);

    /* check for errors calling svc_tli_create() */
    if (svc == (SVCXPRT *)NULL) {
        /* print error messages and exit */
        fprintf(stderr, "Error calling %s.\n", "svc_tli_create");
        fprintf(stderr, "errno: %d\n", errno);
        return 1;
    }

    /* (bool_t)svc_reg(svcxprt, proignum, versnum, dispatch, netconf) */
    rslt = svc_reg(svc, PROGNUM, VERSNUM, myapp_dispatch, nconf);

    /* check for errors calling svc_reg() */
    if (rslt == FALSE) {
        /* print error messages and exit */
        fprintf(stderr, "Error calling svc_reg()\n");
        fprintf(stderr, "PROG: %lu VERS: %lu tNET: %s\n",
                PROGNUM, VERSNUM, NETTYPE);
        fprintf(stderr, "errno: %d\n", errno);
        return 1;
    }
}
```

```

/* this should loop indefinitely waiting for client connections */
svc_run();

/* if we get here, svc_run() returned */
fprintf(stderr, "svc_run() returned.  ERROR has occurred.\n");
fprintf(stderr, "errno: %d\n", errno);

/* clean up by unregistering.  then, exit */
svc_unreg(PROGNUM, VERSNUM);

return 1;

} /* end of main() */

```

## 例: TI-RPC サービスへの認証の追加

次のコードの一部は、RPC で認証システムが作用する方法を表します。

i5/OS オペレーティング・システムに備わっている唯一の認証方法はシステムによるものです。次の情報が設定され、毎回の clnt\_call() でクライアントからサービスに渡されます。次のコードの一部では、  
rpc-call() はデフォルトで authnone (空の認証トークン) を使用するので、認証情報を使用する際に  
rpc\_call() では十分でないという点に注意してください。

- aup\_time - 認証情報のタイム・スタンプ
- aup\_machname - リモート・クライアントのホスト名
- aup\_uid - クライアントのリモート・ユーザーの UID
- aup\_gid - リモート・ユーザーの 1 次 GID
- aup\_gids - リモート・ユーザーの 2 次グループの配列

認証情報は、リモート要求の一部としてサービスに直接入ります。この情報を解析し、クライアントが承認されたマシン、および承認されたユーザーからきているかどうかを検証することはサーバー側の責任です。認証タイプが間違っている場合、またはサーバーが受け入れられないほど不適切なものである場合、  
svcerr\_weakauth() を使ってエラー・メッセージが戻され、これをクライアントに通知します。

注: コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

```

#include <sys/types.h> /* needed for gid_t and uid_t */
#include <stdlib.h>    /* misc. system auth APIs */
#include <errno.h>

struct authsys_parms *credentials; /* authentication information */
char *remote_machine;           /* machine name (from the credentials) */
uid_t remote_user;              /* remote user's UID (from credentials) */

/* make sure we got the correct flavor of authentication */
if (request->rq_cred.oa_flavor != AUTH_UNIX) {
    /* if not, send back a weak authentication message and return */
    svcerr_weakauth(svc);
    return;
}

/* get our credentials */
credentials = (struct authsys_parms *) (request->rq_clntcred);

/* get the remote user's GID */
remote_user = credentials->aup_uid;

/* get the remote hostname of the client */

```

```

remote_machine = credentials->aup_machname;

/* check to see if this machine is "trusted" by us */
if ((strcmpi("remote1", remote_machine) != 0) &&
    (strcmpi("remote2", remote_machine) != 0)) {

    /* not from a machine we trust */
    /* send back an authentication error the client */
    svcerr_weakauth(svc);
    return;

} /* end of if (!trusted hostname) */

else {

    /* now check the user id for one we trust */
    /* information can be gotten from DSPUSRPRF */
    if ((remote_user != 568) &&
        (remote_user != 550) &&
        (remote_user != 528)) {

        /* not a user id we trust */
        /* send back an authentication error the client */
        svcerr_weakauth(svc);
        return;

} /* end of if (!trusted uid) */

} /* end of else (trusted hostname) */

/* we fall out of the loop if the hostname and uid are trusted */

```

## 例: TI-RPC コードに基づいてクライアント・アプリケーションを開発する

i5/OS オペレーティング・システムでクライアント・アプリケーションを開発するには、ガイドラインとしてこのコード例を使用します。

### 関連概念

4 ページの『例: TI-RPC コードに基づいてサービス・アプリケーションを開発する』  
トランスポート層に依存しないリモート・プロシージャー・コール (TI-RPC) プログラミングは、  
i5/OS オペレーティング・システム上でクライアント/サーバー・ベースの分散アプリケーションを開発  
するための効率的な方法を提供します。

### 関連資料

アプリケーション・プログラミング・インターフェース

## 例: TI-RPC 簡易レベル・クライアント API

以下のコード例では、TI-RPC アプリケーションの開発で使用する、簡易レベル・クライアント API について説明します。

簡易レベル・クライアント API は、最も速く短いコードのセットです。これは、クライアントの作成、制御、使用、および破棄がすべて 1 回のコールで済むためです。便利ではありますが、クライアント・ハンドルを使ってカスタマイズすることはできません。タイムアウトとバッファー・サイズについては、デフォルトが受け入れられます。これが簡易レベルと他のレベルの間の最も重要な相違点です。

**注:** コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

```

#include <stdio.h>
#include <errno.h>
#include "myapp.h"

#define EXIT 100

int main(void) {

    enum clnt_stat rslt; /* return value of rpc_call() */
    char hostname[256]; /* buffer for remote service's hostname */
    unsigned long procnum; /* procedure to call */
    char filename[512]; /* buffer for filename */
    char *arg = filename; /* pointer to filename buffer */

    union {
        u_int myapp_get_uid_result;
        char *myapp_get_uid_string_result;
        int myapp_get_size_result;
        long myapp_get_mtime_result;
        char *myapp_get_mtime_string_result;
        u_short myapp_get_codepage_result;
        char *myapp_get_objtype_result;
        char *myapp_get_filetype_result;
    } result; /* a union of all the possible results */

    /* get the hostname from the user */
    printf("Enter the hostname where the remote service is running: \n");
    scanf("%s", (char *)&hostname);

    myapp_print_menu(); /* print out the menu choices */

    /* get the procedure number to call from the user */
    printf("\nEnter a procedure number to call: \n");
    scanf("%lu", &procnum);

    /* get the filename from the user */
    printf("\nEnter a filename to stat: \n");
    scanf("%s", (char *)&arg);

    /* switch on the input */
    switch (procnum) {

        case NULLPROC:
            /* rpc_call(host, prognum, versnum, procnum,      */
            /*         *xdr_in, in, xdr_out, out, nettype); */
            rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,
                            (xdrproc_t)xdr_void, (char *)NULL, /* xdr_in */
                            (xdrproc_t)xdr_void, (char *)NULL, /* xdr_out */
                            NETTYPE);

            /* check return value of rpc_call() */
            if (rslt != RPC_SUCCESS) {
                fprintf(stderr, "Error calling rpc_call(%lu)\n", procnum);
                fprintf(stderr, "clnt_stat: %d\n", rslt);
                fprintf(stderr, "errno: %d\n", errno);
                return 1;
            }

            /* print results and exit */
            printf("NULLRPOC call succeeded\n");
            break;

        case GET_UID:
            /* rpc_call(host, prognum, versnum, procnum,      */
            /*         *xdr_in, in, xdr_out, out, nettype); */

```

```

rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,
                xdr_wrapstring, (char *)&arg, /* xdr_in */
                xdr_u_int, (char *)&result,           /* xdr_out */
                NETTYPE);

/* check return value of rpc_call() */
if (rslt != RPC_SUCCESS) {
    fprintf(stderr, "Error calling rpc_call(%lu)%n", procnum);
    fprintf(stderr, "clnt_stat: %d%n", rslt);
    fprintf(stderr, "errno: %d%n", errno);
    return 1;
}

/* print results and exit */
printf("uid of %s: %u%n",
       filename, result.myapp_get_uid_result);
break;

case GET_UID_STRING:

/* rpc_call(host, proignum, versnum, procnum,      */
/*          xdr_in, in, xdr_out, out, nettype); */
rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,
                xdr_wrapstring, (char *)&arg, /* xdr_in */
                xdr_wrapstring, (char *)&result, /* xdr_out */
                NETTYPE);

/* check return value of rpc_call() */
if (rslt != RPC_SUCCESS) {
    fprintf(stderr, "Error calling rpc_call(%lu)%n", procnum);
    fprintf(stderr, "clnt_stat: %d%n", rslt);
    fprintf(stderr, "errno: %d%n", errno);
    return 1;
}

/* print results and exit */
printf("owner of %s: %s%n",
       filename, result.myapp_get_uid_string_result);
break;

case GET_SIZE:

/* rpc_call(host, proignum, versnum, procnum,      */
/*          xdr_in, in, xdr_out, out, nettype); */
rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,
                xdr_wrapstring, (char *)&arg, /* xdr_in */
                xdr_int, (char *)&result, /* xdr_out */
                NETTYPE);

/* check return value of rpc_call() */
if (rslt != RPC_SUCCESS) {
    fprintf(stderr, "Error calling rpc_call(%lu)%n", procnum);
    fprintf(stderr, "clnt_stat: %d%n", rslt);
    fprintf(stderr, "errno: %d%n", errno);
    return 1;
}

/* print results and exit */
printf("size of %s: %d%n",
       filename, result.myapp_get_size_result);
break;

case GET_MTIME:

/* rpc_call(host, proignum, versnum, procnum,      */
/*          xdr_in, in, xdr_out, out, nettype); */
rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,

```

```

        xdr_wrapstring, (char *)&arg, /* xdr_in */
        xdr_long, (char *)&result, /* xdr_out */
        NETTYPE);

/* check return value of rpc_call() */
if (rslt != RPC_SUCCESS) {
    fprintf(stderr, "Error calling rpc_call(%lu)\n", procnum);
    fprintf(stderr, "clnt_stat: %d\n", rslt);
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

/* print results and exit */
printf("last modified time of %s: %ld\n",
       filename, result.myapp_get_mtime_result);
break;

case GET_MTIME_STRING:

/* rpc_call(host, prognum, versnum, procnum,      */
/*          xdr_in, in, xdr_out, out, nettype); */
rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,
                xdr_wrapstring, (char *)&arg, /* xdr_in */
                xdr_wrapstring, (char *)&result, /* xdr_out */
                NETTYPE);

/* check return value of rpc_call() */
if (rslt != RPC_SUCCESS) {
    fprintf(stderr, "Error calling rpc_call(%lu)\n", procnum);
    fprintf(stderr, "clnt_stat: %d\n", rslt);
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

/* print results and exit */
printf("last modified time of %s: %s\n",
       filename, result.myapp_get_mtime_string_result);
break;

case GET_CODEPAGE:

/* rpc_call(host, prognum, versnum, procnum,      */
/*          xdr_in, in, xdr_out, out, nettype); */
rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,
                xdr_wrapstring, (char *)&arg, /* xdr_in */
                xdr_u_short, (char *)&result, /* xdr_out */
                NETTYPE);

/* check return value of rpc_call() */
if (rslt != RPC_SUCCESS) {
    fprintf(stderr, "Error calling rpc_call(%lu)\n", procnum);
    fprintf(stderr, "clnt_stat: %d\n", rslt);
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

/* print results and exit */
printf("codepage of %s: %d\n",
       filename, result.myapp_get_codepage_result);
break;

case GET_OBJTYPE:

/* rpc_call(host, prognum, versnum, procnum,      */
/*          xdr_in, in, xdr_out, out, nettype); */
rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,
                xdr_wrapstring, (char *)&arg, /* xdr_in */

```

```

        xdr_wrapstring, (char *)&result, /* xdr_out */
        NETTYPE);

/* check return value of rpc_call() */
if (rslt != RPC_SUCCESS) {
    fprintf(stderr, "Error calling rpc_call(%lu)\n", procnum);
    fprintf(stderr, "clnt_stat: %d\n", rslt);
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

/* print results and exit */
printf("object type of %s: %s\n",
       filename, result.myapp_get_objtype_result);
break;

case GET_FILETYPE:

/* rpc_call(host, proignum, versnum, procnum,      */
/*          xdr_in, in, xdr_out, out, nettype); */
rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,
                xdr_wrapstring, (char *)&arg, /* xdr_in */
                xdr_wrapstring, (char *)&result, /* xdr_out */
                NETTYPE);

/* check return value of rpc_call() */
if (rslt != RPC_SUCCESS) {
    fprintf(stderr, "Error calling rpc_call(%lu)\n", procnum);
    fprintf(stderr, "clnt_stat: %d\n", rslt);
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

/* print results and exit */
printf("file type of %s: %s\n",
       filename, result.myapp_get_filetype_result);
break;

case END_SERVER:

/* rpc_call(host, proignum, versnum, procnum,      */
/*          xdr_in, in, xdr_out, out, nettype); */
rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,
                (xdrproc_t)xdr_void, (char *)NULL, /* xdr_in */
                (xdrproc_t)xdr_void, (char *)NULL, /* xdr_out */
                NETTYPE);

/* check return value of rpc_call() */
if (rslt != RPC_SUCCESS) {
    fprintf(stderr, "Error calling rpc_call(%lu)\n", procnum);
    fprintf(stderr, "clnt_stat: %d\n", rslt);
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

/* print results and exit */
printf("Service has been unregistered.\n");
printf("You must still kill the job in QBATCH\n");
break;

case EXIT:

/* do nothing and exit */
printf("Exiting program now.\n");
return 1;
break;

```

```

default:

/* an invalid procedure number was entered */
/* we could just exit here */
printf("Invalid choice. Issuing NULLRPC instead.\n");
procnum = NULLPROC;

/* rpc_call(host, proignum, versnum, procnum,      */
/*          xdr_in, in, xdr_out, out, nettype); */
rslt = rpc_call(hostname, PROGNUM, VERSNUM, procnum,
                (xdrproc_t)xdr_void, (char *)NULL, /* xdr_in */
                (xdrproc_t)xdr_void, (char *)NULL, /* xdr_out */
                NETTYPE);

/* check return value of rpc_call() */
if (rslt != RPC_SUCCESS) {
    fprintf(stderr, "Error calling rpc_call(%lu)\n", procnum);
    fprintf(stderr, "clnt_stat: %d\n", rslt);
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

/* print results and exit */
printf("NULLRPC call succeeded\n");
break;

} /* end of switch(procnum) */

/* no cleanup is required for rpc_call() */
return 0;
}

void myapp_print_menu(void) {

/* print out the procedure choices */
printf("%.2ld - GET_UID           %.2ld - GET_UID_STRING\n",
       GET_UID, GET_UID_STRING);
printf("%.2ld - GET_SIZE          %.2ld - GET_MTIME\n",
       GET_SIZE, GET_MTIME);
printf("%.2ld - GET_MTIME_STRING %.2ld - GET_CODEPAGE\n",
       GET_MTIME_STRING, GET_CODEPAGE);
printf("%.2ld - GET_OBJTYPE        %.2ld - GET_FILETYPE\n",
       GET_OBJTYPE, GET_FILETYPE);
printf("%.2ld - END_SERVER         %.2d - EXIT\n",
       END_SERVER, EXIT);
}

```

## 例: TI-RPC トップレベル・クライアント API

以下のコード例では、TI-RPC アプリケーションの開発で使用する、トップレベル・クライアント API について説明します。

トップレベルでは、使用または修正する前にクライアント・ハンドルを作成することが必要です。トップレベル API は簡単に使用でき、さらには簡易レベルよりも多くの操作とエラー処理が可能です。

**注:** コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

```
#include <stdio.h>
#include <netconfig.h>
#include <netdir.h>
#include <errno.h>
#include "myapp.h"
```

```

#define EXIT 100

int main(void) {

    enum clnt_stat rs1t; /* return value of clnt_call() */
    char hostname[256]; /* buffer for remote service's hostname */
    unsigned long proignum; /* procedure to call */
    char filename[512]; /* buffer for filename */
    xdrproc_t xdr_argument; /* xdr procedure to encode arguments */
    xdrproc_t xdr_result; /* xdr procedure to decode results */
    CLIENT *clnt; /* pointer to client handle */
    struct timeval tout; /* timeout for clnt_call() */
    char *arg = filename; /* pointer to filename buffer */

    union {
        u_int myapp_get_uid_result;
        char *myapp_get_uid_string_result;
        int myapp_get_size_result;
        long myapp_get_mtime_result;
        char *myapp_get_mtime_string_result;
        u_short myapp_get_codepage_result;
        char *myapp_get_objtype_result;
        char *myapp_get_filetype_result;
    } result; /* a union of all the possible results */

    tout.tv_sec = 30; /* set default timeout to 30.00 seconds */
    tout.tv_usec = 0;

    /* get the hostname from the user */
    printf("Enter the hostname where the remote service is running: \n");
    scanf("%s", (char *)&hostname);

    myapp_print_menu(); /* print out the menu choices */

    /* get the procedure number to call from the user */
    printf("\nEnter a procedure number to call: \n");
    scanf("%lu", &proignum);

    /* get the filename from the user */
    printf("\nEnter a filename to stat: \n");
    scanf("%s", (char *)&filename);

    /* clnt_create(host, proignum, versnum, nettype); */
    clnt = clnt_create(hostname, PROGNUM, VERSNUM, NETTYPE);

    /* check to make sure clnt_create() didn't fail */
    if (clnt == (CLIENT *)NULL) {
        /* if we failed, print out all appropriate error messages and exit */
        fprintf(stderr, "Error calling clnt_create()\n");
        fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
                PROGNUM, VERSNUM, NETTYPE);
        fprintf(stderr, "clnt_stat: %d\n", rpc_createerr.cf_stat);
        fprintf(stderr, "errno: %d\n", errno);
        fprintf(stderr, "re_errno: %d\n", rpc_createerr.cf_error.re_errno);
        return 1;
    }

    /* switch on the input */
    switch (proignum) {

        case NULLPROC:
            /* set the encode procedure */
            xdr_argument = (xdrproc_t)xdr_void;
            /* set the decode procedure */
            xdr_result = (xdrproc_t)xdr_void;
            break;
    }
}

```

```

case GET_UID:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result = xdr_u_int;
    break;

case GET_UID_STRING:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result = xdr_wrapstring;
    break;

case GET_SIZE:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result = xdr_int;
    break;

case GET_MTIME:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result = xdr_long;
    break;

case GET_MTIME_STRING:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result = xdr_wrapstring;
    break;

case GET_CODEPAGE:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result = xdr_u_short;
    break;

case GET_OBJTYPE:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result = xdr_wrapstring;
    break;

case GET_FILETYPE:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result = xdr_wrapstring;
    break;

case END_SERVER:
    /* set the encode procedure */
    xdr_argument = (xdrproc_t)xdr_void;
    /* set the decode procedure */
    xdr_result = (xdrproc_t)xdr_void;
    break;

case EXIT:
    /* we're done. clean up and exit */
    clnt_destroy(clnt);

```

```

    return 1;
    break;

default:
    /* invalid procedure number entered. defaulting to NULLPROC */
    printf("Invalid choice. Issuing NULLRPOC instead.\n");
    procnum = NULLPROC;
    /* set the encode procedure */
    xdr_argument = (xdrproc_t)xdr_void;
    /* set the decode procedure */
    xdr_result = (xdrproc_t)xdr_void;
    break;

} /* end of switch(procnum) */

/* clnt_call(client, procnum, xdr_inproc, in, xdr_outproc, out, timeout) */
rslt = clnt_call(clnt, procnum, xdr_argument, (char *)&arg,
                  xdr_result, (char *)&result, tout);

/* check to make sure clnt_call() succeeded */
if (rslt != RPC_SUCCESS) {
    /* if clnt_call() failed, print errors and exit */
    printf("An error occurred calling %u procedure\n", procnum);
    printf("clnt_stat: %d(errno: %d)\n", rslt, errno);
    clnt_destroy(clnt);
    return 1;
}

/* clnt_call() succeeded. switch on procedure and print results */
switch (procnum) {

    case NULLPROC:
        /* print results and exit */
        printf("NULLRPOC call succeeded\n");
        break;

    case GET_UID:
        /* print results and exit */
        printf("uid of %s: %u\n",
               filename, result.myapp_get_uid_result);
        break;

    case GET_UID_STRING:
        /* print results and exit */
        printf("owner of %s: %s\n",
               filename, result.myapp_get_uid_string_result);
        break;

    case GET_SIZE:
        /* print results and exit */
        printf("size of %s: %d\n",
               filename, result.myapp_get_size_result);
        break;

    case GET_MTIME:
        /* print results and exit */
        printf("last modified time of %s: %ld\n",
               filename, result.myapp_get_mtime_result);
        break;

    case GET_MTIME_STRING:
        /* print results and exit */
        printf("last modified time of %s: %s\n",
               filename, result.myapp_get_mtime_string_result);
        break;

    case GET_CODEPAGE:

```

```

/* print results and exit */
printf("codepage of %s: %d\n",
      filename, result.myapp_get_codepage_result);
break;

case GET_OBJTYPE:
/* print results and exit */
printf("object type of %s: %s\n",
      filename, result.myapp_get_objtype_result);
break;

case GET_FILETYPE:
/* print results and exit */
printf("file type of %s: %s\n",
      filename, result.myapp_get_filetype_result);
break;

case END_SERVER:
/* print results and exit */
printf("Service has been unregistered.\n");
printf("You must still kill the job in QBATCH\n");
break;

default:
/* we should never get the default case. */
/* the previous switch should catch it. */
break;

} /* end of switch(procnum) */

/* clean up and exit */
cInt_destroy(cInt);

return 0;
}

void myapp_print_menu(void) {

/* print out the procedure choices */
printf("%.2ld - GET_UID          %.2ld - GET_UID_STRING\n",
       GET_UID, GET_UID_STRING);
printf("%.2ld - GET_SIZE         %.2ld - GET_MTIME\n",
       GET_SIZE, GET_MTIME);
printf("%.2ld - GET_MTIME_STRING %.2ld - GET_CODEPAGE\n",
       GET_MTIME_STRING, GET_CODEPAGE);
printf("%.2ld - GET_OBJTYPE      %.2ld - GET_FILETYPE\n",
       GET_OBJTYPE, GET_FILETYPE);
printf("%.2ld - END_SERVER       %.2d - EXIT\n",
       END_SERVER, EXIT);
}

```

## 例: TI-RPC 中間レベル・クライアント API

以下のコード例では、TI-RPC アプリケーションの開発で使用する、中間レベル・クライアント API について説明します。

クライアントの中間レベルは、サービスの中間レベルと同じパスに従います。例えば、プログラマーは簡単なテキスト・ストリングを渡すのではなく、ネットワーク選択 API を使ってトランスポート情報を入手する責任があります。

注: コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

```
#include <stdio.h>
#include <netconfig.h>
#include <netdir.h>
#include <errno.h>
#include "myapp.h"

#define EXIT 100

int main(void) {

    enum clnt_stat rslt; /* return value of clnt_call() */
    char hostname[256]; /* buffer for remote service's hostname */
    unsigned long proignum; /* procedure to call */
    char filename[512]; /* buffer for filename */
    xdrproc_t xdr_argument; /* xdr procedure to encode arguments */
    xdrproc_t xdr_result; /* xdr procedure to decode results */
    CLIENT *clnt; /* pointer to client handle */
    struct timeval tout; /* timeout for clnt_call() */
    struct netconfig *nconf; /* transport information */
    char *arg = filename; /* pointer to filename buffer */

    union {
        u_int myapp_get_uid_result;
        char *myapp_get_uid_string_result;
        int myapp_get_size_result;
        long myapp_get_mtime_result;
        char *myapp_get_mtime_string_result;
        u_short myapp_get_codepage_result;
        char *myapp_get_objtype_result;
        char *myapp_get_filetype_result;
    } result; /* a union of all the possible results */

    tout.tv_sec = 30; /* set default timeout to 30.00 seconds */
    tout.tv_usec = 0;

    /* get the hostname from the user */
    printf("Enter the hostname where the remote service is running: \n");
    scanf("%s", (char *)&hostname);

    myapp_print_menu(); /* print out the menu choices */

    /* get the procedure number to call from the user */
    printf("\nEnter a procedure number to call: \n");
    scanf("%lu", &proignum);

    /* get the filename from the user */
    printf("\nEnter a filename to stat: \n");
    scanf("%s", (char *)&filename);

    /* getnetconfigent(nettype) */
    nconf = getnetconfigent(NETTYPE);

    /* check to make sure getnetconfigent() didn't fail */
    if (nconf == NULL) {
        /* if getnetconfigent() failed, print error messages and exit */
        fprintf(stderr, "Error calling getnetconfigent(%s)\n", NETTYPE);
        fprintf(stderr, "errno: %d\n", errno);
        return 1;
    }

    /* clnt_tp_create(host, proignum, versnum, netconf) */
    clnt = clnt_tp_create(hostname, PROGNUM, VERSNUM, nconf);
```

```

/* check to make sure clnt_tp_create() didn't fail */
if (clnt == (CLIENT *)NULL) {
    fprintf(stderr, "Error calling clnt_tp_create()\n");
    fprintf(stderr, "PROG: %lu$VERS: %lu$NET: %s\n",
            PROGNUM, VERSNUM, NETTYPE);
    fprintf(stderr, "clnt_stat: %d\n", rpc_createerr.cf_stat);
    fprintf(stderr, "errno: %d\n", errno);
    fprintf(stderr, "re_errno: %d\n", rpc_createerr.cf_error.re_errno);
    return 1;
}

/* switch on the input */
switch (procnum) {

    case NULLPROC:
        /* set the encode procedure */
        xdr_argument = (xdrproc_t)xdr_void;
        /* set the decode procedure */
        xdr_result   = (xdrproc_t)xdr_void;
        break;

    case GET_UID:
        /* set the encode procedure */
        xdr_argument = xdr_wrapstring;
        /* set the decode procedure */
        xdr_result   = xdr_u_int;
        break;

    case GET_UID_STRING:
        /* set the encode procedure */
        xdr_argument = xdr_wrapstring;
        /* set the decode procedure */
        xdr_result   = xdr_wrapstring;
        break;

    case GET_SIZE:
        /* set the encode procedure */
        xdr_argument = xdr_wrapstring;
        /* set the decode procedure */
        xdr_result   = xdr_int;
        break;

    case GET_MTIME:
        /* set the encode procedure */
        xdr_argument = xdr_wrapstring;
        /* set the decode procedure */
        xdr_result   = xdr_long;
        break;

    case GET_MTIME_STRING:
        /* set the encode procedure */
        xdr_argument = xdr_wrapstring;
        /* set the decode procedure */
        xdr_result   = xdr_wrapstring;
        break;

    case GET_CODEPAGE:
        /* set the encode procedure */
        xdr_argument = xdr_wrapstring;
        /* set the decode procedure */
        xdr_result   = xdr_u_short;
        break;

    case GET_OBJTYPE:
        /* set the encode procedure */
        xdr_argument = xdr_wrapstring;
        /* set the decode procedure */

```

```

xdr_result = xdr_wrapstring;
break;

case GET_FILETYPE:
/* set the encode procedure */
xdr_argument = xdr_wrapstring;
/* set the decode procedure */
xdr_result = xdr_wrapstring;
break;

case END_SERVER:
/* set the encode procedure */
xdr_argument = (xdrproc_t)xdr_void;
/* set the decode procedure */
xdr_result = (xdrproc_t)xdr_void;
break;

case EXIT:
/* we're done. clean up and exit */
clnt_destroy(clnt);
return 1;
break;

default:
/* invalid procedure number entered. defaulting to NULLPROC */
printf("Invalid choice. Issuing NULLRPOC instead.\n");
procnum = NULLPROC;
/* set the encode procedure */
xdr_argument = (xdrproc_t)xdr_void;
/* set the decode procedure */
xdr_result = (xdrproc_t)xdr_void;
break;

} /* end of switch(procnum) */

/* clnt_call(client, procnum, xdr_inproc, in, xdr_outproc, out, timeout) */
rslt = clnt_call(clnt, procnum, xdr_argument, (char *)&arg,
                  xdr_result, (char *)&result, tout);

/* check to make sure clnt_call() succeeded */
if (rslt != RPC_SUCCESS) {
/* if clnt_call() failed, print errors and exit */
printf("An error occurred calling %u procedure\n", procnum);
printf("clnt_stat: %d errno: %d\n", rslt, errno);
clnt_destroy(clnt);
return 1;
}

/* clnt_call() succeeded. switch on procedure and print results */
switch (procnum) {

case NULLPROC:
/* print results and exit */
printf("NULLRPOC call succeeded\n");
break;

case GET_UID:
/* print results and exit */
printf("uid of %s: %u\n",
      filename, result.myapp_get_uid_result);
break;

case GET_UID_STRING:
/* print results and exit */
printf("owner of %s: %s\n",
      filename, result.myapp_get_uid_string_result);
break;
}

```

```

case GET_SIZE:
    /* print results and exit */
    printf("size of %s: %d\n",
           filename, result.myapp_get_size_result);
    break;

case GET_MTIME:
    /* print results and exit */
    printf("last modified time of %s: %ld\n",
           filename, result.myapp_get_mtime_result);
    break;

case GET_MTIME_STRING:
    /* print results and exit */
    printf("last modified time of %s: %s\n",
           filename, result.myapp_get_mtime_string_result);
    break;

case GET_CODEPAGE:
    /* print results and exit */
    printf("codepage of %s: %d\n",
           filename, result.myapp_get_codepage_result);
    break;

case GET_OBJTYPE:
    /* print results and exit */
    printf("object type of %s: %s\n",
           filename, result.myapp_get_objtype_result);
    break;

case GET_FILETYPE:
    /* print results and exit */
    printf("file type of %s: %s\n",
           filename, result.myapp_get_filetype_result);
    break;

case END_SERVER:
    /* print results and exit */
    printf("Service has been unregistered.\n");
    printf("You must still kill the job in QBATCH\n");
    break;

default:
    /* we should never get the default case. */
    /* the previous switch should catch it. */
    break;

} /* end of switch(procnum) */

/* clean up and exit */

/* free the netconfig struct */
freenetconfigent(nconf);
/* free the universal address buffer */
free(svcaddr.buf);
/* destroy the client handle */
clnt_destroy(clnt);

return 0;
}

void myapp_print_menu(void) {

```

```

/* print out the procedure choices */
printf("%.2ld - GET_UID           %.2ld - GET_UID_STRING\n",
       GET_UID, GET_UID_STRING);
printf("%.2ld - GET_SIZE          %.2ld - GET_MTIME\n",
       GET_SIZE, GET_MTIME);
printf("%.2ld - GET_MTIME_STRING %.2ld - GET_CODEPAGE\n",
       GET_MTIME_STRING, GET_CODEPAGE);
printf("%.2ld - GET_OBJTYPE       %.2ld - GET_FILETYPE\n",
       GET_OBJTYPE, GET_FILETYPE);
printf("%.2ld - END_SERVER        %.2d - EXIT\n",
       END_SERVER, EXIT);
}

}

```

## 例: TI-RPC エキスパート・レベル・クライアント API

以下のコード例では、TI-RPC アプリケーションの開発で使用する、エキスパート・レベル・クライアント API について説明します。

クライアント API の開発用のエキスパート・レベルはより複雑です。また、カスタマイズを最大限に行えます。これは、クライアント API に合わせてバッファー・サイズを調整できる唯一のレベルです。エキスパート・レベルでは、プログラマーは名前からアドレスへの変換 API または他のエキスパート・レベル API のどちらかを使用することによって、クライアントが接続するための汎用アドレスを設定することが必要です。どちらにしてもこのレベルでは多くの作業が必要になりますが、プログラマーは、このレベルが実行する環境に合わせてクライアント・アプリケーションを調整することが可能になります。

注: コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

```

#include <stdio.h>
#include <netconfig.h>
#include <netdir.h>
#include <errno.h>
#include "myapp.h"

#define EXIT 100

int main(void) {

    enum clnt_stat rslt; /* return value of clnt_call() */
    char hostname[256]; /* buffer for remote service's hostname */
    unsigned long procnum; /* procedure to call */
    char filename[512]; /* buffer for filename */
    xdrproc_t xdr_argument; /* xdr procedure to encode arguments */
    xdrproc_t xdr_result; /* xdr procedure to decode results */
    CLIENT *clnt; /* pointer to client handle */
    struct timeval tout; /* timeout for clnt_call() */
    struct netconfig *nconf; /* transport information */
    struct netbuf svcaddr; /* universal address of remote service */
    bool_t rpcb_rslt; /* return value for rpcb_getaddr() */
    char *arg = filename; /* pointer to filename buffer */

    union {
        u_int myapp_get_uid_result;
        char *myapp_get_uid_string_result;
        int myapp_get_size_result;
        long myapp_get_mtime_result;
        char *myapp_get_mtime_string_result;
        u_short myapp_get_codepage_result;
        char *myapp_get_objtype_result;
        char *myapp_get_filetype_result;
    } result; /* a union of all the possible results */
}

```

```

/* initialize the struct netbuf space */
svcaddr maxlen = 16;
svcaddr.buf = (char *)malloc(svcaddr maxlen);

if (svcaddr.buf == (char *)NULL) {
    /* if malloc() failed, print error messages and exit */
    fprintf(stderr, "Error calling malloc() for struct netbuf\n");
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

tout.tv_sec = 30; /* set default timeout to 30.00 seconds */
tout.tv_usec = 0;

/* get the hostname from the user */
printf("Enter the hostname where the remote service is running: \n");
scanf("%s", (char *)&hostname);

myapp_print_menu(); /* print out the menu choices */

/* get the procedure number to call from the user */
printf("\nEnter a procedure number to call: \n");
scanf("%lu", &procnum);

/* get the filename from the user */
printf("\nEnter a filename to stat: \n");
scanf("%s", (char *)&filename);

/* getnetconfigent(nettype) */
nconf = getnetconfigent(NETTYPE);

/* check to make sure getnetconfigent() didn't fail */
if (nconf == NULL) {
    /* if getnetconfigent() failed, print error messages and exit */
    fprintf(stderr, "Error calling getnetconfigent(%s)\n", NETTYPE);
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

/* rpcb_getaddr(prognum, versnum, nconf, output netbuf, hostname) */
/* this sets the universal address svcaddr */
rpcb_rslt = rpcb_getaddr(PROGNUM, VERSNUM, nconf, &svcaddr, hostname);

/* check to make sure rpcb_getaddr() didn't fail */
if (rpcb_rslt == FALSE) {
    /* if rpcb_getaddr() failed, print error messages and exit */
    fprintf(stderr, "Error calling rpcb_getaddr()\n");
    fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
            PROGNUM, VERSNUM, NETTYPE);
    fprintf(stderr, "clnt_stat: %d\n", rpc_createerr.cf_stat);
    fprintf(stderr, "errno: %d\n", errno);
    fprintf(stderr, "re_errno: %d\n", rpc_createerr.cf_error.re_errno);
    return 1;
}

/* clnt_tli_create(filedes, netconfig, netbuf, */
/*                  prognum, versnum, sendsz, recvsz); */
clnt = clnt_tli_create(RPC_ANYFD, nconf, &svcaddr,
                       PROGNUM, VERSNUM, 0, 0);

/* check to make sure clnt_tli_create() didn't fail */
if (clnt == (CLIENT *)NULL) {
    /* if we failed, print out all appropriate error messages and exit */
    fprintf(stderr, "Error calling clnt_tli_create()\n");
    fprintf(stderr, "PROG: %luVERS: %luNET: %s\n",
            PROGNUM, VERSNUM, NETTYPE);
    fprintf(stderr, "clnt_stat: %d\n", rpc_createerr.cf_stat);
}

```

```

fprintf(stderr, "errno: %d\n", errno);
fprintf(stderr, "re_errno: %d\n", rpc_createerr.cf_error.re_errno);
return 1;
}

/* switch on the input */
switch (procnum) {

case NULLPROC:
    /* set the encode procedure */
    xdr_argument = (xdrproc_t)xdr_void;
    /* set the decode procedure */
    xdr_result   = (xdrproc_t)xdr_void;
    break;

case GET_UID:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result   = xdr_u_int;
    break;

case GET_UID_STRING:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result   = xdr_wrapstring;
    break;

case GET_SIZE:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result   = xdr_int;
    break;

case GET_MTIME:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result   = xdr_long;
    break;

case GET_MTIME_STRING:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result   = xdr_wrapstring;
    break;

case GET_CODEPAGE:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result   = xdr_u_short;
    break;

case GET_OBJTYPE:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
    /* set the decode procedure */
    xdr_result   = xdr_wrapstring;
    break;

case GET_FILETYPE:
    /* set the encode procedure */
    xdr_argument = xdr_wrapstring;
}

```

```

/* set the decode procedure */
xdr_result = xdr_wrapstring;
break;

case END_SERVER:
    /* set the encode procedure */
    xdr_argument = (xdrproc_t)xdr_void;
    /* set the decode procedure */
    xdr_result = (xdrproc_t)xdr_void;
break;

case EXIT:
    /* we're done. clean up and exit */
    clnt_destroy(clnt);
    return 1;
break;

default:
    /* invalid procedure number entered. defaulting to NULLPROC */
    printf("Invalid choice. Issuing NULLRPOC instead.\n");
    procnum = NULLPROC;
    /* set the encode procedure */
    xdr_argument = (xdrproc_t)xdr_void;
    /* set the decode procedure */
    xdr_result = (xdrproc_t)xdr_void;
break;

} /* end of switch(procnum) */

/* clnt_call(client, procnum, xdr_inproc, in, xdr_outproc, out, timeout) */
rslt = clnt_call(clnt, procnum, xdr_argument, (char *)&arg,
                  xdr_result, (char *)&result, tout);

/* check to make sure clnt_call() succeeded */
if (rslt != RPC_SUCCESS) {
    /* if clnt_call() failed, print errors and exit */
    printf("An error occurred calling %lu procedure\n", procnum);
    printf("clnt_stat: %derrno: %d\n", rslt, errno);
    clnt_destroy(clnt);
    return 1;
}

/* clnt_call() succeeded. switch on procedure and print results */
switch (procnum) {

case NULLPROC:
    /* print results and exit */
    printf("NULLRPOC call succeeded\n");
break;

case GET_UID:
    /* print results and exit */
    printf("uid of %s: %u\n",
          filename, result.myapp_get_uid_result);
break;

case GET_UID_STRING:
    /* print results and exit */
    printf("owner of %s: %s\n",
          filename, result.myapp_get_uid_string_result);
break;

case GET_SIZE:
    /* print results and exit */
    printf("size of %s: %d\n",
          filename, result.myapp_get_size_result);
break;
}

```

```

case GET_MTIME:
    /* print results and exit */
    printf("last modified time of %s: %ld\n",
           filename, result.myapp_get_mtime_result);
    break;

case GET_MTIME_STRING:
    /* print results and exit */
    printf("last modified time of %s: %s\n",
           filename, result.myapp_get_mtime_string_result);
    break;

case GET_CODEPAGE:
    /* print results and exit */
    printf("codepage of %s: %d\n",
           filename, result.myapp_get_codepage_result);
    break;

case GET_OBJTYPE:
    /* print results and exit */
    printf("object type of %s: %s\n",
           filename, result.myapp_get_objtype_result);
    break;

case GET_FILETYPE:
    /* print results and exit */
    printf("file type of %s: %s\n",
           filename, result.myapp_get_filetype_result);
    break;

case END_SERVER:
    /* print results and exit */
    printf("Service has been unregistered.\n");
    printf("You must still kill the job in QBATCH\n");
    break;

default:
    /* we should never get the default case. */
    /* the previous switch should catch it. */
    break;

} /* end of switch(procnum) */

/* clean up and exit */

/* free the netconfig struct */
freenetconfigent(nconf);
/* free the universal address buffer */
free(svcaddr.buf);
/* destroy the client handle */
clnt_destroy(clnt);

return 0;
}

void myapp_print_menu(void) {

/* print out the procedure choices */
printf("%.2ld - GET_UID          %.2ld - GET_UID_STRING\n",
       GET_UID, GET_UID_STRING);
printf("%.2ld - GET_SIZE          %.2ld - GET_MTIME\n",
       GET_SIZE, GET_MTIME);
printf("%.2ld - GET_MTIME_STRING %.2ld - GET_CODEPAGE\n",
       GET_MTIME_STRING, GET_CODEPAGE),

```

```

        GET_MTIME_STRING, GET_CODEPAGE);
printf("%.2ld - GET_OBJTYPE      %.2ld - GET_FILETYPE\n",
       GET_OBJTYPE, GET_FILETYPE);
printf("%.2ld - END_SERVER      %.2d - EXIT\n",
       END_SERVER, EXIT);
}

```

## 例: TI-RPC クライアントへの認証の追加

次のコードの一部は、RPC で認証システムが作用する方法を表します。

i5/OS オペレーティング・システムに備わっている唯一の認証方法はシステムによるものです。次の情報が設定され、毎回の clnt\_call() でクライアントからサービスに渡されます。次のコードの一部では、  
rpc-call() はデフォルトで authnone (空の認証トークン) を使用するので、認証情報を使用する際に  
rpc\_call() では十分でないという点に注意してください。

- aup\_time - 認証情報のタイム・スタンプ
- aup\_machname - リモート・クライアントのホスト名
- aup\_uid - クライアントのリモート・ユーザーの UID
- aup\_gid - リモート・ユーザーの 1 次 GID
- aup\_gids - リモート・ユーザーの 2 次グループの配列

認証情報を設定して、それをクライアント・ハンドルの一部として含めるのはクライアント側の責任です。その後で行われる clnt\_call() へのすべてのコールは、認証情報に従って渡されます。認証されていないクライアントを報告するのはサーバーの役目です。RPC は、情報を伝達するための簡単な方法しか提供しません。クライアントが送信するデータは、認証されてはいますが、暗号化されてはいません。サービスからの応答も暗号化されていません。認証では、リモート・ホスト名とユーザー ID を検証するという簡単な方法しか提供していません。したがって、これを安全でプライベートな通信方法であると見なすことはできません。

注: コード例の使用をもって、37 ページの『コードに関するライセンス情報および特記事項』の条件に同意したものとします。

```

#include <sys/types.h> /* needed for gid_t and uid_t */
#include <stdlib.h>    /* misc. system auth APIs */
#include <unistd.h>    /* misc. system auth APIs */
#include <errno.h>

#ifndef NGROUPS_MAX
#define NGROUPS_MAX 16
#endif

char hostname[256];           /* hostname for credentials */
int rslt;                     /* return value of gethostname() */
gid_t groups[NGROUPS_MAX];   /* array of groups set by getgroups() */
gid_t *aup_gids;              /* pointer to array of gid_t */
uid_t uid;                    /* uid, return value for geteuid() */
gid_t gid;                    /* gid, return value for getegid() */
int num_groups;               /* return value for getgroups(), number of groups set */

aup_gids = groups;            /* point to the array of groups */
uid = geteuid();               /* get the effective uid of the user */
gid = getegid();               /* get the effect primary gid of the user */

/* get a list of other groups the user is a member of */
/* (int)getgroups(maxgroups, array) */
num_groups = getgroups(NGROUPS_MAX, groups);

```

```

/* check return value of getgroups() for error */
if (num_groups == -1) {
    /* print error message and exit */
    fprintf(stderr, "getgroups() failed for %d\n", uid);
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

/* (int)gethostname(buffer, buflen) */
rslt = gethostname(hostname, 256);

/* check return value of gethostname() for error */
if (rslt == -1) {
    /* print error message and exit */
    fprintf(stderr, "gethostname() failed\n");
    fprintf(stderr, "errno: %d\n", errno);
    return 1;
}

/* insert just before clnt_call() */
/* (AUTH *)authsys_create(hostname, uid, gid, num_groups, gid[]); */
clnt->cl_auth = authsys_create(hostname, uid, gid, num_groups, aup_gids);

if (clnt->cl_auth == NULL) {
    /* print error messages and exit */
    fprintf(stderr, "authsys_create() failed\n");
    fprintf(stderr, "errno: %d\n", errno);
    /* clean up */
    clnt_destroy(clnt);
    return 1;
}

```

---

## コードに関するライセンス情報および特記事項

IBM は、お客様に、すべてのプログラム・コードのサンプルを使用することができる非独占的な著作使用権を許諾します。お客様は、このサンプル・コードから、お客様独自の特別のニーズに合わせた類似のプログラムを作成することができます。

強行法規で除外を禁止されている場合を除き、IBM、そのプログラム開発者、および供給者は「プログラム」および「プログラム」に対する技術的サポートがある場合にはその技術的サポートについて、商品性の保証、特定目的適合性の保証および法律上の瑕疵担保責任を含むすべての明示もしくは黙示の保証責任を負わないものとします。

いかなる場合においても、IBM および IBM のサプライヤーならびに IBM ビジネス・パートナーは、その予見の有無を問わず発生した以下のものについて賠償責任を負いません。

1. データの喪失、または損傷。
2. 直接損害、特別損害、付随的損害、間接損害、または経済上の結果的損害
3. 逸失した利益、ビジネス上の収益、あるいは節約すべかりし費用

国または地域によっては、法律の強行規定により、上記の責任の制限が適用されない場合があります。



---

## 付録. 特記事項

本書は米国 IBM が提供する製品およびサービスについて作成したものです。

本書に記載の製品、サービス、または機能が日本においては提供されていない場合があります。日本で利用可能な製品、サービス、および機能については、日本 IBM の営業担当員にお尋ねください。本書で IBM 製品、プログラム、またはサービスに言及していても、その IBM 製品、プログラム、またはサービスのみが使用可能であることを意味するものではありません。これらに代えて、IBM の知的所有権を侵害することのない、機能的に同等の製品、プログラム、またはサービスを使用することができます。ただし、IBM 以外の製品とプログラムの操作またはサービスの評価および検証は、お客様の責任で行っていただきます。

IBM は、本書に記載されている内容に関して特許権（特許出願中のものを含む）を保有している場合があります。本書の提供は、お客様にこれらの特許権について実施権を許諾することを意味するものではありません。実施権についてのお問い合わせは、書面にて下記宛先にお送りください。

〒106-8711

東京都港区六本木 3-2-12  
IBM World Trade Asia Corporation  
Intellectual Property Law & Licensing

以下の保証は、国または地域の法律に沿わない場合は、適用されません。IBM およびその直接または間接の子会社は、本書を特定物として現存するままの状態で提供し、商品性の保証、特定目的適合性の保証および法律上の瑕疵担保責任を含むすべての明示もしくは黙示の保証責任を負わないものとします。国または地域によっては、法律の強行規定により、保証責任の制限が禁じられる場合、強行規定の制限を受けるものとします。

この情報には、技術的に不適切な記述や誤植を含む場合があります。本書は定期的に見直され、必要な変更は本書の次版に組み込まれます。IBM は予告なしに、隨時、この文書に記載されている製品またはプログラムに対して、改良または変更を行うことがあります。

本書において IBM 以外の Web サイトに言及している場合がありますが、便宜のため記載しただけであり、決してそれらの Web サイトを推奨するものではありません。それらの Web サイトにある資料は、この IBM 製品の資料の一部ではありません。それらの Web サイトは、お客様の責任でご使用ください。

IBM は、お客様が提供するいかなる情報も、お客様に対してなんら義務も負うことのない、自ら適切と信ずる方法で、使用もしくは配布することができるものとします。

本プログラムのライセンス保持者で、(i) 独自に作成したプログラムとその他のプログラム（本プログラムを含む）との間での情報交換、および (ii) 交換された情報の相互利用を可能にすることを目的として、本プログラムに関する情報を必要とする方は、下記に連絡してください。

IBM Corporation  
Software Interoperability Coordinator, Department YBWA  
3605 Highway 52 N  
Rochester, MN 55901  
U.S.A.

本プログラムに関する上記の情報は、適切な使用条件の下で使用することができますが、有償の場合もあります。

- | 本書で説明されているライセンス・プログラムまたはその他のライセンス資料は、IBM 所定のプログラム
- | 契約の契約条項、IBM プログラムのご使用条件、IBM 機械コードのご使用条件、またはそれと同等の条項
- | に基づいて、IBM より提供されます。

この文書に含まれるいかなるパフォーマンス・データも、管理環境下で決定されたものです。そのため、他の操作環境で得られた結果は、異なる可能性があります。一部の測定が、開発レベルのシステムで行われた可能性がありますが、その測定値が、一般に利用可能なシステムのものと同じである保証はありません。さらに、一部の測定値が、推定値である可能性があります。実際の結果は、異なる可能性があります。お客様は、お客様の特定の環境に適したデータを確かめる必要があります。

IBM 以外の製品に関する情報は、その製品の供給者、出版物、もしくはその他の公に利用可能なソースから入手したものです。IBM は、それらの製品のテストは行っておりません。したがって、他社製品に関する実行性、互換性、またはその他の要求については確認できません。 IBM 以外の製品の性能に関する質問は、それらの製品の供給者にお願いします。

IBM の将来の方向または意向に関する記述については、予告なしに変更または撤回される場合があり、単に目標を示しているものです。

表示されている IBM の価格は IBM が小売り価格として提示しているもので、現行価格であり、通知なしに変更されるものです。卸価格は、異なる場合があります。

本書はプランニング目的としてのみ記述されています。記述内容は製品が使用可能になる前に変更になる場合があります。

本書には、日常の業務処理で用いられるデータや報告書の例が含まれています。より具体性を与えるために、それらの例には、個人、企業、ブランド、あるいは製品などの名前が含まれている場合があります。これらの名称はすべて架空のものであり、名称や住所が類似する企業が実在しているとしても、それは偶然にすぎません。

#### 著作権使用許諾:

本書には、様々なオペレーティング・プラットフォームでのプログラミング手法を例示するサンプル・アプリケーション・プログラムがソース言語で掲載されています。お客様は、サンプル・プログラムが書かれているオペレーティング・プラットフォームのアプリケーション・プログラミング・インターフェースに準拠したアプリケーション・プログラムの開発、使用、販売、配布を目的として、いかなる形式においても、IBM に対価を支払うことなくこれを複製し、改変し、配布することができます。このサンプル・プログラムは、あらゆる条件下における完全なテストを経ていません。従って IBM は、これらのサンプル・プログラムについて信頼性、利便性もしくは機能性があることをほのめかしたり、保証することはできません。

それぞれの複製物、サンプル・プログラムのいかなる部分、またはすべての派生的創作物にも、次のように、著作権表示を入れていただく必要があります。

© (お客様の会社名) (西暦年). このコードの一部は、IBM Corp. のサンプル・プログラムから取られています。 © Copyright IBM Corp. \_年を入れる\_. All rights reserved.

この情報をソフトコピーでご覧になっている場合は、写真やカラーの図表は表示されない場合があります。

---

## | プログラミング・インターフェース情報

この「分散アプリケーション開発に Sun TI-RPC の使用」資料には、プログラムを作成するユーザーが IBM i5/OS のサービスを使用するためのプログラミング・インターフェースが記述されています。

---

## 商標

以下は、International Business Machines Corporation の米国およびその他の国における商標です。

i5/OS

IBM

IBM (ロゴ)

Integrated Language Environment

System i

- | 他の会社名、製品名およびサービス名などはそれぞれ各社の商標または登録商標です。

---

## 使用条件

これらの資料は、以下の条件に同意していただける場合に限りご使用いただけます。

**個人使用:** これらの資料は、すべての著作権表示その他の所有権表示をしていただくことを条件に、非商業的な個人による使用目的に限り複製することができます。ただし、IBM の明示的な承諾をえずに、これらの資料またはその一部について、二次的著作物を作成したり、配布（頒布、送信を含む）または表示（上映を含む）することはできません。

**商業的使用:** これらの資料は、すべての著作権表示その他の所有権表示をしていただくことを条件に、お客様の企業内に限り、複製、配布、および表示することができます。ただし、IBM の明示的な承諾をえずにこれらの資料の二次的著作物を作成したり、お客様の企業外で資料またはその一部を複製、配布、または表示することはできません。

ここで明示的に許可されているもの以外に、資料や資料内に含まれる情報、データ、ソフトウェア、またはその他の知的所有権に対するいかなる許可、ライセンス、または権利を明示的にも黙示的にも付与するものではありません。

資料の使用が IBM の利益を損なうと判断された場合や、上記の条件が適切に守られていないと判断された場合、IBM はいつでも自らの判断により、ここで与えた許可を撤回できるものとさせていただきます。

お客様がこの情報をダウンロード、輸出、または再輸出する際には、米国のすべての輸出入関連法規を含む、すべての関連法規を遵守するものとします。

IBM は、これらの資料の内容についていかなる保証もしません。これらの資料は、特定物として現存するままの状態で提供され、商品性の保証、特定目的適合性の保証および法律上の瑕疵担保責任を含むすべての明示もしくは默示の保証責任なしで提供されます。





**IBM**

Printed in Japan

**日本アイ・ビー・エム株式会社  
〒106-8711 東京都港区六本木3-2-12**