

Infoprint ProcessDirector for Linux



# Planning and Installation

*Version 1, Release 2.1*



Infoprint ProcessDirector for Linux



# Planning and Installation

*Version 1, Release 2.1*

**Note:**

Before using this information and the product it supports, read the information in "Notices" on page 49.

| This edition applies to the IBM Infoprint ProcessDirector for Linux, Version 1 Release 2 Modification 1 (Program  
| Number 5697-N55), with PTF U811077 (April 2007), and to all subsequent releases and modifications until otherwise  
| indicated in new editions or technical newsletters. Be sure to use the correct edition for the level of the product. The  
| Infoprint ProcessDirector PTFs are cumulative; that is, you only need to apply the latest PTF to get all the changes  
| since the product's general availability.

Order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address given below.

The IBM Printing Systems Division welcomes your comments. A form for reader's comments is provided at the back of this publication. If the form has been removed, you may send your comments to the following address:

INFORMATION DEVELOPMENT  
IBM PRINTING SYSTEMS DIVISION  
DEPARTMENT H7FE BUILDING 004N  
PO BOX 1900  
BOULDER CO 80301-9191  
U.S.A.

If you prefer to respond electronically, you can e-mail your comments to [printpub@us.ibm.com](mailto:printpub@us.ibm.com).

**Internet**

Visit our home page at: <http://www.ibm.com/printers>

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 2006, 2007. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>About this publication</b> . . . . .	<b>v</b>
Who should read this publication . . . . .	v
Related information . . . . .	v

<b>Chapter 1. Overview of Infoprint ProcessDirector</b> . . . . .	<b>1</b>
Components . . . . .	1
Infoprint ProcessDirector Features . . . . .	2
Infoprint ProcessDirector Extensions . . . . .	2
Compatible products . . . . .	3
Supported printers . . . . .	4
System configurations . . . . .	4

<b>Chapter 2. Planning for installation</b> . . . . .	<b>7</b>
Hardware requirements. . . . .	7
Primary server. . . . .	7
Secondary servers . . . . .	7
Determining your file system setup. . . . .	8
Simple partition setup . . . . .	8
Installing required software . . . . .	9
Installing the SLES 9.0 operating system . . . . .	9
Installing the AIX operating system . . . . .	10
Installing the Windows operating system . . . . .	11
User interface software . . . . .	11
Planning for optional software . . . . .	13
Job submission . . . . .	13
Data transforms . . . . .	14
Infoprint Manager for AIX . . . . .	15
Fonts . . . . .	15

<b>Chapter 3. Installing Infoprint ProcessDirector</b> . . . . .	<b>17</b>
Installing Infoprint ProcessDirector on the primary Linux server . . . . .	18
Installing Infoprint ProcessDirector secondary servers . . . . .	19
Installing on Linux servers . . . . .	20
Installing on AIX servers . . . . .	21
Installing on Windows servers . . . . .	22
Completing post-installation tasks . . . . .	25
Verifying the installation . . . . .	26
Configuring Infoprint ProcessDirector . . . . .	26

<b>Chapter 4. Starting, stopping, and uninstalling Infoprint ProcessDirector</b> . . . . .	<b>29</b>
Starting Infoprint ProcessDirector servers on Linux . . . . .	29

Deactivating the autostart script on Linux . . . . .	29
Activating the autostart script on Linux . . . . .	29
Starting secondary servers on AIX. . . . .	30
Starting the Windows secondary server service . . . . .	30
Disabling automatic start of the Windows secondary server service . . . . .	30
Automatically starting the Windows secondary server service. . . . .	31
Stopping Infoprint ProcessDirector on Linux . . . . .	31
Stopping secondary servers on AIX . . . . .	32
Stopping the Windows secondary server service . . . . .	32
Uninstalling Infoprint ProcessDirector . . . . .	32
Uninstalling from the primary server. . . . .	32
Uninstalling the Linux or AIX secondary servers . . . . .	34
Uninstalling the secondary server on Windows . . . . .	35

<b>Chapter 5. Backing up data, applying service, and adding features</b> . . . . .	<b>37</b>
Backing up and restoring Infoprint ProcessDirector data . . . . .	37
Backing up data . . . . .	37
Restoring data . . . . .	38
Applying service updates and adding feature software on the Linux primary server . . . . .	39
Applying service updates on Linux secondary servers . . . . .	40
Applying service updates on AIX secondary servers . . . . .	41
Applying service updates on Windows secondary servers . . . . .	41

<b>Chapter 6. Installation planning checklist</b> . . . . .	<b>43</b>
---	-----------

<b>Chapter 7. Accessibility</b> . . . . .	<b>47</b>
Using assistive technologies . . . . .	47
Keyboard navigation of the user interface . . . . .	47
Infoprint ProcessDirector viewer shortcut keys . . . . .	47

<b>Notices</b> . . . . .	<b>49</b>
Trademarks . . . . .	51

<b>Glossary</b> . . . . .	<b>53</b>
---------------------------	-----------

<b>Index</b> . . . . .	<b>57</b>
------------------------	-----------



---

## About this publication

This publication provides planning and installation information about the IBM® Infoprint® ProcessDirector for Linux®, Version 1 Release 2.1 licensed program (Program Number 5697-N55). Infoprint ProcessDirector runs on a Linux server and is accessed from a Web-based user interface. Additional secondary servers can run on AIX and Windows servers.

---

## Who should read this publication

This publication is for system administrators who need to plan for and install Infoprint ProcessDirector for Linux.

---

## Related information

For information about IBM printing products, see these Web pages:

<http://www.ibm.com/printers>

<http://publib.boulder.ibm.com/infocenter/printer/index.jsp>

For information about using Infoprint ProcessDirector, see the information center and the online help, which you can access from the Web-based user interface.

For information about the IBM products used with Infoprint ProcessDirector, see these publications:

- *IBM AFP Fonts: Font Summary for AFP Font Collection*, S544-5633
- *IBM Infoprint Fonts: Font Summary*, G544-5846
- *Infoprint Manager for AIX: Getting Started*, G544-5817
- *Infoprint Manager for AIX: Introduction and Planning Guide*, G544-5833
- *Infoprint Manager: PSF and Server Messages*, G550-0524
- *Infoprint Manager: Reference*, S544-5475
- *Infoprint Transform Manager for Linux*, S550-0391
- *Infoprint Transform Manager for Linux: afp2pdf Transform Installation and User's Guide*, G550-0538
- *Infoprint XT for AIX: Installation and User's Guide*, GLD0-0024
- *Infoprint XT for Windows: Installation and User's Guide*, GLD0-0025
- *PSF for z/OS: AFP Download Plus*, S550-0433
- *PSF for z/OS: Download for z/OS*, S550-0429





---

# Chapter 1. Overview of Infoprint ProcessDirector

IBM Infoprint ProcessDirector is a product that lets you manage all aspects of your printing processes from a comprehensive Web-based user interface. Infoprint ProcessDirector supports job submission from z/OS® host systems using Download for z/OS and AFP™ Download Plus and from other systems using file copying methods. You can copy or move jobs into directories that you specify (*hot folders*), and you can configure Infoprint ProcessDirector so that it continually monitors the directories and automatically processes jobs as they arrive.

Infoprint ProcessDirector incorporates IBM DB2® technology for database management. The extensive database that Infoprint ProcessDirector uses provides detailed audit information about your printing workload and tasks.

You can access Infoprint ProcessDirector from a supported Web browser on the Microsoft® Windows® and Linux workstations in your network. You do not need to install Infoprint ProcessDirector on the Windows and Linux workstations to access the user interface; you only need to install Infoprint ProcessDirector on the Linux server that is managing your workflow.

---

## Components

Infoprint ProcessDirector is made up of these components:

### Infoprint ProcessDirector server

The Infoprint ProcessDirector server manages all job activities, including input devices that create the jobs and printers that print the jobs. The server also processes jobs through a series of steps, some of which include other programs. It controls both the flow of jobs and the IBM DB2 tables that store system information.

The Infoprint ProcessDirector server is installed on an xSeries® machine with the Linux operating system. Infoprint ProcessDirector can support more than one server; that is, a primary server and a secondary server.

Secondary servers can be defined with the primary server on the Linux xSeries system, installed on a separate Linux xSeries system, installed on an AIX® pSeries® system, or installed on a Windows xSeries system. Secondary servers on all the platforms can be used to do additional or special types of processing. A secondary Linux server can be used for processing steps and managing printers or input devices. A secondary AIX server can be used for processing steps and for managing printers when IBM Infoprint Manager for AIX is installed. A secondary Windows server can be used for processing steps.

The Infoprint ProcessDirector server contains these programs:

#### Print Services Facility™

Print Services Facility (PSF) is a print-driver program that manages and controls data transmitted to Advanced Function Presentation™ (AFP) printers that are TCP/IP-attached. The PSF program is installed on the same Linux xSeries machine as the primary Infoprint ProcessDirector server. It is also installed on secondary Linux servers, but not on secondary AIX or Windows servers.

**DB2** IBM DB2 tables contain Infoprint ProcessDirector properties and

their corresponding values. The DB2 program supplied with the Infoprint ProcessDirector product is a special version of DB2 that you must install before you install the Infoprint ProcessDirector program; you cannot use any other version of DB2 with Infoprint ProcessDirector. In addition, you cannot use the Infoprint ProcessDirector version of DB2 for any other purpose.

The DB2 program is installed on the same Linux xSeries machine as the primary Infoprint ProcessDirector server; it is not installed on secondary Linux, AIX, or Windows servers.

### Infoprint ProcessDirector user interface

The Infoprint ProcessDirector user interface is a Web-based interface that lets you manage the printing process. Users can access the user interface from a supported Web browser on a Windows or Linux workstation as long as they have an Infoprint ProcessDirector user ID. The Windows workstation must have either a Microsoft Internet Explorer or a Mozilla Web browser installed; the Linux workstation must have a Mozilla Web browser installed. The user interface program is installed on the same Linux xSeries machine as the primary Infoprint ProcessDirector server.

The user interface contains field-level help and an information center for Infoprint ProcessDirector. The information center displays administrative and operational topics that help users learn about the Infoprint ProcessDirector product. It also includes procedures that describe how to use the product.

The user interface also has a Web-based file viewer that uses the Adobe Acrobat Reader to display AFP files so you can select pages to reprint.

## Infoprint ProcessDirector Features

Infoprint ProcessDirector has features you can add to the base product.

Here are the features for Infoprint ProcessDirector:

*Table 1. Features for Infoprint ProcessDirector*

Description	One-time charge feature number	CD-ROM medium
Secondary Server	0013	5849
Connectivity	0014	5859
Low-speed Printer Engine	0012	5839
Medium-speed Printer Engine	0009	5829
High-speed Printer Engine	0006	5819

## Infoprint ProcessDirector Extensions

The modular design of Infoprint ProcessDirector lets you add Extensions to the base product so that you can add product functions as your business needs change.

Infoprint ProcessDirector Extensions are customizable software components that you can purchase from your IBM Printing Systems representative. The representative installs the Extensions on the existing Infoprint ProcessDirector primary server. The Extensions are integrated seamlessly into the user interface.

Some examples of Infoprint ProcessDirector Extensions and the functions they provide are:

- **AFP Editor**

The AFP Editor Extension lets you create bar codes and hide areas in AFP files. You can create bar codes that contain index values, job properties, and static text. For example, if the ZIP codes in an AFP file are index values, you can create bar codes that contain the ZIP codes. You can hide areas in AFP files so that no one can see the data in the hidden areas and so that the data does not print. For example, you can hide areas that contain existing bar codes that you want to replace.

The AFP Editor supports these types of bar codes:

- Code 39
- DataMatrix
- Interleaved 2-of-5
- PDF417
- US Postnet
- USPS Four-State

- **AFP Indexer**

The AFP Indexer Extension lets you create page groups and indexes in AFP files. When you view an AFP print file that contains page groups and indexes in Infoprint ProcessDirector, you can navigate in the file to find pages containing specific index values. You can also reprint all the pages in one or more page groups.

- **Reports**

The Reports Extension lets Infoprint ProcessDirector collect data about job events, user actions, and printer activity. Then, you can generate reports based on the data. You can use the reports for capacity planning, production efficiency measurement and optimization, and problem determination.

- **Service Level Agreement (SLA)**

The Service Level Agreement Extension lets you manage your progress towards meeting your performance objectives. If you have service level agreements in place with your customers, this Extension can help you make sure that their print jobs are on schedule to be completed on time.

---

## Compatible products

As an option, these products can be used with Infoprint ProcessDirector:

### **AFP Download Plus**

AFP Download Plus is a separately ordered feature of IBM Print Services Facility (PSF) for z/OS (Program Number 5655-M32) that transforms line data to Mixed Object Document Content Architecture™ for Presentation (MO:DCA-P) data and then transmits the print job with all required resources to Infoprint ProcessDirector.

### **Download for z/OS**

Download for z/OS is a separately ordered feature of PSF for z/OS (Program Number 5655-M32) and is used to submit jobs to Infoprint ProcessDirector. Download for z/OS automatically transmits output across the TCP/IP network from the host system to Infoprint ProcessDirector for printing or archiving.

### **Infoprint Manager for AIX**

IBM Infoprint Manager for AIX (Program Number 5765-F68) is a print

server that handles the scheduling, archiving, retrieving, and assembly of a print job and its related resource files.

#### **Infoprint Transform Manager for Linux**

IBM Infoprint Transform Manager for Linux (Program Number 5639-P51) receives print jobs from Infoprint ProcessDirector, transforms them to AFP, and returns them to Infoprint ProcessDirector for printing.

If you purchase the IBM Infoprint Transform Manager for Linux: afp2pdf Transform i-listed PRPQ (Program Number 5799-TWL) with Infoprint Transform Manager, you can use the afp2pdf transform to convert Mixed Object Document Content Architecture (MO:DCA-P) documents, also called AFP documents, into Adobe Portable Document Format (PDF) documents.

#### **Infoprint XT for AIX**

IBM Infoprint XT for AIX (Program Number 5799-GTF) transforms Xerox metacode and line conditioned data stream (LCDS) jobs to AFP.

#### **Infoprint XT for Windows**

IBM Infoprint XT for Windows (Program Number 5799-RZA) transforms Xerox metacode and line conditioned data stream (LCDS) jobs to AFP.

#### **Infoprint Fonts for Multiplatforms**

IBM Infoprint Fonts for Multiplatforms (Program Number 5648-E77) contains AFP outline fonts and TrueType and OpenType fonts.

#### **AFP Font Collection**

IBM AFP Font Collection (Program Number 5648-B45) contains a wide selection of core interchange outline and raster AFP fonts.

---

## **Supported printers**

Infoprint ProcessDirector supports these IBM printer models:

- Infoprint 2090ES
- Infoprint 2105ES
- Infoprint 2190
- Infoprint 2210
- Infoprint 2235

**Note:** Infoprint ProcessDirector can pass PCL, PostScript, and PDF data through to the Infoprint 2190, the Infoprint 2210, and the Infoprint 2235 printers, but it does not support the finishing options available on these printers.

- Infoprint 4000
- Infoprint 4100
- Infoprint 5000

---

## **System configurations**

You can install Infoprint ProcessDirector with various system configurations, depending on whether you use secondary servers. The hardware configurations can include:

- Primary Linux server
- Primary Linux server with one or more secondary servers on the same system or on different Linux systems

- Primary Linux server with one or more secondary AIX, Linux, or Windows servers

The graphic in Figure 1 shows a configuration with a primary Linux server, a secondary Linux server on a separate system, a secondary AIX server, and a secondary Windows server. The graphic also shows Infoprint ProcessDirector components and the optional products you might use with Infoprint ProcessDirector, including Download for z/OS, AFP Download Plus, Infoprint Transform Manager for Linux, and Infoprint Manager for AIX.




Figure 1. Example of an Infoprint ProcessDirector system configuration



---

## Chapter 2. Planning for installation

Table 6 on page 43 is an installation planning checklist that includes planning considerations and tasks for your Infoprint ProcessDirector installation. You can use the checklist to help you keep track of the planning tasks you have completed.

Before you can install Infoprint ProcessDirector, you must complete the planning tasks listed in the checklist, including those detailed in this section:

- Obtain required hardware.
- Determine your file system setup.
- Install required software.
- Install optional software.

---

### Hardware requirements

The system hardware requirements for Infoprint ProcessDirector are:

- One or more 2.8 GHz or faster processors
- Minimum of 4 GB RAM for the primary server
- Minimum of 1 GB RAM for secondary servers
- Minimum of 1024 x 768 display resolution

**Note:** A higher display resolution, 1280 x 1024, is recommended if you need to display more printers or input devices in the user interface.

The performance of Infoprint ProcessDirector and its attached printers depends on the availability and efficiency of memory, processors, disk space, and network resources in the system configuration. Performance also depends on the content of the print data streams being processed and the overall load on the system. For example, complex print jobs, such as those containing images or bar codes, require more resources than those containing plain text. For help determining what hardware configuration meets your print requirements, contact your IBM Printing Systems representative.

#### Primary server

The hardware required to install the primary Infoprint ProcessDirector server is an xSeries system that is able to run this operating system: SUSE Linux Enterprise Server (SLES) 9.0 with Service Pack 3 (SP3) for x86.

Novell has a program that certifies the hardware on which you can install the SLES operating system. For example, you can run SLES on an IBM eServer™ xSeries 255 Model 8685-2RX. To determine which hardware is currently certified, see:

<http://developer.novell.com/yessearch/Search.jsp>

Make sure you specify SUSE Linux Enterprise Server 9 for x86 as the Novell product when you search for supported hardware.

#### Secondary servers

You can install Infoprint ProcessDirector on Linux, AIX, or Windows systems that have a minimum of 1 GB RAM:

- Linux secondary servers require an xSeries system with the same operating system requirements as the primary server.
- AIX secondary servers require a pSeries system that runs on this operating system: AIX 5L Version 5.2 with Maintenance Level (ML) 7 or later.
- Windows secondary servers require an xSeries system that runs on one of these operating systems: Windows XP Professional with Service Pack 2 or later, or Windows 2003 Server with Service Pack 1 or later. In addition, the Windows system must have Microsoft Windows Services for UNIX (SFU) Version 3.5 or later.

## Determining your file system setup

You can set up your file system as partitions or as a mounted file system from other storage units. Consider these when making your decision:

- System configuration
- File sharing strategy
- Storage and backup needs
- Production volumes and print resource management
- Network capacity
- Failure recovery

You need to set up partitions and mount the file directories on your system before you install Infoprint ProcessDirector.

### Simple partition setup

A single partition is the simplest file system setup. However, a single partition does not allow the system to continue functioning when it runs out of space. Table 2 shows the recommended simple partition setup for the primary Infoprint ProcessDirector server with a 180 GB hard drive and for secondary Linux and AIX servers.

**Note:** File system partitioning does not apply to the Windows operating system. Installation of the Windows secondary server requires 150 MB of free space.

Table 2. Simple partition for primary Infoprint ProcessDirector server (180 GB hard drive) and secondary Linux and AIX servers

File system partition	Size	Description	Server
/	10 GB	Root directory	Primary and secondary
/aiw	80+ GB	Directory for Infoprint ProcessDirector print jobs, resources, backup files, and trace files. This directory is only required for the primary server; it is shared by the secondary servers as a mounted file system.	Primary: required Secondary: shared
/var/psf	50+ GB	To improve performance, this directory must be bigger than your biggest job. It requires enough space to store data for concurrent jobs on multiple printers. This is the recommended minimum size for five printers. Increase the size by 10 GB for each additional printer.	Primary Secondary Linux
/aiw/aiw1/db2	20 GB	Directory for DB2 tables. This directory is only applicable on the primary Infoprint ProcessDirector server.	Primary only
/aiw/aiw1/db2_logs	2 GB	Directory for DB2 logs. This directory is only applicable on the primary Infoprint ProcessDirector server.	Primary only



---

## Installing required software

Infoprint ProcessDirector requires that the operating system you install runs in 32-bit mode. You can install this level of the operating system, depending on the hardware it is installed on:

**xSeries system (install on primary or Linux secondary):**

SUSE Linux Enterprise Server (SLES) 9.0 with Service Pack 3 for x86

**Note:** In this publication, "SLES" represents this level of SUSE Linux.

**pSeries system (install on AIX secondary):**

AIX 5L Version 5.2 with ML 7 or later

**xSeries system (install on Windows secondary):**

One of these:

- Windows XP Professional with Service Pack 2 or later
- Windows 2003 Server with Service Pack 1 or later

**Note:** To run the Windows secondary server, you must install Microsoft Windows Services for UNIX (SFU) Version 3.5 or later. SFU includes all the facilities needed to mount and export network file systems and map user names.

## Installing the SLES 9.0 operating system

1. See the SLES documentation to install SLES with these required components:
  - libredcarpet-python 2.0.2
  - Apache-Ant
  - Acroread 7 PDF viewer
  - Mozilla 1.7 Web browser
  - Japanese installations only:
    - kochi-substitute Version 20030809 or later (font substitutes for Japanese Kochi TrueType fonts)
    - xfontjp Version 20020904 (Japanese fixed fonts for X11)
  - The Java runtime environment installed on the Linux machine you are using for the Infoprint ProcessDirector primary server must be the IBM Runtime Environment for Linux Java 2 Technology Edition. This version (IBMJAVA2-JRE) is contained in the SLES distribution that is a prerequisite for Infoprint ProcessDirector; however, multiple versions of Java are included on the SLES 9 compact disks, so be sure you pick this one.

**Note:** The latest levels of some of the required components are only available with Service Pack 3 (SP3).

2. Create Linux partitions and file systems. See "Determining your file system setup" on page 8 for recommendations and considerations.
3. Run these commands and look for the expected results to verify that you installed SLES correctly:

*Table 3. SLES commands and expected results*

Command	Expected result
<code>rpm -qa   grep suse</code>	susehelp_en-2004.04.05-3.1 susehelp-2004.04.05-3.1 suse-build-key-1.0-662.10 (for SP3)

Table 3. SLES commands and expected results (continued)

Command	Expected result
<code>uname -rv</code>	<p>One of these:</p> <ul style="list-style-type: none"> <li>2.6.5-7.244-smp #1 SMP Tue Nov 8 20:19:28 UTC 2005</li> <li>2.6.5-7.236-bigsmpp #1 SMP Mon Dec 12 18:32:25 UTC 2005</li> </ul> <p><b>Note:</b> "smp" and "bigsmpp" might be replaced by "default".</p>
<code>getconf GNU_LIBPTHREAD_VERSION</code>	NPTL 2.3.5
<code>rpm -q apache-ant</code>	apache-ant-1.6.0-77.1

If the command results are not as you expect, use YaST (Yet Another Setup Tool) to make sure you have installed the required components (see Step 1). In YaST, click **Software** → **Install/Remove Software**.

4. Verify time zone settings through YaST, and correct if necessary:  
Click **System** → **Date and Time** → **Clock and Time Zone Configuration**.
5. Set up networking based on system networking information.
6. Verify network connectivity:
  - a. From the system where you will access the Infoprint ProcessDirector user interface, use both the host name and the IP address to ping the primary Infoprint ProcessDirector server.
  - b. From the secondary server, ping the primary Infoprint ProcessDirector server.
  - c. From the primary server, ping the secondary server.
  - d. Contact the network administrator if you are not successful with any of these verifications.
7. For optimum performance, verify that your Ethernet settings are running full duplex mode with autonegotiation off. For example:
  - a. Enter `ethtool eth0` to display the Ethernet settings.
  - b. Enter `ethtool -s eth0 autoneg off` if autonegotiation is set to on.
  - c. Enter `ethtool -s eth0 duplex full` if duplex is not set to full.

## Installing the AIX operating system

1. See the AIX documentation to install AIX 5L Version 5.2 or later.
2. Verify time zone settings through System Management Interface Tool (SMIT) and correct if necessary:  
Click **System Environments** → **Change/show date and time**.
3. Set up networking based on system networking information.
4. Verify network connectivity:
  - a. From the secondary server, ping the primary Infoprint ProcessDirector server.
  - b. From the primary server, ping the secondary server.
  - c. Contact the network administrator if you are not successful with any of these verifications.

## Installing the Windows operating system

When you use a secondary server on a Windows operating system, you must install the Windows operating system and Windows Services for UNIX (SFU) Version 3.5 or later.

To install the Windows operating system, see the Windows documentation to install Windows XP Professional with Service Pack 2 or Windows 2003 Server with Service Pack 1 or later.

For information about SFU, see “Installing Windows Services for UNIX (SFU) on Windows” on page 23.

## User interface software

Infoprint ProcessDirector requires a Web browser to access and display the user interface. You can access the interface from the same Linux system where the primary server is installed, from another Linux system, or from a system with Microsoft Windows installed. One of these browsers must be installed and configured on the system where you access the user interface:

### Linux system:

Mozilla 1.7, which is provided with the SLES 9.0 operating system; you must choose to install it when you are installing the operating system.

### Windows system:

- Mozilla 1.7. For information about obtaining this browser, see: <http://www.mozilla.org>
- Microsoft Internet Explorer 6.x and Internet Explorer 7. For information about obtaining these browsers, see: <http://www.microsoft.com>

**Note:** Infoprint ProcessDirector only supports Microsoft Internet Explorer running on Windows XP.

The user interface has a Web-based file viewer that requires the Adobe Reader to display AFP files so you can select pages to reprint. To view print files, these supported versions of Adobe Reader must be installed on the Linux or Windows system where you are accessing the user interface:

### Linux system:

Adobe Reader 7.0, which is included with SLES. You might need to make the Adobe Reader available to the Web browser after Infoprint ProcessDirector is installed. See “Making the Adobe Reader available to the Web browser” on page 12.

### Windows system:

Adobe Reader 7.0. For information about obtaining this Adobe Reader, see: <http://www.adobe.com>

To obtain Adobe Reader in your preferred language, go to the Web page and do this:

1. Click **(Change)** in the top right portion of the page.
2. Select a region and language, and then click **Go**.
3. Download Adobe Reader.

## Configuring Mozilla

To access the Infoprint ProcessDirector user interface with the Mozilla Web browser, configure the browser with these settings:

1. Click **Edit** → **Preferences**.
2. To change the language for text used in the user interface and for most of the messages that Infoprint ProcessDirector issues, click **Navigator** → **Languages** in the **Category** pane. Add your language to the top of the list, and then click **OK**. Infoprint ProcessDirector supports these languages and locales:
  - English (en\_US)
  - French (fr\_FR)
  - German (de\_DE)
  - Italian (it\_IT)
  - Japanese (ja\_JP)
  - Spanish (es\_ES)
3. In the **Category** pane, click **Privacy & Security** → **Cookies**.
4. Click **Allow all cookies**.
5. In the **Category** pane, click **Advanced** → **Scripts & Plugins**.
6. Under **Enable JavaScript for**, click **Navigator**.
7. In the **Category** pane, click **Advanced** → **Cache**.
8. Under **Compare the page in the cache to the page on the network**, click **Every time I view the page**.
9. Click **OK**.

### Configuring Internet Explorer

To access the Infoprint ProcessDirector user interface with the Internet Explorer Web browser, configure the browser with these settings:

1. Click **Tools** → **Internet Options**.
2. On the **General** tab, click **Settings**. If you are using Internet Explorer 7, click **Settings** in the **Browsing history** section.
3. Under **Check for newer versions of stored pages**, click **Automatically** and then click **OK**.
4. To change the language that Infoprint ProcessDirector uses for the user interface text and most of the messages that it issues, click **Languages**. Then, click **Add** to add your language to the list. Move your language up so that it is the first entry in the list and click **OK**. Infoprint ProcessDirector supports these languages and locales:
  - English (en\_US)
  - French (fr\_FR)
  - German (de\_DE)
  - Italian (it\_IT)
  - Japanese (ja\_JP)
  - Spanish (es\_ES)
5. Click the **Security** tab.
6. With the Internet zone selected, click **Custom Level**.
7. Make sure that **Enable** is selected for **Allow META REFRESH**.
8. Make sure that **Enable** is selected for **Active scripting** in the **Scripting** section.
9. Click **OK**.

### Making the Adobe Reader available to the Web browser

The Adobe Reader is available on the Linux system when SLES is installed. However, you might need to make the Adobe Reader available to the Mozilla Web browser on Linux. If so, follow this procedure:

1. Enter `/usr/local/Adobe/ Acrobat7.0/Browser/install_browser_plugin` at the command prompt. If the command is not found, enter `/usr/X11R6/lib/ Acrobat7/Browser/install_browser_plugin`.
2. Press Enter to install the Web browser plug-in.
3. Click the option for the user-specific installation.
4. Close any open Web browsers.
5. Open a new browser.
6. To check that the plug-in installed correctly, click **Help** → **About Plug-ins**. You should see Adobe Acrobat 7.0.

---

## Planning for optional software

This section explains planning information for installing optional software to be used with Infoprint ProcessDirector.

### Job submission

Infoprint ProcessDirector can receive jobs for processing from the Job Entry Subsystem (JES) spool on a z/OS host or from any system that can send jobs to hot folders. Jobs are submitted to input devices that you define in Infoprint ProcessDirector. Input devices receive the jobs and then initiate job processing. The supported job submission methods are:

#### Download for z/OS

Automatically transmits output across the TCP/IP network from the host system to Infoprint ProcessDirector for printing or archiving.

#### AFP Download Plus

Converts line data to AFP data and transmits the print job with all required resources across the TCP/IP network from the host system to Infoprint ProcessDirector for printing.

#### Hot folders

Receives print files through File Transfer Protocol (FTP) or your preferred file copying method. When you copy or move a print file to the hot folder directory, the input device that is associated with the hot folder automatically receives the job and initiates job processing.

Download for z/OS and AFP Download Plus are separately ordered features of PSF for z/OS. For information about PSF for z/OS and its features, see:

[http://www.printers.ibm.com/internet/wwsites.nsf/vwebpublished/psfhome\\_z\\_ww](http://www.printers.ibm.com/internet/wwsites.nsf/vwebpublished/psfhome_z_ww)

In addition to deciding what job submission methods to use, you need to determine the naming convention for the job submission directories on the Linux primary server where you want the input files to reside. You must specify these directories when you create an input device:

#### Folder location directory

The name of the directory that an input device monitors for incoming jobs. For example, `/aiw/aiw1/System/dl` for Download for z/OS or AFP Download Plus jobs, or `/aiw/aiw1/System/hf` for hot folder jobs.

#### Staging location directory

The name of the directory where the job submission method places the input file. Consider creating a subdirectory of the folder location directory. For example, `/aiw/aiw1/System/dl/staged` for AFP input files received

from Download for z/OS or AFP Download Plus, or /aiw/aiw1/System/hf/  
staged for line data input files received from hot folders.

Each directory must provide read and write access to the aiwgrp1 group so Infoprint ProcessDirector can read and modify the input files. See “Completing post-installation tasks” on page 25 for more information about the aiwgrp1 group.

Before you use Download for z/OS or AFP Download Plus with Infoprint ProcessDirector, you must configure the software to communicate with Infoprint ProcessDirector. Some of the configuration tasks include:

- Define a JES initialization statement for a functional subsystem application (FSA).
- Create a startup procedure to identify program name, region size, and printing defaults for the FSA.
- Create a routing control data set that points to the port number and IP address of the Infoprint ProcessDirector server. You only do this in Download for z/OS.
- Use installation exits, if necessary, for modifications to software functions. Both Download for z/OS and AFP Download Plus can use installation Exit 15, which transmits additional print parameters to Infoprint ProcessDirector.

See the Infoprint ProcessDirector information center in the user interface for information about configuring Download for z/OS and AFP Download Plus with Infoprint ProcessDirector. For more information about configuring Download for z/OS and AFP Download Plus, see *PSF for z/OS: Download for z/OS* and *PSF for z/OS: AFP Download Plus*. For information about copying files to hot folders, see the Infoprint ProcessDirector information center in the user interface.

## Data transforms

Infoprint Transform Manager for Linux receives print jobs from Infoprint ProcessDirector and transforms the data so it can be printed.

Infoprint Transform Manager for Linux can transform these data streams to AFP:

- GIF, JPEG, and TIFF
- PCL
- PDF and PostScript

Infoprint ProcessDirector supports Infoprint Transform Manager 1.2 with Service Pack 2 or 3.

If you have the IBM Infoprint Transform Manager for Linux: **afp2pdf** Transform i-listed PRPQ (Program Number 5799-TWL) installed, Infoprint Transform Manager can transform AFP data to PDF. For information about Infoprint Transform Manager, see *Infoprint Transform Manager for Linux* or this Web page:

[http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/itmhome\\_1\\_ww](http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/itmhome_1_ww)

For information about the **afp2pdf** transform, see *Infoprint Transform Manager for Linux: afp2pdf Transform Installation and User's Guide*.

You can also use Infoprint XT™ for AIX or Windows to transform Xerox metacode and LCDS jobs to AFP.

For information about Infoprint XT for AIX, see *Infoprint XT for AIX: Installation and User's Guide* or this Web page:

[http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/ipxthome\\_p\\_ww](http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/ipxthome_p_ww)

For information about Infoprint XT for Windows, see *Infoprint XT for Windows: Installation and User's Guide* or this Web page:

[http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/ipxthome\\_x\\_ww](http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/ipxthome_x_ww)

## Infoprint Manager for AIX

Infoprint ProcessDirector can send print jobs to printers defined on secondary AIX servers that have Infoprint Manager for AIX, Version 4 Release 2 with PTF U810787 installed. For information about Infoprint Manager for AIX, see the Infoprint Manager publications or this Web page:

[http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/ipmhome\\_p\\_ww](http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/ipmhome_p_ww)

## Fonts

Infoprint ProcessDirector provides a basic set of 240-pel and 300-pel fonts (IBM compatibility fonts) with the product. For a more robust font set, IBM recommends you install additional AFP fonts on your primary Linux server. IBM Infoprint Fonts for Multiplatforms (Program Number 5648-E77) contains AFP outline fonts and TrueType and OpenType fonts. Table 4 lists the AFP outline font features of Infoprint Fonts that you can order and install on your Linux workstation.

*Table 4. Infoprint Fonts for AIX, Linux, and Windows*

Font Library Name	Program Number	Feature Number
General Font Library	5648-E77	5957
Japanese Font Library	5648-E77	5849
Korean Font Library	5648-E77	5889
Simplified Chinese Font Library	5648-E77	5879
Traditional Chinese Font Library	5648-E77	5809

For more information about Infoprint Fonts for Multiplatforms, see this Web page:

[http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/ipfontshome\\_m\\_ww](http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/ipfontshome_m_ww)

If your AFP files require additional raster fonts for printing, you might need fonts from the AFP Font Collection (Program Number 5648-B45). Table 5 lists the AFP Font Collection features you can order.

*Table 5. AFP Font Collection*

Font Collection Name	Program Number	Feature Number
Fonts for AIX, OS/2, Windows NT®, and Windows 2000	5648-B45	5970
Japanese Fonts for AIX, Windows NT, and Windows 2000	5648-B45	5809
Korean Fonts for AIX, Windows NT, and Windows 2000	5648-B45	5819
Simplified Chinese Fonts for AIX, Windows NT, and Windows 2000	5648-B45	5829
Traditional Chinese Fonts for AIX, Windows NT, and Windows 2000	5648-B45	5839

The AFP Font Collection does not provide an installation program for Linux. To use the AFP Font Collection on your Linux server, copy the fonts from the AFPONTS directory on the AFP Font Collection CD-ROM to the /usr/lpp/afpfonts directory on your Linux workstation. Be sure to copy all files

from the subdirectories in the AFP FONTS directory to /usr/lpp/afpfonTS. Do not maintain the subdirectory structure from the AFP FONTS directory, but do make sure that the uppercase file names are preserved.

For more information about AFP Font Collection, see this Web page:

[http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/afpfonhome\\_m\\_ww](http://www.printers.ibm.com/internet/wwsites.nsf/vwwebpublished/afpfonhome_m_ww)



---

## Chapter 3. Installing Infoprint ProcessDirector

The Infoprint ProcessDirector installation package consists of several compact discs (CDs) that contain:

- Installation program for DB2
- Installation program for Infoprint ProcessDirector
- Installation programs for feature software (optional)
- Publications

Each program is installed from its own CD. To install Infoprint ProcessDirector on the primary server, you must install the DB2 program first, and then install the Infoprint ProcessDirector program, which installs the base Infoprint ProcessDirector program, the PSF program, and the user interface program. After the Infoprint ProcessDirector program is installed, you can install programs for any of the feature software and any of the Infoprint ProcessDirector Extensions.

On secondary servers, you do not install the DB2 program; you only install the base Infoprint ProcessDirector program. For Linux secondary servers, the PSF program is also installed.

### Important:

1. The installation instructions describe the installation with the InstallShield Wizard graphical display. If you cannot run the InstallShield Wizard in graphical mode, use the console option at the end of a setup command to install with a text-based installation program. For example, enter:

#### Linux server

```
./setup -console
```

#### AIX server

```
cd /aix  
./setup_aiw_aix.bin -console
```

2. To see what attributes you can use with the setup command on Linux servers, enter `./setup -h`.
3. During the installation of any Infoprint ProcessDirector program, the program files are copied to the system. However, the installation is not complete until you click **Activate now**. If you skip the activation step and click **Activate later** (for example, to view the publications CD), you must insert any additional software CD and click **Activate now** before using Infoprint ProcessDirector. If you install any new Infoprint ProcessDirector software, you must activate again.
4. If you already have Infoprint ProcessDirector installed and you want to apply a service update, see Chapter 5, "Backing up data, applying service, and adding features," on page 37.

After you finish installing Infoprint ProcessDirector, you do post-installation tasks to verify the installation and configure Infoprint ProcessDirector.

---

## Installing Infoprint ProcessDirector on the primary Linux server

This procedure explains how to install the DB2 and Infoprint ProcessDirector programs on the primary server. Separate InstallShield Wizards are used to install each program.

To install Infoprint ProcessDirector on a primary Linux server:

1. Make sure the planning checklist is complete and the required hardware and software is available and installed. See Chapter 2, “Planning for installation,” on page 7.
2. Make sure that DB2 is not installed on the system.
3. Log in as the root user.
4. Insert the DB2 CD in the CD-ROM drive.
5. Mount the CD, if necessary. For example, enter `mount /media/cdrom` or `mount /media/cdrecorder`.
6. Open a console window and change to the CD directory. For example, enter `cd /media/cdrecorder`.
7. From the Linux console command line, enter `./setup` to start the installation.
8. For each program that is installed:
  - a. Select the appropriate language for the InstallShield Wizard, and then click **OK**.  
You see a welcome window for the InstallShield Wizard.
  - b. Reply to the prompts as the InstallShield Wizard steps you through the installation.
9. When you see a window that displays the default user ID (UID) and group ID (GID) values, select the defaults or use the numeric values you established during installation planning for use on all the servers (see Chapter 6, “Installation planning checklist,” on page 43).
10. The final program that is installed asks you to select the language for the Infoprint ProcessDirector server. Make sure you select a language if you want one different from the language used during the installation. The language in which the Infoprint ProcessDirector server is installed determines the language for some messages and object descriptions, even if you set the browser for the user interface to a different language.
11. When you see a message that all your files have been copied to your system, click **Activate later** if you have additional software or a service update to install. Otherwise, click **Activate now**.  
The final window displays the URL for accessing the user interface in the format:  
`http://hostname:15080/aIW`  
The host name of the primary Linux server is *hostname*.
12. Click **Finish** to complete the installation. You see an installation complete message in the console window, which indicates that all programs have been installed.
13. Remove the Infoprint ProcessDirector CD from the CD-ROM drive.
14. To install software from any additional Infoprint ProcessDirector CDs, including service updates, insert the CD in the CD-ROM drive and do these steps:
  - a. Repeat steps 5 and 6.

- b. From the Linux console command line, enter `./setup` to start the installation.
  - c. Reply to any prompts. Be sure to click **Activate now** during the final installation.
15. Verify the installation through the Web browser:
- a. The Web browser on your Linux workstation automatically launches the Infoprint ProcessDirector login page.

**Note:** If the Infoprint ProcessDirector login page does not automatically launch, manually launch the browser and enter this URL:

`http://hostname:15080/aiw`

The host name of the primary Linux server is *hostname*.

- b. If you receive a message that the browser cannot connect to the primary server:
  - 1) Log in to the Linux server as the Infoprint ProcessDirector user. The default user ID is `aiw1` and the default password is `aiwpass1`.
  - 2) Enter `stopaiw` at the command prompt.
  - 3) Enter `startaiw` at the command prompt.
  - 4) From the Web browser, enter `http://hostname:15080/aiw`.
- c. On the Infoprint ProcessDirector login page, type the default administrator user ID `aiw` and the default password `aiw` and then click **Log in**. You are prompted to change the password before you can log in to the user interface. Make note of your new password on the Chapter 6, "Installation planning checklist," on page 43.

Infoprint ProcessDirector is now running on your primary Linux server. See "Completing post-installation tasks" on page 25 to verify the installation by printing a test job.

---

## Installing Infoprint ProcessDirector secondary servers

After successfully installing Infoprint ProcessDirector on a primary server, you can install Infoprint ProcessDirector secondary servers on separate Linux, AIX, and Windows systems.

For any type of secondary server, do these common tasks from the primary server and then do the installation tasks specific to your operating system:

1. Set up the primary server to export the Infoprint ProcessDirector shared file system to the secondary server. The secondary server uses the `/aiw` file system on the primary server.
  - a. Use YaST to verify that the NFS server on the primary system is started:
    - 1) Click **Network Services** → **NFS Server**.
    - 2) Verify that **Start NFS Server** is set. If not, click **Start NFS Server** and then click **Next**. You see that `/aiw` is one of the available directories.
    - 3) Click **Finish**.
  - b. Update `netgroup` to allow access to one or more secondary servers:
    - 1) Use an editor, such as `vi`, to edit `/etc/netgroup`. For example, enter `vi /etc/netgroup`.
    - 2) Add this line: `aiwhosts (server1,,) (server2,,)`. The secondary server host name is `server1`.

**Note:** The parentheses and commas are required as shown.

2. Use the Infoprint ProcessDirector user interface to add and enable the secondary server:
  - a. Access the user interface at **http://hostname:15080/aiw**. The host name of the primary Linux server is *hostname*.
  - b. Log in as an administrator. The default user name is *aiw*.
  - c. On the Main page, click the **Administration** tab.
  - d. From the shortcuts list, click **Add a Secondary Server**.
  - e. Specify a server name and the IP address or host name for the secondary server. As an option, specify a description and values for the other properties of the server.
  - f. For a Linux secondary server, you can specify either **Yes** or **No** for **In general server pool**. For an AIX or Windows secondary server, specify **No** for **In general server pool**.

**Note:** If any external steps send jobs to the AIX or Windows secondary server, you must tune the step template appropriately. For information about how to tune the step template, click **Help** from the top task bar of the Infoprint ProcessDirector user interface to see the information center.

- g. Click **OK**.
  - h. Select the server and then click **Enable**.
3. Continue with the appropriate installation task for your secondary server. Choose from: "Installing on Linux servers," "Installing on AIX servers" on page 21, or "Installing on Windows servers" on page 22.

## Installing on Linux servers

You can install a secondary server on a separate Linux system.

To install Infoprint ProcessDirector on a secondary Linux system, other than the system with the primary server:

1. Make sure that DB2 is not installed on the system.
2. Log in as the root user.
3. Enter `df -k` to verify that the `/opt/IBM` and `/tmp` directories are each at least 175 MB in size. If both `/opt/IBM` and `/tmp` are contained in the `/` file system, at least 350 MB of space must be available. If not, increase the directory size.
4. Insert the Infoprint ProcessDirector CD in the CD-ROM drive.
5. Mount the CD, if necessary. For example, enter `mount /media/cdrom` or `mount /media/cdrecorder`.
6. Open a console window and change to the CD directory. For example, enter `cd /media/cdrecorder`.
7. From the Linux console command line, enter `./setup` to start the installation.
8. For each program that is installed:
  - a. Select the appropriate language and then click **OK**. You see a welcome window for the InstallShield Wizard.
  - b. Reply to the prompts as the InstallShield Wizard steps you through the installation.
9. When you see a window that displays the default user ID (UID) and group ID (GID) values, select the defaults or use the same numeric values you specified for the primary server.

10. You see a message that all your files have been copied to your system. If you are installing a service update in addition to the base product code, click **Activate later**. If you are installing only the base product code, click **Activate now**. The final window displays the URL for accessing the user interface in the format:

`http://hostname:15080/aiw`

The host name of the primary Linux server is *hostname*.

11. Click **Finish** to complete the installation.
12. Remove the Infoprint ProcessDirector CD from the CD-ROM drive.
13. Apply any service updates needed to keep the Infoprint ProcessDirector secondary server level the same as the primary server level:
  - a. Insert the CD for the service update in the CD-ROM drive.
  - b. From the Linux console command line, enter `./setup` to start the installation.
  - c. Click **Activate now**.
  - d. Click **Finish** to complete the installation.
14. Enter `ps -ef | grep Instance` on the console command line to verify that the Infoprint ProcessDirector server is running. You should see an instance statement such as:

`java com.ibm.aiw.instance.SecondaryInstance hostname`

If the server is not running, contact IBM Software Support.

After your server is running, you must determine how this server is used and change the properties of some objects accordingly. For example:

- What printers and input devices do you want the server to manage?  
Create or modify those devices so this server is listed as their **Parent server**.
- What step templates can run on this server?  
Tune those step templates so that they can run on this server.
- What external programs on this server can be accessed using an external step?  
Set up the external program and configure a step based on the **RunExternalProgram** step template so it uses that program.

## Installing on AIX servers

You can install an Infoprint ProcessDirector secondary server on an AIX system in your network.

To install Infoprint ProcessDirector on a secondary AIX server:

1. Log in as the root user.
2. Enter `df -k` to verify that the `/opt/IBM` and `/tmp` directories are at least 175 MB in size. If not, increase the directory size.
3. Insert the Infoprint ProcessDirector CD in the CD-ROM drive.
4. Mount the CD, if necessary. For example, enter `mount /cdrom`.
5. For a faster installation, copy **setup\_aiw\_aix.bin** from the `aix` directory on the CD to a temporary directory on your workstation with at least 175 MB (such as `/tmp`) and run the installation from that directory. For example, enter `cp /cdrom/aix/setup_aiw_aix.bin /tmp`.
6. From the temporary directory on your workstation, enter `./setup_aiw_aix.bin` to install the Infoprint ProcessDirector program. You see a welcome window for the Infoprint ProcessDirector installation.

7. Reply to the prompts as the InstallShield wizard steps you through the installation.
8. When you see a window that displays the default user ID (UID) and group ID (GID) values, select the defaults or use the same numeric values you specified for the primary server.
9. Click **Finish** to complete the installation.
10. Remove the Infoprint ProcessDirector CD from the CD-ROM drive.
11. Apply any service updates needed to keep the Infoprint ProcessDirector secondary server level the same as the primary server level. To apply a service update, see “Applying service updates on AIX secondary servers” on page 41.
12. Enter `ps -ef | grep Instance` on the console command line to verify that the Infoprint ProcessDirector server is running. You should see an instance statement such as:
 

```
java com.ibm.aiw.instance.SecondaryInstance hostname
```

 If the server is not running, contact IBM Software Support.

Once your server is running, you must determine how this server is used and change the properties of some objects accordingly. For example:

- What external programs on this server can be accessed using an external step?
  - Set up the external program and configure a step based on the **RunExternalProgram** step template so it uses that program.
- If you have Infoprint Manager installed on this system, do you want to create and manage printers on this server?
  - Create those printers so this server is listed as their **Parent server**.

## Installing on Windows servers

The Infoprint ProcessDirector Windows secondary server runs as a Windows service, with the permissions of the Windows user ID specified during installation. Like all secondary servers, the Windows secondary server uses the NFS protocol to access the exported `/aiw` file system on the primary server. The NFS protocol requires Microsoft Windows Services for UNIX® (SFU) to be installed, primarily for the use of the bundled NFS client.

The tasks included in this section are provided as an example configuration, using the NFS client and the User Name Mapping service provided with SFU. To facilitate the use of the User Name Mapping service, you should configure and run a Network Information Service (NIS) server on your Infoprint ProcessDirector primary system. Be aware that your network environment might require a different configuration than the one described here.

### Configuring the Network Information Service (NIS) server on the primary server

The NIS server provides the Windows User Name Mapping service with a list of user IDs and groups available on this server.

The list of user IDs and groups facilitates the user name mapping process, letting you select the UID and GID you want to map to from a list. The NIS server should be on the same system as the primary server.

Use YaST to configure the NIS server:

1. Click **Network Services** → **NIS Server**.
2. Click **Reconfigure NIS Master Server Setup** and then click **Next**.

3. In the **Master Server Setup** window, type the domain name in the **NIS Domain Name** field and click **Next**. To determine the domain name, on the Linux command line enter `hostname -d`.
4. Accept the defaults (**\_group**, **netid**, **passwd**, **rpc**, and **services**) on the **NIS Server Maps Setup** window and click **Next**.
5. In the **NIS Server Query Hosts Setup** window, accept the defaults of 255.0.0.0 and 0.0.0.0 for the **Netmask** and 127.0.0.0 and 0.0.0.0 for the **Network**.
6. Click **Finish**. The NIS Server is running.

### Installing Windows Services for UNIX (SFU) on Windows

After you install the Windows operating system, you need to install SFU Version 3.5 or later on your Windows system. SFU includes all the facilities needed to mount network file systems, including the NFS client and User Name Mapping Service.

**Note:** Determine the NIS domain name on the Infoprint ProcessDirector primary server before you begin this procedure. You can enter the `hostname -d` command on the primary server to obtain this information.

To install SFU:

1. Download the latest version of Windows Services for UNIX (SFU) from this Web site:  
<http://www.microsoft.com/technet/interopmigration/unix/sfu/default.mspx>.  
 The downloaded version of SFU is a self-extracting executable with a name similar to `SFU35SEL_EN.exe`.
2. Double-click the `.exe` file to unzip the files and begin the installation.
  - a. In the **Customer Information** window, type your customer information and click **Next**.
  - b. In the **License and Support Information** window, read the information. Click **I accept the agreement** and then click **Next**.
3. In the **Installation Options** window, click **Custom Installation** and click **Next**.
4. Under **Authentication tools for NFS**, click **User Name Mapping** and then click **Will be installed on local hard drive**.
5. In the **Security Settings** window, accept the defaults and click **Next**.
6. In the **User Name Mapping** window under the **Configure the User Name Mapping server** subtitle, make sure the **Local User Name Mapping Server** and **Network Information Service (NIS)** are selected, and then click **Next**.
7. In the **User Name Mapping** window under the **Configure local User Name Mapping using NIS** subtitle, type the NIS domain name that you specified previously with "Configuring the Network Information Service (NIS) server on the primary server" on page 22, specify the NIS Server host name, and then click **Next**.
8. Click **Next** until you see the window that shows the **Finish** button, and then click **Finish**.

### Configuring User Name Mapping on Windows

The User Name Mapping service creates an association between Windows and UNIX or Linux user names. This lets users connect to NFS resources without having to log on to UNIX and Linux and Windows systems separately.

The User Name Mapping service also allows control over the UNIX or Linux file permissions that individual Windows users have. See the User Name Mapping section in the documentation provided with SFU for more information.

To configure user name mapping on Windows:

1. Access the **Control Panel** and click **Administrative Tools**.
2. Click **Services for UNIX Administration**.
3. In the left pane of the the **Welcome to Services for UNIX on local computer** window, click **User Name Mapping**.
4. In the **User Name Mapping on Local Computer** window, make sure that **Use Network Information Services (NIS)** is selected.
5. Click the **Maps** tab and clear the **Simple maps** check box.
6. Click **Show User Maps** under **Advanced maps**. If you see an error message when you click **Show User Maps**, you stop and restart the User Name Mapping service by right-clicking **User Name Mapping** in the left navigation pane, then clicking **Stop** and then **Start**.
7. Click **List Windows Users**, which fills in all the user IDs from your Windows system. You might need to scroll down to see the **Advanced maps** section.
8. Make sure the **NIS Domain Name** and **NIS Server Name** fields are filled in. Click **List UNIX Users**, which fills in all the UNIX users on your Linux system.
9. Select the Windows user that you want your secondary server to run as, then select **aiw1** from the UNIX users list, and click **Add** to map the users.
10. On the **User Name Mapping on local computer** window, click **Apply** in the upper right corner.
11. Click **Show Group Maps**. You might need to scroll up or down to see the **Advanced maps** section.
12. Click **List Windows groups**, which fills in all the Windows groups from your Windows system. Select the Windows group that the previous user ID belongs to. You might need to scroll up or down to see the **Advanced maps** section.
13. Make sure the **NIS Domain Name** and **NIS Server Name** fields are filled in. Click **List UNIX groups**, which fills in all the UNIX groups on your Linux system. Select **aiwgrp1**, which is the group that the **aiw1** user is in on the primary server.
14. Click **Add** to map the groups.
15. On the **User Name Mapping on local computer** window, click **Apply** in the upper right corner.
16. Close SFU.

### Testing the connection to the NFS server

Another step in setting up for a Windows secondary server involves verifying the connection to the NFS server.

To test the connection to the NFS server:

1. Click **My Computer**. In the address bar, type *\\hostname of primary server*, such as `\\base.penn.boulder.ibm.com` or an IP address (`\\9.99.183.294`). You see the `\aiw` directory in the right pane.
2. If you can open the **aiw** folder, the connection to the NFS server is successful.
3. If you cannot open the **aiw** folder, see the "Windows secondary server will not connect" troubleshooting topic in the Infoprint ProcessDirector information



center for more information. Click **Help** from the top task bar of the Infoprint ProcessDirector user interface to see the information center.

**Note:** If your environment uses firewalls for security, contact your network administrator to make sure that the firewall is not preventing access to the primary server.

## Installing Infoprint ProcessDirector on Windows secondary servers

After you have completed the prerequisite steps, you can install an Infoprint ProcessDirector secondary server on a Windows system in your network.

To install a Infoprint ProcessDirector secondary server on a Windows server:

1. Log in as an administrator.
2. Insert the Infoprint ProcessDirector CD in the CD-ROM drive.
3. The Infoprint ProcessDirector InstallShield Wizard runs automatically from the CD if the Windows system is configured to autorun CDs.
4. If the installation wizard does not run automatically:
  - a. Change to the drive where you inserted the CD.
  - b. Click `setup.exe`.
5. Reply to the prompts as the InstallShield Wizard steps you through the installation.
6. Click **Finish** to complete the installation.
7. Remove the Infoprint ProcessDirector CD from the CD-ROM drive.
8. Apply any service updates needed to keep the Infoprint ProcessDirector secondary server level the same as the primary server level. To apply a service update, see "Applying service updates on Windows secondary servers" on page 41.
9. To make sure that the Windows secondary server is connected to the primary server on Linux, log in to the Infoprint ProcessDirector user interface and click **Administration** → **System** → **Servers** to verify that the **CStatus** column contains **Connected**.
10. If the Windows secondary server is not connected to the primary server on Linux, see the "Windows secondary server will not connect" troubleshooting topic in the Infoprint ProcessDirector information center for more information. Click **Help** from the top task bar of the Infoprint ProcessDirector user interface to see the information center.

After your server is running, you must determine how this server is used and change the properties of some objects accordingly. For example:

- What external programs on this server can be accessed using an external step?  
Set up the external program and configure a step based on the **RunExternalProgram** step template so it uses that program.

---

## Completing post-installation tasks

After you finish installing Infoprint ProcessDirector, you complete post-installation tasks to verify the installation and to configure Infoprint ProcessDirector.

**Note:** During installation, Infoprint ProcessDirector creates files with a default group ownership set to `aiwgrp1`. Any user who is in the `aiwgrp1` group can access files created by Infoprint ProcessDirector. If you have users with

Linux system user IDs who need to work directly with Infoprint ProcessDirector files or submit files to hot folders, you must add their user IDs to the aiwgrp1 group. Be sure to use the aiwgrp1 group name as an additional group for your users, not as their default group.

## Verifying the installation

If you have just finished installing Infoprint ProcessDirector and want to test the system, do the steps in this procedure to define a printer, submit a test job, and then print the job:

1. Log in to the primary Linux server as the Infoprint ProcessDirector user. The default user ID is aiw1 and the default password is aiwpass1.
2. Access the user interface at **http://hostname:15080/aiw**. The host name of the primary Linux server is *hostname*.
3. Type an administrator user name and password and then click **Log in** to log in to the user interface. The default user name is aiw.
4. On the Main page, click the **Administration** tab.
5. From the shortcuts list, click **Add a Printer Device**.
6. Specify the printer name, TCP/IP address or host name, TCP/IP port number, and language for the printer you want to send a test job to.
7. Click **OK**.
8. In the left pane, click **Printers**.
9. Select the printer you just created and then click **Enable**.
10. In the left pane, click **Input Devices**.
11. Select the HotFolderLineData input device and then click **Connect**.
12. Select the HotFolderLineData input device and then click **Enable**.
13. On the Linux command line, enter this command to copy a test file into the hot folder that the HotFolderLineData input device monitors:  

```
cp /aiw/aiw1/testfiles/TestLineData.txt /aiw/aiw1/System/hf/LineData
```
14. After a few minutes, refresh the Infoprint ProcessDirector user interface. You should see a job in the jobs table on the Main page.
15. Pick up your test job at the printer.

This verifies that Infoprint ProcessDirector is installed correctly.

## Configuring Infoprint ProcessDirector

You use the user interface to complete configuration tasks for Infoprint ProcessDirector, such as setting up job processing, defining input devices for job submission, defining your printer hardware to Infoprint ProcessDirector, and adding users. The Infoprint ProcessDirector information center describes these configuration tasks.

To access the Infoprint ProcessDirector information center to learn about configuration tasks:

1. From the Web browser on a Linux or Windows workstation, enter **http://hostname:15080/aiw**. The host name of the primary Linux server is *hostname*.
2. Click **Help** from the top task bar. You see the Infoprint ProcessDirector information center.
3. From Contents in the left pane, click **IBM Infoprint ProcessDirector** and then click **Configuring**. You see a list of configuration tasks in the right pane.

4. Select the configuration tasks that apply to your installation.



---

## Chapter 4. Starting, stopping, and uninstalling Infoprint ProcessDirector

This section explains how to start and stop Infoprint ProcessDirector servers. It also explains how to uninstall Infoprint ProcessDirector.

---

### Starting Infoprint ProcessDirector servers on Linux

When they are installed, Infoprint ProcessDirector primary and secondary servers start automatically when the Linux systems on which they are installed start. However, you might need to start the primary server or a secondary server without affecting the actual Linux hardware system.

To start Infoprint ProcessDirector servers on a Linux system:

1. Log in to the Linux system as the Infoprint ProcessDirector user (**aiw1**).
2. Access the command line.
3. Enter this command:

```
startaiw
```

For the primary server, Infoprint ProcessDirector system starts DB2, the Web server and user interface program, and the primary server. For a secondary server, Infoprint ProcessDirector connects to the primary server and starts the secondary server.

### Deactivating the autostart script on Linux

If you do not want the Infoprint ProcessDirector primary or secondary servers to start automatically when you restart the Linux system on which they are installed, you can deactivate the autostart script. You remove two symbolic links from the script to deactivate it. The Infoprint ProcessDirector system can be running when you deactivate the script.

To deactivate the autostart script:

1. Log in as the Linux **root** user.
2. Access the command line.
3. On the command line, enter: `cd /etc/init.d/rc5.d`
4. Enter: `rm S15aiwserv`
5. Enter: `cd /etc/init.d/rc3.d`
6. Enter: `rm S15aiwserv`

### Activating the autostart script on Linux

If you previously deactivated the autostart script on the Linux system, you can reactivate the it. Reactivating the autostart script causes the Infoprint ProcessDirector primary server or secondary server to start automatically when the Linux system starts. You add two symbolic links to reactivate the script.

**Note:** When you install Infoprint ProcessDirector, the default is that it activates the autostart script. If you have not deactivated it, you do not have to do this procedure.

To activate the autostart script:

1. Log in as the Linux **root** user.
2. Access the command line.
3. Enter: `ln -s /etc/init.d/aiwserver /etc/init.d/rc5.d/S15aiwserver`
4. Enter: `ln -s /etc/init.d/aiwserver /etc/init.d/rc3.d/S15aiwserver`

---

## Starting secondary servers on AIX

Infoprint ProcessDirector AIX secondary servers are configured to start automatically when the AIX system on which they are installed start. However, you might need to start the secondary server without affecting the actual AIX hardware system.

To start an Infoprint ProcessDirector secondary server on an AIX system:

1. Log in to the AIX system as the Infoprint ProcessDirector user (**aiw1**).
2. Access the command line.
3. Enter this command:

```
startaiw
```

Infoprint ProcessDirector connects to the primary server and starts the secondary server.

---

## Starting the Windows secondary server service

When a Windows secondary server is installed, it is configured to start running automatically as a Windows service when the Windows system starts. If you stopped the secondary server or disabled the automatic start, you can start it manually.

To manually start the Windows secondary server service:

1. Log in to the Windows system as an administrator.
2. From the Windows Control Panel, click **Administrative Tools** → **Services**.
3. Right-click **Infoprint ProcessDirector Secondary Server** and then click **Start**.

## Disabling automatic start of the Windows secondary server service

You can disable the automatic start function of the Windows secondary service by configuring the Windows system.

To disable the automatic start of a Windows secondary server service:

1. Log in to the Windows system as an administrator.
2. Open the **Control Panel**.
3. Click **Administrative Tools** → **Services**.
4. Locate the Infoprint ProcessDirector Secondary Server entry in the list. Right click it and click **Properties**.
5. On the **General** tab, set the **Startup type** to **Manual**.
6. Click **OK**.

The Windows secondary server no longer starts automatically when the Windows system starts. You can manually start the secondary server through the Windows interface.

## Automatically starting the Windows secondary server service

If you previously disabled the automatic start of the Windows secondary server service on the Windows system, you can enable the automatic start again. Enabling the automatic start of the service causes the Infoprint ProcessDirector secondary server to automatically start when the Windows system starts.

**Note:** When you install Infoprint ProcessDirector, it enables the automatic start of the service. If you have not disabled the service, you do not have to do this procedure.

To automatically start the Windows secondary server service:

1. Log in to the Windows system as an administrator.
2. From the Windows Control Panel, click **Administrative Tools** → **Services**.
3. Right-click **Infoprint ProcessDirector Secondary Server** and then click **Properties**.
4. On the **General** tab, set the **Startup type** to **Automatic**.
5. Click **OK**.

---

## Stopping Infoprint ProcessDirector on Linux

When you stop the Infoprint ProcessDirector primary server or a secondary server, you can stop the system with or without waiting for job-processing steps to complete.

To stop the system immediately without waiting for steps to complete, use the `stopaiw` command. Any steps that were in a processing state will move to an error state when you restart the system. To stop the system after the currently processing steps are complete, use the `stopaiw -q` command.

To minimize the impact of shutting down the system on processes that are currently running, you can disable the input devices associated with the server before you stop it.

To stop the primary and secondary servers on a Linux system:

1. Log in to the Linux system as the Infoprint ProcessDirector user (**aiw1**).
2. Access the command line.
3. If the Linux system has only the primary server or only a single secondary server installed, enter one of these commands to stop the primary or secondary server:

```
stopaiw  
or  
stopaiw -q
```

For the primary server, Infoprint ProcessDirector shuts down DB2, the Web server and user interface program, and the primary server. For a secondary server, Infoprint ProcessDirector disconnects from the primary server and stops the secondary server.

---

## Stopping secondary servers on AIX

When you stop an Infoprint ProcessDirector secondary server running on AIX, you can stop the server with or without waiting for job-processing steps to complete.

To stop the AIX secondary server immediately without waiting for steps to complete, use the `stopaiw` command. Any steps that were in a processing state will move to an error state when you restart the system. To stop the secondary server after the currently processing steps are complete, use the `stopaiw -q` command.

To stop a secondary server on an AIX system:

1. Log in to the AIX system as the Infoprint ProcessDirector user (**aiw1**).
2. Access the command line.
3. If the AIX system has only a single secondary server installed, enter one of these commands to stop the secondary server:

```
stopaiw  
or  
stopaiw -q
```

Infoprint ProcessDirector disconnects the secondary server from the primary server and stops the secondary server.

---

## Stopping the Windows secondary server service

You can stop the Windows secondary server service through the Windows interface. Stopping the service prevents Infoprint ProcessDirector from accessing any external programs on the Windows system through external steps in job types.

To stop the Windows secondary server service:

1. Log in to the Windows system as an administrator.
2. From the Windows Control Panel, click **Administrative Tools** → **Services**.
3. Right-click **Infoprint ProcessDirector Secondary Server** and then click **Stop**.

---

## Uninstalling Infoprint ProcessDirector

You might need to uninstall Infoprint ProcessDirector (for example, if you need to restore to a previous level). This section explains how to uninstall Infoprint ProcessDirector from the primary and secondary servers. Keep in mind that your primary and secondary servers must be at the same Infoprint ProcessDirector level. Therefore, if you uninstall Infoprint ProcessDirector from your primary server and install a previous level, you must also uninstall Infoprint ProcessDirector from all your secondary servers and install the same level.

**Note:** The instructions in this section describe uninstalling with the InstallShield Wizard graphical display. If you cannot run the InstallShield Wizard in graphical mode, use `-console` at the end of an uninstallation command to uninstall with a text-based program; for example:

```
./uninstaller.bin -console
```

### Uninstalling from the primary server

This procedure explains how to uninstall, in the correct order, the Infoprint ProcessDirector programs from the primary server. You must remove the base



Infoprint ProcessDirector program first, the PSF program or the user interface program next, and the DB2 program last. Separate InstallShield Wizards are used to uninstall each program.

To uninstall Infoprint ProcessDirector:

1. Log in as the root user.
2. Uninstall the base Infoprint ProcessDirector program:
  - a. Enter these commands:
    - 1) `cd /opt/IBM/aiw/V1.0/_uninst/aiw`
    - 2) `./uninstaller.bin`You see a welcome window.
  - b. Reply to the prompts as the InstallShield Wizard steps you through the uninstallation. You see numerous processing messages that give the status of the uninstallation. When the uninstallation is complete, you see either a message that the uninstallation was successful or a message that there were errors and the location of the error log file.
  - c. Click **Finish**.
3. Uninstall the PSF program:
  - a. Enter these commands:
    - 1) `cd /opt/IBM/aiw/V1.0/_uninst/aiw_ipsf`
    - 2) `./uninstaller.bin`You see a welcome window.
  - b. Reply to the prompts as the InstallShield Wizard steps you through the uninstallation. You see numerous processing messages that give the status of the uninstallation. When the uninstallation is complete, you see either a message that the uninstallation was successful or a message that there were errors and the location of the error log file.
  - c. Click **Finish**.
4. Uninstall the user interface program:
  - a. Enter these commands:
    - 1) `cd /opt/IBM/aiw/V1.0/_uninst/aiw_ws/`
    - 2) `./uninstaller.bin`You see a welcome window.
  - b. Reply to the prompts as the InstallShield Wizard steps you through the uninstallation. You see numerous processing messages that give the status of the uninstallation. When the uninstallation is complete, you see either a message that the uninstallation was successful or a message that there were errors and the location of the error log file.
  - c. Click **Finish**.
5. Uninstall the DB2 program:
  - a. Enter these commands:
    - 1) `cd /opt/IBM/db2/db2aiw`
    - 2) `./uninstalldb2.sh`

The uninstallation program first runs from the command line. Be patient because this portion of the uninstallation might take 10-15 minutes before it goes to the InstallShield Wizard portion.

**Note:** The InstallShield Wizard is displayed in text mode, not graphical mode.

- b. Reply to the prompts as the InstallShield Wizard steps you through the uninstallation. You see numerous processing messages that give the status of the uninstallation. When the uninstallation is complete, you see either a message that the uninstallation was successful or a message that there were errors and the location of the error log file.
  - c. Click **Finish**.
6. To completely remove all files installed by Infoprint ProcessDirector, remove these working directories and their subdirectories:

```
/aiw  
/var/psf
```

## Uninstalling the Linux or AIX secondary servers

This procedure explains how to uninstall, in the correct order, the Infoprint ProcessDirector programs from the Linux or AIX secondary servers. You must remove the base Infoprint ProcessDirector program first and, for Linux servers, the PSF program next. Separate InstallShield Wizards are used to uninstall each program.

To uninstall Infoprint ProcessDirector:

1. Log in as the root user.
2. Uninstall the base Infoprint ProcessDirector program:
  - a. Enter these commands:
    - 1) `cd /opt/IBM/aiw/V1.0/_uninst/aiw` to uninstall on Linux servers or `cd /opt/IBM/aiw/V1.0/_uninst/aiw_aix` to uninstall on AIX servers.
    - 2) `./uninstaller.bin`

You see a welcome window.
  - b. Reply to the prompts as the InstallShield Wizard steps you through the uninstallation. You see processing messages that give the status of the uninstallation. When the uninstallation is complete, you see either a message that the uninstallation was successful or a message that there were errors and the location of the error log file.
  - c. Click **Finish**.
3. Uninstall the PSF program on Linux servers:
  - a. Enter these commands:
    - 1) `cd /opt/IBM/aiw/V1.0/_uninst/aiw_ipsf`
    - 2) `./uninstaller.bin`

You see a welcome window.
  - b. Reply to the prompts as the InstallShield Wizard steps you through the uninstallation. You see processing messages that give the status of the uninstallation. When the uninstallation is complete, you see either a message that the uninstallation was successful or a message that there were errors and the location of the error log file.
  - c. Click **Finish**.
  - d. To completely remove all files installed by Infoprint ProcessDirector, remove the `/var/psf` working directory and its subdirectories.

## Uninstalling the secondary server on Windows

To uninstall the secondary server on Windows:

1. Log in as the administrator.
2. From the Windows Control Panel, click **Add or Remove Programs**.
3. Scroll down the list until you find **Infoprint ProcessDirector secondary server on Windows** and select it.
4. Follow all instructions as directed.
5. Click **Finish**.



---

## Chapter 5. Backing up data, applying service, and adding features

If you already have Infoprint ProcessDirector installed on your system and you want to apply a service update or add feature software, you can do so without uninstalling Infoprint ProcessDirector. The installation update program migrates your Infoprint ProcessDirector objects, such as printers and input devices, to the updated level.

**Keep in mind:** Your primary and secondary servers must be at the same Infoprint ProcessDirector level. Therefore, if you install a service update on your primary server, you must also install the service update on all your secondary servers.

Before installing any service updates or adding feature software, you must stop the primary server and all secondary servers. The activation step restarts the primary server. Apply service updates or features as necessary on the secondary servers and then restart the secondary servers by entering `startaiw` on the secondary system. For more information, see Chapter 4, “Starting, stopping, and uninstalling Infoprint ProcessDirector,” on page 29.

IBM recommends that you back up your system data *before* you install an update and periodically for failure recovery. Then, if you need to reinstall Infoprint ProcessDirector (for example, to remove an update you installed), you can run a restore program to recover your data.

This section explains how to back up and restore data, how to apply a service update, and how to add feature software to Infoprint ProcessDirector.

---

### Backing up and restoring Infoprint ProcessDirector data

To prevent loss of data from a system failure or to recover data (for example, if you want to return your system to a previously installed level with all the settings and objects restored), Infoprint ProcessDirector provides backup and restore programs.

The backup program saves this data:

- System data, such as job types, step templates, users, input devices, and printers stored in the database
- Control files, such as those used for header sheets
- User data, such as job files in the spool directory

Then, if you need to reinstall Infoprint ProcessDirector, you can run a restore program to recover your data. System data and control files are always backed up and restored; as an option, you can back up and restore user data.

#### Backing up data

You can use a backup script to archive a copy of your Infoprint ProcessDirector system configuration.

To back up Infoprint ProcessDirector data:

1. Stop all secondary servers. See “Stopping Infoprint ProcessDirector on Linux” on page 31, “Stopping secondary servers on AIX” on page 32, and “Stopping the Windows secondary server service” on page 32.
2. On the primary Linux server, log in as the Infoprint ProcessDirector user. The default user ID is aiw1 and the default password is aiwpass1.
3. Enter aiwbackup.pl with any of these optional options:

**-f filename**

Back up data to a directory and file name other than the default /tmp/aiw\_backup\_data.[timestamp].tar.gz.

**-r** Jobs and input files in addition to system data and control files are saved by default. A backup with the -r option requests that jobs and input files are not saved.

**-h or -?**

Display help for the aiwbackup.pl command.

You see a message that all servers will be stopped, whether jobs and input files will be backed up, and the location of the backed up files.

4. Enter Y to proceed with the backup. When the backup is complete, you see a message that the backup was successful.
5. To continue using this level of Infoprint ProcessDirector, see “Starting Infoprint ProcessDirector servers on Linux” on page 29. To update Infoprint ProcessDirector to a new level, see “Applying service updates and adding feature software on the Linux primary server” on page 39.

## Restoring data

You can use an Infoprint ProcessDirector restore script to return your system to the configuration that you stored in a backup archive.

To restore Infoprint ProcessDirector to a previous level, including any service updates, you must back up your data *before* you install an update of Infoprint ProcessDirector.

Keep these considerations in mind when restoring an Infoprint ProcessDirector level:

- All existing jobs and input files from the current Infoprint ProcessDirector level are removed when you restore to a previous level.
- If you used a new level of Infoprint ProcessDirector and then restored to a previous level, or if you installed and used the previous level before you restored the backup files, any changes you made to system data, control files, or user data is lost. Therefore, if you need to restore your backup files, do it as soon as possible to reduce the amount of lost data.

To restore Infoprint ProcessDirector data:

1. Stop all primary and secondary servers. See “Stopping Infoprint ProcessDirector on Linux” on page 31, “Stopping secondary servers on AIX” on page 32, and “Stopping the Windows secondary server service” on page 32.
2. Uninstall Infoprint ProcessDirector on all servers (see “Uninstalling Infoprint ProcessDirector” on page 32).
3. On the primary and secondary servers, install the same level of Infoprint ProcessDirector as the backup you previously created (see Chapter 3, “Installing Infoprint ProcessDirector,” on page 17).

4. On the primary Linux server, log in as the Infoprint ProcessDirector user. The default user ID is aiw1 and the default password is aiwpass1.
5. Enter aiwrestore.pl with any of these optional options:

**-f filename**  
Restore data from a directory and file name other than the default /tmp/aiw\_backup\_data.[timestamp].tar.gz.

**-h or -?**  
Display help for the aiwrestore.pl command.

You see a message that all servers will be stopped and the location the files are restored from.

6. Enter Y to proceed with the restore.
7. When you see a database warning message, enter Y. When the restore is complete, you see a message that the restore was successful.
8. Start the servers to use the restored level of Infoprint ProcessDirector. See “Starting Infoprint ProcessDirector servers on Linux” on page 29.

---

## Applying service updates and adding feature software on the Linux primary server

You or your service representative might want to apply a service update for Infoprint ProcessDirector to address issues or add new functions. If you receive a service update or purchase an additional feature for Infoprint ProcessDirector, you can install them without uninstalling the system.

Before installing a service update of Infoprint ProcessDirector, you should back up your data in case you need to reinstall the level of Infoprint ProcessDirector you removed with the update. See “Backing up data” on page 37.

To update or add feature software to Infoprint ProcessDirector:

1. Delete as many jobs as possible from the system to minimize time and storage requirements.
2. Stop all primary and secondary servers. See “Stopping Infoprint ProcessDirector on Linux” on page 31, “Stopping secondary servers on AIX” on page 32, and “Stopping the Windows secondary server service” on page 32.
3. Log in as the root user.
4. Enter `df -k` to verify that the /opt/IBM and /tmp directories are at least 175 MB in size. If not, increase the directory size.
5. Insert the CD for the service update or feature software in the CD-ROM drive.
6. Mount the CD, if necessary. For example, enter `mount /media/cdrom` or `mount /media/cdrecorder`.
7. Open a console window and change to the CD directory. For example, enter `cd /media/cdrecorder`.
8. From the Linux console command line, enter `./setup` to start the installation.
9. Select the appropriate language for the wizard to use and then click **OK**. You see a welcome window for the InstallShield Wizard.
10. Reply to any prompts as the InstallShield Wizard steps you through the installation. On the primary server, Infoprint ProcessDirector runs a migration script at the beginning of the installation. The migration script uses a list of configuration files that you might have customized for your installation and

copies all files in the list to the migration directory, /tmp/aigsaw. The installation program then installs the updated configuration files. After you have completed the installation process, you can compare the modified files in /tmp/aigsaw with the updated versions and merge your customized changes into the updated files.

During the installation on the primary server, the contents of the Infoprint ProcessDirector database are copied to migration directories to preserve the data, and then the objects, such as users, printers, input devices, and job types, are restored in the update. This process might take a long time.

11. When you see a message that all your files have been copied to your system, click **Activate later** if you have additional software or a service update to install. Otherwise, click **Activate now**. The final window displays the URL for accessing the user interface in the format:

```
http://hostname:15080/aigw
```

The host name of the primary Linux server is *hostname*.

12. Click **Finish** to complete the installation.
13. Remove the CD from the CD-ROM drive.
14. If you have additional feature software or a service update to install, insert the CD in the CD-ROM drive and repeat steps 8 through 13.
15. The primary server restarts as part of the activation, but you might need to restart your secondary servers. See “Starting secondary servers on AIX” on page 30 and “Starting the Windows secondary server service” on page 30 for information about restarting the secondary servers.
16. See “Completing post-installation tasks” on page 25.

After you run the update for several days and are satisfied with its operation, you can delete the migration directories that contain copies of the database contents. Enter these commands:

1. `cd /opt/IBM/aigw/V1.0/bin`
2. `clean_migrate_files.pl`

---

## Applying service updates on Linux secondary servers

You or your service representative might want to apply a service update for Infoprint ProcessDirector Linux secondary servers to address issues or add new functions. If you install a service update on your primary server, you must also install it on your secondary Linux servers.

The Linux secondary server should have been stopped when you applied the update on the primary server.

To apply a service update to an Infoprint ProcessDirector Linux secondary server:

1. Log in as the root user.
2. Enter `df -k` to verify that the /opt/IBM and /tmp directories are at least 175 MB in size. If not, increase the directory size.
3. Insert the CD for the service update or feature software in the CD-ROM drive.
4. Mount the CD, if necessary. For example, enter `mount /media/cdrom` or `mount /media/cdrecorder`.
5. Open a console window and change to the CD directory. For example, enter `cd /media/cdrecorder`.
6. From the Linux console command line, enter `./setup` to start the installation.



7. Select the appropriate language for the wizard to use and then click **OK**. You see a welcome window for the InstallShield Wizard.
8. Reply to any prompts as the InstallShield Wizard steps you through the installation.
9. When you see a message that all your files have been copied to your system, click **Activate now**.
10. Click **Finish** to complete the installation.
11. Remove the CD from the CD-ROM drive.
12. Restart your secondary servers. See “Starting Infoprint ProcessDirector servers on Linux” on page 29 for information.
13. See “Completing post-installation tasks” on page 25.

---

## Applying service updates on AIX secondary servers

You or your service representative might want to apply a service update for Infoprint ProcessDirector AIX secondary servers to address issues or add new functions. If you receive a service update for your AIX secondary servers, you can install them without uninstalling the system.

To apply a service update to an Infoprint ProcessDirector AIX secondary server:

1. Log in as the root user.
2. Enter `df -k` to verify that the `/opt/IBM` and `/tmp` directories are at least 175 MB in size. If not, increase the directory size.
3. Insert the CD for the service update in the CD-ROM drive.
4. Mount the CD, if necessary. For example, enter `mount /cdrom`.
5. For a faster installation, copy **setup\_aiw\_aix.bin** from the `/aix` directory on the CD to a temporary directory on your workstation with at least 175 MB (such as `/tmp`) and run the installation from that directory. For example, enter `cp /cdrom/aix/setup_aiw_aix.bin /tmp`.
6. From the temporary directory on your workstation, enter `./setup_aiw_aix.bin` to install the Infoprint ProcessDirector program. You see a welcome window for the Infoprint ProcessDirector installation.
7. Reply to the prompts as the InstallShield Wizard steps you through the installation.
8. Click **Finish** to complete the installation.
9. Remove the Infoprint ProcessDirector CD from the CD-ROM drive.
10. Enter `ps -ef | grep Instance` on the console command line to verify that the Infoprint ProcessDirector server is running. You should see an instance statement such as:
 

```
java com.ibm.aiw.instance.SecondaryInstance hostname
```

 If the server is not running, contact IBM Software Support.

---

## Applying service updates on Windows secondary servers

You or your service representative might want to apply a service update for Infoprint ProcessDirector Windows secondary servers to address issues or add new functions. If you receive a service update for your Windows secondary servers, you can install them without uninstalling the system.

To apply a service update to an Infoprint ProcessDirector Windows secondary server:

- |
  - |
  - |
  - |
  - |
1. Insert the CD for the service update in the CD-ROM drive. The InstallShield Wizard starts automatically.
  2. Follow the instructions on the installation screens to install the update. The destination directory and other necessary settings are obtained automatically based on your initial installation.

---

## Chapter 6. Installation planning checklist

The checklist contains tasks that can help you plan for your Infoprint ProcessDirector installation.

Table 6. Installation planning checklist. Check each item as you complete the task.

	Task	Notes
	Determine your system configuration (see “System configurations” on page 4 for an example of a configuration). Keep in mind your requirements for file sharing (such as Shark, FAST, RAID, or NFS) and a failure recovery system. If you need help setting up a failure recovery system, contact your IBM Printing Systems representative to discuss a custom solution.	
	Estimate your current and future storage and backup needs. Consider production volumes, print resource management, and failure recovery.	
	Make sure that you have adequate network capacity.	
	Determine what printers you want to include in the Infoprint ProcessDirector workflow. See “Supported printers” on page 4 for the printers that Infoprint ProcessDirector supports. When you define printers to Infoprint ProcessDirector, you need this information: <ul data-bbox="272 1255 625 1354" style="list-style-type: none"><li>• Printer name</li><li>• TCP/IP port number</li><li>• TCP/IP address or host name</li></ul> You should also decide on the language for the printer driver component to use when it returns messages to Infoprint ProcessDirector.	
	Obtain the required hardware for your configuration that meets your storage and backup requirements (see “Hardware requirements” on page 7).	
	Decide whether to set up your file system as partitions or as mounted file systems from other storage units. See “Determining your file system setup” on page 8.	

Table 6. Installation planning checklist (continued). Check each item as you complete the task.

	Task	Notes
	<p>Determine whether to use the default system group ID (GID) for Infoprint ProcessDirector or your own numeric value. Keep in mind that the GID must be the same across all servers; therefore, if you choose your own, make sure the value is large enough to avoid conflicts.</p> <p>The default system GID value is 32458, which has a name of aiwgrp1.</p>	
	<p>Determine whether to use the default system user ID (UID) for Infoprint ProcessDirector or your own numeric value. Keep in mind that the UID must be the same across all servers; therefore, if you choose your own, make sure the value is large enough to avoid conflicts.</p> <p>The default system UID value is 32457, which has a name of aiw1 and a password of aiwpass1.</p>	
	<p>Establish a host name and IP address for each server. Infoprint ProcessDirector supports IPv4 addresses.</p> <p><b>Note:</b> Be sure to choose a host name you want to keep. If you change the host name after Infoprint ProcessDirector is installed, you might have to uninstall and then install Infoprint ProcessDirector again.</p>	
	<p>Determine what password to use when you log in to Infoprint ProcessDirector with the aiw user name. The first time you log in to Infoprint ProcessDirector with the default user name of aiw and the default password of aiw, you are prompted to change the password. The password can be 8 to 32 alphanumeric characters.</p>	
	<p>Determine how many user IDs you want to create and what authority you want each ID to have, such as monitor, operator, supervisor, or administrator.</p>	
	<p>Consider what job submission method you are going to use to send jobs to Infoprint ProcessDirector. You can use Download for z/OS, AFP Download Plus, or copy or ftp files into hot folders. The job submission method you use depends on the system you are sending the jobs from. For more information, see "Job submission" on page 13.</p>	
	<p>Determine what resources must be available for Infoprint ProcessDirector to use (such as standard and non-standard AFP fonts). Then, consider how you want to share your AFP resources so they are available to Infoprint ProcessDirector (for example, NFS or Samba). Also, keep in mind that you must do post-installation configuration so Infoprint ProcessDirector can use the resources (such as updating the font mapping files for the file viewer). See the Infoprint ProcessDirector information center for information about AFP resource directories.</p>	

Table 6. Installation planning checklist (continued). Check each item as you complete the task.

	Task	Notes
	Install the required software for your configuration (see “Installing required software” on page 9).	
	Install any optional software, such as Download for z/OS, AFP Download Plus, or Infoprint Transform Manager (see “Planning for optional software” on page 13).	
	<p>Change the language for the server, if required:</p> <p><b>Linux</b> In YaST:</p> <ul style="list-style-type: none"> <li>• Click <b>System</b> -&gt; <b>Choose Language</b>.</li> <li>• Click <b>System</b> -&gt; <b>Select Keyboard Layout</b>.</li> </ul> <p>In the KDE Control Center, click <b>Regional &amp; Accessibility</b> -&gt; <b>Country/Region &amp; Language</b>.</p> <p><b>AIX</b> With SMIT, select <b>System Environments</b> -&gt; <b>Manage Language Environment</b>.</p> <p><b>Windows</b> Click <b>Control Panel</b> -&gt; <b>Regional and Language Options</b>.</p>	



---

## Chapter 7. Accessibility

Accessibility features help a user who has a physical disability, such as restricted mobility or limited vision, use software products successfully. The major accessibility features in Infoprint ProcessDirector let users:

- Use assistive technologies such as screen-readers and screen magnifier software.
- Operate specific or equivalent features using only the keyboard.
- Customize display attributes such as color, contrast, and font size.

---

### Using assistive technologies

Assistive technology products, such as screen-readers, function with the user interfaces found in Infoprint ProcessDirector.

To enable assistive technology support in the InstallShield Wizard, specify the console at the end of the setup command. For example, enter `./setup -console` to enable assistive technology on Linux servers, or on AIX servers enter `./setup_aiw_aix.bin -console`.

Assistive technology runs with the text-based installation program instead of the graphical display. Consult the assistive technology documentation for specific information when using it to access Infoprint ProcessDirector.

---

### Keyboard navigation of the user interface

The Infoprint ProcessDirector user interface complies with the accessibility guidelines for HTML. Users can use keyboard shortcuts or function keys (PF keys) in the Web browser to access the Infoprint ProcessDirector user interface. For example, Tab lets you move forward through the items on a page, the Address bar, and the Links bar. See your browser documentation for keyboard shortcuts and default settings for the PF keys and for explanations about how to modify their functions.

#### Infoprint ProcessDirector viewer shortcut keys

When the file viewer is displayed, you can use these shortcut keys:

*Table 7. Viewer shortcut keys*

Description	Alt + key
Go to first tag value	1 (number one)
Go to previous tag value	u
Go to next tag value	d
Go to last tag value	l (small-letter L)
Display first page with selected tag value	j
Find next	n
Find previous	p
Cancel	x
Find string	i
Search overlays and page segments	o

Table 7. Viewer shortcut keys (continued)

Description	Alt + key
Rotate clockwise	r
Rotate counter clockwise	c
Yes on a message box	y
No on a message box	z



---

## Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10594-1785  
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106, Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:**

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation  
Department 11PA, Building 002S  
P.O. Box 1900  
Boulder, CO 80301  
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurement may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

For online versions of this book, we authorize you to:

- Copy, modify, and print the documentation contained on the media, for use within your enterprise, provided you reproduce the copyright notice, all warning statements, and other required statements on each copy or partial copy.
- Transfer the original unaltered copy of the documentation when you transfer the related IBM product (which may be either machines you own, or programs, if the program's license terms permit a transfer). You must, at the same time, destroy all other copies of the documentation.

You are responsible for payment of any taxes, including personal property taxes, resulting from this authorization.

Your failure to comply with the terms above terminates this authorization. Upon termination, you must destroy your machine readable documentation.

---

## Trademarks

These terms are trademarks of International Business Machines Corporation in the United States, other countries, or both:

- Advanced Function Presentation
- AFP
- AIX
- DB2
- eServer
- IBM
- Infoprint
- Mixed Object Document Content Architecture
- POWER
- Print Services Facility
- pSeries
- xSeries
- XT
- z/OS

Adobe, Acrobat, Adobe PDF, PostScript, and all Adobe-based trademarks are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, other countries, or both.

Java and all Java-based trademarks are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, or service names may be trademarks or service marks of others.



---

## Glossary

This glossary defines technical terms and abbreviations used in Infoprint ProcessDirector documentation. If you do not find the term you are looking for, see *IBM Terminology* at:

<http://www.ibm.com/ibm/terminology>

Definitions reprinted from the *American National Dictionary for Information Processing Systems* are identified by the symbol (A) following the definition.

Definitions reprinted from a published section of the International Organization for Standardization (ISO) *Vocabulary—Information Processing* or from a published section of *Vocabulary—Office Machines* developed by Subcommittee 1, Joint Technical Committee 1, of the International Organization for Standardization and the International Electrotechnical Committee (ISO/IEC JTC1/SC1) are identified by the symbol (I) following the definition. Because many ISO definitions are also reproduced in the *American National Dictionary for Information Processing Systems*, ISO definitions can also be identified by the symbol (A).

These cross-references are used in this glossary:

- **See.** Refers to multiple-word terms in which this term appears.
- **See also.** Refers to related terms that have similar, but not synonymous, meanings.

### A

**access control.** In computer security, the methods and facilities used to ensure that a computer system and the data, system software, and application programs stored in it can be accessed only by authorized users in authorized ways.

**Advanced Function Presentation (AFP).** A set of licensed programs, together with user applications, that use the all-points-addressable concept to print data on a wide variety of printers or display data on a variety of display devices. AFP also includes creating, formatting, archiving, retrieving, viewing, and distributing information.

**AFP.** See *Advanced Function Presentation*.

**AIX.** Advanced Interactive Executive operating system. A UNIX operating system developed by IBM

that is runs on POWER™ microprocessor-based hardware such as servers, workstations, and blades.

### C

**client.** In a distributed file system environment, a system that is dependent on a server to provide it with programs or access to programs.

**client/server.** In communications, the model of interaction in distributed data processing in which a program at one site sends a request to a program at another site and awaits a response. The requesting program is called a client; the answering program is called a server.

**command.** A request from a terminal or a specification in a batch-processing print file for the performance of an operation or the running of a particular program.

**compatibility fonts.** A group of AFP fonts that emulate the uniformly spaced and fixed-pitch fonts used with line printers. Compatibility fonts include 240-pel and 300-pel fonts.

### F

**file.** (1) A collection of related data that is stored and retrieved by an assigned name. (2) Linear data that can be opened, written, read, and closed. A file can also contain information about the file, such as authorization information. The name used to obtain a file includes the directories in the path to the file.

**File Transfer Protocol (FTP).** In the Internet suite of protocols, an application layer protocol that uses TCP and Telnet services to transfer bulk-data files between machines or hosts.

### G

**GIF.** Graphics interchange format for images.

### H

**host name.** (1) The network name for a print server or transform server. The host name is the fully-qualified domain name or a specific subname of a fully-qualified domain name. For example, if `printserver1.boulder.ibm.com` is the fully-qualified domain name, either `printserver1.boulder.ibm.com` or `printserver1` can be the host name. (2) See also *IP address*.

**hot folder.** A directory that receives input files that are submitted to Infoprint ProcessDirector.

## I

**Infoprint.** A solution of software and hardware products that can supplement or replace the offset presses and copiers in print shops with high-quality, non-impact, black and white or process color printers. Infoprint takes documents from creation to the final product.

**Infoprint Manager for AIX.** A software component of IBM Infoprint. IBM Infoprint Manager for AIX is a print server that handles the scheduling, archiving, retrieving, and assembly of a print job and its related resource files. It also tracks the finishing and packaging of the printed product.

**IP address.** (1) In the Internet suite of protocols, the 32-bit address of a print server or transform server, expressed in dotted decimal notation. For example: 9.99.9.143. (2) See also *host name*.

## J

**JPEG.** Joint Photographic Experts Group image format.

## L

**Linux.** An open source implementation of the UNIX system.

## M

**mount.** To make a file system accessible.

## N

**network.** A collection of data processing products that are connected by communication lines for information exchange between locations.

## O

**OpenType font.** An extension of the TrueType font format that adds support for PostScript outlines and more support for international character sets and advanced typographic control.

**outline font.** A font whose graphic character shapes are defined by mathematical equations rather than by raster patterns.

## P

**PDF.** See *Portable Document Format*.

**port.** (1) A part of the system unit or remote controller to which cables for external devices (display stations, terminals, or printers) are attached. The port is an access point for data entry or exit. (2) A specific communications endpoint within a host. A port is identified by a port number.

**Portable Document Format (PDF).** A universal file format that preserves the fonts, images, graphics, and layout of any source document so it can be viewed and printed on a variety of platforms.

**PostScript (PS).** A page description language with graphics capabilities that was developed by Adobe Systems, Incorporated.

**print server.** A computer to which one or more printers are connected or the process that manages those printers.

**processor.** In a computer, a functional unit that interprets and executes instructions. (I) (A)

**PS.** See *PostScript*.

## R

**raster font.** A font in which the characters are defined directly by the raster bitmap.

**root.** The user name for the system user with the most authority.

## S

**server.** (1) On a network, the computer that contains the data or provides the facilities to be accessed by other computers on the network. (2) A program that handles protocol, queuing, routing, and other tasks necessary for data transfer between devices in a computer system.

**spool.** The system function of putting files or jobs into disk storage for later processing or printing.

## T

**trace.** A record of the execution of a computer program. It exhibits the sequences in which the instructions were executed. (A)

**transform server.** The process that manages data and image transforms.

**TIFF.** Tagged image file format.

**TrueType font.** A font format based on scalable outline technology in which the graphic character shapes are based on quadratic curves. The font is described with a set of tables contained in a TrueType font file.

## U

**user interface.** Any of the actions or items that let a user interact with and perform operations on a computer, including graphical displays, components such as buttons or dials, or operating system commands.

## W

**Web browser.** A client program that initiates requests to a Web server and displays the information that the server returns.

**Web server.** The program that is capable of servicing Hypertext Transfer Protocol (HTTP) requests for display in a Web browser.

**Windows.** Pertaining to a Microsoft Corporation program that provides a graphical user interface for DOS.





---

# Index

## Special characters

- /aiw file system
  - backing up data 37
  - exporting shared to secondary servers 19
  - restoring data 38
  - setup 8
  - unplanned outage 29

## A

- accessibility 47
- Adobe Reader
  - installing 11
  - making available to Web browsers 12
  - obtaining languages for 11
- AFP Download Plus 13
- AFP Editor 2
- AFP Font Collection 15
- AFP Indexer 2
- AIX
  - changing languages on 45
  - Infoprint Manager 15
  - Infoprint XT 14
  - installing secondary servers 21
  - operating system, installing 10
  - requirements 9
  - service updates 41
  - uninstalling Infoprint ProcessDirector on 34
- assistive technologies, using 47
- autostart script for Linux
  - activating 29
  - deactivating 29

## B

- backing up data 37
- base Infoprint ProcessDirector program
  - installing 18, 20
  - uninstalling 33
- browsers, setting up
  - Internet Explorer 12
  - Mozilla 11
- browsers, Web
  - accessing user interface from 18, 40
  - making Adobe Reader available to 12
  - requirements 11
  - setting languages 12

## C

- checklist, planning 43
- commands
  - startaiw 29, 30
  - stopaiw 31, 32
- compatible products 3
- components of Infoprint ProcessDirector 1
- configuration
  - system example 4
  - tasks 26

- configuring
  - NIS server 22
  - user name mapping on Windows 24

## D

- data transforms 14
- DB2
  - description of 1
  - installing 18
  - uninstalling 33
- directories for input devices 13
- disability 47
- Download for z/OS 13

## E

- exporting shared file systems to secondary servers 19
- Extensions 2

## F

- failure recovery, backing up data for 37
- features 2
- file systems
  - backing up data 37
  - exporting shared to secondary servers 19
  - restoring data 38
  - setup 8
  - unplanned outage 29
- fonts, installing 15

## G

- group ID (GID), default 44

## H

- hardware
  - configurations 4
  - requirements 7
- help, accessing 26
- hot folders 13

## I

- Infoprint 2090ES 4
- Infoprint 2105ES 4
- Infoprint 2190 4
- Infoprint 2210 4
- Infoprint 2235 4
- Infoprint 4000 4
- Infoprint 4100 4
- Infoprint 5000 4
- Infoprint Fonts 15
- Infoprint Manager for AIX, installing 15
- Infoprint ProcessDirector
  - backing up data 37

- Infoprint ProcessDirector *(continued)*
  - compatible products 3
  - components 1
  - default group ID 44
  - default user ID 44
  - description of 1
  - installing on primary server 18
  - migrating to new levels 37
  - overview 1
  - planning for 7
  - restoring to previous levels 38
  - system configurations 4
  - uninstalling 32
  - verifying installation 26
- Infoprint ProcessDirector Extensions 2
- Infoprint Transform Manager 14
- Infoprint XT for AIX 14
- information center, accessing 26
- input device directories 13
- installation
  - checklist 43
  - planning 7
  - verification
    - AIX secondary servers 22, 41
    - Infoprint ProcessDirector 26
    - Linux secondary servers 21
    - primary server 19
- installing
  - Adobe Reader 11
  - AIX operating system 10
  - AIX secondary servers 21
  - base Infoprint ProcessDirector program 18, 20
  - DB2 18
  - fonts 15
  - Infoprint Manager for AIX 15
  - Infoprint ProcessDirector product 17
  - Infoprint Transform Manager 14
  - Infoprint XT 14
  - job submitter software 13
  - Linux secondary servers 20
  - optional software 13
  - previous levels 38
  - primary servers 18
  - PSF 18, 20
  - secondary servers 19
  - SFU 23
  - SLES 9.0 9
  - updates to Infoprint ProcessDirector 39
  - updates to Linux secondary 40
  - user interface 18
  - Windows operating system 11
  - Windows secondary servers 22
  - Windows Services for UNIX 23
- Internet Explorer, setting up 12

## J

- JavaScript
  - enabling in Internet Explorer 12
  - enabling in Mozilla 11
- job submission methods 13

## K

- keyboard 47
- keys, viewer shortcut 47

## L

- languages
  - changing on Linux and AIX servers 45
  - obtaining for Adobe Reader 11
  - setting for printer devices 26
  - setting in Web browsers 12
- Linux
  - Adobe Reader 11
  - changing languages on 45
  - Infoprint Transform Manager 14
  - installing
    - operating system 9
    - primary server 18
    - secondary servers 20
  - making Adobe Reader available to Web browser 12
  - requirements 9
  - uninstalling Infoprint ProcessDirector on 33
  - Web browser for 11

## M

- migrating to new levels 37
- Mozilla, setting up 11

## O

- operating systems
  - AIX, installing 10
  - Linux, installing 9
  - requirements 9
  - Windows, installing 11
- optional software 13
- outages, unplanned 29
- overview of Infoprint ProcessDirector 1

## P

- partition setup
  - simple, example 8
- planning
  - checklist 43
  - file systems 8
  - installation tasks 7
  - optional software 13
  - required software 9
- post-installation tasks 25
- pre-installation tasks 7
- primary servers
  - exporting shared file systems to secondary servers 19
  - hardware requirements 7
  - installing Infoprint ProcessDirector on 18
  - software requirements 9
  - uninstalling Infoprint ProcessDirector on 32
  - verifying installation 19
- print drivers, setting languages for 26
- print job, setting up 26
- printers, supported 4
- products, compatible 3
- PSF
  - description of 1
  - installing 18, 20
  - uninstalling 33

## R

- recovering data from system failure 37
- releases
  - migrating to new 37
  - restoring to previous 38
- Reports 2
- requirements
  - hardware 7
  - software 9
  - Web browsers 11
- restoring to previous levels 38

## S

- screen readers, using 47
- secondary server
  - disabling Windows automatic start 30
- secondary servers 35
  - adding and enabling 20
  - AIX 21
  - configuring NIS server on primary server
    - Windows 22
  - configuring user name mapping
    - Windows 24
  - disabling Windows automatic start 30
  - enabling Windows automatic start 31
  - exporting shared file systems to 19
  - hardware requirements 7
  - installing Infoprint ProcessDirector 19, 25
  - installing SFU on Windows 23
  - Linux 20
  - software requirements 9
  - starting on AIX 30
  - starting on Linux 29
  - stopping on AIX 32
  - stopping on Linux 31
  - stopping on Windows 32
  - testing connection to NFS server, Windows 24
  - uninstalling 34
  - uninstalling Infoprint ProcessDirector on 32
  - verifying installation 21, 22, 41
  - Windows 22
- server
  - activating the Linux autostart script 29
  - deactivating the Linux autostart script 29
- servers
  - changing languages on 45
  - hardware requirements 7
  - installing Infoprint ProcessDirector on 17
  - software requirements 9
  - starting on AIX 30
  - starting on Linux 29
  - stopping on AIX 32
  - stopping on Linux 31
  - uninstalling Infoprint ProcessDirector on 32
- Service Level Agreements (SLA) 2
- service update, installing 37
- service updates
  - AIX 41
  - Windows 41
- SFU 23
- shared file systems, exporting to secondary servers 19
- shortcut keys 47
- SLES 9.0, installing 9
- software
  - job submitter 13

- software (*continued*)
  - optional 13
- startaiw command 29, 30
- stopaiw command 31, 32
- submitting test jobs for verification 26
- system configuration, example 4

## T

- test jobs, submitting 26
- testing connection to NFS server 24
- transforms, data 14

## U

- UID, default 44
- uninstalling
  - AIX secondary servers 34
  - Infoprint ProcessDirector 32
  - Linux secondary servers 34
- uninstalling Windows 35
- unplanned outages 29
- updating
  - Infoprint ProcessDirector 39
  - Linux secondary 40
- user ID, default 44
- user interface
  - accessing help from 26
  - adding and enabling secondary servers 20
  - description of 2
  - installing 18
  - required Web browsers for 11
  - uninstalling 33
  - URL for accessing 18, 40
  - verifying primary server installation 19

## V

- verification, installation
  - AIX secondary servers 22, 41
  - Infoprint ProcessDirector 26
  - Linux secondary servers 21
  - primary server 19
- viewer shortcut keys 47

## W

- Web browsers
  - accessing user interface from 18, 40
  - making Adobe Reader available to 12
  - requirements 11
  - setting languages 12
- Windows
  - Adobe Reader 11
  - installing secondary servers 22
  - operating system, installing 11
  - requirements 9
  - secondary servers
    - configuring NIS server on primary server 22
    - configuring user name mapping 24
    - installing Infoprint ProcessDirector 25
    - installing SFU 23
    - testing connection to NFS server 24
    - uninstalling 35
  - service updates 41

Windows (*continued*)  
    Web browser for 11  
Windows Services for UNIX 23

---

## Readers' Comments — We'd Like to Hear from You

Infoprint ProcessDirector for Linux  
Planning and Installation  
Version 1, Release 2.1

Publication No. G550-0527-03

We appreciate your comments about this publication. Please comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. The comments you send should pertain to only the information in this manual or product and the way in which the information is presented.

For technical questions and information about products and prices, please contact your IBM branch office, your IBM business partner, or your authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you. IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you state on this form.

Comments:

Thank you for your support.

Submit your comments using one of these channels:

- Send your comments to the address on the reverse side of this form.
- Send a fax to the following number: 1-800-524-1519 within the United States  
1-303-924-6873 outside the United States
- Send your comments via e-mail to: [printpub@us.ibm.com](mailto:printpub@us.ibm.com)

If you would like a response from IBM, please fill in the following information:

\_\_\_\_\_

Name

\_\_\_\_\_

Address

\_\_\_\_\_

Company or Organization

\_\_\_\_\_

Phone No.

\_\_\_\_\_

E-mail address



Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE  
NECESSARY  
IF MAILED IN THE  
UNITED STATES

# BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation  
IBM Printing Systems Division  
Dept H7FE, Building 004N  
Information Development  
PO Box 1900  
Boulder CO USA 80301-9817



Fold and Tape

Please do not staple

Fold and Tape





Program Number: 5697-N55

Printed in USA

G550-0527-03

