

Gentran:Structure[®] for zSeries

User's Guide

Release 6.4

Sterling Commerce
An IBM Company

Sterling Commerce (Mid America), Inc.
4600 Lakehurst Court Dublin, OH 43016-2000 * 614/793-4000
© Copyright 1988 – 2005—Sterling Commerce, Inc.

December 2005

Gentran:Structure for zSeries
© Copyright 1988 – 2005
Sterling Commerce, Inc.
ALL RIGHTS RESERVED

Sterling Commerce Software

Trade Secret Notice

THE GENTRAN:STRUCTURE AND GENTRAN:BASIC FOR ZSERIES SOFTWARE (“STERLING COMMERCE SOFTWARE”) IS THE CONFIDENTIAL AND TRADE SECRET PROPERTY OF STERLING COMMERCE, INC., ITS AFFILIATED COMPANIES OR ITS OR THEIR LICENSORS, AND IS PROVIDED UNDER THE TERMS OF A LICENSE AGREEMENT. NO DUPLICATION OR DISCLOSURE WITHOUT PRIOR WRITTEN PERMISSION. RESTRICTED RIGHTS.

This documentation, the Sterling Commerce Software it describes, and the information and know-how they contain constitute the proprietary, confidential and valuable trade secret information of Sterling Commerce, Inc., its affiliated companies or its or their licensors, and may not be used for any unauthorized purpose, or disclosed to others without the prior written permission of the applicable Sterling Commerce entity. This documentation and the Sterling Commerce Software that it describes have been provided pursuant to a license agreement that contains prohibitions against and/or restrictions on their copying, modification and use. Duplication, in whole or in part, if and when permitted, shall bear this notice and the Sterling Commerce, Inc. copyright notice.

As and when provided to any governmental entity, government contractor or subcontractor subject to the FARs, this documentation is provided with RESTRICTED RIGHTS under Title 48 CFR 52.227-19. Further, as and when provided to any governmental entity, government contractor or subcontractor subject to DFARs, this documentation and the Sterling Commerce Software it describes are provided pursuant to the customary Sterling Commerce license, as described in Title 48 CFR 227-7202 with respect to commercial software and commercial software documentation.

These terms of use shall be governed by the laws of the State of Ohio, USA, without regard to its conflict of laws provisions. If you are accessing the Sterling Commerce Software under an executed agreement, then nothing in these terms and conditions supersedes or modifies the executed agreement.

Product names mentioned herein may be trademarks and/or registered trademarks of their respective companies. Gentran, Gentran:Basic, Gentran:Control, Gentran:Plus, Gentran:Realtime, Gentran:Structure, and Gentran:Viewpoint are registered trademarks of Sterling Commerce, Inc.

Third Party Software:

Portions of the Sterling Commerce Software may include products, or may be distributed on the same storage media with products, (“Third Party Software”) offered by third parties (“Third Party Licensors”).

Warranty Disclaimer

This documentation and the Sterling Commerce Software which it describes are licensed either "AS IS" or with a limited warranty, as set forth in the Sterling Commerce license agreement. Other than any limited warranties provided, NO OTHER WARRANTY IS EXPRESSED AND NONE SHALL BE IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR USE OR FOR A PARTICULAR PURPOSE. The applicable Sterling Commerce entity reserves the right to revise this publication from time to time and to make changes in the content hereof without the obligation to notify any person or entity of such revisions or changes.

The Third Party Software is provided 'AS IS' WITHOUT ANY WARRANTY AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. FURTHER, IF YOU ARE LOCATED OR ACCESSING THIS SOFTWARE IN THE UNITED STATES, ANY EXPRESS OR IMPLIED WARRANTY REGARDING TITLE OR NON-INFRINGEMENT ARE DISCLAIMED.

Table of Contents

Chapter 1	Getting Started		
	Overview	1-1	
	Introduction	1-2	
	System Overview.....	1-3	
Chapter 2	Tutorial		
	Overview	2-1	
	Getting Started.....	2-3	
	Tutorial Scenario	2-4	
	Creating a Standard	2-12	
	Partner Configuration	2-27	
	Mapping Configuration	2-35	
	Implementing Gentran:Structure	2-38	
	Processing Daily Business.....	2-39	
	Gentran:Structure Tutorial.....	2-40	
Chapter 3	Screens		
	Overview	3-1	
	Jump Codes	3-3	
	How Gentran:Structure Relates with Gentran:Basic Features	3-7	
	Partner Maintenance Subsystem.....	3-8	
	Standards Maintenance Subsystem	3-31	
	Mapping Integration Subsystem.....	3-53	
	Databank Maintenance Subsystem.....	3-64	
	Standards Change Audit Subsystem.....	3-92	
	Gentran:Realtime Screens	3-100	
Chapter 4	Program Descriptions		
	Overview	4-1	
	Inbound Flow	4-3	
	Inbound Pre-Processing Program	EBDI083	4-6
	Inbound Mapping Program	EBDI041	4-19
	Inbound Fixed/Variable Split Program	EBDI094	4-24
	Outbound Flow.....		4-28
	Outbound Mapping Program	EBDI042	4-30
	NCPDP Inbound Pre-Processing Program	NCPDP51I.....	4-39

Table of Contents

NCPDP Outbound Post-Processing Program	NCPDP51O.....	4-42
Structure Application Databank Inquiry Report Program	EDID553.....	4-46
Chapter 5 Gentran:Realtime Program Descriptions		
Overview		5-1
Inbound Flow		5-3
Inbound Fixed/Variable Split Program	EDIR094	5-6
Inbound Pre-processing Program	EDIR083	5-9
Inbound Mapping Program.....	EDIR041	5-13
Inbound NCPDP Pre-processing Program	EDIRNCPI	5-16
Outbound Flow		5-20
Outbound Mapping Program.....	EDIR042	5-22
Outbound NCPDP Post-Processing Program.....	EDIRNCPO	5-25
Appendix A Jump Codes		
Jump Codes by Screen Title		A-1
Jump Codes by Screen Name		A-2
Appendix B Processing NCPDP Data		
Overview		B-1
Processing NCPDP Data in Gentran:Structure.....		B-2
Processing Outbound NCPDP Data		B-8
Processing Inbound NCPDP Data.....		B-34
NCPDP Data Examples.....		B-51
Glossary		
Definition of Terms		G-1
Reserved Word Constants		G-3
Index		

Getting Started

Overview

Welcome to Gentran:Structure for zSeries Release 6.4.

As a subsystem of Gentran:Basic/Realtime, Gentran:Structure® is an optional component of the most sophisticated EDI management software available. Gentran:Structure combines with Gentran:Basic/Realtime to provide advanced capabilities for translating EDI communications. With Gentran:Structure, you can process communications across different standards formats simply and efficiently.

This chapter introduces Gentran:Structure, including features and benefits, system architecture, and system operation. It contains the following topics:

Topic	Page
Introduction	1-2
File Formats and Standards	1-2
Gentran:Structure Features	1-2
System Overview	1-3
Explanation of Standards	1-3
Gentran:Structure System Components	1-4
Restrictions on Fixed-Format Data	1-6
System Flow.....	1-6
Inbound Flow Programs.....	1-12

Introduction

The need for Gentran:Structure is a result of businesses' developing data exchange methods. EDI evolved as companies determined that exchanging certain types of business documents was beneficial. They developed file formats that they could exchange between their respective computer systems. These files were typically in a format similar to the business applications.

File Formats and Standards

Usually, the file formats consisted of multiple, 80-character records describing a business document. The fields contained within these records were in a fixed location in each record (hence the term "fixed-format standards"). Many companies developed such systems for trading business documents with each other. This is how the first EDI standards were developed, not by national or international standards committees, but by people involved in particular industries with specific business needs.

Many of those standards, developed almost 20 years ago, remain in use today. Most of them had two things in common that differentiated them from common EDI standard formats such as ASCX12 and EDIFACT:

- Their structure was a fixed-format composition rather than the variable-format structure of ASCX12 or EDIFACT standards.
- The fixed formats required customized programs for processing, because no third-party software was capable of handling these standards.

The first difference still exists. However, with Gentran:Structure, fixed-format standards now can be processed using the same facilities that hundreds of companies use to process variable-format standards data.

Gentran:Structure Features

The following features enable you to configure EDI communications to fit your specific needs:

- You can define fixed-format standards to contain either fixed-length segments or variable-length segments. The system supports the full range of data types.
- Gentran:Structure supports outbound mapping from an application to a fixed-format standard and inbound mapping to a fixed-format standard. All of the mapping features available for variable-format standards in Gentran:Basic/Realtime also are available for fixed-format standards via Gentran:Structure.
- You can configure the system to generate proprietary enveloping structures for outbound processing and to extract critical envelope information during inbound processing and map it to the application.
- Gentran:Structure enables you to audit, track, and control processing of the fixed-format standards data using the Gentran:Basic/Realtime Application Databank facility.
- The system supports sharing of standard definitions, trading partner profiles, application definitions, transaction definitions (maps), data translation tables, code translation tables, and user-envelope specifications between batch and real-time communications.

System Overview

Gentran:Structure enables you to define proprietary, fixed-format standards using the Standards Maintenance programs, and to map to and from these standards using the Inbound and Outbound Mapping programs.

Explanation of Standards

A fixed-format standard is a standard in which elements within each segment are of a fixed length and are not separated by an element separator. Further, each segment that comprises the standard is defined by a fixed length and is not separated by a segment terminator.

Examples

The following tables illustrate the different specifications between fixed- and variable-format standards.

Variable Standard		Fixed Standard	
Segment 1 – ID is ABC			
Element 1 – PO Number		Element 1 – PO Number	
Minimum Length	1	Length	15
Maximum Length	15	Data	PO123
Data	PO123		
Element 2 – PO Date		Element 2 – PO Date	
Minimum Length	6	Length	6
Maximum Length	6	Data	930315
Data	930315		
Element 3 – PO Type		Element 3 – PO Type	
Minimum Length	1	Length	4
Maximum Length	4	Data	NEW
Data	NEW		

Variable Standard		Fixed Standard	
Segment 2 – ID is XYZ			
Element 1 – Item Number		Element 1 – Item Number	
Minimum Length	1	Length	15
Maximum Length	15	Data	PART123
Data	PART123		
Element 2 – Quantity		Element 2 – Quantity	
Minimum Length	1	Length	7
Maximum Length	7	Data	100
Data	100		
Element 3 – Unit of Measure		Element 3 – Unit of Measure	
Minimum Length	2	Length	2
Maximum Length	2	Data	EA
Data	EA		

- Thus, variable-format data, with an asterisk (*) as an element separator and a semi-colon as a segment terminator, would appear as follows:

```
ABC*PO123*930315*NEW;  
XYZ*PART123*100*EA;
```

- Fixed-format data would appear as follows:

```
ABCPO123bbbbbbbbbb930315NEWb [end of record]  
XYZPART123bbbbbbbb0000100EAb [end of record]
```

Note: The symbol “b” indicates a blank character.

These examples illustrate that the actual length of the segment in variable standards depends on the content of the data. If the quantity specified in the XYZ segment were equal to 10,000 instead of 100, the segment would be two characters longer. If the quantity were changed for the fixed segment, no change would be made in the actual length; instead the number 0000100 would be changed to 0010000. Different alphanumeric values would be handled in a similar manner.

By this example, you can determine that every occurrence of a specific segment in a fixed standard is exactly the same length, while the same segment in a variable standard varies in length depending on the data contained in the segment. This concept holds true for elements: in a fixed standard, an element always starts in the same relative position within a segment. In a variable standard, this concept does not apply.

Gentran:Structure System Components

The Gentran:Structure system components are:

- Application and map definitions
- Trading partner profiles
- Batch translation services
- Online services
- Realtime translation services
- Databank facility
- Standards definitions

System Interaction

Figure 1.1 illustrates Gentran:Structure components interacting in batch and real-time situations.




Figure 1.1 Gentran:Basic for zSeries Batch and Realtime Interaction

Restrictions on Fixed-Format Data

The following restrictions apply to data that can be processed as a fixed-format standard:

- The standard must have a definable segment ID that occurs in the same relative offset in each segment. This segment ID can measure from one to three characters.
- The segment can contain from 10 to 32,760 characters for fixed-blocked files and from 10 to 32,752 characters for variable-blocked files. Segments contained within a fixed-format standard that are defined as variable-blocked need not have the same record length.
- Inbound fixed-format standards must have a segment or segments that can be defined as “envelopes.” These envelope segments must contain information such as partner, user (if processing in relationship mode), version, and transaction set. If any of this information is not available, it must be supplied as a runtime parameter.

System Flow

Gentran:Structure operates with Gentran:Basic/Realtime in such a way that current variable-format processing remains unaffected.

Outbound Flow

Figure 1.2 illustrates outbound flow through Gentran:Structure system components for fixed-format data. The numbers in the illustration correspond to the steps below the figure that describe the flow.




Figure 1.2 Outbound Flow, Fixed-Format Data

The following table describes the outbound flow of fixed-format data through Gentran:Basic using Gentran:Structure.

Stage	Description
1	The application places the data in the Application Extract file.
2	The Outbound Mapper program (EBDI042) reads the data in the Application Extract file and translates it into fixed-format data as instructed by the selected map.
3A	If the Mapper defines the data as fixed-format with standard enveloping requirements, the system directs the output to an output file and directly to Communications.
3B	If the Mapper defines the selected map as fixed-format and the standards have enveloping requirements that cannot be satisfied by the Outbound Mapper's User-Envelope Generation facility, the system passes the data to a user-written format-specific Envelope Generator routine.
3C	If desired, the system passes input application data to the Outbound Application databank. Also, if desired (depending on parameters), the system passes fixed standards output to the Outbound Application databank.
4B	<ul style="list-style-type: none"> If a user-written compliance-checker is installed, the system passes the fixed-format output data from the Envelope Generator to the Compliance Checker for verification before passing the output to Communications. If no user-written compliance-checker is active, the system passes the fixed-format data from the Envelope Generator to Communications.

Outbound Flow Features and Limitations

Gentran:Structure is designed with the following features to facilitate outbound processing:

- Parameters define the type of file to which the system should write any fixed-format output (for example, fixed- or variable-blocked, and record length).
- You can map to the data types supported in the fixed-format standards.
- Gentran:Structure supports generation of user-defined envelopes. These envelopes optionally can be generated for fixed-format standards. The separate Envelope Generation program (EBDI011M) does not support these envelopes.
- Gentran:Structure checks the mandatory/optional code for output segments and elements. If a mandatory segment or element is not generated, the system issues a warning message and sets the return code to 4.

Two limitations of Gentran:Structure outbound processing are:

- Certain proprietary standards have enveloping requirements that are not satisfied by the User-Envelope Generation facility of the Outbound Mapping program. One of these standards is the AISI COMPORD standard. This standard has control totals (message and segment counts) in the header envelope. The Gentran:Basic normal sequential processing of output does not support this process. Users must develop optional routines to support these types of envelopes.
- The Outbound Mapping program does not perform compliance checking of the output for fixed-format standards, and the Outbound Editor does not process fixed-format standards. Therefore, if your organization requires additional compliance checking of data, you can insert a user-written compliance checker after mapping to perform the function.

Inbound Flow

Figure 1.3 illustrates inbound flow through Gentran:Structure system components. The numbers in the illustration correspond to the steps below the figure that describe the flow.




Figure 1.3 Inbound Flow

The following table describes the inbound flow through Gentran using **Gentran:Structure**.

Stage		Description	
	Variable Format Data	Mixed-Format Data	Fixed-Format Data
1	The system sends the data from Communications to the Inbound editor.	The system sends the data from Communications to the Inbound Fixed/Variable Splitter to be separated by format type.	The system sends the data from Communications to the Format Specific Compliance Checker, if used, or directly to the Inbound Pre-processor.
2	If the Inbound Splitter is used, the system passes the data to the Splitter and then to the Inbound Mapper. If the Splitter is not used, the system passes the data directly to the Inbound Mapper.	The Inbound Fixed/Variable Splitter: <ul style="list-style-type: none"> • Sends the variable-format data to the Inbound editor. The data continues on the variable format data path. • Sends the fixed-format data to the Compliance Checker, if used, or directly to the Inbound Pre-processor. The data continues on the fixed-format path. 	The system sends the data from the Pre-processor to the data router, if used, or directly to the Inbound Mapper.
3	The Inbound Mapper sends the file to the Application or to the Inbound Application Databank (if used — See step 3A).		The Inbound Mapper sends the file to the Application or to the Inbound Application Databank (if used; see Stage 3A).
3A	(Optional) The Inbound Application Databank Extract program sends the data to the Application.		(Optional) The Inbound Application Databank Extract program sends the data to the Application.

Inbound Flow Programs

The following table describes inbound flow-related programs.

Program	Description
Inbound Fixed / Variable Split program (EBDI094) OR (EDIR094 for Gentran:Realtime)	This program is an optional step. You must execute it if the system receives fixed- and variable-format data in a single transmission. Note: The input to this program must be 80-character records. The program splits the incoming data into the following categories: <ul style="list-style-type: none"> • Fixed-format COMPORD data • Fixed-format GM (CISCO) data • Fixed-format GENCOD data • Other fixed-format data • Variable-format EDI data
Inbound Pre-processing program (EBDI083) OR (EDIR083 for Gentran:Realtime)	This program performs the identification and partner look-up functions for fixed-format standards, in a manner similar to the Inbound editor for variable-format standards. The program: <ul style="list-style-type: none"> • Determines the standard version and transaction set. • Determines the trading partner. • Determines the user (if relationship mode processing is specified). • Extracts user-defined envelope information to be passed to the Inbound Mapping program. The program can optionally databank the inbound data. The program suspends data that cannot be identified properly, for later processing.
Inbound Mapping Program (EBDI041) OR (EDIR041 for Gentran:Realtime)	The Inbound Mapping program processes data from one of these two sources: <ul style="list-style-type: none"> • The Intermediate file generated by the Inbound Editing program with variable data (this is the default source of data). This file contains the edited and expanded variable-format EDI data. • The fixed-format output file from the Inbound Pre-processing program (this is the optional source of input). Map selection and mapping functionality are identical, regardless of the source of the input data.
Data Router Program (EBDI095)	The Data Router program allows the inbound fixed-format data to be split into different files for input into separate Mapper runs. Splitting is based on values provided by input parameters (Gentran:Structure for Basic only).

Inbound Flow Features and Limitations

Gentran:Structure offers the following features to facilitate inbound processing:

- Specific parameters define whether the input should be processed from the fixed-format input file.
- You can map from the data types supported in the fixed-format standard. These data types include those that are supported for the inbound application definition.
- Gentran:Structure supports mapping from user-defined envelopes. Special reserved word constants have been defined to hold these elements.
- Gentran:Structure checks the mandatory/optional code for application records and fields. If a mandatory record or field is not generated, the system issues a warning message and sets the return code to 4.

Limitations include the following:

- The Inbound Mapping program does not perform compliance checking for mandatory fields (such as data types and lengths) and records for the output (Application file) of fixed-format standards.
- The Inbound Editing program does not process fixed-format standards.

Note: If you need additional compliance checking of data, you can insert a user-written compliance checker before mapping to perform the function.

Overview

The sections in this chapter are arranged to provide you with a basic understanding of Gentran:Structure. The steps are organized around the following subjects:

- Setting up and processing a fixed-format standard.
- Using the online facility.

Note: Do not undertake the procedures in the following sections unless your entire system has been installed and is operational.

This chapter contains the following topics:

Topic	Page
Getting Started	2-3
Fictitious Standard	2-3
Tutorial Scenario	2-4
JASS Standard.....	2-4
Fictitious Trading History	2-4
JASS Standard Information	2-4
Guide to Using the JASS Standard	2-7
Developing a Configuration Strategy	2-11
Creating a Standard	2-12
Screens	2-12
Exercise.....	2-13
JASS Standard Segment Element Structures	2-18
JASS Standard Data Element Listing	2-21
Partner Configuration	2-27
Exercise.....	2-27
Mapping Configuration	2-35
Exercise.....	2-35
Implementing Gentran:Structure	2-38

Processing Daily Business	2-39
Inbound Flow	2-39
Outbound Flow	2-39
Maintenance Procedures	2-39
Gentran:Structure Tutorial	2-40
Purpose.....	2-40
Standards Maintenance	2-41
Mapping Integration – Outbound.....	2-51
Mapping Integration – Inbound	2-56
Partner Maintenance	2-61

Getting Started

This tutorial assumes that you meet the following criteria:

- You understand the business requirements of your application, as well as those of your trading partners.
- You are familiar with Gentran:Basic/Realtime features and functions.

This tutorial is designed to assist you in creating an implementation plan for your actual organization. The tutorial takes you step-by-step through Gentran:Structure to set up and process a fixed-format standard and to use the online facility.

Fictitious Standard

This tutorial provides a fictitious, fixed-format example standard called the JASS standard. In addition, we include inbound and outbound maps associated with the standard, a partner to trade with, and sample data matching the fictitious setup.

Tutorial Scenario

By completing the steps in this chapter, you will implement Gentran:Structure with the fictitious JASS standard, specifically accomplishing the following tasks:

- Create a standard.
- Identify envelope field positions.
- Identify and create a trading partner.
- Tie together the trading partner and standard using envelopes.
- Create inbound and outbound maps.
- Run data through complete Gentran:Structure inbound and outbound flows to verify results.

JASS Standard

The JASS standard is a fictitious example of a lawn care industry standard, created for this tutorial. The scenarios in this tutorial mirror Gentran:Basic/Realtime installation and verification.

Note: Throughout the tutorial, the term “your company” indicates your organization within the fictitious scenario.

Fictitious Trading History

Your company sends purchase orders and receives invoices. You were users of the ASCX12 variable-length standard in EDI communications. However, when you began trading with the vendor LAWNVEND, you were obligated to adopt the JASS standard to trade with them.

Your layout for purchase orders is set in the Application Definition POFILE. The layout for invoices is set in the Application Definition INVFILE.

Note: So that you need not modify your existing scenario files, the tutorial provides similar application layouts called POFILEF and INVFILEF.

The transaction maps supporting these scenarios are called JASSPO and JASSIN. Your trading partner, LAWNVEND, and the JASS standard are set up for your use with this tutorial.

JASS Standard Information

The JASS standard contains two document types: purchase order (0909) and invoice (0926). The layout for these documents is illustrated in Figure 2.1. Two envelopes are used: a packet header/trailer and a transaction header/trailer. Other standards may have different requirements.

Some components of the complete scenario are missing. As you proceed through the tutorial, you will complete the scenario. The omissions include the following items:

- The note segment for purchase orders (ONT) and respective elements.
- The packet trailer (PTR) and transaction trailer (TTR).
- Outbound mapping of the ONT segment.

- Mapping inbound control numbers from the PHD and THD envelopes.
- Coding the requirements for the PTR and TTR trailer envelopes outbound.

Note: You can use the sample purchase order and invoice data provided on the installation tape to demonstrate tutorial scenarios and the completed tutorial. However, the missing pieces result in a mapping error when you run installation verification. Because the segments for the trailers are not defined yet, the system sets the return code to 4 in inbound mapping. This code is normal; mapping results are unaffected.

Tutorial Enveloping Process

Figure 2.1 illustrates the enveloping process used in the tutorial example.




Figure 2.1 Envelope Structure

Guide to Using the JASS Standard

The JASS proprietary standard example is for use between trading partners in the lawn care industry.

The JASS standard contains the following two document types (transactions):

- 0909 – purchase order document
- 0926 – invoice document

A purchase order (0909) contains five distinct segments:

- OHD – purchase order header information
- OAD – address information
- ONT – purchase order notes
- ODT – order detail information
- OSM – order summary information

An invoice (0926) contains four distinct segments:

- IHD – invoice header information
- IRN – invoice remit name information
- IDT – invoice detail information
- ISM – invoice summary information

Data Elements

The JASS standard contains 31 different data elements. Figure 2.2 is the key to reading the JASS standard.




Figure 2.2 JASS Standard Key

Figure 2.3 and Figure 2.5 illustrate the JASS standard.

PHD – Packet Header Segment

Sender ID	Receiver ID	Current Date	Current Time	Standard Identifier	Security Code	Packet Control Number	PHD Segment ID
1/15	16/15	0001 31/6 JD	37/4	41/4	45/6	51/9	78/3

THD – Transaction Header Segment

Transaction Type (Number)	Current Date	Current Time	Transaction Control Number	THD Segment ID
1/4	0001 5/8 JD	13/4	17/9	78/3

OHD – Purchase Order Header Segment

Purchase Order Number	Ship-To Name	Bill-To Name	Date Type	Date	Date Type	Date	Reserve Element	OHD Segment ID
0004 1/6	0006 7/25	0007 32/25	0002 57/2	0001 59/5	0002 64/2	0001 66/5	7 0029 71/7	78/3

OAD – Purchase Order Address Information Segment

Address Code	Address	City	State	Zip Code	Reserve Element	OAD Segment ID
0008 1/2	0009 3/20	0010 23/20	0011 43/2	0012 45/9	24 0024 54/24	78/3

ONT – Purchase Order Notes

Note Type	Note Text	ONT Segment ID
0030 1/2	0031 3/75	78/3

ODT – Purchase Order Detail Segment

Line Item Number	Item Number	Quantity Type	Quantity	Unit of Measure	Price	Extended Price	Item Description
0014 1/4	0015 5/8	0016 13/2	0017 15/6	0020 21/4	0018 25/10	0019 35/14	0021 49/27

Reserve Element 2	ODT Segment ID
0027 76/2	78/3

Figure 2.3 0909 Purchase Order Layout

OSM – Purchase Order Summary Segment

Total Line Items	Total Amount	Reserve Element	OSM Segment ID
0023	0022	57 0028	
1/4	5/16	21/57	78/3

TTR – Transaction Trailer

Number of Segment in Trans	Trans Control Number	TTR Segment ID
1/8	9/9	78/3

PTR – Packet Trailer

# of Segments in Packet	# of Trans in Packet	Packet Control Number	PTR Segment ID
1/8	9/8	17/9	78/3

Figure 2.4 0909 Purchase Order Layout

PHD – Packet Header Segment

Sender ID	Receiver ID	Current Date	Current Time	Standard Identifier	Security Code	Packet Control Number	PHD Segment ID
1/15	16/15	0001 31/6 JD	37/4	41/4	45/6	51/9	78/3

THD – Transaction Header Segment

Transaction Type (Number)	Current Date	Current Time	Transaction Control Number	THD Segment ID
1/4	0001 5/8 JD	13/4	17/9	78/3

IHD – Invoice Header Detail

Invoice Number	Purchase Order Number	Date Type	Date	Date Type	Date	Billing Cycle Code	Reserve Element 49
0003 1/6	0004 7/6	0002 13/2	0001 15/5	0002 20/2	0001 22/5	0013 27/2	0025 29/49

IHD Segment ID
78/3

IRN – Invoice Remit Name

Remit-To Name	Address	City	State	Zip Code	Reserve Element 1	IRN Segment ID
0005 1/25	0009 26/20	0010 46/20	0011 66/2	0012 68/9	0026 77/1	78/3

IDT – Invoice Detail

Line Item Number	Item Number	Quantity Type	Quantity	Unit of Measure	Price	Extended Price	Item Description
0014 1/4	0015 5/8	0016 13/2	0017 15/6	0020 21/4	0018 25/10	0019 35/14	0021 49/27

Reserve Element 2	IDT Segment ID
0027 76/2	78/3

Figure 2.5 0926 Invoice Layout

ISM – Invoice Summary

Total Line Items	Total Amount	Reserve Element	ISM Segment ID
0023	0022	57 0028	
1/4	5/16	21/57	78/3

TTR – Transaction Trailer

Number of Segment in Trans	Trans Control Number	TTR Segment ID
1/8	9/9	78/3

PTR – Packet Trailer

# of Segments in Packet	# of Trans in Packet	Packet Control Number	PTR Segment ID
1/8	9/8	17/9	78/3

Figure 2.6 0926 Invoice Layout**Developing a Configuration Strategy**

Before you can configure Gentran:Structure in this tutorial, you must make decisions regarding the following issues:

- What standards information do you want to create?
- What envelope field positions will you need?
- With which trading partner do you want to do business?
- What envelopes (headers and trailers) do you want to use to convey information?
- What information do you want to exchange with your trading partner?

Creating a Standard

The JASS standard, a fictitious standard used by the lawn care industry, is completed and ready for your use with this tutorial. The following table provides a concise listing of the JASS standard information explained in “Guide to Using the JASS Standard” on page 2-7. Use this table as a reference tool.

Guide to Using the JASS Standard
<p><i>JASS Standard Transactions</i></p> <p>The following two document types (transactions) are contained in the JASS standard:</p> <ul style="list-style-type: none"> • 0909 – purchase order document • 0926 – invoice document
<p><i>Purchase Order Segments</i></p> <p>A purchase order (0909) contains the following four distinct segments:</p> <ul style="list-style-type: none"> • OHD – purchase order header information • OAD – address information • ODT – order detail information • OSM – order summary information
<p><i>Invoice Segments</i></p> <p>An invoice (0926) contains the following four distinct segments:</p> <ul style="list-style-type: none"> • IHD – invoice header information • IRN – invoice remit name information • IDT – invoice detail information • ISM – invoice summary information
<p><i>Data Elements</i></p> <p>The JASS standard contains 31 different data elements.</p>

Screens

You use the following Gentran:Basic/Structure screens to create a standard:

- Version screen (EDIM110)
- Transaction screen (EDIM120)
- Segments screen (EDIM130)
- Segment Element screen (EDIM140)
- Data Element Definition screen (EDIM160)
- Data Element Codes Values screen (EDIM170)
- User Envelope Specification screen (EDIM190)
- Version/Outbound Specification screen (EDIM191)

Note: For detailed information about using these Gentran:Basic screens, see Chapter 3, “The Standards Subsystem,” in the *Gentran:Basic for zSeries Release 6.4 User’s Guide*, or Chapter 3, “Screens,” in this guide.

Exercise

Complete the following steps to create a standard. The screens already contain information for the JASS standard.

1. From the Standards Maintenance Menu, type **2** to select Version and press **Enter**.

The system displays the Version screen.

2. Type **JASS** in the Version ID field and press **Enter**.

```

EDIM110 2.2_____          VERSION          XXX          12/01/2005
                                          12:00:00

Version Id.....:  JASS_____
Agency.....:    SC_
Description.....:  LAWN_CARE_PROPRIETARY_STANDARD_____
Envelope Type....:  D  (A=ANA, E=Edifact, T=TDCC, X=X12, D=User Defined)
Update Allowed...:  Y  (Y/N)

                                          Last Update Date: 12/01/05
                                          Time: 12:00:00
                                          User: XXX

Enter PF1=Help PF2=Tdir  PF3=Exit PF4=Vdir          PF5=Trans          PF6=Nxt Vers
                                          PF9=Add PF10=Updt
    
```

The system displays the following standards information already entered on the Version screen for the JASS standard in this tutorial. If you were creating your own standard you would enter your own appropriate values.

Version Screen	
Field:	Entered Value:
Version ID	JASS
Agency	SC
Description	Lawn Care Proprietary Standard
Envelope Type	D – User Defined
Update Allowed	Y

3. Press **PF5=Trans**.

The system displays the Transaction screen for the first transaction (0909).

```

EDIM120 2.5_____      TRANSACTION                XXX      12/01/2005
                                                12:00:00

Transaction Code.....: 0909__
Version Id.....: JASS_____ Agency.: SC_
Description.....: PURCHASE_ORDER_____
Functional Id.....: 0909__
LS/LE Bounding Ind...: _ (Y/N/ )
NTE Float Ind.....: _ (Y/N/ )
Number of Segments...: 0004          Repeat Ind: N (Y/N)

                                                Job Name: _____

                                                Last Update Date: 12/01/05
                                                Time: 12:00:00
                                                User: XXX

Enter PF1=Help PF2=Vers  PF3=Exit PF4=Tdir      PF5=Segment  PF6=Nxt Tran
                PF9=Add PF10=Updt PF11=Del      PF14=VTdir

                PF7=Rpt

```

4. Press **PF6=Nxt Tran**.

The system displays the Transaction screen for the 0926 transaction.

```

EDIM120 2.5_____      TRANSACTION                XXX      12/01/2005
                                                12:00:00

Transaction Code.....: 0926__
Version Id.....: JASS_____ Agency.: SC_
Description.....: INVOICE_____
Functional Id.....: 0926__
LS/LE Bounding Ind...: _ (Y/N/ )
NTE Float Ind.....: _ (Y/N/ )
Number of Segments...: 0004          Repeat Ind: N (Y/N)

                                                Job Name: _____

                                                Last Update Date: 12/01/05
                                                Time: 12:00:00
                                                User: XXX

PRESS PF6 TO REVIEW NEXT TRANSACTION RECORD
Enter PF1=Help PF2=Vers  PF3=Exit PF4=Tdir      PF5=Segment  PF6=Nxt Tran
                PF9=Add PF10=Updt PF11=Del      PF14=VTdir

                PF7=Rpt

```


The following table describes information already added to the Transaction screen for the tutorial. JASS transactions are 0909 and 0926 only. If there were more transactions you could continue to press **PF6=Nxt Tran** to view or edit that information.

If you were creating your own standard, you would enter your own appropriate information on this screen.

Transaction Screen	
Field:	Entered Value:
For Purchase Order	
Transaction Code:	0909
Version ID:	JASS
Agency:	SC Note: The Agency field requires a value, however, you can enter any option. The value will not affect processing.
Description:	Purchase Order
Functional Id:	0909
Number Segments:	4
Repeat Ind:	N
For Invoice	
Transaction Code:	0926
Version ID:	JASS
Agency:	SC
Description:	Invoice
Functional Indicator:	0926
Number Segments:	4
Repeat Ind:	N

5. Type **0909** over the value in the Transaction Code field and Press **Enter** to return to the Purchase Order transaction for this tutorial.
6. Press **PF5=Segment**.

The system displays the Segments screen for the 0909 transaction.

```

Add Delete Update Select Info
EDIM130 2.6 _____ SEGMENTS          XXX      12/01/2005
                                           12:00:00

Version Id.....: JASS _____ Agency...: SC_
Transaction ID...: 0909__

*****Segment*****  Man ***Use***  **Loop***  DE   Seg  Loop  LP  Act
A  No   Id  Ver Ty Req Cde Min  Max  Min  Max  Count Grp  Id  B/E  Cnt
-  0010 OHD_ 00 H  _ M  1  _  _  _  _  _  8  _  _  _  _
      PURCHASE_ORDER_HEADER
-  0020 OAD_ 00 H  _ O  _  _  3  _  _  _  6  _  _  _  _
      ADDRESS_INFORMATION
-  0040 ODT_ 00 D  _ M  1  _  _  1  _  9999  _  9  _  ODT_  _  B  _
      PURCHASE_ORDER_DETAIL
-  0050 OSM_ 00 S  _ M  1  _  _  1  _  _  _  3  _  _  _  _
      PURCHASE_ORDER_SUMMARY
-  _  _  _  _  _  _  _  _  _  _  _  _  _  _  _  _

END OF SEGMENTS
Enter PF1=Help          PF3=Exit PF4=Trans      PF5=Elements  PF6=Nxt Tran
      PF7=Bwd  PF8=Fwd
    
```

The following information has already been added to the 0909 Segments screen.

Segments Screen										
Field:	Seg Num	Seg ID	Ty	Man Cde	Max Use	Max Loop	DE Count	Loop ID	LP B/E	Description
Entered Value:	0010	OHD	H	M	1		8			Purchase Order Header
	0020	OAD	H	O	3		6			Address Information
	0040	ODT	D	M	1	9999	9	ODT	B	Purchase Order Detail
	0050	OSM	S	M	1		3			Purchase Order Summary

- In the Transaction ID field, type **0926** and press **Enter** to display the segment screen for the invoice.

The system displays the Segments screen for the 0926 transaction.

```

Add Delete Update Select Info
EDIM130 2.6_____ SEGMENTS          XXX      12/01/2005
                                           12:00:00

Version Id.....: JASS_____ Agency...: SC_
Transaction ID...: 0926__

*****Segment*****  Man ***Use***  **Loop***  DE   Seg  Loop  LP  Act
A  No  Id  Ver Ty Req Cde Min  Max  Min  Max  Count Grp  Id  B/E  Cnt
- 0010 IHD_ 00 H  _  M  1  _  _  _  _  _  8  _  _  _  _
      INVOICE_HEADER
- 0020 IRN_ 00 H  _  M  1  _  _  _  _  _  6  _  _  _  _
      REMIT_NAME_INFORMATION
- 0030 IDT_ 00 D  _  M  1  _  _  1  _  9999  _  9  _  IDT_  B  _
      INVOICE_DETAIL
- 0040 ISM_ 00 S  _  M  1  _  _  _  _  _  _  3  _  _  _  _
      INVOICE_DETAIL
-  _  _  _  _  _  _  _  _  _  _  _  _  _  _  _  _

END OF SEGMENTS
Enter PF1=Help          PF3=Exit PF4=Trans      PF5=Elements  PF6=Nxt Tran
      PF7=Bwd  PF8=Fwd
    
```

The following table lists information already added to the 0926 Segments screen:

Segments Screen										
Field:	Seg Num	Seg ID	Ty	Man Cde	Max Use	Max Loop	DE Count	Loop ID	Lp B/E	Description
Entered Value:	0010	IHD	H	M	1		8			Invoice Header
	0020	IRN	H	M	1		6			Remit Name Information
	0030	IDT	D	M	1	9999	9	IDT	B	Invoice Detail
	0050	ISM	S	M	1		3			Invoice Detail

How to use

To add the segment information on this screen (as you would need to do if the JASS standard were not set up for you already), you complete the following tasks:

- Type the information for a segment.
 - Type **A** in the A (Action Code) field corresponding to the segment
 - Press **Enter** to add the information.
8. To select an individual segment to code the elements, type **S** in the A (Action Code) field corresponding to the segment and press **PF5=Elements**.

JASS Standard Segment Element Structures

0909 Purchase Order

The following table details the Segment Element structure for the 0909 purchase order.

Seg ment	Seg Seq	Sub Ele	Man Ele	Com Ele	Aud Ind	Ele ID	Element Description	ST Pos	Length
OHD	02	00	M	M		4	Purchase Order Number	1	6
	04	00	M	M		6	Ship-To Name	7	25
	06	00	M	M		7	Bill-To Name	32	25
	08	00	M	M		2	Date Type	57	2
	10	00	M	M		1	Date	59	5
	12	00	M	M		2	Date Type	64	2
	14	00	M	M		1	Date	66	5
	16	00	O	O		29	Reserve Element 7	71	7
OAD	02	00	M	M		8	Address Code	1	2
	04	00	M	M		9	Address	3	20
	05	00	M	M		10	City	23	20
	06	00	M	M		11	State	43	2
	10	00	M	M		12	Zip Code	45	9
	12	00	O	O		24	Reserve Element 24	54	24
ODT	02	00	M	M		14	Line Item Number	1	4
	04	00	M	M		15	Item Number	5	5
	06	00	M	M		16	Quantity Type	10	2
	08	00	M	M		17	Quantity	12	6
	10	00	M	M		20	Unit of Measure	18	4
	12	00	M	M		18	Price	22	10
	14	00	M	M		19	Extended Price	32	14
	16	00	M	M		21	Item Description	46	27
	18	00	0	0		27	Reserve Element 2	73	2
OSM	02	00	M	M		23	Total Line Items	1	4
	04	00	M	M		22	Total Amount	5	16
	06	00	O	O		28	Reserve Element 57	21	57

0926 Invoice

The following table details the Segment Element structure for the 0926 invoice.

Segment	Seg Seq	Sub Ele	Man Ele	Com Ele	Aud Ind	Ele ID	Element Description	ST Pos	Length
IHD	02	00	M	M		3	Invoice Number	1	6
	04	00	M	M		4	PO Number	7	6
	06	00	M	M		2	Date Type	13	2
	08	00	M	M		1	Date	15	5
	10	00	M	M		2	Date Type	20	2
	12	00	M	M		1	Date	22	5
	14	00	M	M		13	Billing Cycle Code	27	2
	16	00	O	O		25	Reserve Element 49	29	3
IRN	02	00	M	M		5	Remit-To Name	1	25
	04	00	M	M		9	Address	26	20
	06	00	M	M		10	City	46	20
	08	00	M	M		11	State	66	2
	10	00	M	M		12	Zip Code	68	9
	12	00	O	O		26	Reserve Element 1	77	1
IDT	02	00	M	M		14	Line Item Number	1	4
	04	00	M	M		15	Item Number	5	5
	06	00	M	M		16	Quantity Type	10	2
	08	00	M	M		17	Quantity	12	6
	10	00	M	M		20	Unit of Measure	18	4
	12	00	M	M		18	Price	22	10
	14	00	M	M		19	Extended Price	32	14
	16	00	M	M		21	Item Description	46	27
	18	00	O	O		27	Reserve Element 2	73	2
ISM	02	00	M	M		23	Total Line Items	1	4
	04	00	M	M		22	Total Amount	5	16
	06	00	O	O		28	Reserve Element 57	21	57

Notes: Reserve Elements are place holders used for filler.

See “Standards Maintenance” in Chapter 3 of this guide for more information on segment IDs.

9. On the Segment screen, change the Transaction ID value to 0909 (for the purposes of this tutorial) and press **Enter**.

The system displays the Segment element information for transaction 0909.

10. Press **PF5=Elements**.

The system displays the 0909 OHD Segment Element screen.

```

Add Update Delete Select Info
EDIM140 2.7 _____ SEGMENT ELEMENT          XXX      12/01/2005
                                                    12:00:00

Version Id...: JASS _____ Agency...: SC_
Segment Id...: OHD_   Segment Version...: 00

Seq  Ele  Sub Man Com Ad  Element      **Group**
A   Num  Seq  Ele Ele Ele  In  Id  Ver  R   Dsg  Ty  Description      Cd
-   -    -    -  -  -  -  -  -  -   -   -   -
-   0002 002  000 M  M  -  4  00 0001  -   -   PURCHASE ORDER NUMBER
-   0004 004  000 M  M  -  6  00 0001  -   -   SHIP-TO NAME
-   0006 006  000 M  M  -  7  00 0001  -   -   BILL-TO NAME
-   0008 008  000 M  M  -  2  00 0001  -   -   DATE TYPE
-   0010 010  000 M  M  -  1  00 0001  -   -   DATE
-   0012 012  000 M  M  -  2  00 0001  -   -   DATE TYPE
-   0014 014  000 M  M  -  1  00 0001  -   -   DATE
-   0016 016  000 O  O  -  29 00 0001  -   -   RESERVE ELEMENT 7
-   -    -    -    -  -  -  -  -  -  -   -   -   -
-   -    -    -    -  -  -  -  -  -  -   -   -   -

END OF SEGMENT ELEMENTS
Enter PF1=Help PF2=Actvty PF3=Exit PF4=Segment  PF5=Elem Def  PF6=Nxt Segm
      PF7=Bwd  PF8=Fwd
    
```

The following table details the information already added to the screen.

Seg.	Ele Seq	Sub Ele	Man Ele	Com Ele	Ad In	Ele. ID	Ver	Element Description	ST Pos	Length
OHD	02	00	M	M		4		Purchase Order Number	1	6
	04	00	M	M		6		Ship-To Name	7	25
	06	00	M	M		7		Bill-To Name	32	25
	08	00	M	M		2		Date Type	57	2
	10	00	M	M		1		Date	59	5
	12	00	M	M		2		Date Type	64	2
	14	00	M	M		1		Date	66	5
	16	00	O	O		29		Reserve Element 7	71	7

Note: We have displayed the OHD segment of the purchase order *only*. The other segments and elements are in the Standards file for you to view.

- To select specific elements, select the element by typing **s** in the A (Action Code) field corresponding to the element and pressing **PF5=Elem Def**.

The system displays the Data Element Definition screen.

```

EDIM160 2.9 _____ DATA ELEMENT DEFINITION PRW 12/01/2005
                                                    12:00:00

Version Id....: JASS _____ Agency.....: SC_

Element Id....: 4 _____ Element Version: 00

Description:
PURCHASE_ORDER_NUMBER _____

Element Type...: AN (AN/ID/R/Nn/DT/D8/TM/T6/T8/CD/B - ALL STANDARDS)
                  (DD/MM/JD/YY/PD/PJ/PM/PY/Pn/Sn - USER DEFINED )
                  (CM/J8/CY/ZD/ZJ/ZM/ZY - USER DEFINED )

Minimum Length: 006

Maximum Length: 00006

Composite Code Definition: _____ Last Update Date: 12/01/05
                                                    Time: 12:00:00
                                                    User: XXX

Enter PF1=Help PF3=Exit PF4=Seg Elem PF5=Code Dir PF6=Nxt Elem
PF9=Add PF10=Updt PF11=Del
    
```

JASS Standard Data Element Listing

The following table illustrates data elements that are already added on the Data Element Definition screen. Those elements with codes can be optionally added to the Data Element Code Values screen. They are not needed for Gentran:Structure because no validation takes place. We recommend that you do code them, because the system displays them when the standards are printed.

Element ID	Element Name	DT TP	Lgth	Codes
1	Date	JD	5	
2	Date Type	ID	2	22 = Invoice Date 33 = Expected Ship Date 44 = Actual Ship Date 55 = Purchase Order Date
3	Invoice Number	AN	6	
4	Purchase Order Number	AN	6	
5	Remit-To Name	AN	25	
6	Ship-To Name	AN	25	
7	Bill-To Name	AN	25	
8	Address Code	ID	2	BT = Billing Address SH = Shipping Address RT = Remit Address
9	Address	AN	20	
10	City	AN	20	
11	State	AN	2	

Element ID	Element Name	DT TP	Lgth	Codes
12	Zip Code	AN	29	
13	Billing Cycle	ID	2	30 = 30 Days 45 = 45 Days 60 = Days 90 = Days
14	Line Item Number	NO	4	
15	Item Number	AN	8	
16	Quantity Type	ID	2	OR = Ordered AS = Actually Shipped
17	Quantity	NO	6	
18	Price	N2	10	
19	Extended Price	N2	14	
20	Unit of Measure	ID	4	UOM1 = Box UOM2 = Carton UOM3 = Gallon UOM4 = Pound
21	Item Description	AN	27	
22	Total Amount	N2	16	
23	Total Line Items	N0	4	
24	Reserve Element 24	AN	24	
25	Reserve Element 49	AN	49	
26	Reserve Element 1	AN	1	
27	Reserve Element 2	AN	2	
28	Reserve Element 57	AN	57	
29	Reserve Element 7	AN	7	

12. For this tutorial, type 2 over the value in the Element Id field and press **Enter**.
13. Press **PF5=Code Dir**.

The system displays the Standard Code Directory screen.

```

Select Info
EDIM171 2.10.1_____ STANDARD CODE DIRECTORY      XXX      12/01/2005
                                                    12:00:00

Version Id:  JASS_____ Agency:  SC_  Language.:  EN_
Element Id:  2_____ Element Version:  00  Min/Max..:  002 /  00002

A  Comp Code/Description
--  --  22_____ INVOICE_DATE_____
--  --  33_____ EXPECTED_SHIP_DATE_____
--  --  44_____ ACTUAL_SHIP_DATE_____
--  --  55_____ PURCHASE_ORDER_DATE_____
--  --  _____
--  --  _____
--  --  _____
--  --  _____
--  --  _____

END OF CODE LIST
Enter PF1=Help      PF3=Exit PF4=Elem Defin PF5=Code Maint PF6=Nxt Code
      PF7=Bwd  PF8=Fwd
    
```

The following information is already added.

Element ID	Element Name	DT TP	Lgth	I/O	Codes
0001	Date	JD	5	B	
0002	Date Type	ID	2	B	22 = Invoice Date 33 = Expected Ship Date 44 = Actual Ship Date 55 = Purchase Order Date

The standards information is now completely entered.

- Press **PF3=Exit** twice.

The system displays the Standards Maintenance Menu.

- Type **12** to select User Envelope Specification.

The system displays the User Envelope Specification screen.

```

Add Delete Update Version/outbound-specification
EDIM190 2.12_____ USER ENVELOPE SPECIFICATION          XXX  12/01/2005
                                                                12:00:00

Starting Segment ID.: _____

A ---Segment-- -Seg ID- -Env- -Usr ID- -Prt ID- -Associated- Ver  Last Updt
   ID      Mod  Start Ln  Lvl D  Start Ln  Start Ln  Hdr/Trl  Mod  Spc  Date User
-  PHD_____ -   78  3  BI B  _____  _____  _____  -   Y  010698 XXX
-  THD_____ -   78  3  BT B  _____  _____  _____  -   Y  042897 XXX
-  20_____ -    1  3  BI B  _____  _____  _____  -   Y  041796 XXX
-  20G_____ -    1  3  BG B  _____  _____  _____  -   N  041796 XXX
-  20T_____ -    1  3  BT B  _____  _____  _____  -   N  041796 XXX
-  99_____ -    1  3  EI B  _____  _____  _____  -   N  041796 XXX
-  99G_____ -    1  3  EG B  _____  _____  _____  -   N  041796 XXX
-  99T_____ -    1  3  ET B  _____  _____  _____  -   N  041796 XXX
-  _____ -    -  -  -  -  _____  _____  _____  -   -  -  -  -  -
-  _____ -    -  -  -  -  _____  _____  _____  -   -  -  -  -  -

END OF USER ENVELOPE RECORDS
Enter PF1=Help          PF3=Exit
      PF7=Bwd   PF8=Fwd
    
```

The following table details information already added on the User Envelope Specification screen.

Note: The 20 and 99 envelopes are for the Compord standards.

Element Description	Segment	Seg Start	Length	Env Lvl	Dir	Part Start	Part Lgth
Packet Header	PHD	78	3	BI	B	1	15
Transaction Header	THD	78	3	BT	B		

- Type **v** in the A (Action Code) field next to the PHD segment ID and press **Enter**.

The system displays the Version Outbound Specification screen for the PHD segment ID.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: PHD          Modifier:          Length:  __80
Default Version ID...: _____ Agency...:  __ Transaction ID:  _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....:  __41         _4          Transaction ID.....:  _____
Sender ID.....:  __ 1         15         Receiver ID.....:  __16         15
Reference Number...:  __51         _9         Generic Element 1...:  __45         _6
Generic Element 2...:  _____          Generic Element 3...:  _____
Generic Element 4...:  _____          Generic Element 5...:  _____
Generic Element 6...:  _____          Generic Element 7...:  _____
Generic Element 8...:  _____          Generic Element 9...:  _____
Generic Element 10...:  _____        Current Date.....:  __31         _6
Current Time.....:  __37         _4          Current Date Format: YY

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX

Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                        PF10=Updt
    
```

This screen defines and maintains envelope version, transaction set, and outbound specification fields for user-defined envelopes.

The following PHD packet header structure information is already added to the screen.

Segment ID	Envelope Element	ST Pos	Length	Screen Field
PHD	Sender-ID	1	15	Sender ID
	Receiver-ID	16	15	Receiver ID
	Current Date (YY)	31	6	Current Date
	Current Time	37	4	Current Time
	Standard Identifier	41	4	Version ID
	Security Code	45	6	Gen Element 1
	Packet Control Number	51	9	Reference Num

The Date and Time fields receive values during the mapping process. The other information derives from the Partner screens. This screen maintains the envelope structure for the mapping process.

- From the Version/Outbound Specification screen, press **PF6=Nxt Env**.

The system displays the Version/Outbound Specification screen for Segment ID THD.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: THD          Modifier:          Length:  __80
Default Version ID...: _____ Agency...:  __ Transaction ID:  _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....:  _____  __ Transaction ID.....:  __1      _4
Sender ID.....:  _____  __ Receiver ID.....:  _____  __
Reference Number...:  __17      _9 Generic Element 1...:  _____  __
Generic Element 2...:  _____  __ Generic Element 3...:  _____  __
Generic Element 4...:  _____  __ Generic Element 5...:  _____  __
Generic Element 6...:  _____  __ Generic Element 7...:  _____  __
Generic Element 8...:  _____  __ Generic Element 9...:  _____  __
Generic Element 10...:  _____  __ Current Date.....:  __5      _8
Current Time.....:  __13      _4 Current Date Format: YY

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX
PRESS PF6 TO REVIEW NEXT USER ENVELOPE RECORD
Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                          PF10=Updt
    
```

The following table illustrates the THD envelope structure information that is already added on the Version/Outbound Specification screen.

Segment ID	Envelope Element	ST Pos	Length	Screen Field
THD	Transaction Type (Number)	1	4	Transaction ID
	Current Date	5	8	Current Date
	Current Time	13	4	Current Time
	Transaction Control Number	17	9	Reference Num

The Segment name field has no reference because it will be mapped as specified on the User Envelope Specification screen.

Partner Configuration

You will complete the following screens to identify a trading partner in this section:

- Partner Selection Menu – EDIM007
- Control Information screen 1 – EDIM015
- Control Information screen 2 – EDIM011
- Group Information screen – EDIM034
- Transaction Information screen – EDIM044
- Name and Address screen – EDIM035

Exercise

For this tutorial, we have created a fictitious trading partner called LAWNVEND.

Note: This portion of the tutorial is illustrated with screens as they appear in Partner/Qualifier processing mode. If you are processing in Relationship mode, your screens will display the fields User and Partner instead of Partner ID and Qualifier. The partner profile ID for Relationship mode for this tutorial is User: YOUR COMPANY; Partner: LAWNVEND. The functionality is the same for either mode.

Complete the following steps to access the Lawnvend trading partner.

1. On the Gentran Main Menu, type **1** to select the Partner Maintenance Menu.
2. Type **1** to select Partner Directory.
3. Type **s** in the A (Action Code) field beside the LAWNVEND trading partner and press **PF5=Maint**.

The system displays the LAWNVEND Partner Selection menu.

```

EDIM007 1.2 _____ PARTNER SELECTION MENU XXX 12/01/2005
                                                    12:00:00

LAWN VENDOR FOR DEMONSTRATION
Part ID: LAWNVEND _____ Qual: _____
Copy ID: _____ Qual: _____
Type the number of your selection below and press ENTER,
or press the PF3 key to Exit.
  _ 1. Header Information
    2. Interchange Directory
    3. Group Directory
    4. Transaction Directory
    5. Name and Address
    6. User Defined
    7. Data Separation
    8. Error Rejection

    9. Copy All Records

Job Name: _____

Enter PF1=Help          PF3=Exit PF4=Dir
    
```

4. Type **1** to select Header Information and press **Enter**.

The system displays the Header Information screen for Lawnvend.

```

EDIM026 1.2.1 _____ HEADER INFORMATION XXX 12/01/2005
                                                    12:00:00

LAWN VENDOR FOR DEMONSTRATION
Part ID: LAWNVEND _____ Qual: _____

Description:
LAWN_VENDOR_FOR_DEMONSTRATION _____
_____

Underscore Character : _
Division . . . . . : 000
Update Allowed . . . : Y (Y/N)

Last Update Date . . : 00/00/00 Time . . : 00:00:00 User . . : SCI

Enter PF1=Help          PF3=Exit          PF5=Idir
    
```

5. Press **PF5=IDir**.

The system displays the Control Information screen 2.

```

EDIM011 _____ CONTROL INFORMATION XXX 12/01/2005
                                           12:00:00

LAWN VENDOR FOR DEMONSTRATION
Part ID: LAWNVEND Qual:
Multiple Envelope Id:
Outbound envelope information for Generic Interchange:
A Envelope ID...: PHD Modifier.....: _
B Sender ID.....: LAWNCUST
C Receiver ID...: LAWNVEND
D Version ID...: JASS
Transaction ID:
E Reference.....: 000000000000000001
F Gen Element 1.: MOWING Gen Element 2.: _____
Gen Element 3.: _____ Gen Element 4.: _____
Gen Element 5.: _____ Gen Element 6.: _____
Gen Element 7.: _____ Gen Element 8.: _____
Gen Element 9.: _____ Gen Element 10.: _____

Enter PF1=Help PF3=Exit PF4=Ctrl PF5=GDir PF14=Info
PF10=Updt
    
```

For outbound processing, the envelope-building process uses the partner profile to pass information during the mapping process. The system defines envelope segments in Standards with their respective positions. The partner profiles move the values into those positions in the mapping process. The following table describes the values.

Callout Indicator in Diagram Above	Field	Mapping Information
A	Envelope ID	Maps to position 78 – 80 (Segment ID) as defined on the User Envelope Specification screen in the standards.
B	Sender ID	Maps to position 1 – 15 (Sender ID) on the Version/Outbound Specification screen.
C	Receiver ID	Maps to position 16 – 30 (Receiver ID) on the Version/Outbound Specification screen.
D	Version ID	Maps to position 41 – 44 (Version ID) on the Version/Outbound Specification screen.
E	Reference	Maps to position 51 – 59 (Reference Number) on the Version/Outbound Specification screen.
F	Gen Element 1	Maps to position 45 – 50 (Generic Element 1) on the Version/Outbound Specification screen.

The following two example screens show the positional relationships formed during the mapping process. The callout indicators on those screens correspond to those shown above.

Example 1

The following illustrates the User Envelope Specification screen with the positional relationships created during the mapping process.

Add Delete Update Version/outbound-specification
 EDIM190 2.12 _____ USER ENVELOPE SPECIFICATION XXX 12/01/2005
 12:00:00

Starting Segment ID...: PHD _____

A

Segment ID	Mod	Start Ln	Env Lvl	Usr ID Start Ln	Prt ID Start Ln	Associated Hdr/Trl	Ver Mod Spc	Last Updt Date	User
PHD		78	3	BI B 16 15	1 15		Y	010698	XXX
THD		78	3	BT B			Y	042897	XXX
20		1	3	BI B	8 9	99	Y	041796	XXX
20G		1	3	BG B		99G	N	041796	XXX
20T		1	3	BT B		99T	N	041796	XXX
99		1	3	EI B		20	N	041796	XXX
99G		1	3	EG B		20G	N	041796	XXX
99T		1	3	ET B		20T	N	041796	XXX

END OF USER ENVELOPE RECORDS
 Enter PF1=Help PF3=Exit
 PF7=Bwd PF8=Fwd

Example 2

The following illustrates the Version/Outbound Specification screen with Envelope Structure information.

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION XXX 12/01/2005
 12:00:00

Segment ID.....: PHD Modifier: Length: 80
 Default Version ID...: Agency...: Transaction ID: _____

Envelope Field	Start	Length	Envelope Field	Start	Length
Version ID.....	41	4	Transaction ID.....		
Sender ID.....	1	15	Receiver ID.....	16	15
Reference Number...	51	9	Generic Element 1..	45	6
Generic Element 2..			Generic Element 3..		
Generic Element 4..			Generic Element 5..		
Generic Element 6..			Generic Element 7..		
Generic Element 8..			Generic Element 9..		
Generic Element 10..			Current Date.....	31	6
Current Time.....	37	4	Current Date Format: YY		

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX

Enter PF1=Help PF3=Exit PF4=User PF6=Nxt Env
 PF10=Updt

D B E C F

8. Press **PF5=GDir** on the Control Information screen 2.

The system displays the Group Directory screen.

9. Type **s** in the A (Action Code) field to select Group ID 0909 on the Group Directory screen and press **PF5=Group**.

The system displays Group Information screen for the 0909 transaction.

You must create a group record because this screen will alert the mapping process to call a map from the JASS standard. Mapping requires a group record to indicate which standard (map) to process.

```

EDIM034 1.2.3.1___          GROUP INFORMATION          XXX  12/01/2005
                                                                12:00:00

          LAWN VENDOR FOR DEMONSTRATION
Part ID:  LAWNVEND          Qual:
Group ID:  0909___        Multiple Env Id:

Outbound envelope information for Generic Group:

Envelope ID...:  ___          Modifier.....:  _
Sender ID.....:  _____
Receiver ID...:  _____
Version ID....:  JASS_____
Transaction ID:  _____          Reference.....:  _____
Gen Element 1.:  _____          Gen Element 2.:  _____
Gen Element 3.:  _____          Gen Element 4.:  _____
Gen Element 5.:  _____          Gen Element 6.:  _____
Gen Element 7.:  _____

Enter PF1=Help          PF3=Exit PF4=GDir          PF5=TDir          PF6=Next Grp
                        PF9=Add PF10=Updt PF11=Del          PF14=Info
  
```

10. Press **PF5=TDir**.
- The system displays the Transaction Directory screen.
11. Type **s** to select the 0909 Trans ID and press **PF5=Trans**.

The system displays the Transaction Information screen. On this screen, we have added the Transaction ID and Reference number to the THD envelope.

```

EDIM044 1.2.4.1___      TRANSACTION INFORMATION      XXX  12/01/2005
                                                                12:00:00

                LAWN VENDOR FOR DEMONSTRATION
Part ID: LAWNVEND                      Qual:
B Transaction ID: 0909 Multiple Env Id:

Translation Map ID Inbound..: _____ Outbound: _____
Application Databank Inbound: F (F/D/N)   Outbound: F (F/D/N)

Outbound envelope information for Generic Transaction:
A Envelope ID..: THD Modifier.....: -
  Sender ID....: _____ Receiver ID...: _____ C
  Version ID...: _____ Reference.....: 0000000000000000001
  Gen Element 1: _____ Gen Element 2.: _____
  Gen Element 3: _____ Gen Element 4.: _____
  Gen Element 5: _____

Enter PF1=Help          PF3=Exit PF4=TDir      PF5=Name      PF6=Nxt Tran
                        PF9=Add PF10=Updt PF11=Del  PF14=Info
    
```

The following table describes the mapping information.

Callout Indicator in Diagram Above	Mapping Information
A	Maps to position 78 – 80 (Segment ID) as defined on the User Envelope Specification screen in the standards.
B	Maps to position 1 – 4 (Transaction ID) on the Version/Outbound Specification screen.
C	Maps to position 17 – 26 (Reference Number) on the Version/Outbound Specification screen.

12. Press **PF5=Name** on the Transaction Information screen to advance to the Name and Address screen.

Name and address information is already added for the Lawnvend trading partner on the Name and Address screen.

```

EDIM035 1.2.5_____          NAME AND ADDRESS          XXX 12/01/2005
                                                12:00:00

Partner...:  LAWNVEND                      Qual:

Name...:    LAWN_VENDOR_FOR_DEMONSTRATION_____
Address:    123_STATE_STREET_____
            _____
            _____
            _____
City...:    ANYTOWN_____
State...:   OH_____
Zip...:    00000 - 0000    Country Code: 00
Contact:   CATALOG_MANAGER_____
Phone...:  ( ___ ) ___ - ___ x ___
International Dial Code: 000

Enter PF1=Help          PF3=Exit PF4=Trans    PF5=User Def
                        PF9=Add PF10=Updt PF11=Del    PF14=Info
  
```

13. Press **F3=Exit** three times.
The system displays the Gentran Main Menu.
14. Type **5** to select Mapping Maintenance Menu and press **Enter**.
The system displays the Mapping Maintenance Menu.
15. Type **1** to select Application Definition and press **Enter**.
The system displays the Application Definition Menu.
16. Type **1** to select Application Directory and press **Enter**.
The system displays the Application Directory.
17. Type **s** in the A (Action Code) field next to the Application ID POFILEF and press **PF5=Data ID**.
The system displays the Application Data ID screen.

Mapping Configuration

For this exercise, we have supplied the POFILEF application definition.

You must complete the following screens to identify the information you want to map.

- Application Data ID screen – EDIM552
- Transaction Maintenance screen – EDIM503
- Transaction Maintenance – Gentran:Structure – EDIM516

Exercise

You navigated to the Application Data ID screen as you completed the previous section. The Application Data ID is already coded for you. The Mapping process on this screen operates like normal Gentran:Basic mapping.

```

EDIM552 5.1.2_____ APPLICATION DATA ID XXX 12/01/2005
                                                12:00:00

Application Data ID.....: POFILEF___ Send or Receive: S
Division Code.....: 000
Description.....: PURCHASE_ORDER_MASTER_FILE_FIX
Functional Group.....: PO___ OG___ 0909__

Fixed or Variable Length..: V (F/V)
Record Length.....: 00250
Record Type Start Pos.....: 00021 Length.....: 03
Inbound Pass-Thru.....: -
Underscore Character.....: -
Update Allowed.....: Y

Last Update User.....: SCI Date.....: 00/00/00
Time.....: 00:00:00

Enter PF1=Help PF2=Copy PF3=Exit PF4=Dir PF5=Records PF6=Refer
PF9=Add PF10=Updt PF11=Del PF12=NuMap PF13=Envel
  
```

Complete the following steps to identify the information to map.

1. Press **PF3=Exit** twice.
The system displays the Mapping Maintenance Menu.
2. Type **2** to select Transaction Mapping and press **Enter**.
The system displays the Transaction Mapping Menu.
3. Type **1** to select Transaction Directory and press **Enter**.
The system displays the Transaction Directory.

- Type **s** in the A (Action Code) field next to the Transaction ID JASSPO and press **PF5=Trans**.

The system displays the Transaction Maintenance screen.

Points to JASS standard
User-defined envelope

```

EDIM503 5.2.2 _____ TRANSACTION MAINTENANCE XXX 12/01/2005
                                           12:00:00

Transaction ID.....: JASSPO _____ Send or Receive (S/R)...: S
Division Code.....: 000
Description.....: PURCHASE ORDER FOR JASS STDS
Standards Version.....: JASS _____ Agency: SC
Transaction Set.....: 0909
Transaction Set Release...: _____ (0-9, ANA Tradacoms Only)
Transaction Status.....: T (D=Development, T=Test, P=Production)
Use Code.....: G (G=General, P=Partner Specific)
Envelope Type.....: D (E=Edifact, X=X12, U=UCS, G=GS, A=ANA, D=User)
Application Data ID.....: POFILEF _____
Application Selection Field Values: _____

Standard Type.....: F (V=Variable, F=Fixed)
RSGRSG Level.....: _____ (1/2/ ANA Tradacoms Only)
Underscore Character.....: _____
Update Allowed.....: Y Job Name: _____

Enter PF1=Help PF2=Fixed PF3=Exit PF4=Dir PF5=Segments PF6=Copy
PF7=Rpt PF9=Add PF10=Updt PF11=Del PF12=NuMap PF14=Info
    
```

Fixed-format type

- Press **PF2=Fixed**.

The system displays the Transaction Maintenance – (Gentran:Structure) screen for fixed format standards.

```

EDIM516 _____ TRANSACTION MAINTENANCE XXX 12/01/2005
                (Gentran:Structure)                12:00:00

Transaction ID.....: JASSPO _____ S/R.....: S
Division Code.....: 000
Description.....: PURCHASE ORDER FOR JASS STDS
Standards Version.....: JASS _____ Agency.....: SC
Transaction Set.....: 0909
Transaction Set Release...: _____ (0-9, ANA Tradacoms Only)

Envelope Format.....: F (V=Variable, F=Fixed)
Segment ID Start.....: 78 (1 to 32743)
Segment ID Length.....: 3 (1 to 10)

Last Update Date.....: 00/00/00
Time.....: 00:00:00
User.....: SCI

Enter PF1=Help PF3=Exit PF4=Maint PF5=Segments
PF10=Updt
    
```

Where mapping segment ID starts and ends

For this JASS standard model, we have not coded a specific segment ID element in the Standards file, but the Mapper will put the segment ID in position 78 for 3 bytes.

Gentran:Basic Users

The Batch jobs STRINB and STROUT, which we supply with the product, run the installation verification. The jobs use test data, the JASSPO and JASSIN maps, the POFILEF and INFILEF applications, and the JASS standard. You may run these jobs again to examine the results more closely.

Gentran:Realtime Users

The inbound and outbound processes from the installation verification can be reprocessed to allow you to examine the results more closely.

See Chapter 4, “Performing Verification for Gentran:Realtime Users,” in the *Gentran:Structure for zSeries Release 6.4 Installation Guide*.

Implementing Gentran:Structure

This section explains how to proceed with the actual implementation of Gentran:Structure, including the resources you will need and the questions you must ask.

Figure 2.7 illustrates the implementation process that begins by installing the Gentran:Structure Install Tape. The other implementation steps may be executed in any order.




Figure 2.7 Implementation

Processing Daily Business

Inbound Flow

The first step of the inbound flow is the Inbound Fixed/Variable Splitter program (EBDI094). This program is optional and is only needed if you receive fixed-format and variable-format data in the same transmission. The next step is the Inbound Pre-Processor program (EBDI083), which reads the partner profile to create the map records and the user envelope files to define control records. Finally, the Inbound Mapper (EBDI042) processes the data.

Outbound Flow

The Outbound Mapper runs either fixed data or variable data. The Mapper reads the partner profile and envelope file to obtain information to build envelopes. An optional, user-written Format Specific Envelope Generator may be used to generate envelopes outside the mapping process. No editing or compliance checking is performed.

Maintenance Procedures

No additional daily maintenance procedures need to be executed as a result of Gentran:Structure installation.

The following activity needs to be executed on an as-needed basis, depending on particulars of your company's operations:

- Add the Backup of User Envelope file to your normal backup activity.
- If you are using databanking on Gentran:Structure, Databank Maintenance on the application databank is required.

Gentran:Structure Tutorial

Purpose

The Gentran:Structure Tutorial gives you practical experience working with the online components of the system.

The phases of work are:

1. Setting up the standards files.
2. Building an application definition and a transaction definition for mapping.
3. Creating a trading partner.

In this Tutorial, you will complete the sample scenario we have developed for this product. The following table outlines the stages of the process.

Stage	Description
1	Work with the JASS standard to create a new segment for outbound purchase orders. This segment is the Order Notes (ONT) segment. You will add this segment and its associated data elements.
2	Add packet and transaction trailer envelopes for the JASS standard.
3	Modify the transaction map JASSPO to map note information to the EDI output file.
4	Modify the transaction map JASSIN to capture packet and transaction control numbers.
5	Modify the trading partner LAWNVEND to add transaction and segment counts to pass to the new defined trailer envelopes.

At the completion of the tutorial, you will run the jobs **STRINB** and **STROUT** again.

Standards Maintenance

Overview

In this section of the Tutorial, you will:

- Add the ONT segment to the JASS standard.
- Add trailer envelopes used in this standard.

To accomplish the tasks listed above, you will complete the following process:

Stage	Description
1	Increase number of segments to 5 on the Transaction screen.
2	Add ONT segment on Segments screen.
3	Add Note Type (element 30) on the Elements screen, and then add codes for this element on the Data Element Code Values screen.
4	Add Note Text (element 31) on the Elements screen.
5	Update PHD to point to its associated trailer PTR on the User Envelope Specification screen.
6	Update THD to point to its associated trailer TTR on the User Envelope Specification screen.
7	Add envelope PTR and point to its associated header PHD on the User Envelope Specification screen.
8	Add envelope TTR and point to its associated header THD on the User Envelope Specification screen.
9	Fill in detail for PTR envelope on the Version/Outbound Specification screen.
10	Fill in detail for TTR envelope on the Version/Outbound Specification screen.

Exercise

Complete the following steps to complete the Standards Maintenance portion of the Tutorial.

1. On the Gentran Main Menu, type **2** to select the Standards Maintenance Menu.
The system displays the Standards Maintenance Menu.
2. Type **2** to select Version and press **Enter**.
The system displays the Version screen.
3. Type **JASS** in the Version Id field and press **Enter**.

The system displays the Version screen with JASS standard data.

```

EDIM110 2.2_____          VERSION          XXX      12/01/2005
                                           12:00:00

Version Id.....:  JASS_____
Agency.....:     SC_
Description.....:  LAWN_CARE_PROPRIETARY_STANDARD_____
Envelope Type....: D  (A=ANA, E=Edifact, T=TDCC, X=X12, D=User Defined)
Update Allowed...: Y  (Y/N)

                                           Last Update Date: 12/01/05
                                           Time: 12:00:00
                                           User: XXX

Enter PF1=Help PF2=Tdir  PF3=Exit PF4=Vdir      PF5=Trans      PF6=Nxt Vers
                                           PF9=Add PF10=Updt

```

4. Press **PF5=Trans** to advance to the Transaction screen.

We are adding the ONT – Purchase Order Notes segment to the 0909 Purchase Order document.

5. To increase the number of segments from four to five, type **5** in the No of Segments field and press **PF10=Updt**.

```

EDIM120 2.5_____          TRANSACTION          XXX      12/01/2005
                                           12:00:00

Transaction Code.....:  0909__
Version Id.....:     JASS_____ Agency.:  SC_
Description.....:     PURCHASE_ORDER_____
Functional Id.....:    0909__
LS/LE Bounding Ind...:  _ (Y/N/ )
NTE Float Ind.....:   _ (Y/N/ )
Number of Segments...:  0005          Repeat Ind:  N (Y/N)

                                           Job Name: _____

                                           Last Update Date: 12/01/05
                                           Time: 12:00:00
                                           User: XXX

TRANSACTION RECORD UPDATED
Enter PF1=Help PF2=Vers  PF3=Exit PF4=Tdir      PF5=Segment    PF6=Nxt Tran
      PF7=Rpt          PF9=Add PF10=Updt PF11=Del      PF14=VTdir

```

6. Press **PF5=Segment**.

The system displays the Segments screen.

- Enter the ONT information from the following table. (Type the information in the first available line by typing over the OHD information; the system will place the segment in numerical order.)

Seg Num	Seg ID	Seg Version	Type	Req	Man Code	Min Use	Max Use	Min Loop	Max Loop	DE Count	Seg GRP	Loop ID	Loop B/E	Act CNT	Desc.
0030	ONT	00	H		O	1	25			2					Purchase Order Notes

- Type **a** in the A (Action Code) field for your ONT line and press **Enter**.

The system displays the Segments screen with your new segment in correct numerical order.

Note: After you press **Enter** to add the ONT information, you may need to press **PF7=Bwd** to display the list from the beginning, as illustrated below.

```

Add Delete Update Select
EDIM130 2.6 _____ SEGMENTS XXX 12/01/2005
12:00:00

Version Id.....: JASS _____ Agency...: SC_
Transaction ID...: 0909__

*****Segment*****  Man ***Use***  **Loop***  DE  Seg  Loop  LP  Act
A  No  Id  Ver Ty Req Cde Min  Max  Min  Max  Count Grp  Id  B/E  Cnt
- 0010 OHD_ 00 H  _ M  1  _ 1  _  _  _  8  _  _  _
PURCHASE_ORDER_HEADER
- 0020 OAD_ 00 H  _ O  _  _ 3  _  _  _  6  _  _  _
ADDRESS_INFORMATION
- 0030 ONT_ 00 H  _ O  1  _ 25  _  _  _  2  _  _  _
PURCHASE_ORDER_NOTES
- 0040 ODT_ 00 D  _ M  1  _ 1  1  _ 9999  _ 9  _ ODT_  _ B  _
PURCHASE_ORDER_DETAIL
- 0050 OSM_ 00 S  _ M  1  _ 1  _  _  _  3  _  _  _
PURCHASE_ORDER_SUMMARY

BEGINNING OF SEGMENTS
Enter PF1=Help PF3=Exit PF4=Trans PF5=Elements PF6=Nxt Tran
PF7=Bwd PF8=Fwd
    
```

- Type **s** in the A (Action Code) field corresponding to the ONT segment and press **PF5=Elements**.

The system displays the Segment Element screen.

- On the Segment Element screen, enter the ONT information from the following table.

Seg	Seg Num	Ele/Seq	Sub Ele	Man Ele	Com Ele	Aud Ind	Ele ID	Ele Ver	Repeat	Group DSG	Ty
ONT	0001	001	000	M	M		30	00	1		
	0002	002	000	M	M		31	00	1		

- To add the information you have entered, type **A** in the A (Action Code) field for both lines and press **Enter**.

The system displays the Segment Element screen with the ONT element information and a Status value showing **ADD: 2**.

```

Add Update Delete Select Info
EDIM140 2.7 _____ SEGMENT ELEMENT          XXX      12/01/2005
                                                12:00:00

Version Id...: JASS_____ Agency...: SC_
Segment Id...: ONT_   Segment Version...: 00

Seq  Ele  Sub Man Com Ad  Element          **Group**
A  Num  Seq  Ele Ele Ele In  Id  Ver  R   Dsg  Ty  Description      Cd
-  0001 001 000 M  M  -   30  00 0001  -   -   NOT AVAILABLE
-  0002 002 000 M  M  -   31  00 0001  -   -   NOT AVAILABLE
-  -   -   -   -   -   -   -   -   -   -   -   -
-  -   -   -   -   -   -   -   -   -   -   -   -
-  -   -   -   -   -   -   -   -   -   -   -   -
-  -   -   -   -   -   -   -   -   -   -   -   -
-  -   -   -   -   -   -   -   -   -   -   -   -
-  -   -   -   -   -   -   -   -   -   -   -   -
-  -   -   -   -   -   -   -   -   -   -   -   -
-  -   -   -   -   -   -   -   -   -   -   -   -
-  -   -   -   -   -   -   -   -   -   -   -   -
-  -   -   -   -   -   -   -   -   -   -   -   -

END OF SEGMENT ELEMENTS                      STATUS  ADD: 2 DEL: 0 UPD: 0
Enter PF1=Help PF2=Actvty PF3=Exit PF4=Segment PF5=Elem Def PF6=Nxt Segm
      PF7=Bwd  PF8=Fwd
    
```

- Type **S** in the A (Action Code) field corresponding to the 0030 element and press **PF5=Elem Def**.

The system displays the Data Element Definition screen.

- Enter the information from the following table to add the 30 element.

Element ID	Element Description	Element Type	Minimum Length	Maximum Length	Composite Code Definition
30	Note Type	ID	002	0002	

- Press **PF9=Add** to add the element information you have entered.

The system displays the completed Data Element Definition screen.

```

EDIM160 2.9 _____ DATA ELEMENT DEFINITION XXX 12/01/2005
                                                12:00:00

Version Id....: JASS _____ Agency.....: SC_

Element Id....: 30___ Element Version: 00

Description:
NOTE_TYPE _____

Element Type...: ID (AN/ID/R/Nn/DT/D8/TM/T6/T8/CD/B - ALL STANDARDS)
                  (DD/MM/JD/YY/PD/PJ/PM/PY/Pn/Sn - USER DEFINED )
                  (CM/J8/CY/ZD/ZJ/ZM/ZY - USER DEFINED )

Minimum Length: 002

Maximum Length: 00002

Composite Code Definition: _____ Last Update Date: 12/01/05
                                                Time: 12:00:00
                                                User: XXX

ELEMENT ID INSERTED
Enter PF1=Help PF3=Exit PF4=Seg Elem PF5=Code Dir PF6=Nxt Elem
PF9=Add PF10=Updt PF11=Del

```

15. Press **PF5=Code Dir**.

The system displays the Standard Code Directory screen for this element.

16. Press **PF3=Exit**.

The system displays the Standard Code Menu.

17. Type **2** to select Standard Code Maintenance and press **Enter**.

The system displays the Standard Code Maintenance screen.

Adding element information to this screen is optional, but it is helpful.

18. For this Tutorial, type the following information in the Code/Description fields:

Note: Type the code number on the top line and the description on the second line.

- 01 – ORDER INSTRUCTIONS
- 02 – HANDLING
- 03 – PACKAGING
- 04 – SHIPPING INSTRUCTIONS
- 05 – GENERAL

19. Type **A** in the A (Action Code) field and press **Enter** to add the information you have entered.

The system displays the Standard Code Maintenance screen with the new element information.

20. Press **PF4=Code Dir**.

The system displays the Standard Code Directory screen.

```

Select Info
EDIM171 2.10.1_____ STANDARD CODE DIRECTORY      XXX      12/01/2005
                                                    12:00:00

Version Id:  JASS_____ Agency:  SC_  Language.:  EN_
Element Id:  30___ Element Version:  00  Min/Max...:  002 /  0002

A  Comp Code/Description

--  --  01___ ORDER_INSTRUCTIONS_____
--  --  02___ HANDLING_____
--  --  03___ PACKAGING_____
--  --  04___ SHIPPING_INSTRUCTIONS_____
--  --  05___ GENERAL_____
--  --  _____
--  --  _____
--  --  _____
--  --  _____

END OF CODE LIST
Enter  PF1=Help      PF3=Exit  PF4=Elem Defn  PF5=Code Maint  PF6=Nxt Code
      PF7=Bwd  PF8=Fwd
    
```

21. Press **PF4=Elem Defn**.

The system displays the Data Element Definition screen.

22. Enter the following Note Text information (type over the existing information).

Element Id	Description	Element Type	Minimum Length	Maximum Length	Composite Code Definition
31	Note Text	AN	075	00075	Spaces

23. Press **PF9=Add** to add the information you entered.

The system displays the completed Data Element Definition screen.

```

EDIM160 2.9 _____ DATA ELEMENT DEFINITION XXX 12/01/2005
12:00:00

Version Id....: JASS _____ Agency.....: SC_

Element Id....: 31___ Element Version: 00

Description:
NOTE_TEXT_____

Element Type...: AN (AN/ID/R/Nn/DT/D8/TM/T6/T8/CD/B - ALL STANDARDS)
(DD/MM/JD/YY/PD/PJ/PM/PY/Pn/Sn - USER DEFINED )
(CM/J8/CY/ZD/ZJ/ZM/ZY - USER DEFINED )

Minimum Length: 075

Maximum Length: 00075

Composite Code Definition: _____ Last Update Date: 12/01/05
Time: 12:00:00
User: XXX

ELEMENT ID INSERTED
Enter PF1=Help PF3=Exit PF4=Seg Elem PF5=Code Dir PF6=Nxt Elem
PF9=Add PF10=Updt PF11=Del
  
```

24. Press **PF3=Exit**.

The system displays the Standards Maintenance Menu.

25. Type **12** to select User Envelope Specification.

The system displays the User Envelope Specification screen.

First, you must update the PHD and THD to point to their associated trailers, PTR and TTR:

26. For PHD, type **U** in the A (Action Code) field, and **PTR** in the Associated Hdr/Trl field.
27. For THD, type **TTR** in the Associated Hdr/Trl field, and **U** in the A (Action Code) field.
28. Press **Enter** to add both trailers.

The system displays the screen with the trailers added.

29. To add the associated trailers, type the following trailer information over the existing information (the system lists the new entries in the correct order).

Element Description	Segment	Seg Start	Length	Env Lvl	Dir	Part Start	Part Lgth	Assoc HD/TR
Packet Trailer	PTR	78	3	EI	B			PHD
Transaction Trailer	TTR	78	3	ET	B			THD

30. Type **A** in the A (Action Code) field for the two lines you have entered and press **Enter**.

The system displays the screen with the addition of the associated trailers in the list.

```

Add Delete Update Version/outbound-specification
EDIM190 2.12_____ USER ENVELOPE SPECIFICATION          XXX  12/01/2005
                                                                12:00:00

Starting Segment ID.: _____

A ---Segment-- -Seg ID- -Env-  -Usr ID-  -Prt ID-  -Associated- Ver  Last Updt
   ID      Mod  Start Ln Lvl D  Start Ln  Start Ln Hdr/Trl  Mod Spc  Date User
- PHD_____ -   78  3  BI B  _____  _____ 1 15 PTR_____ -   Y  072301 XXX
- PTR_____ -   78  3  EI B  _____  _____  _____ PHD_____ -   N  072301 XXX
- THD_____ -   78  3  BT B  _____  _____  _____ TTR_____ -   Y  072301 XXX
- TTR_____ -   78  3  ET B  _____  _____  _____ THD_____ -   N  072301 XXX
- 20_____ -    1  3  BI B  _____  _____  8  9 99_____ -   Y  041796 XXX
- 20G_____ -    1  3  BG B  _____  _____  _____ 99G_____ -   N  041796 XXX
- 20T_____ -    1  3  BT B  _____  _____  _____ 99T_____ -   N  041796 XXX
- 99_____ -    1  3  EI B  _____  _____  _____ 20_____ -   N  041796 XXX
- 99G_____ -    1  3  EG B  _____  _____  _____ 20G_____ -   N  041796 XXX
- 99T_____ -    1  3  ET B  _____  _____  _____ 20T_____ -   N  041796 XXX

Enter PF1=Help          PF3=Exit
      PF7=Bwd   PF8=Fwd

                                STATUS..ADD: 2 DEL: 0 UPD: 0
    
```

31. Type **v** in the A (Action Code) field for the PTR segment and press **Enter**.

The system displays the Version/Outbound Specification screen.

32. Add the following PTR information to the screen.

Segment ID	Screen Field	ST Pos	Length	Envelope Element
PTR	Gen Element 2	1	8	Number of Segment in Packet
	Gen Element 3	9	8	Number of Trans in Packet
	Reference Number	17	9	Packet Control Number

33. Press **PF10=Updt**.

The system displays the message: **USER ENVELOPE RECORD UPDATED**

The system displays the completed Version/Outbound Specification screen.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: PTR          Modifier:          Length:  __80
Default Version ID...: _____ Agency...:  __ Transaction ID:  _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....:  _____ Transaction ID.....:  _____
Sender ID.....:  _____ Receiver ID.....:  _____
Reference Number...:  __17      __9      Generic Element 1...:  _____
Generic Element 2...:  __1      __8      Generic Element 3...:  __9      __8
Generic Element 4...:  _____ Generic Element 5...:  _____
Generic Element 6...:  _____ Generic Element 7...:  _____
Generic Element 8...:  _____ Generic Element 9...:  _____
Generic Element 10.:  _____ Current Date.....:  _____
Current Time.....:  _____ Current Date Format:  __

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX
USER ENVELOPE RECORD UPDATED
Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                          PF10=Updt
    
```

- 34. Press **PF6=Nxt Env** twice.

The system displays the screen for the TTR segment.

- 35. Add the following TTR information to the Version/Outbound Specification screen.

Segment ID	Screen Field	ST Pos	Length	Envelope Element
TTR	Gen Element 1	1	8	Number of Segment in Tran
	Reference Number	9	9	Trans Control Number

- 36. Press **PF10=Updt**.

The system displays the updated screen for the TTR segment with the message:

USER ENVELOPE RECORD UPDATED

The system displays the completed Version/Outbound Specification screen.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: TTR          Modifier:          Length:  __80
Default Version ID...: _____ Agency...:  __ Transaction ID:  _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....:  _____ Transaction ID.....:  _____
Sender ID.....:  _____ Receiver ID.....:  _____
Reference Number...:  __9      _9      Generic Element 1...:  __1      _8
Generic Element 2...:  _____ Generic Element 3...:  _____
Generic Element 4...:  _____ Generic Element 5...:  _____
Generic Element 6...:  _____ Generic Element 7...:  _____
Generic Element 8...:  _____ Generic Element 9...:  _____
Generic Element 10...:  _____ Current Date.....:  _____
Current Time.....:  _____ Current Date Format:  _____

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX
USER ENVELOPE RECORD UPDATED
Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                        PF10=Updt
    
```

The Standards section of this Tutorial is now complete.

- 37. Press **PF3=Exit** twice to return to the Gentran Main Menu.

Mapping Integration – Outbound

Overview

In this section of the Tutorial, you will:

- Copy the ONT segment from the JASS standards and add it to the transaction map JASSPO/S.
- Map the Note Text data from the POFILEF application data to the JASSPO map.

To accomplish the tasks listed above, you will complete the following process

Stage	Description
1	Select ONT segment on the Element Mapping Outbound screen.
2	Hard code constant 01 for the Note Type element (order instructions), with If test on the 002-MESSAGE element.
3	Move 002-MESSAGE to the Note Text.

Exercise

Complete the following steps to complete the outbound mapping integration procedure.

1. Type **5** on the Gentran Main Menu to select the Mapping Maintenance Menu.
The system displays the Mapping Maintenance Menu.
2. Type **2** to select Transaction Mapping.
The system displays the Transaction Mapping Menu.
3. Type **2** to select Transaction Maintenance.
The system displays the Transaction Maintenance screen.
4. Type **JASSPO** in the Transaction Id field, type **S** in the Send or Receive field and press **Enter**.
The system displays the transaction information for JASSPO.
5. Press **PF6=Copy**.
The system displays the Copy Transaction screen.
6. Type **JASS** in the Copy from Standard Version Id field and **SC** in the Agency field.

The system displays the Copy Transaction screen.

```
EDIM501 5.2.3 _____ COPY TRANSACTION XXX 12/01/2005
                                         12:00:00

Transaction Id.....: JASSPO____
Send or Receive (S/R).....: S
Transaction Description.....: PURCHASE ORDER FOR JASS STDS
Application Data Format Id.: POFILF
Transaction Set.....: 0909

Copy from Standard
  Version Id.....: JASS_____ Agency.....: SC_

Copy from Transaction Mapping
  Transaction Id.....: _____

Enter PF1=Help          PF3=Exit PF4=Trans
```

7. Press **Enter**.

The system displays the Copy Segments From Standard screen. On this screen, you will copy the ONT segment.

Note: The system displays additional Cs in the A (Action Code) fields because the corresponding segments are mandatory. However, the system copies only the segment you indicate (ONT); it treats the other segments as duplicates that will not be copied.

8. Type **c** in the A (Action Code) field corresponding to the ONT segment and press **Enter**.

The system displays the completed Copy Segments From Standard screen.

ONT Segment that was copied

```

Copy
EDIM502 5.2.4 _____ COPY SEGMENTS FROM STANDARD      XXX      12/01/2005
                                                    12:00:00

Transaction Id...: JASSPO _____ S/R...: S      Trans Set: 0909
Version ID.....: JASS _____ Agency: SC_
Starting Seg ID..: _____ Area...: _
Seq      Segment Man Max      Loop      Max
A No     Area Id  Ver Cd  Use      Id          Loop      Description
C 0010   H   OHD  00 M    1          1          1          PURCHASE ORDER HEADER
  0020   H   OAD  00 O    3          3          3          ADDRESS INFORMATION
  0030   H   ONT  00 O   25         25         25         PURCHASE ORDER NOTES
C 0040   D   ODT  00 M    1 ODT      9999      9999      PURCHASE ORDER DETAIL
C 0050   S   OSM  00 M    1          1          1          PURCHASE ORDER SUMMARY

Enter PF1=Help      PF3=Exit PF4=Copy Trans PF5=Segments
    PF7=Bwd  PF8=Fwd
STATUS...COPY  SEG: 1 DUPS: 3 ELEM: 2
    
```

Other segments are duplicates

9. Press **PF5=Segments**.

The system displays the Segments screen.

```

Copy Delete Info Loop-end Select Update
EDIM504 5.2.5 _____ SEGMENTS      XXX      12/01/2005
                                                    12:00:00

Transaction Id...: JASSPO _____ S/R...: S      Trans Set: 0909
Version ID.....: JASS _____ Agency: SC
Starting Seg ID..: _____ Area...: _ Sequence..: _____
A Seq  A Segment M  Max  Loop  Max  Description      User  W
No     C ID  Ver C  Use  ID   Loop           Exit  F
- 00100 H OHD  00 M    1          1          PURCHASE_ORDER_HEADER  Y
- 00200 H OAD  00 O    3          3          ADDRESS_INFORMATION    Y
- 00202 H OAD  00 O    3          3          ADDRESS_INFORMATION    Y
- 00300 H ONT  00 O   25         25         PURCHASE_ORDER_NOTES  Y
- 00400 D ODT  00 M    1 PO1     9999      PURCHASE_ORDER_DETAIL  Y
- 00500 S OSM  00 M    1          1          PURCHASE_ORDER_SUMMARY Y
-
-
-
-
END OF SEGMENTS
Enter PF1=Help      PF3=Exit PF4=Trans      PF5=Elem Map  PF6=Ext Map
    PF7=Bwd  PF8=Fwd
    
```

10. Type **S** in the A (Action Code) field corresponding to the ONT segment and press **PF5=Elem Map**.

The system displays the Element Mapping Outbound screen.

11. Type the following:
 - **U** in the first A (Action Code) field
 - **'01'** (which means to code for purchase order notes that we defined in standards) in the Mapping Constant/Field for the 30 element
 - **U** in the A (Action Code) field and **002-MESSAGE** in the Mapping Constant/Field for the 31 element

12. Press **Enter**.

The system updates the fields and displays the message: **STATUS: UPDATED: 2**

The system displays the completed Element Mapping Outbound screen.

```

Extended-mapping Info Update Subfield Repeat
EDIM511 _____ ELEMENT MAPPING OUTBOUND XXX 12/01/2005
                                           12:00:00

Transaction ID.....: JASSPO_____ Send or Receive...: S
Segment Sequence.....: 00300 Segment ID.....: ONT Ver: 00
Segment Description...: PURCHASE ORDER NOTES

A Mapping Table Ext Alt-Element- Repeat Md T C
Constant/Field ID Map Map No ID No. Cd P Desc R
- '01' _____ 00010 30 0001 M ID NOTE_TYPE _____
- 002-MESSAGE _____ 00020 31 0001 M AN NOTE_TEXT _____
- _____
- _____
- _____
- _____
- _____
- _____
- _____
- _____
- _____
END OF ELEMENTS STATUS.. UPDATED: 2
Enter PF1=Help PF2=Appl PF3=Exit PF4=Segments PF5=Codes PF6=Next Seg
PF7=Bwd PF8=Fwd PF13=Relat
    
```

We need to ensure that the ONT segment will only write when there is a note to send. We use the Extended Mapping Outbound screen to accomplish this task.

13. Type **E** in the A (Action Code) field next to 01 and press **Enter**.

The system displays the Extended Element Mapping Outbound screen.

14. Type the following values:
 - **002-MESSAGE** in the If field
 - **NE** in the first Op field
 - A space surrounded by apostrophes (**' '**) in the first Value field

15. Press **PF10=Updt**.

The system updates the fields and displays the message

TRANSACTION ELEMENT UPDATED

```

EDIM508 _____ EXTENDED ELEMENT MAPPING OUTBOUND   XXX   12/01/2005
                                                    12:00:00

Transaction ID.....: JASSPO      S/R.....: S
Segment Sequence.....: 00300      Segment ID.: ONT  Segment Version: 00
Segment Description...: PURCHASE ORDER NOTES
Element # / Repeat #..: ___10 / 0001 ID...: 30   Ver: 00 NOTE TYPE
Mandatory Cd.....: M      Type.: ID   Length (Min-Max): 2 - 2
Element Group.....:      Type.:      Group Req Cd.....: M  Related...: N
Mapping of Data Element: Mapping Number.....: 00
      Value      Op      Value      Op      Value
Element = '01'
If 002-MESSAGE NE ' '
And/Or _ _ _ _ _
And/Or _ _ _ _ _
And/Or _ _ _ _ _
Table ID.....:      Type of Table.....:
Add to Hash Total #: __ Save in Constant #: __ Add 1 to Accumulator #: __
User Exit Routine..: _____ Map Zeroes: _
User Error Number..: _____
Last Update Date...: 12/01/05   Time.....: 12:00:00   User.....: XXX
TRANSACTION ELEMENT UPDATED
Enter PF1=Help PF2=Appl  PF3=Exit PF4=Return  PF5=Codes  PF6=Next
      PF9=Add PF10=Updt PF11=Del  PF13=Relat
  
```

Indicates to only write the constant '01' if data is in the application field 002-MESSAGE

If no data or notes exist in the 002-MESSAGE, the ONT segment will not be written.

Outbound mapping is complete.

16. Press **PF3=Exit**.

The system displays the Transaction Mapping Menu.

Mapping Integration – Inbound

Overview

In this section of the Tutorial you will map packet and transaction control numbers for the envelopes to the INFILEF application definition.

To accomplish this task, you will complete the following process.

Stage	Description
1	Position to map JASSIN/R on the Segments screen.
2	Select IHD on the Element Mapping Inbound screen.
3	Using Reserve Element 24 as the source field, go to the Extended Mapping Inbound screen and perform the moves with multiple mapping numbers for the following: <ul style="list-style-type: none"> • Mapping 00 – move ‘GEN-INT-REF’ to ‘0-INT-CONTROL.’ • Mapping 01 – move ‘GEN-TRN-REF’ to ‘0-TRN-CONTROL.’

When we set up our inbound application definition INVFILEF, we hard-coded reserved word constants to pick up control numbers from variable-length envelopes. We can keep the application structure intact and map the control numbers from a fixed-format envelope by mapping directly from the standards.

We can use elements that are not being mapped to facilitate this activity.

Exercise

Complete the following steps to complete the inbound mapping integration procedure.

1. Type **2** on the Transaction Mapping Menu to select Transaction Maintenance.
The system displays the Transaction Maintenance screen.
2. Type (over existing values) **JASSIN** in the Transaction Id field, type **R** in the Send or Receive field and press **Enter**.

The system displays the transaction information for JASSIN.

```

EDIM503 5.2.2_____ TRANSACTION MAINTENANCE XXX 12/01/2005
                                           12:00:00

Transaction ID.....: JASSIN_____ Send or Receive(S/R)...: R
Division Code.....: 000
Description.....: INVOICE_FOR_JASS_STANDARDS_____
Standards Version.....: JASS_____ Agency: SC_
Transaction Set.....: 0926_____
Transaction Set Release...: _ (0-9, ANA Tradacoms Only)
Transaction Status.....: T (D=Development, T=Test, P=Production)
Use Code.....: G (G=General, P=Partner Specific)
Envelope Type.....: D (E=Edifact, X=X12, U=UCS, G=GS, A=ANA, D=User)
Application Data ID.....: INVFILEF_____
Application Selection Field Values: _____
Standard Type.....: F (V=Variable, F=Fixed)
RSGRSG Level.....: _ (1/2/ ANA Tradacoms Only)
Underscore Character.....: _
Update Allowed.....: Y Job Name: _____

Enter PF1=Help PF2=Fixed PF3=Exit PF4=Dir PF5=Segments PF6=Copy
      PF7=Rpt PF9=Add PF10=Updt PF11=Del PF12=NuMap PF14=Info
    
```

3. Press **PF5=Segments**.

The system displays the Segments screen.

```

Copy Delete Info Loop-end Select Update
EDIM504 5.2.5_____ SEGMENTS XXX 12/01/2005
                                           12:00:00

Transaction Id...: JASSIN_____ S/R...: R Trans Set: 0926
Version ID.....: JASS Agency: SC
Starting Seg ID..: _____ Area...: _ Sequence..: _____
A Seq A Segment M Max Loop Max Description User W
No C ID Ver C Use ID Loop Loop Description Exit F
_ 01000 H IHD 00 M _____ 1 _____ INVOICE_HEADER _____ -
_ 02000 H IRN 00 M _____ 1 _____ REMIT_NAME_INFORMATION _____ -
_ 03000 D IDT 00 M _____ 1 IT1 _____ 9999 INVOICE_DETAIL _____ -
_ 04000 S ISM 00 M _____ 1 _____ INVOICE_DETAIL _____ -
- - - - - - - - - - - - - - - - - - - - - - - - - - - - -
- - - - - - - - - - - - - - - - - - - - - - -
- - - - - - - - - - - - - - - - - - - - - - -
- - - - - - - - - - - - - - - - - - - - - - -
- - - - - - - - - - - - - - - - - - - - - - -
- - - - - - - - - - - - - - - - - - - - - - -

END OF SEGMENTS
Enter PF1=Help PF3=Exit PF4=Trans PF5=Elem Map PF6=Ext Map
      PF7=Bwd PF8=Fwd
    
```

4. Type **s** in the A (Action Code) field next to the IHD segment and press **PF5=Elem Map**.

The system displays the Element Mapping Inbound screen.

```

Extended-mapping Info Update Subfield Repeat
EDIM514 _____ ELEMENT MAPPING INBOUND      XXX  12/01/2005
                                                12:00:00

Transaction ID.....: JASSIN_____ Send or Receive...: R
Segment Sequence.....: 01000      Segment ID.....: IHD Ver: 00
Segment Description..: INVOICE HEADER

Mapping No.....: 00      Cond.....: _____
A   Mapping      Table  Ext Alt-Element- Repeat Md T _____ C
   Target Field   ID    Map Map  No ID      No. Cd P Description   R
- 1-INVOICE-NO   _____ 00020 3    0001 M AN INVOICE_NUMBER
- 0-ORIGINAL-PO  _____ Y   Y 00040 4    0001 M AN PURCHASE_ORDER_NU
- _____      _____ 00060 2    0001 M ID DATE_TYPE
- 1-INV-DATE     _____ C   Y 00080 1    0001 M JD DATE
- _____      _____ 00100 2    0001 M ID DATE_TYPE
- 1-INV-DATE     _____ C   Y 00120 1    0001 M JD DATE
- _____      _____ 00140 13   0001 M ID BILLING_CYCLE_COD
- _____      _____ 00160 25   0001 O AN RESERVE_ELEMENT_4
- _____      _____
END OF ELEMENTS
Enter PF1=Help PF2=Appl PF3=Exit PF4=Segments PF5=Codes PF6=Map/Seg
      PF7=Bwd  PF8=Fwd
                                                PF13=Relat
    
```

5. Type **E** in the A (Action Code) field corresponding with the 160 element (Reserve Element 49) and press **Enter**.

The system displays the Extended Element Mapping Inbound screen.

Since no mapping is performed on the Reserve Element 49, we will use this element to move control numbers from the PHD and THD envelopes to the application.

6. Type **0-INT-CONTROL** in the Application Target field and **GEN-INT-REF** in the Target Field, then press **PF10=Updt** to update the fields.

The system displays the message:

TRANSACTION ELEMENT UPDATED

The system moves the value in the **GEN-INT-REF** (reserved word for Interchange Control number values) into the **0-INT-CONTROL** field in the application.

Your screen should look like this..

```

EDIM513 _____ EXTENDED ELEMENT MAPPING INBOUND          XXX 12/01/2005
                                                              12:00:00

Transaction ID.....: JASSIN      S/R.....: R
Segment Sequence.....: 01000      Segment ID.: IHD Segment Version: 00
Segment Description...: INVOICE HEADER
Element No/Repeat No..: __160 0001 ID...: 25   Ver: 00 RESERVE ELEMENT 49
Mandatory Cd.....: O      Type.: AN   Length (Min-Max)...: 49 - 49
Element Group.....:          Type.:      Group Req Cd.....:      Related...: N
Application Target Field: 0-INT-CONTROL__ Mapping Number...: 00
                        VALUE          OP   VALUE          OP   VALUE
Target Field = GEN-INT-REF_____
If
  And/OR _____
  And/OR _____
  And/OR _____
Table ID.....: _____ Type of Table.....:
Add to Hash Total #: __ Save in Constant #: __ Add 1 to Accumulator #: __
User Exit Routine..: _____
User Error Number...: _____
Last Update Date...: 12/01/05   Time.....: 12:00:00   User.....: XXX
TRANSACTION ELEMENT UPDATED
Enter PF1=Help PF2=Appl  PF3=Exit PF4=Return   PF5=Codes   PF6=Next
                PF9=Add PF10=Updt PF11=Del     PF13=Relat
  
```

GEN-INT-REF value will be moved into 0-INT-CONTROL

If you want to change the application to hard code these values, you may. For the purpose of this Tutorial, we are mapping from the standards so as not to alter the application.

7. Type the following values:
 - **01**, over the 00 in the Mapping Number field.
 - **0-TRN-CONTROL**, in the Application Target field.
 - **GEN-TRN-REF**, in the Target Field.
8. Press **PF9=Add** to add the fields.

The system displays the message:

ALTERNATE ELEMENT MAPPING ADDED

The system moves the value in the **GEN-TRN-REF** (reserved word for Transaction Control number values) into the **0-TRN-CONTROL** field in the application.

```

EDIM513 _____ EXTENDED ELEMENT MAPPING INBOUND          XXX 12/01/2005
                                                    12:00:00

Transaction ID.....: JASSIN      S/R.....: R
Segment Sequence.....: 01000      Segment ID.: IHD Segment Version: 00
Segment Description...: INVOICE HEADER
Element No/Repeat No..: __160 0001 ID...: 25   Ver: 00 RESERVE ELEMENT 49
Mandatory Cd.....: 0      Type.: AN   Length (Min-Max)...: 49 - 49
Element Group.....:          Type.:      Group Req Cd.....:      Related...: N
Application Target Field: 0-TRN-CONTROL Mapping Number...: 01

      VALUE          OR          VALUE          OP          VALUE
Target Field = GEN-TRN-REF _____
If _____
And/OR _____
And/OR _____
And/OR _____
Table ID.....: _____ Type of Table.....:
Add to Hash Total #: __ Save in Constant #: __ Add 1 to Accumulator #: __
User Exit Routine...: _____
User Error Number...: _____
Last Update Date...: 12/01/05   Time.....: 12:00:00   User.....: XXX
ALTERNATE ELEMENT MAPPING ADDED
Enter PF1=Help PF2=Appl   PF3=Exit PF4=Return   PF5=Codes   PF6=Next
                    PF9=Add PF10=Updt PF11=Del       PF13=Relat
    
```

GEN-INT-REF value will be moved into 0-TRN-CONTROL

Inbound Mapping is complete.

9. Press **PF3=Exit** three times.

The system displays the Gentran Main Menu.

Partner Maintenance

Overview

In this section of the Tutorial, you will modify the Partner Outbound Information screen to put segments and transaction counts in the envelope trailer segments.

To accomplish the task listed above, you will:

- Enter the values needed for the PTR envelope: Generic Element 2 – &SEGCNT2 and Generic Element 3 – &TRNCNT.
- Enter the value needed for the TTR envelope: Generic Element 1 – &SEGCNT2.

Exercise

Complete the following steps to complete the Partner Maintenance procedure.

Note: This portion of the tutorial is illustrated with screens as they appear in Partner/Qualifier processing mode. If you are processing in Relationship mode, your screens will display the fields User and Partner instead of Partner ID and Qualifier. The partner profile ID for Relationship mode for this tutorial is User: Yourcompany; Partner: Lawnvend. The functionality is the same for either mode.

1. Type **1** on the Gentran Main Menu to select Partner Maintenance Menu.
The system displays the Partner Maintenance Menu.
2. Type **2** to select Partner Maintenance.
The system displays the Partner Selection Menu.
3. Type **LAWN VEND** in the Partner ID field and press **Enter**.

The system displays the **LAWN VEND** partner name and partner ID.

```

EDIM007 1.2_____ PARTNER SELECTION MENU XXX 12/01/2005
                                                    12:00:00

LAWN VENDOR FOR DEMONSTRATION
Part ID: LAWNVEND_____ Qual: _____
Copy ID: _____ Qual: _____
Type the number of your selection below and press ENTER,
or press the PF3 key to Exit.
    - 1. Header Information
      2. Interchange Directory
      3. Group Directory
      4. Transaction Directory
      5. Name and Address
      6. User Defined
      7. Data Separation
      8. Error Rejection
      9. Copy All Records

PLEASE ENTER OPTION Job Name: _____
Enter PF1=Help      PF3=Exit PF4=Dir
      PF7=Rpt
    
```

4. Type **2** to select Interchange Directory and press **Enter**.

The system displays the Interchange Directory screen.

5. Type **s** in the A (Action Code) field next to the GEN header option and press **PF5=Ctrl**.

The system displays the Control Information screen – 1.

```

EDIM015 1.2.2.1___ CONTROL INFORMATION XXX 12/01/2005
                                                    12:00:00

LAWN VENDOR FOR DEMONSTRATION
Part ID: LAWNVEND_____ Qual: _____
Multiple Envelope Id: _____ Version: _____
Interchange Header Option....: GEN (ISA ICS BG GS UNA UNB SCH STX GEN)
Last Incoming Sequence Number: _____
EDI Databank Inbound.....: _ (D/N) Outbound.....: _ (F/D/N)
Expect a TA1, AC1, or UCI....: _ (Y/N) Network Tracking..: _ (Y/N)
Acknowledge Interchange.....: _ (Y/N/E) Errors.....: _ (Y/N)

Last Incoming BG Password....: _____ Syntax Version...: /
Mailbox/Remote ID (For Plus)..: _____
Network ID.(For PLUS).....: _____
Viewpoint - Exception.....: _ (Y/N) Tracking.....: _ (Y/N)
Reconciliation Delay (days)..: _____

Enter PF1=Help      PF3=Exit PF4=IDir      PF5=Control      PF6=Next Ctl
                    PF9=Add PF10=Updt PF11=Del      PF14=Info
    
```

6. Press **PF5=Control**.

The system displays the Control Information screen – 2.

We have already tied the PTR envelope to the PHD in Standards Maintenance. We have already used Generic Element 1 in the PHD envelope—we want to move the count of segments and transaction totals into the PTR envelope. We will use Generic Elements 2 and 3 to fulfill this purpose. These are reserved values for segment counts.

7. Type **&SEGCNT2** in the Generic Element 2 field.

This value contains the number of segments in the packet.

8. Type **&TRNCNT2** in the Generic Element 3 field.

This value contains the number of transactions in the packet.

9. Press **PF10=Update**.

The system updates the fields and displays the message **PARTNER UPDATED**.

```

EDIM011 _____ CONTROL INFORMATION          XXX  12/01/2005
                                                12:00:00

          LAWN VENDOR FOR DEMONSTRATION
Part ID: LAWNVEND                               Qual:
Multiple Envelope Id:
Outbound envelope information for Generic Interchange:

Envelope ID...: PHD                               Modifier.....: _
Sender ID.....: LAWNCUST _____
Receiver ID...: LAWNVEND _____
Version ID...: JASS _____
Transaction ID: _____
Reference.....: 00000000000000000001
Gen Element 1.: MOWING _____ Gen Element 2.: &SEGCNT2 _____
Gen Element 3.: &TRNCNT2 _____ Gen Element 4.: _____
Gen Element 5.: _____ Gen Element 6.: _____
Gen Element 7.: _____ Gen Element 8.: _____
Gen Element 9.: _____ Gen Element 10: _____
PARTNER UPDATED
Enter PF1=Help          PF3=Exit PF4=Ctrl      PF5=GDir
                        PF10=Updt             PF14=Info

```

10. Press **PF5=GDir**.

The system displays the Group Directory screen.

11. Type **s** beside the 0909 Group ID and press **PF5=Group**.

The system displays the Group Information screen.

12. Press **PF5=TDir**.

The system displays the Transaction Directory screen.

13. Type **s** in the A (Action Code) field beside the 0909 Trans ID and press **PF5=Trans**.

The system displays the Transaction Information screen.

We have already tied the TTR envelope to the THD in Standards Maintenance. We want the count of transactions moved into the TTR envelope. We will use Generic-Element 1 to fulfill this purpose.

14. Type **&SEGCNT2** in the Generic Element 1 field and press **PF10=Updt**.

This value contains the number of segments in a transaction. The system updates the field and displays the message **TRANS 0909 UPDATED**.

```

EDIM044 1.2.3_____ TRANSACTION INFORMATION          XXX  12/01/2005
                                                12:00:00

          LAWN VENDOR FOR DEMONSTRATION
Part ID:  LAWNVEND                               Qual:
Transaction ID:  0909__ Multiple Env Id:

Translation Map ID Inbound...: _____ Outbound: _____
Application Databank Inbound:  F (F/D/N)      Outbound:  F (F/D/N)

Outbound envelope information for Generic Transaction:
Envelope ID...: THD                               Modifier.....:  _
Sender ID...:  _____ Receiver ID...:  _____
Version ID...:  _____ Reference.....:  000000000000000001
Gen Element 1:  &SEGCNT2_____ Gen Element 2.:  _____
Gen Element 3:  _____ Gen Element 4.:  _____
Gen Element 5:  _____

TRANS 0909  UPDATED
Enter PF1=Help          PF3=Exit PF4=TDir      PF5=Name      PF6=Nxt Tran
                        PF9=Add PF10=Updt PF11=Del  PF14=Info

```

The Partner Tutorial is complete.

15. Press **PF3=Exit** three times.

The system displays the Gentran Main Menu.

Gentran:Basic Users

You should now run the **STRINB** and **STROUT** jobs to process the inbound and outbound scenarios.

Gentran:Realtime Users

You should execute the inbound and outbound processes as outlined in Chapter 4, “Performing Installation Verification” in the *Gentran:Structure for zSeries Release 6.4 Installation Guide*.

Overview

This chapter describes the Gentran:Structure screens and how the system features relate to those of Gentran:Basic and Gentran:Realtime.

This chapter contains the following topics:

Topic	Page
Jump Codes	3-3
How to Jump Between Screens	3-3
Types of Jump Codes	3-3
User-Defined Jump Code Table	3-5
Jump Code Guidelines	3-5
How Gentran:Structure Relates with Gentran:Basic Features	3-7
Subsystems	3-7
Partner Maintenance Subsystem	3-8
Overview	3-8
Control Information – Screen 1 with Generic Header Option EDIM015	3-9
Control Information – Screen 2 with Generic Options	EDIM011 3-14
Group Information Screen – Generic	EDIM034 3-19
Transaction Information Screen – Generic	EDIM044 3-25
Standards Maintenance Subsystem	3-31
Overview	3-31
Standards Maintenance Menu	EDIM100 3-32
Version Screen	EDIM110 3-33
Data Element Definition Screen	EDIM160 3-36
User Envelope Specification Screen	EDIM190 3-39
Version/Outbound Specification Screen	EDIM191 3-44
Mapping Integration Subsystem	3-53
Overview	3-53
Transaction Maintenance Screen	EDIM503 3-54
Transaction Maintenance – Gentran:Structure Screen.....	EDIM516 3-59
Application Data ID Screen	EDIM552 3-62

Databank Maintenance Subsystem	3-64
Overview	3-64
Structure Document Directory Screen	EDIM272 3-65
Structure Document Status Screen	EDIM273 3-69
Structure Document Status Detail Screen	EDIM275 3-74
Structure Document Display Screen	EDIM274 3-79
Structure Record Display Screen	EDIM276 3-83
Structure Field Display Screen	EDIM277 3-86
Structure Envelope Display Screen	EDIM192 3-89
Standards Change Audit Subsystem.....	3-92
Overview	3-92
Standards Change Audit Director	EDIM181 3-93
Standards Change Audit Status - Structure	EDIM184 3-95
Standards Change Audit Detail - Structure	EDIM185 3-98
Gentran:Realtime Screens	3-100
Overview	3-100
Fixed Format Pre-Processor Path Maintenance	EDIM840 3-101
Fixed/Variable Splitter Path Maintenance.....	EDIM841 3-105
NCPDP Outbound Parm's Maintenance Screen	EDIM84G 3-108

Jump Codes

A jump code is a 10-character alphanumeric field located at the upper left corner of each Gentran screen. This field enables you to move, or *jump*, directly from one screen to another while bypassing menus. All screens that are accessible by means of a menu have jump code values associated with them. Screens that are accessible only from detail screens do not have jump code values associated with them.

How to Jump Between Screens

You can jump between screens without having to navigate using the menus. Use the following procedure to jump between screens:

1. Press **Home**.

The insertion point moves to the jump code field at the top of the screen to the right of the screen name.

2. Type the jump code, and press **Enter**.

For a complete list of Gentran:Structure jump codes and their associated screens, see Appendix A of this guide.

The following table describes some of the terms and definitions used in this discussion:

Term	Meaning
Subsystem	A set of functionally-related screens that are directly accessible from the Gentran Main Menu (e.g., Partner Maintenance, Standards Maintenance, Databank Maintenance, Administrative Maintenance, Mapping Maintenance).
Navigation	The movement from screen to screen by typing data then pressing the function keys (e.g., PF1 , PF2) or by selecting options on menus and pressing Enter .
Position	The location within a subsystem file (or group of files) that displays the data (either one record or multiple records) on the screen.

Types of Jump Codes

The three types of jump codes are:

- Numeric
- Alphabetic
- Special Character

Numeric Jump Codes

Numeric jump codes consist of numbers separated by periods (.). The numbers in the jump code correspond to the numbers selected on menus, in the order in which they are selected.

Example

To display the Application Data ID screen without using the jump code, you could navigate using the Gentran:Realtime menus by performing the following steps:

1. Type **5** on the Gentran Main Menu, and press **Enter**.
2. Type **1** on the Mapping Maintenance Menu, and press **Enter**.
3. Type **2** on the Application Definition Menu, and press **Enter**.

... OR you could jump directly to the Application Data ID screen by performing these steps:

1. Press **Home**.
2. Type **5 . 1 . 2** in the jump code field of any screen, and press **Enter**.

For a complete list of Gentran:Structure jump codes and their associated screens, see Appendix A of this guide.

Alphabetic Jump Codes

Alphabetic jump codes consist of alphabetic characters separated by periods (.). The alphabetic code is an abbreviated reference to the screen name or function.

Example

To display the Application Data ID screen using the alphabetic jump code, type **APP . DEF** or **APP . ID** in the jump code field of any screen, and press **Enter**.

For a complete list of Gentran:Structure jump codes and their associated screens, see Appendix A of this guide.

Special Character Jump Codes

Special character jump codes enable you to perform standard or generic functions with jump codes. The two special character jump codes are SWAP and EXIT.

- SWAP enables you to jump *between* Gentran:Realtime online subsystems, not *within* subsystems. When you use jump code SWAP, you jump to the last screen you *jumped from* (but not *navigated from*), from another subsystem. When you jump from a different subsystem, you reset the SWAP positioning to the screen you're jumping from.

Example

Let's say you have the Group Information screen in the Partner subsystem displayed, and then you bring up the Transaction Information screen (also in the Partner subsystem). From here, you *jump* to the Name and Address screen (again, in the Partner subsystem). Next, you *jump* to the Transaction screen in the Standards subsystem. After you view the information on the Transaction screen, you type **SWAP** in the jump code field to return to your previous location in the Partner subsystem. SWAP returns you to the Name and Address screen in the Partner subsystem, because this is the screen from which you jumped to the Standards subsystem.

- EXIT (or X) enables you to jump to the Gentran:Realtime Logoff screen. This feature provides a quick and easy way to exit the Gentran:Realtime system from any screen.

User-Defined Jump Code Table

The User-Defined Jump Code table is a user customization facility that enables you to define your own jump code values. This facility requires a table that consists of the 10-character user code and the 10-character Gentran:Realtime jump code. It must be coded in an Assembler table and the name of the table must be entered on the Configuration file (Record Type 0). An entry for the table name must be added to your CICS PPT table.

When you enter a jump code, the system verifies that the jump code you entered is valid by first checking the User-Defined Jump Code table. If you have not defined a User-Defined Jump Code table, or if the jump code you entered is not in that table, then the system checks the default jump code table.

For help using the User-Defined Jump Code Table, refer to Installing Gentran:Basic Release 6.4 in the *Gentran:Basic for zSeries Release 6.4 Installation Guide*. Also, see member EDIJUMP in the GENTRAN.V6X1.BSC.UTILITY.SOURCE library.

Jump Code Guidelines

The Gentran:Basic system keeps independent position information for each subsystem (Partner, Standards, Databank, Administrative, Mapping), as well as for Gentran:Realtime add-on products (Plus, Control, Realtime, Viewpoint). Gentran:Structure functionality is part of Gentran:Basic. The independence of these subsystems enables you to jump or navigate from subsystem to subsystem without having to re-enter a key for that screen.

The general rules for using jump codes are the following:

- You can only *jump to* screens that are directly accessible through selecting menu options.
- You can *jump from* any screen.
- Navigating or jumping to the Gentran:Realtime Copyright/Signon screen or exiting the Gentran:Realtime system clears the positions for all subsystems.

- After you *jump from* a subsystem to another subsystem, you can return directly to the screen you *jumped from* by typing **SWAP** in the jump code field.
- You cannot use **SWAP** to jump between screens within the same subsystem.
- Typing **SWAP** is the only method by which you can *jump to* a screen that has no jump code associated with it, as long as **SWAP** positioning has been established by jumping from one subsystem screen to a different subsystem screen.
- Typing an invalid jump code causes the system to return to the *jumped from* screen and display the message **Invalid jump code entered**.
- You cannot *jump to* subsystems that are not installed or for which you do not have security access. If you try, the system displays the message **Invalid jump – user lacks authority** on the current screen.

How Gentran:Structure Relates with Gentran:Basic Features

Subsystems

The following Gentran:Basic subsystems support Gentran:Structure:

- Partner Maintenance
- Standards Maintenance
- Mapping Integration
- Databank Maintenance

A description of each subsystem follows.

Partner Maintenance

This subsystem enables you to define generic or user-defined envelopes that might be necessary to support a proprietary, fixed-format standard. An interchange header option, identified by the characters 'GEN,' identifies this type of enveloping.

Screens are defined at the interchange, group, and transaction levels, where it is possible to specify exactly what information should be loaded to these generic envelopes during envelope generation.

Standards Maintenance

You must define fixed-format standards to Gentran:Basic before they can be mapped. The Standards Maintenance screens enable you to define these standards.

The Element Definition screen permits the specification of the additional data types that are supported for fixed-format standards.

Two additional screens describe the layout of all of the envelope structures that are necessary to process the standard. The system uses these definitions in conjunction with the information defined for the trading partner to generate outbound envelopes. During inbound processing, the system uses this information for version/transaction identification, partner determination, and mapping.

Mapping Integration

The Transaction Definition identifies the standard type to be mapped and determines the location of the segment ID.

Databank Maintenance

The Databank Maintenance subsystem enables you to view Gentran:Structure documents from Gentran:Realtime or Gentran:Basic databanks.

Change Audit

This subsystem allows you to view change audit records that were created during online maintenance of selected files. For Gentran:Structure, two additional screens allow you to view change audit records created for the User Envelope file. These screens are used when viewing user envelope change audit records.

Partner Maintenance Subsystem

Overview

This section describes how the Partner Maintenance subsystem supports Gentran:Structure.

The Partner Maintenance subsystem allows the definition of inbound and outbound generic envelope information on the partner profile at the Control (Interchange), Group, and Transaction levels. The following table describes the screens that define the envelopes.

Screen	Description
Control Information – screen 1 (EDIM015)	Allows partners to be set up with generic interchange header types to support Gentran:Structure.
Control Information – screen 2 (EDIM011)	Defines outbound envelope information for generic interchanges.
Group Information screen (EDIM034)	Defines outbound envelope information for generic groups.
Transaction Information screen (EDIM044)	Defines outbound envelope information for generic transactions.

Note: See the *Gentran:Basic for zSeries Release 6.4 User's Guide* for more information concerning the Partner Maintenance subsystem.

Screen information follows.

Control Information – Screen 1 with Generic Header Option**EDIM015***Purpose*

The Control Information screen displays a generic interchange Header Option prompt (GEN) when Gentran:Structure is enabled. Selecting the GEN option indicates to the system that you are going to define your own envelopes for this trading partner. You control the format of these envelopes.

The system displays this screen if the GEN Interchange Header Option is available to handle proprietary, fixed-format standards.

If Gentran:Structure is not enabled, the system displays the Standard Control Information screen and the GEN Interchange Header Option is not available.

Some Fields Not Required

Certain fields on this screen are not required for using proprietary, fixed-format standards. These fields are protected; you cannot enter your own values. If you are setting up a Generic Interchange Header option and these fields have values, the system moves spaces to these fields and prevents further updates to them. The fields not required are:

- Last Incoming Sequence Number
- EDI Databank Inbound
- Expect a TA1, AC1, or UCI
- Acknowledge Interchange
- Last Incoming BG Password
- Network ID (For PLUS)

See the “Field Descriptions” section for detailed field information.

How to Access

Access the Control Information screen by completing the following steps.

1. On the Partner Maintenance Menu, type **1** to select Partner Directory. The system displays the Partner Directory screen.
2. Type an **s** in the A (Action Code) field next to the Partner you want to select, and press **PF5=Maint**. The system displays the Partner Selection Menu.
3. Type **2** to select Interchange Directory and press **Enter**. The system displays the Interchange Directory screen.
4. Type an **s** in the A (Action Code) field next to an interchange with a GEN header, and press **PF5=Ctrl**.

The system displays the Control Information screen.

Screen Examples

The following diagrams illustrate the Control Information – Screen 1 with Generic Entry for both the Partner/Qualifier and Relationship (User/Partner) modes.

Partner/Qualifier Mode

```

EDIM015 1.2.2.1___          CONTROL INFORMATION          XXX  12/01/2005
                                                                12:00:00

          LAWN VENDOR FOR DEMONSTRATION
Part ID: LAWNVEND                      Qual:
Multiple Envelope Id: ___              Version: _____
Interchange Header Option....: GEN  (ISA ICS BG GS UNA UNB SCH STX GEN)
Last Incoming Sequence Number: _____
EDI Databank Inbound.....: _ (D/N)          Outbound.....: _ (F/D/N)
Expect a TA1, AC1, or UCI.....: _ (Y/N)      Network Tracking.: _ (Y/N)
Acknowledge Interchange.....: _ (Y/N/E)      Errors.....: _ (Y/N)

Last Incoming BG Password....: _____    Syntax Version...: /
Mailbox/Remote ID (For Plus)..: _____
Network ID.(For PLUS).....: _____
Viewpoint - Exception.....: _ (Y/N)          Tracking.....: _ (Y/N)
Reconciliation Delay (days)..: ___

Enter PF1=Help          PF3=Exit PF4=IDir          PF5=Control    PF6=Next Ctl
                        PF9=Add PF10=Updt PF11=Del          PF14=Info
  
```

Relationship Mode

```

EDIM015 1.2.2.1___          CONTROL INFORMATION          XXX  12/01/2005
                                                                12:00:00

          YOUR COMPANY                      EXAMPLE OF A FIX FORMAT PARTNE
User...: YOUR COMPANY                Partner: LAWNVEND
Multiple Envelope Id: ___              Version: _____
Interchange Header Option....: GEN  (ISA ICS BG GS UNA UNB SCH STX GEN)
Last Incoming Sequence Number: _____
EDI Databank Inbound.....: _ (D/N)          Outbound.....: _ (F/D/N)
Expect a TA1, AC1, or UCI.....: _ (Y/N)      Network Tracking.: _ (Y/N)
Acknowledge Interchange.....: _ (Y/N/E)      Errors.....: _ (Y/N)

Last Incoming BG Password....: _____    Syntax Version...: /
Mailbox/Remote ID (For Plus)..: _____
Network ID.(For PLUS).....: _____
Viewpoint - Exception.....: _ (Y/N)          Tracking.....: _ (Y/N)
Reconciliation Delay (days)..: ___

Enter PF1=Help          PF3=Exit PF4=IDir          PF5=Control    PF6=Next Ctl
                        PF9=Add PF10=Updt PF11=Del          PF14=Info
  
```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

PF4=IDir	Displays the Interchange Directory.
PF5=Control	Displays the Control Information screen (screen 2), for the Partner ID and interchange header option selected. For example, if the GEN interchange header option is selected for the specified Partner ID, the system displays the Control Information (screen 2 – GEN OPTIONS) screen.
PF6=Next Ctl	Displays the next sequential control record.
PF9=Add	Adds a control record for a new Partner ID being added to the partner profile.

Note: When you add a new Control record, Gentran automatically adds default Group and Transaction records, based on the !!!GENTRAN-RESERVED-PARTNER- ID-1 (Partner/Qualifier mode)

OR

!!!GENTRAN-RU1/!!!GENTRAN-RP1 (Relationship mode)

PF10=Updt	Updates the control record for an existing Partner ID.
PF11=Del	Deletes a control record and its subordinates (records with the same Version/Multiple Envelope IDs) for an existing Partner ID for the indicated header option.
PF14=Info	Displays the date, time and user initials on the message line, to indicate when the information on this screen was created or last changed.

Field Descriptions

Note: Fields that are display-only contain the statement (protected) next to the field name in the documentation.

Fields in which you *must* enter a value are labelled as “required” in the documentation.

Jump Code

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed in the jump code field for that screen.

To *jump* to another screen, press **Home**, type the jump code of the screen to which you want to jump and press **Enter**.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
(Partner Name – protected)	A 35–position alphanumeric field used to display the partner name, as found on the Name and Address record. The partner name can help to further identify the Partner ID.	(User Name – protected)	A 35–position alphabetic field displaying the user name, if it exists on file for the User/Partner ID.
Part ID (protected)	Displays the Partner ID that you have entered or selected. Note: The Partner ID and Qualifier make up the key for all associated records.	(Partner Name– protected)	A 35–position alphabetic field displaying the partner name, if it exists on file for the User/Partner ID.
Qual (protected)	Displays the Qualifier associated with the Partner ID, if applicable.	User/Partner (protected)	Two 15–position alphabetic fields that display the User/ Partner ID you have entered or selected.

Multiple Envelope Id

A 3–position alphabetic field used to identify the envelope type for this interchange record within the partner profile. This field allows a single partner profile to have multiple EDI standards (e.g., X12, EDIFACT, TRADACOMS) defined under it. It eliminates the need to create multiple partner profiles for a single trading partner in the event that the partner uses more than one EDI standard. Valid values include these standards: **ISA, ICS, BG, GS, UNA, UNB, SCH, STX, GEN**, and spaces.

Version

Gentran:Structure does not use this field.

Interchange Header Option (required)

A 3–position alphabetic field identifying the type of interchange envelope to be used for outbound transactions. The envelope allows you to label an outbound transaction. Valid values include these standards: **ISA, ICS, BG, GS, UNA, UNB, SCH, STX, GEN**. For example, **ISA** = the segment ID for the interchange envelope header segment; **GS** = the segment ID for group envelope header segment when an interchange envelope is not used.

Last Incoming Sequence Number

Gentran:Structure does not use this field.

EDI Databank Inbound

Gentran:Structure does not use this field.

Outbound

Gentran:Structure does not use this field.

Expect a TAI, AC1, or UCI

Gentran:Structure does not use this field.

Network Tracking

Gentran:Structure does not use this field.

Acknowledge Interchange

Gentran:Structure does not use this field.

Errors

Gentran:Structure does not use this field.

Last Incoming BG Password

Gentran:Structure does not use this field.

Syntax Version

Gentran:Structure does not use this field.

Mailbox/Remote ID (For PLUS) (For Gentran:Plus for zSeries Only)

Gentran:Structure does not use this field.

Network ID (For PLUS) (For Gentran:Plus for zSeries Only)

Gentran:Structure does not use this field.

Gentran:Viewpoint Installed**Viewpoint – Exception**

A 1–position field indicating whether Gentran:Viewpoint Exception Management activity is performed at the interchange level for this partner. Valid values are:

- Y** = Yes, Tracking Management is performed.
- N** = No, Exception Management is not performed.
- blank**= Defaults to the value **Y** and the Exception Management processing is controlled by the Configuration File Exception Management Partner Default Indicator.

Viewpoint – Tracking

A 1–position field indicating whether Gentran:Viewpoint Tracking Management activity is performed at the interchange level for this trading partner. Valid values are:

- Y** = Yes, Tracking Management is performed.
- N** = No, Tracking Management is not performed.
- blank**= Defaults to the value **Y** and the Tracking Management processing is controlled by the Configuration Field Tracking Management Partner default indicator.

See “Defining and Initializing Files” in the Gentran:Viewpoint *Installation Guide* for more information.

The installation default is Exception Management.

Reconciliation Delay (days)

Gentran:Structure does not use this field.

Control Information – Screen 2 with Generic Options**EDIM011***Purpose*

The Control Information screen enables you to create outbound envelopes. If you are not sending documents to your trading partner, you can skip this screen. If you plan to send outbound documents and you are sending envelopes at the interchange level, you must complete this screen.

This screen specifies the information that is placed in the generic interchange envelope for a proprietary, fixed-format standard. The system moves the information specified on this screen to either the header envelope identified by the Envelope ID field or its associated trailer envelope.

The location of the fields to be moved and the associated trailer envelope are defined using the User Envelope Specification screens in Standards Maintenance. If these envelopes are not defined in the User-Envelope file, the envelope generation process fails.

Note: This Gentrans:Structure screen will generate change audit records for Fixed Format Partner Control records if Partner Change Audit is enabled. See chapter 7, “Tips and Techniques,” in the *Gentrans:Basic User’s Guide* for more information about the Change Audit functionality.

How to Access

Access this screen from the Control Information – screen 1 by pressing **PF5=Control**.

Screen Example

The following diagrams illustrate the Control Information – screen 2 with Generic Options for both the Partner/Qualifier and Relationship (User/Partner) modes.

Partner/Qualifier Mode

```

EDIM011 _____ CONTROL INFORMATION          XXX  12/01/2005
                                                12:00:00

          LAWN VENDOR FOR DEMONSTRATION
Part ID: LAWNVEND                               Qual:
Multiple Envelope Id:
Outbound envelope information for Generic Interchange:

Envelope ID...: PHD                               Modifier.....: _
Sender ID.....: LAWNCUST_____
Receiver ID...: LAWNVEND_____
Version ID....: JASS_____
Transaction ID: _____
Reference.....: 00000000000000000001
Gen Element 1.: MOWING_____ Gen Element 2.: _____
Gen Element 3.: _____ Gen Element 4.: _____
Gen Element 5.: _____ Gen Element 6.: _____
Gen Element 7.: _____ Gen Element 8.: _____
Gen Element 9.: _____ Gen Element 10.: _____

Enter PF1=Help          PF3=Exit PF4=IDir          PF5=GDir
                        PF10=Updt                    PF14=Info

```


Relationship Mode

```

EDIM011 _____ CONTROL INFORMATION XXX 12/01/2005
                                           12:00:00

      YOUR COMPANY                               EXAMPLE OF A FIX FORMAT PARTNE
User...: YOUR COMPANY                           Partner: LAWNVEND
Multiple Envelope Id:
Outbound envelope information for Generic Interchange:

Envelope ID...: PHD                               Modifier.....: _
Sender ID.....: LAWNCUST_____
Receiver ID...: LAWNVEND_____
Version ID...: JASS_____
Transaction ID: _____
Reference.....: 00000000000000000001
Gen Element 1.: MOWING_____ Gen Element 2.: _____
Gen Element 3.: _____ Gen Element 4.: _____
Gen Element 5.: _____ Gen Element 6.: _____
Gen Element 7.: _____ Gen Element 8.: _____
Gen Element 9.: _____ Gen Element 10.: _____

Enter PF1=Help          PF3=Exit PF4=IDir      PF5=GDir
                        PF10=Updt           PF14=Info

```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

To delete the specified trading partner's ISA parameters, you must first return to the Control Information screen (screen 1) by pressing the **PF4** key.

PF4=IDir	Displays the Interchange Directory screen for the Partner ID selected.
PF5=GDir	Displays the Group Directory for the Partner ID currently displayed.
PF10=Updt	Updates the ISA parameters for an existing Partner ID.
PF14=Info	Displays the date, time and user initials on the message line, to indicate when the information on this screen was created or last changed.

Field Descriptions

Note: Fields that are display-only contain the statement (protected) next to the field name in the documentation.

Fields in which you *must* enter a value contain the statement (required) next to the field name in the documentation.

Jump Code

A 10–position alphabetic or numeric field containing the jump code for this screen. A screen’s jump code is displayed in the jump code field for that screen.

To *jump* to another screen, press **Home**, type the jump code of the screen to which you want to jump, and then press **Enter**.

See the “Jump Codes” section at the beginning of this chapter for further information on using jump codes.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
(Partner Name – protected)	A 35–position alphanumeric field used to display the partner name, as found on the Name and Address record. The partner name can help to further identify the Partner ID.	(User Name – protected)	A 35–position alphabetic field displaying the user name, if it exists on file for the User/Partner ID.
Part ID (protected)	Displays the Partner ID that you have entered or selected. Note: The Partner ID and Qualifier make up the key for all associated records.	(Partner Name– protected)	A 35–position alphabetic field displaying the partner name, if it exists on file for the User/Partner ID.
Qual (protected)	Displays the Qualifier associated with the Partner ID, if applicable.	User/Partner (protected)	Two 15–position alphabetic fields that display the User/ Partner ID you have entered or selected.

Multiple Envelope Id

A 3–position alphabetic field to identify the envelope type for this interchange record within the partner profile. This field allows a single partner profile to have multiple EDI standards (e.g., X12, EDIFACT, TRADACOMS) defined under it. It eliminates the need to create multiple partner profiles for a single trading partner in the event that the partner uses more than one EDI standard. Valid values include these standards: **ISA, ICS, BG, GS, UNA, UNB, SCH, STX, GEN**, and spaces.

Envelope ID

A 3–position alphanumeric field that defines which generic envelope should be used when generating the generic interchange. This envelope ID should be defined using the User Envelope Specification screen in Standards Maintenance. If this field has a value, the Outbound Mapping program attempts to generate this envelope and its associated trailer (if one is defined).

Modifier

A 1-position alphanumeric field to differentiate one Envelope ID from another, if the same Envelope ID is defined multiple times in the user-envelope specification.

Sender ID

A 15-position alphanumeric field to define your interchange Sender ID.

If you type data in the Sender ID field, the system maps it into the header envelope or associated trailer envelope as specified in the Sender ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

Receiver ID

A 15-position alphanumeric field to define your trading partner's interchange Receiver ID.

If you type data in the Receiver ID field, the system maps it into the header envelope or associated trailer envelope as specified in the Receiver ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

Version ID

A 12-position alphanumeric field to define the version of the proprietary, fixed-format standard used to process the data sent to this trading partner.

If you type a value in the Version ID field, it will be mapped into the header envelope or associated trailer envelope as specified in the Version ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

Transaction ID

A 6-position alphanumeric field to define the transaction set for the proprietary, fixed-format version.

If you type a value in the Transaction ID field, the system maps it into the header envelope or associated trailer envelope as specified in the Transaction ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

Reference

An 18-position alphanumeric field to automatically generate the interchange reference number.

If the Reference field contains numeric data, the system increments it by '1' and maps it into the header envelope or associated trailer envelope as specified in the Reference Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance. If this field contains alphanumeric data, the system maps it into the envelope unchanged.

Gen Element 1 (Generic Element 1)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 2 (Generic Element 2)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 3 (Generic Element 3)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 4 (Generic Element 4)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 5 (Generic Element 5)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 6 (Generic Element 6)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 7 (Generic Element 7)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 8 (Generic Element 8)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 9 (Generic Element 9)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 10 (Generic Element 10)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Reserved Words

The following reserved words can be used in Generic Elements 1 through 10. **These reserved words are only valid in the interchange trailer segments.**

&SEGCNT	The number of segments generated between the interchange header and the interchange trailer. This count does <i>not</i> include the interchange header and trailer.
&SEGCNT2	The number of segments generated between the interchange header and the interchange trailer. This count <i>does</i> include the interchange header and trailer.
&TRNCNT	The number of transaction headers generated between the interchange header and trailer.
&GRPCNT	The number of group headers generated between the interchange header and trailer.

Group Information Screen – Generic**EDIM034***Purpose*

The Group Information screen allows you to identify separate types of processing for various functional groups.

The system automatically adds a default group record when a new Partner Control record is added. If you intend to use the default group record, you should update the record to reflect the appropriate information for your trading partner. Most often, however, users create a separate group record for each type of functional group that will be sent or received.

This screen specifies the information that will be placed in the generic group envelope for a proprietary, fixed-format standard. The system moves the information specified on this screen to either the header envelope identified by the Envelope ID field or its associated trailer envelope.

The location of the fields to be moved and the associated trailer envelope are defined using the User Envelope Specification screens in Standards Maintenance. If these envelopes are not defined in the User-Envelope file, the envelope generation process fails.

Note: This Gentran:Structure screen will generate change audit records for Fixed Format Partner Group records if Partner Change Audit is enabled. See chapter 7, “Tips and Techniques,” in the *Gentran:Basic User’s Guide* for more information about the Change Audit functionality.

How to Access

Access the Group Information screen by completing the following steps.

1. On the Partner Maintenance Menu, select **2**, Partner Maintenance, and press **Enter**. The system displays the Partner Selection Menu.
2. **For Partner/Qualifier Mode:**
Type a valid Partner ID in the Part ID field and Qualifier in the Qual field.

OR
For Relationship (User/Partner) Mode:
Type a valid User in the User field and Partner in the Partner field.
3. Type **3** to select Group Directory and press **Enter**. The system displays the Group Directory screen.
4. Type an **s** in the A (Action Code) field next to the selected Group ID and press **PF5=Group**. The system displays the Group Information screen.

Screen Examples

The following diagrams illustrate the Group Information screen for both the Partner/Qualifier and Relationship (User/Partner) modes.

Partner/Qualifier Mode

```

EDIM034 1.2.3.1___          GROUP INFORMATION          XXX  12/01/2005
                                                12:00:00

          LAWN VENDOR FOR DEMONSTRATION
Part ID:  LAWNVEND          Qual:
Group ID:  !!!DFT          Multiple Env Id:

Outbound envelope information for Generic Group:

Envelope ID...:  ___          Modifier.....:  _
Sender ID.....:  _____
Receiver ID...:  _____
Version ID....:  _____
Transaction ID:  _____          Reference.....:  _____
Gen Element 1.:  _____          Gen Element 2.:  _____
Gen Element 3.:  _____          Gen Element 4.:  _____
Gen Element 5.:  _____          Gen Element 6.:  _____
Gen Element 7.:  _____

Enter PF1=Help          PF3=Exit PF4=GDir          PF5=TDir          PF6=Next Grp
                        PF9=Add PF10=Updt PF11=Del          PF14=Info

```

Relationship Mode

```

EDIM034 1.2.3.1___          GROUP INFORMATION          XXX  12/01/2005
                                                12:00:00

          YOUR COMPANY          LAWNVENDOR FOR DEMONSTRATION
User.....:  YOUR COMPANY          Partner:  LAWNVEND
Group ID:  !!!DFT          Multiple Env Id:

Outbound envelope information for Generic Group:

Envelope ID...:  ___          Modifier.....:  _
Sender ID.....:  _____
Receiver ID...:  _____
Version ID....:  _____
Transaction ID:  _____          Reference.....:  _____
Gen Element 1.:  _____          Gen Element 2.:  _____
Gen Element 3.:  _____          Gen Element 4.:  _____
Gen Element 5.:  _____          Gen Element 6.:  _____
Gen Element 7.:  _____

Enter PF1=Help          PF3=Exit PF4=GDir          PF5=TDir          PF6=Next Grp
                        PF9=Add PF10=Updt PF11=Del          PF14=Info

```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran: Basic for zSeries Release 6.4 User's Guide*.

Enter	Displays a different group definition. Type a complete Group ID in the Group ID field and press Enter .
PF4=GDir	Displays the Group Directory screen for the Partner ID selected.
PF5=TDir	Displays the Transaction Directory screen for the Partner ID selected.
PF6=Next Grp	Displays the next functional group record for the specified Group ID.
PF9=Add	Adds group information to a new trading partner. Enter the appropriate parameter values and press PF9=Add .
PF10=Updt	Updates group information for an existing trading partner. Type the new data over the existing data and press PF10=Updt .
PF11=Del	Deletes the displayed group record for an existing trading partner. Press PF11=Del to delete the data. The system will prompt you to confirm the delete.
PF14=Info	Displays the date, time and user initials on the message line, to indicate when the information on this screen was created or last changed.

Field Descriptions

Note: Display-only fields contain the statement (protected) next to the field name in the documentation.

Fields in which you *must* enter a value contain the statement (required) next to the field name in the documentation.

Jump Code

A 10–position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed in the jump code field for that screen.

To *jump* to another screen, press **Home**, type the jump code of the screen to which you want to jump, and then press **Enter**.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
(Partner Name – protected)	A 35–position alphanumeric field used to display the partner name, as found on the Name and Address record. The partner name can help to further identify the Partner ID.	(User Name – protected)	A 35–position alphabetic field displaying the user name, if it exists on file for the User/Partner ID.
Part ID (protected)	Displays the Partner ID that you have entered or selected. Note: The Partner ID and Qualifier make up the key for all associated records.	(Partner Name – protected)	A 35–position alphabetic field displaying the partner name, if it exists on file for the User/Partner ID.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
Qual (protected)	Displays the Qualifier associated with the Partner ID, if applicable.	User/Partner (protected)	Two 15–position alphabetic fields that display the User/ Partner ID you have entered or selected.

Group ID

A 6-position alphanumeric field to define the group ID for the proprietary, fixed-format version for the Partner ID displayed.

Multiple Env Id

A 3–position alphabetic field to identify the envelope type for this interchange record within the partner profile. This field allows a single partner profile to have multiple EDI standards (e.g., X12, EDIFACT, TRADACOMS) defined under it. It eliminates the need to create multiple partner profiles for a single trading partner in the event that the partner uses more than one EDI standard. Valid values include these standards: **ISA**, **ICS**, **BG**, **GS**, **UNA**, **UNB**, **SCH**, **STX**, **GEN**, and spaces.

Envelope ID

A 3-position alphanumeric field that defines which generic envelope the system will use when generating the generic group. This envelope ID should be defined using the User Envelope Specifications screen in Standards Maintenance. If this field has a value, the Outbound Mapping program attempts to generate this envelope and its associated trailer (if one is defined).

Modifier

A 1-position alphanumeric field to differentiate one Envelope ID from another, if the same Envelope ID is defined multiple times in the user-envelope specifications.

Sender ID

A 15-position alphanumeric field to define your interchange Sender ID.

If the Sender ID field contains data, the system maps it into the header envelope or associated trailer envelope as specified in the Sender ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

Receiver ID

A 15-position alphanumeric field to define your trading partner's interchange Receiver ID.

If the Receiver ID field contains data, the system maps it into the header envelope or associated trailer envelope as specified in the Receiver ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

Version ID

A 12-position alphanumeric field to define the version of the proprietary, fixed-format standard to process the data sent to this trading partner.

If the Version ID field contains data, the system maps it into the header envelope or associated trailer envelope as specified in the Version ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

The system also uses this field to determine which general transaction map will be selected for outbound processing.

Transaction ID

A 6-position alphanumeric field to define the transaction set for the proprietary, fixed-format version.

If the Transaction ID field contains data, the system maps it into the header envelope or associated trailer envelope as specified in the Transaction ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

Reference

An 18-position alphanumeric field to automatically generate the interchange reference number.

If the Reference field contains numeric data, the system increments it by '1' and maps it into the header envelope or associated trailer envelope as specified in the Reference Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance. If the field contains alphanumeric data, the system maps it into the envelope unchanged.

Gen Element 1 (Generic Element 1)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 2 (Generic Element 2)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 3 (Generic Element 3)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 4 (Generic Element 4)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 5 (Generic Element 5)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 6 (Generic Element 6)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 7 (Generic Element 7)

A 20-position field to define what data the system will map to the interchange header or associated trailer into the position defined on the Version/Outbound Specification screen.

Reserved Words

The following reserved words can be used in Generic Elements 1 through 7. **These reserved words are only valid in the group trailer segments.**

&SEGCNT	The number of segments generated between the group header and the group trailer. This count <u>does not</u> include the group header and trailer.
&SEGCNT2	The number of segments generated between the group header and the group trailer. This count <u>does</u> include the group header and trailer.
&TRNCNT	The number of transaction headers generated between the group header and trailer.

Transaction Information Screen – Generic**EDIM044***Purpose*

The Transaction Information screen allows you to identify separate processing for various transactions.

The system automatically adds a default transaction record when a new Partner Control record is added. If you intend to use the default transaction record, you should update the record to reflect the appropriate information for your trading partner. Most often, however, users create a separate transaction record for each type of transaction set that will be sent or received.

This screen specifies the information that is placed in the generic transaction envelope for a proprietary, fixed-format standard. The system moves the information specified on this screen to either the header envelope identified by the Envelope ID field or its associated trailer envelope.

The location of the fields to be moved and the associated trailer envelope are defined using the User Envelope Specifications screens in Standards Maintenance. If these envelopes are not defined in the User-Envelope file, the envelope generation process fails.

Note: This Gentrans:Structure screen will generate change audit records for Fixed Format Partner Transaction records if Partner Change Audit is enabled. See chapter 7, “Tips and Techniques,” in the *Gentrans:Basic User’s Guide* for more information about the Change Audit functionality.

How to Access

Access the Transaction Information screen by completing the following steps.

1. On the Partner Maintenance Menu, type **2** to select Partner Maintenance. The system displays the Partner Selection screen.
2. **For Partner/Qualifier Mode:**
Type a valid Partner ID in the Part ID field and Qualifier in the Qual field.

OR

For Relationship Mode:
Type a valid User in the User field and Partner in the Partner field.
3. Type **4** to select Transaction Directory and press **Enter**. The system displays the Transaction Directory screen.
4. Type **s** in the A (Action Code) field for the selected Transaction ID and press **PF5=Trans**. The system displays the Transaction Information screen.

Screen Examples

The following diagrams illustrate the Transaction Information screen for both the Partner/Qualifier and Relationship (User/Partner) modes.

Partner/Qualifier Mode

```

EDIM044 1.2.4.1__      TRANSACTION INFORMATION      XXX  12/01/2005
                                      12:00:00

          LAWN VENDOR FOR DEMONSTRATION
Part ID:  LAWNVEND                      Qual:
Transaction ID:  !!!DFT  Multiple Env Id:

Translation Map ID Inbound..:  _____  Outbound:  _____
Application Databank Inbound:  _ (F/D/N)    Outbound:  _ (F/D/N)

Outbound envelope information for Generic Transaction:
Envelope ID..:  _____  Modifier.....:  _
Sender ID....:  _____  Receiver ID...:  _____
Version ID...:  _____  Reference.....:  _____
Gen Element 1:  _____  Gen Element 2.:  _____
Gen Element 3:  _____  Gen Element 4.:  _____
Gen Element 5:  _____

Enter PF1=Help      PF3=Exit PF4=TDir      PF5=Name      PF6=Nxt Tran
                   PF9=Add PF10=Updt PF11=Del    PF14=Info

```

Relationship Mode

```

EDIM044 1.2.4.1__      TRANSACTION INFORMATION      XXX  12/01/2005
                                      12:00:00

          YOUR COMPANY                      EXAMPLE OF A FIX FORMAT PARTNE
User...:  YOUR COMPANY                      Partner:  LAWNVEND
Transaction ID:  0909__  Multiple Env Id:

Translation Map ID Inbound..:  _____  Outbound:  _____
Application Databank Inbound:  F (F/D/N)    Outbound:  F (F/D/N)

Outbound envelope information for Generic Transaction:
Envelope ID..:  THD                      Modifier.....:  _
Sender ID....:  _____  Receiver ID...:  _____
Version ID...:  _____  Reference.....:  000000000000000001
Gen Element 1:  _____  Gen Element 2.:  _____
Gen Element 3:  _____  Gen Element 4.:  _____
Gen Element 5:  _____

Enter PF1=Help      PF3=Exit PF4=TDir      PF5=Name      PF6=Nxt Tran
                   PF9=Add PF10=Updt PF11=Del    PF14=Info

```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran: Basic for zSeries Release 6.4 User's Guide*.

To display a different transaction definition, type a partial or complete Transaction ID in the Transaction ID field, and press **Enter**.

- PF4=TDI** Displays the Transaction Directory screen for the selected Partner ID.
- PF5=Name** Displays the Name And Address screen for the selected Partner ID.
- PF6=Nxt Tran** Displays processing instructions for the next transaction defined for this Partner ID.
- PF9=Add** Adds the new transaction definition for the Partner ID displayed. Type the appropriate parameter values and press **PF9=Add**.
- PF10=Updt** Updates an existing transaction definition. Type the new data over the existing data and press **PF10=Updt**.
- PF11=Del** Deletes the transaction information record for the specified Partner ID. Press **PF11=Del** to delete the data. The system will prompt you to confirm the delete.
- PF14=Info** Displays the date, time and user initials on the message line, to indicate when the information on this screen was created or last changed.

Field Descriptions

Note: Fields that are display-only contain the statement (protected) next to the field name in the documentation.

Fields in which you *must* enter a value contain the statement (required) next to the field name in the documentation.

Jump Code

A 10–position alphabetic or numeric field containing the jump code for this screen. A screen’s jump code is displayed in the jump code field for that screen.

To *jump* to another screen, press **Home**, type the jump code of the screen to which you want to jump, and then press **Enter**.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
(Partner Name – protected)	A 35–position alphanumeric field used to display the partner name, as found on the Name and Address record. The partner name can help to further identify the Partner ID.	(User Name – protected)	A 35–position alphabetic field displaying the user name, if it exists on file for the User/Partner ID.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
Part ID (protected)	Displays the Partner ID that you have entered or selected. Note: The Partner ID and Qualifier make up the key for all associated records.	(Partner Name – protected)	A 35–position alphabetic field displaying the partner name, if it exists on file for the User/Partner ID.
Qual (protected)	Displays the Qualifier associated with the Partner ID, if applicable.	User/Partner (protected)	Two 15–position alphabetic fields that display the User/ Partner ID you have entered or selected.

Transaction ID

A 6-position alphanumeric field to define the Transaction ID for the proprietary, fixed-format version for the Partner ID displayed.

Multiple Env Id

A 3–position alphabetic field to identify the envelope type for this interchange record within the partner profile. This field allows a single partner profile to have multiple EDI standards (e.g., X12, EDIFACT, TRADACOMS) defined under it. It eliminates the need to create multiple partner profiles for a single trading partner in the event that the partner uses more than one EDI standard. Valid values include these standards: **ISA, ICS, BG, GS, UNA, UNB, SCH, STX, GEN**, and spaces.

Translation Map ID Inbound

A 10-position alphanumeric field identifying the specific map for the application to use for this partner and transaction. Used for partner-specific mapping only.

Translation Map ID Outbound

A 10-position alphanumeric field that identifies the specific map for the application to use for this partner and transaction. Used for partner-specific mapping only.

Application Databank Inbound

A 1-position alphabetic field identifying the level of Application Databank to be used. Valid values are:

F = Full
D = Directory-only
N = None

This field is only applicable if used with Global Parameter – ‘Partner Databank.’

Application Databank Outbound

A 1-position alphabetic field identifying the level of Application Databank to be used.
Valid values are:

F	=	Full
D	=	Directory-only
N	=	None

This field is only applicable if used with Global Parameter – ‘Partner Databank.’

Envelope ID

A 3-position alphanumeric field that defines which generic envelope the system should use when generating the generic transaction. This Envelope ID should be defined using the User Envelope Specifications screens in Standards Maintenance. If this field contains a value, the Outbound Mapping program attempts to generate this envelope and its associated trailer (if one is defined).

Modifier

A 1-position alphanumeric field that will differentiate one Envelope ID from another, if the same Envelope ID was defined multiple times in the user-envelope specifications.

Sender ID

A 15-position alphanumeric field to define your transaction Sender ID.

If the Sender ID field contains data, the system maps it into the header envelope or associated trailer envelope as specified in the Sender ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

Receiver ID

A 15-position alphanumeric field to define your trading partner’s transaction Receiver ID.

If the Receiver ID field contains data, the data will be mapped into the header envelope or associated trailer envelope as specified in the Receiver ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

Version ID

A 12-position alphanumeric field to define the version of the proprietary, fixed-format standard used to process the data sent to this trading partner.

If the Version ID field contains data, it will be mapped into the header envelope or associated trailer envelope as specified in the Version ID Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance.

Reference

An 18-position alphanumeric field to automatically generate the transaction reference number.

If the Reference field contains numeric data, the system increments it by ‘1’ and maps it into the header envelope or associated trailer envelope as specified in the Reference Start and Length fields on the Version/Outbound Specification screen in Standards Maintenance. If this field contains alphanumeric data, the system maps it into the envelope unchanged.

Gen Element 1 (Generic Element 1)

A 20-position field defining what data the system will map to the transaction header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 2 (Generic Element 2)

A 20-position field to define what data the system will map to the transaction header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 3 (Generic Element 3)

A 20-position field to define what data the system will map to the transaction header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 4 (Generic Element 4)

A 15-position field to define what data the system will map to the transaction header or associated trailer into the position defined on the Version/Outbound Specification screen.

Gen Element 5 (Generic Element 5)

A 15-position field to define what data the system will map to the transaction header or associated trailer into the position defined on the Version/Outbound Specification screen.

Reserved Words

The following reserved words can be used in Generic Elements 1 through 5. **These reserved words are only valid in the transaction trailer segments.**

&SEGCNT	The number of segments generated between the transaction header and the transaction trailer. This count does <i>not</i> include the transaction header and trailer.
&SEGCNT2	The number of segments generated between the transaction header and the transaction trailer. This count <i>does</i> include the transaction header and trailer.

Standards Maintenance Subsystem

Overview

This section describes how the Standards Maintenance subsystem supports Gentran:Structure.

The Standards Maintenance screens enable you to enter user-defined standards. The following table describes the screens that enable you to define user envelopes.

Screen	Description
User Envelope Specification screen (EDIM190)	Defines and maintains envelope structures for fixed-format standards. Use this screen to add, display or change a user envelope.
Version/Outbound Specification screen (EDIM191)	Defines and maintains envelope version, transaction set, and outbound specification fields for user-defined envelopes.

Handling the Fixed-Format Segment ID

The following rules apply to handling the fixed-format segment ID:

- If the segment ID starts in position 1, you do not need to code a data element for it in the standards.
- If the segment ID starts in a position after the last element of the segment, you do not need to code a data element for it in the standards.
- If the segment ID starts in the middle of a segment, you must code the segment ID as an element in the standards, and map to it via transaction mapping. You should code a constant value that will write every time the segment writes.

In our example of the JASS standards in the Tutorial in chapter 2 of this guide, every EDI segment length is 80 bytes. The last three bytes are reserved for the segment ID. We set up the standards so the last data field would end in position 77. We did not code a specific element to fall in positions 78 – 80. The Mapper automatically puts the segment ID in this position without an element for “segment ID” being coded in the standards.

See the *Gentran:Basic for zSeries Release 6.4 User's Guide* for more information on the Standards feature.

Standards Maintenance Menu

EDIM100

The Standards Maintenance Menu contains menu options that you can use to perform Standards file maintenance online. Use these screens to display, add, and change EDI standards. When you implement Gentran:Structure, the User Envelope Specification option (option 12) becomes enabled on this screen. Select the User Envelope Specification option to add, display, or change a user envelope.


See the *Gentran:Basic for zSeries User's Guide* for additional information about the Standards Maintenance Menu.

How to Access

Access the Standards Maintenance Menu from the Gentran Main Menu by typing **2** to select the Standards Maintenance Menu, and pressing **Enter**.

Screen Example

The following diagram illustrates the Standards Maintenance Menu.



Gentran:Structure

Version Screen**EDIM110***Purpose*

The Version screen displays the highest level of standards maintenance. All standards records are associated with a specific version ID, the definition for which is maintained at this level. This screen enables you to view, change, or delete the definition for the version ID. When you implement *Gentran:Structure*, the system makes the envelope type User-Defined available.

How to Access

Access the Version screen by selecting **2**, Version, from the Standards Maintenance Menu and pressing **Enter**.

Screen Example

The following diagram illustrates the Version screen.

```

EDIM110 2.2_____          VERSION          XXX      12/01/2005
                                           12:00:00

Version Id.....:  JASS_____
Agency.....:     SC

LAWN_CARE_PROPRIETARY_STANDARD_____          Description.....:

Envelope Type....:  D  (A=ANA, E=Edifact, T=TDCC, X=X12, D=User Defined)
Update Allowed...:  N  (Y/N)

Last Update Date: 01/01/98
Time: 12:00:00
User: XXX

Enter PF1=Help PF2=Tdir  PF3=Exit PF4=Vdir    PF5=Trans    PF6=Nxt Vers
          PF9=Add PF10=Updt PF11=Del
  
```

Gentran:Structure*Function Key Descriptions*

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

- PF2=Tdir** Displays the Transaction Directory for the version displayed on the Version screen.
- PF4=Vdir** Displays the Version Directory beginning with the version displayed on the Version screen.

PF5=Trans	Displays the Transaction screen for the displayed version.
PF6=Nxt Vers	Displays the next consecutive Version record. Versions are displayed in ascending alphanumeric order.
PF9=Add	Creates a new Version record.
PF10=Updt	Updates the current Version record after you have changed information on the Version screen.
PF11=Del	Deletes the current Version record.

Field Descriptions

Note: Fields that are display-only contain the statement (protected) next to the field name in the documentation.

Fields in which you *must* enter a value contain the statement (required) next to the field name in the documentation.

Jump Code

A 10–position alphabetic or numeric field containing the jump code for this screen. A screen’s jump code is displayed in the jump code field for that screen.

To *jump* to another screen, press **Home**, and type the jump code of the screen to which you want to jump, and then press **Enter**.

See the “Jump Codes” section at the beginning of this chapter for further information on using jump codes.

Version Id (required)

A 12–position alphanumeric field for you to enter the version identification of the standard.

Agency

A 3–position alphabetic field that contains the agency associated with the Version ID.

Description

A 54–position alphanumeric field that contains information about this version.

Envelope Type

A 1–position alphanumeric field to enter the codes for selecting EDI envelope type. Valid values are:

A	=	TRADACOMS
E	=	Edifact
T	=	TDCC
X	=	X12
D	=	User-Defined – This option indicates to the system that a proprietary, fixed-format standard version is defined.

Update Allowed

A 1–position alphabetic field that indicates whether or not this Version record can be updated. Valid values are:

Y = Yes, any records for this version can be updated.

N = No, none of the records for this version can be updated.

Last Update Date (protected)

An 8-position field that displays the date on which this Version record was created or last changed. The date format is **MM/DD/YY**.

Last Update Time (protected)

An 8-position field that displays the time at which this version record was created or last changed. The time format is **HH:MM:SS**.

User (protected)

A 3-position field that displays the initials of the user who created or last changed this Version record.

Data Element Definition Screen**EDIM160***Purpose*

The Data Element Definition screen allows you to add, display, and change the definition of individual data elements within a segment.

The system displays different values in the Element Type field depending on the version definition. When the Version definition has an envelope type of D, indicating a user-defined standard, the system makes additional data types available. These are the data types that are available for defining application fields and have the same definitions.

How to Access

Access the Data Element Definition screen either of the following ways:

- Type **9** to select Data Element Definition on the Standards Maintenance Menu and press **Enter**.
- OR
- On the Segment Element screen, type an **s** in the A (Action Code) field next to the appropriate element, then press **PF5 =Elem Def**.

Screen Examples

The following diagrams illustrate the Data Element Definition screen both for non-user-defined standards and for user-defined standards.

For Non-User-Defined Standards

```

EDIM160 2.9 _____ DATA ELEMENT DEFINITION PRW 12/01/2005
                                                    12:00:00

Version Id....: _____ Agency.....: SC_
Element Id....: _____ Element Version:  __
Description:
_____

Element Type...: __ (AN/ID/R/Nn/DT/D8/TM/T6/T8/CD/B)

Minimum Length:  __
Maximum Length:  _____

Composite Code Definition: _____ Last Update Date:
                                                    Time:
                                                    User:

PLEASE ENTER VERSION, AGENCY, ELEMENT ID
Enter PF1=Help          PF3=Exit PF4=Seg Elem  PF5=Code Dir  PF6=Nxt Elem
                        PF9=Add PF10=Updt PF11=Del

```

For User-Defined Standards

Showing User-Defined Element Types

```

EDIM160 2.9_____ DATA ELEMENT DEFINITION PRW 12/01/2005
                                           12:00:00

Version Id....: JASS_____ Agency.....: SC_

Element Id....: 4_____ Element Version: 00

Description:
PURCHASE_ORDER_NUMBER_____

Element Type..: AN (AN/ID/R/Nn/DT/D8/TM/T6/T8/CD/B - ALL STANDARDS)
                  (DD/MM/JD/YY/PD/PJ/PM/PY/Pn/Sn - USER DEFINED )
                  (CM/J8/CY/ZD/ZJ/ZM/ZY - USER DEFINED )

Minimum Length: 006

Maximum Length: 00006

Composite Code Definition: _____ Last Update Date: 12/01/05
                                           Time: 12:00:00
                                           User: XXX

Enter PF1=Help          PF3=Exit PF4=Seg Elem  PF5=Code Dir  PF6=Nxt Elem
                        PF9=Add PF10=Updt PF11=Del

```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran: Basic for zSeries Release 6.4 User's Guide*.

PF4=Seg Elem	Displays the Segment Element screen for this Data Element Definition record.
PF5=Code Dir	Displays the Standard Code Directory for the displayed Data Element Definition record. Codes are valid only with element type of AN or ID.
PF6=Nxt Elem	Displays the next consecutive Data Element Definition record. The system displays Data Element Definition records in ascending alphanumeric sequence.

Field Descriptions

Element Type

A 2-position alphanumeric field to enter the code for the element type. Valid values are:

AN	=	String type
ID	=	Identifier Type, used with code lists
R	=	Decimal type (data contains explicit decimal point)
Nn	=	Numeric with 'n' decimal places implied
DT	=	Date format – YYMMDD or YYYYMMDD
TM	=	Time format – HHMM
CD	=	Date format – DDMMYYYY

- D8** = An 8-position Date – YYYYMMDD
- T6** = A 6-position Time – HHMMSS
- T8** = An 8-position Time – HHMMSShh
- B** = Binary

The following values are valid only for versions that have been defined with an envelope type of D (indicating a user-defined standard):

- Sn** = Zoned Decimal
- Pn** = Packed Decimal
- YY** = Character Date – YYMMDD
- MM** = Character Date – MMDDYY
- DD** = Character Date – DDMMYY
- JD** = Character Date – YYDDD
- PY** = Packed Date – YYMMDD
- PM** = Packed Date – MMDDYY
- PD** = Packed Date – DDMMYY
- PJ** = Packed Date – YYDDD
- CM** = Date format – MMDDYYYY
- J8** = Date format – Julian YYYYDDD
- CY** = Date format – YYYYMMDD
- ZD** = Date format – Packed DDMMYYYY
- ZJ** = Date format – Packed YYYYDDD
- ZM** = Date format – Packed MMDDYYYY
- ZY** = Date format – Packed YYYYMMDD

Note: For complete field descriptions for this screen, see Chapter 3 in the *Gentran: Basic for zSeries Release 6.4 User's Guide*.

User Envelope Specification Screen**EDIM190***Purpose*

The User Envelope Specification screen enables you to view and maintain definitions for user envelopes. You may also add a new definition and delete an existing definition.

Note: This Gentran:Structure screen will generate change audit records for Fixed Format Standards User Envelope records if Standards Change Audit is enabled. See chapter 7, “Tips and Techniques,” in the *Gentran:Basic User’s Guide* for more information about the Change Audit functionality.

Gentran:Structure requires the definition of each of the generic envelope structures used for fixed-format standards. The envelope definitions determine the layout of the envelope as follows:

- For outbound processing, the system uses these definitions in conjunction with Partner Maintenance screens where these generic envelopes are referenced. Using information from both of these sources, the Outbound Mapping program generates these envelopes automatically.
- For inbound processing, the system uses these envelope definitions to accurately split fixed-format data from variable-format EDI data. The Inbound Pre-Processing program also uses them to extract trading partner, version, and transaction set information from the fixed-format data. **The system does not perform data extraction for trailer envelopes.**

Note: In addition to the User Envelope Specification screen, you will use the Version/Outbound Specification screen to enter detailed information about each defined envelope.

How to Access

Access this screen by typing **12** to select User Envelope Specification from the Standards Maintenance Menu, and pressing **Enter**.

Screen Example

The following example illustrates the User Envelope Specification screen.

```

Add Delete Update Version/outbound-specification
EDIM190 2.12 _____ USER ENVELOPE SPECIFICATION      XXX  12/01/2005
                                                    12:00:00

Starting Segment ID.: _____

A ---Segment-- -Seg ID- -Env-  -Usr ID-  -Prt ID-  -Associated- Ver  Last Updt
   ID      Mod  Start Ln Lvl D  Start Ln  Start Ln  Hdr/Trl  Mod Spc  Date User
- GBG _____ 1 3  BG B  _____ 4 15  GEN _____  Y  020598 XXX
- GEN _____ 1 3  EG B  _____  _____  _____  Y  020598 XXX
- GHD _____ 78 3  BG B  _____ 1 15  GTR _____  Y  020598 XXX
- GTR _____ 78 3  EG B  _____  _____  GHD _____  Y  020598 XXX
- IBG _____ 1 3  BI B  _____ 4 15  IEN _____  Y  020598 XXX
- IEN _____ 1 3  EI B  _____  _____  IBG _____  Y  020598 XXX
- PHD _____ 78 3  BI B  _____ 1 15  PTR _____  Y  020598 XXX
- PTR _____ 78 3  EI B  _____  _____  PHD _____  Y  020598 XXX
- TBG _____ 1 3  BT B  _____  _____  TEN _____  Y  020598 XXX
- TEN _____ 1 3  ET B  _____  _____  TBG _____  Y  020598 XXX

Enter PF1=Help          PF3=Exit
      PF7=Bwd   PF8=Fwd
  
```

Screen Actions

The system displays the screen actions on the top line of the User Envelope Specification screen. The following table describes each screen action function and gives instructions on how to perform those actions.

To perform this action ...	Associated with this screen action ...	Do this ...
Add a user envelope definition record	Add	Type A in the A (Action Code) field, type the required data (type over displayed data), and press Enter . The system redisplay the screen and displays a confirmation message.
Delete an existing record	Delete	Type D in the A (Action Code) field and press Enter . The system redisplay the screen and displays a confirmation message.
Update the information for an existing definition	Update	Type U in the A (Action Code) field for the specified line, type the changes over the existing data, and press Enter . The system redisplay the screen and displays a confirmation message.
Select a record so that you may view the fields associated with Version/Outbound Specification	Version/Outbound-Specification	Type V in the A (Action Code) field and press Enter . The system displays the Version/Outbound Specification screen.

Note: To display a list of user-envelope specification file records starting at a selected Segment ID, type the value in the Starting Segment ID field and press **Enter**.

Field Descriptions

Starting Segment ID

This field enables you to designate a starting position for the list of user envelopes the system displays on the screen.

A (Action Code)

A 1-position alphabetic field for entering an action to be performed. Valid values are:

A (Add) – Add a User Envelope definition record.

Type **a** in the A (Action Code) field next to the desired record, type the required data (type over displayed values), and press **Enter**.

D (Delete) – Delete an existing record.

Type **d** in the A (Action Code) field next to the desired record and press **Enter**.

U (Update) – Update the information for an existing definition.

Type **u** in the A (Action Code) field next to the desired line, type the changes over the existing data, and press **Enter**.

V (Version/Outbound-Specification) – Displays the Version/Outbound Specification screen so that you may view the fields associated with Version/Outbound Specification.

Type **v** in the A (Action Code) field next to the desired record and press **Enter**.

Segment ID

A 10-position alphanumeric field to define the characters that will identify this envelope. Currently, Standards Maintenance will only support 3-position segment IDs. The system issues the following warning if you type more than three characters:

WARNING: SEG IDS > 3 CHAR LONG NOT SUPPORTED

Segment Mod

A 1-position alphanumeric field to enable you to enter the same Segment ID multiple times.

Example

You would use this field if the same segment ID defined an envelope in two different standards and each of the envelopes had different characteristics.

Seg ID Start

A 5-position numeric field to define the starting offset of the Segment ID field. Valid values are: **1 – 32760**.

Seg ID Ln

A 2-position numeric field to define the length of the Segment ID field. Valid values are **1 – 3**. Currently, Standards Maintenance only supports segment IDs up to three positions in length.

Env Lvl

A 2-position alphabetic field to define what type of envelope this segment defines. Valid values are:

- BI** Beginning Interchange
The system generates these envelopes each time the receiver changes during outbound processing.
- BG** Beginning Group
The system generates these envelopes each time the sender or receiver changes during outbound processing.
- BT** Beginning Transaction (message)
The system generates these envelopes at the start of each transaction or message during outbound processing.
- ET** Ending Transaction (message)
The system generates these envelopes at the end of each transaction or message to correspond to a beginning transaction envelope.
- EG** Ending Group
The system generates these envelopes at the end of a message to correspond to a beginning group envelope. The system generates the envelopes prior to a sender/receiver change or end of file.
- EI** Ending Interchange
The system generates these envelopes at the end of a message to correspond to a beginning interchange envelope. The system generates the envelopes prior to a receiver change or end of file.

Env D (Direction)

A 1-position alphabetic field to define the type of processing for which the system will use the envelope. The batch processing programs use this information to achieve maximum processing efficiency. Inbound envelopes will be loaded only by the inbound process. Valid values are:

- I** = Inbound-only processing
O = Outbound-only processing
B = Inbound and outbound processing

Usr ID Start

A 5-position numeric field to define the starting position of the field that contains the User ID information used to access the partner profile. The Inbound Pre-Processing program uses this field to determine the user ID that is needed for processing in relationship mode processing. The User ID Start field is valid only when the Usr ID Ln field contains a value. Valid values are **1 – 32760**.

Usr ID Ln

A 2-position numeric field to define the length of the field that contains the User ID information used to access the partner profile. The Inbound Pre-Processing program uses this field to determine the User ID that is needed for processing in relationship mode. The User ID Ln field is valid only when the Usr ID Start field contains a value. Valid values are **1 – 35**.

Prt ID Start

A 5-position numeric field to define the start of the field that contains the Partner ID information used to access the partner profile. The Inbound Pre-Processing program uses this field to determine the Partner ID that is needed by the Mapping Program. Partner ID Start is valid only when Prt ID Ln also contains a value. Valid values are **1 – 32760**.

Prt ID Ln

A 2-position numeric field to define the length of the field that contains the Partner ID information, which is used to access the partner profile. The Inbound Pre-Processing program uses this field to determine the Partner ID that is needed by the Mapping Program. The Partner ID Ln field is valid only when the Prt ID Start field contains a value. Valid values are **1–35**.

Associated Hdr/Trl

A 10-position alphanumeric field to identify the Segment ID of the corresponding header (for trailer type envelopes) or trailer (for header type envelopes). The system uses this field to form a link between corresponding User-Envelope Headers and Trailers. Currently, Standards Maintenance supports only 3-position segment IDs. The system issues a warning if you type more than 3 characters.

Associated Mod

A 1-position alphanumeric field to identify the Segment ID of the corresponding header or trailer envelope, if that corresponding envelope was defined with a modifier.

Example

You would use this field if the same segment ID defined an envelope in two different standards and each of the envelopes had different characteristics.

Ver Spc (Version/Outbound Specification) (protected)

A 1-character alphabetic field to indicate whether envelope fields have been identified for this envelope on the Version/Outbound Specification screen (EDIM191). Valid values are:

Y	=	Version/Outbound Specifications have been defined for this envelope.
N	=	No Version/Outbound Specifications have been defined for this envelope.

Last Date (protected)

Displays the date on which this user envelope specification was last updated.

Updt User (protected)

Displays the initials of the user who made the last update to this user envelope specification.

Version/Outbound Specification Screen

EDIM191

Purpose

The Version/Outbound Specification screen enables you to view and maintain more detailed information about each defined envelope, including the Version, Transaction Set, and Outbound Specification fields that you can define for specific user envelopes.

Note: This Gentran:Structure screen will generate change audit records for Fixed Format Standards User Envelope records if Standards Change Audit is enabled. See chapter 7, “Tips and Techniques,” in the *Gentran:Basic User’s Guide* for more information about the Change Audit functionality.

How to Access

Access this screen by typing a **v** in the A (Action Code) field next to the desired record on the User Envelope Specification screen, and pressing **Enter**.

Screen Example

The following diagram illustrates the Version/Outbound Specification screen.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          PRW 12/01/2005
                                                    12:00:00

Segment ID.....: PHD          Modifier:          Length:  __80
Default Version ID...: _____ Agency...:  __ Transaction ID:  _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....:  __41         _4          Transaction ID.....:  _____
Sender ID.....:   __1          15          Receiver ID.....:   __16         15
Reference Number...:  __51         _9          Generic Element 1..:  __45         _6
Generic Element 2...:  _____          Generic Element 3...:  _____
Generic Element 4...:  _____          Generic Element 5...:  _____
Generic Element 6...:  _____          Generic Element 7...:  _____
Generic Element 8...:  _____          Generic Element 9...:  _____
Generic Element 10...:  _____          Current Date.....:  __31         _6
Current Time.....:  __37         _4          Current Date Format: YY

                               Last Update Date: 12/01/05 Time: 12:00:00 User: XXX

Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env

```

Function Key Descriptions:

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User’s Guide*.

Enter

Re-displays the User Envelope Version/Outbound information that is currently contained on the file. Using this key cancels any updates that might have been entered on the screen prior to **PF10=Updt** being pressed.

PF3=Exit	Returns to the previous menu.
PF4=User	Returns to the User-Envelope Specification screen.
PF6=Nxt Env	Displays the next logical User Envelope record on the file.
PF10=Updt	Updates the fields on this screen. Type the changes over the existing data and press PF10=Updt . The system re-displays the screen with the updated information, and displays a confirmation message.

Field Descriptions

Segment ID (protected)

Displays the characters that identify the segment ID of the envelope that is processed.

Modifier (protected)

Displays the Segment ID modifier of the envelope that is processed.

Length

A 5-position numeric field that defines the length of the envelope record. The default is 80. Valid values are **1 – 2000**.

Default Version ID

A 12-position alphanumeric field to define what standard version the system should use for processing purposes when this user envelope is received. This field is intended to be used for proprietary, fixed-format standards, where the version is not specified on the envelope. The Inbound Pre-Processing program uses this field for version determination. It will not be used by the outbound process.

Default Agency

A 3-position alphanumeric field to define what agency the system should use.

Default Transaction ID

A 6-position alphanumeric field to define what transaction set the system should use for processing purposes when this user envelope is received. This field is intended to be used for proprietary, fixed-format standards where the transaction set is not specified on the envelope. The Inbound Pre-Processing program uses this field for transaction determination. It will not be used by the outbound process.

Version ID Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the standard version. The system uses this field to extract a version during inbound processing and to load a version for outbound processing. The Version ID Start field is valid only when the Version ID Length field also contains a value. Valid values are **1 – 2000**.

Version ID Length

A 2-position numeric field to define the length of the field that contains the standard version. The system uses this field to extract a version during inbound processing and to load a version for outbound processing. The Version ID Length field is only valid when the Version ID Start field contains a value. Valid values are **1 – 12**.

Transaction ID Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the transaction set ID. The system uses this field to extract a transaction set ID during inbound processing and to load a transaction set ID for outbound processing. The Transaction Set ID Start field is valid only when Transaction Set ID Length field also contains a value. Valid values are **1 – 2000**.

Transaction ID Length

A 2-position numeric field to define the length of the field that contains the transaction set ID. The system uses this field to extract a transaction set ID during inbound processing and to load a transaction set ID for outbound processing. The Transaction Set ID Length field is valid only when the Transaction Set ID Start field contains a value. Valid values are **1 – 6**.

Sender ID Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the sender ID. The system uses this field to extract the sender ID during inbound processing. The reserved word constants GEN-INT-SNDR, GEN-GRP-SNDR, and GEN-TRN-SNDR will contain the resolved Partner ID of the sender. The system also uses the field to load the sender ID specified on the partner profile (using the generic envelope screens) for outbound processing. The Sender ID Start field is valid only when Sender ID Length field also contains a value. Valid values are **1 – 2000**.

Sender ID Length

A 2-position numeric field to define the length of the field that contains the sender ID. The system uses this field to extract the sender ID during inbound processing. The reserved word constant GEN-INT-SNDR, GEN-GRP-SNDR, and GEN-TRN-SNDR will contain the resolved Partner ID of the sender. The system also uses the field to load the sender ID specified on the partner profile (using the generic envelope screens) for outbound processing. The Sender ID Length field is valid only when the Sender ID Start field contains a value. Valid values are **1 – 15**.

Receiver ID Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the receiver ID. The system uses this field to extract the receiver ID during inbound processing. The reserved word constant GEN-INT-RCVR, GEN-GRP-RCVR, and GEN-TRN-RCVR will contain the resolved partner ID of the receiver. The system also uses the field to load the receiver ID specified on the partner profile (using the generic envelope screens) for outbound processing. The Receiver ID Start field is valid only when Receiver ID Length field also contains a value. Valid values are **1 – 2000**.

Receiver ID Length

A 2-position numeric field to define the length of the field that contains the receiver ID. The system uses this field to extract the receiver ID during inbound processing. The reserved word constants GEN-INT-RCVR, GEN-GRP-RCVR, and GEN-TRN-RCVR will contain the resolved partner ID of the receiver. The system uses it to load the receiver ID specified on the partner profile (using the generic envelope screens) for outbound processing. The Receiver ID Length field is valid only when the Receiver ID Start field contains a value. Valid values are **1 – 15**.

Reference Number ID Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the reference number. This number is also called the control number. The system uses this field to extract the reference number during inbound processing (the reference number will be available for mapping in the reserved word constants GEN-INT-REF, GEN-GRP-REF, and GEN-TRN-REF depending upon the envelope level). The system also uses it to load the reference number specified on the partner profile (using the generic envelope screens) for outbound processing. The Reference Number Start field is valid only when Reference Number Length field also contains a value. Valid values are **1 – 2000**.

Reference Number Length

A 2-position numeric field to define the length of the field that contains the reference number. This number is also called the control number. The system uses this field to extract the reference number during inbound processing (the reference number will be available for mapping in the reserved word constants GEN-INT-REF, GEN-GRP-REF, and GEN-TRN-REF depending upon the envelope level). The system also uses it to load the reference number specified on the partner profile (using the generic envelope screens) for outbound processing. The Reference Number Length field is valid only when the Reference Number Start field contains a value. Valid values are **1 – 18**.

Generic Element 1 Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the Generic Element 1 information. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 1 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-ELEMENT-01). The system also uses it to load the Generic Element 1 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 1 Start field is only valid when the Generic Element 1 Length field also contains a value. Valid values are **1 – 2000**. This field is valid for all envelope types.

Generic Element 1 Length

A 2-position numeric field to define the length of the field that contains the reference number. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 1 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP/TRN)-ELEMENT-01). The system also uses it to load the Generic Element 1 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 1 Length field is valid only when the Generic Element 1 Start field contains a value. Valid values are **1 – 20**. This field is valid for all envelope types.

Generic Element 2 Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the Generic Element 2 information. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 2 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP/TRN)-ELEMENT-02). The system also uses it to load the Generic Element 2 data specified on the partner profile

(using the generic envelope screens) for outbound processing. The Generic Element 2 Start field is valid only when Generic Element 2 Length field also contains a value. Valid values are **1 – 2000**. This field is valid for all envelope types.

Generic Element 2 Length

A 2-position numeric field to define the length of the field that contains the reference number. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 2 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP/TRN)-ELEMENT-02). The system also uses it to load the Generic Element 2 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 2 Length field is valid only when the Generic Element 2 Start field contains a value. Valid values are **1 – 20**. This field is valid for all envelope types.

Generic Element 3 Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the Generic Element 3 information. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 3 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP/TRN)-ELEMENT-03). The system also uses it to load the Generic Element 3 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 3 Start field is valid only when Generic Element 3 Length field also contains a value. Valid values are **1 – 2000**. This field is valid for all envelope types.

Generic Element 3 Length

A 2-position numeric field to define the length of the field that contains the reference number. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 3 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP/TRN)-ELEMENT-03). The system also uses it to load the Generic Element 3 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 3 Length field is valid only when the Generic Element 3 Start field contains a value. Valid values are **1 – 20**. This field is valid for all envelope types.

Generic Element 4 Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the Generic Element 4 information. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 4 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP/TRN)-ELEMENT-04). The system also uses it to load the Generic Element 4 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 4 Start field is valid only when Generic Element 4 Length field also contains a value. Valid values are **1 – 2000**. This field is valid for all envelope types.

Generic Element 4 Length

A 2-position numeric field to define the length of the field that contains the reference number. Defining the generic elements allows mapping to and from fields in the generic

envelopes. The system uses this field to extract the Generic Element 4 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP)-ELEMENT-04). The system also uses it to load the Generic Element 4 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 4 Length field is valid only when the Generic Element 4 Start field contains a value. Valid values are **1 – 20**. This field is valid for all envelope types.

Generic Element 5 Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the Generic Element 5 information. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 5 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP)-ELEMENT-05). The system also uses it to load the Generic Element 5 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 5 Start field is valid only when Generic Element 5 Length field also contains a value. Valid values are **1 – 2000**. This field is valid for all envelope types.

Generic Element 5 Length

A 2-position numeric field to define the length of the field that contains the reference number. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 5 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP)-ELEMENT-05). The system also uses it to load the Generic Element 5 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 5 Length field is valid only when the Generic Element 5 Start field contains a value. Valid values are **1 – 20**. This field is valid for all envelope types.

Generic Element 6 Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the Generic Element 6 information. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 6 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP)-ELEMENT-06). The system also uses it to load the Generic Element 6 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 6 Start field is valid only when Generic Element 6 Length field also contains a value. Valid values are **1 – 2000**. The system does not use this field to load outbound transaction level envelopes.

Generic Element 6 Length

A 2-position numeric field to define the length of the field that contains the reference number. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 6 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP)-ELEMENT-06). The system also uses it to load the Generic Element 6 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 6 Length field is valid only when the Generic Element 6

Start field contains a value. Valid values are **1 – 20**. The system will not use this field to load outbound transaction level envelopes.

Generic Element 7 Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the Generic Element 7 information. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 7 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP)-ELEMENT-07). The system also uses it to load the Generic Element 7 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 7 Start field is valid only when Generic Element 7 Length field also contains a value. Valid values are **1 – 2000**. The system will not use this field to load outbound transaction level envelopes.

Generic Element 7 Length

A 2-position numeric field to define the length of the field that contains the reference number. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 7 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP)-ELEMENT-07). The system also uses it to load the Generic Element 7 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 7 Length field is valid only when the Generic Element 7 Start field contains a value. Valid values are **1 – 20**. The system will not use this field to load outbound transaction level envelopes.

Generic Element 8 Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the Generic Element 8 information. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 8 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP)-ELEMENT-08). The system also uses it to load the Generic Element 8 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 8 Start field is valid only when Generic Element 8 Length field also contains a value. Valid values are **1 – 2000**. The system will not use this field to load outbound transaction level envelopes.

Generic Element 8 Length

A 2-position numeric field to define the length of the field that contains the reference number. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 8 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP)-ELEMENT-08). The system also uses it to load the Generic Element 8 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 8 Length field is valid only when the Generic Element 8 Start field contains a value. Valid values are **1 – 20**. The system will not use this field to load outbound transaction level envelopes.

Generic Element 9 Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the Generic Element 9 information. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract

the Generic Element 9 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-(INT/GRP)-ELEMENT-09). The system also uses it to load the Generic Element 9 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 9 Start field is valid only when Generic Element 9 Length field also contains a value. Valid values are **1 – 2000**. The system will not use this field to load outbound transaction level envelopes.

Generic Element 9 Length

A 2-position numeric field to define the length of the field that contains the reference number. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the generic element 9 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-INT-ELEMENT-09). The system also uses it to load the Generic Element 9 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 9 Length field is valid only when the Generic Element 9 Start field contains a value. Valid values are **1 – 20**. The system will not use this field to load outbound transaction or group level envelopes.

Generic Element 10 Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the Generic Element 10 information. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the generic element 10 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-INT-ELEMENT-10). The system also uses it to load the Generic Element 10 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 10 Start field is valid only when Generic Element 10 Length field also contains a value. Valid values are **1 – 2000**. The system will not use this field to load outbound transaction or group level envelopes.

Generic Element 10 Length

A 2-position numeric field to define the length of the field that contains the reference number. Defining the generic elements allows mapping to and from fields in the generic envelopes. The system uses this field to extract the Generic Element 10 data during inbound processing (the data will be available for mapping in the reserved word constant GEN-INT-ELEMENT-10). The system also uses it to load the Generic Element 10 data specified on the partner profile (using the generic envelope screens) for outbound processing. The Generic Element 10 Length field is valid only when the Generic Element 10 Start field contains a value. Valid values are **1 – 20**. The system will not use this field to load outbound transaction or group level envelopes.

Current Date Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the current date. The system maps the current date to the outbound envelope in CCYYMMDD format or YYMMDD format depending upon the length specified below. The system uses this field only during outbound processing. The Current Date Start field is valid only when the Current Date Length field also contains a value. Valid values are **1 – 2000**.

Current Date Length

A 2-position numeric field to define the length of the field that contains the current date. The system uses this field only during outbound processing. The Current Date Length field is valid only when Current Date Start field also contains a value. Valid values are:

- 6** = System will map the current date to the outbound envelope in YYMMDD format.
- 8** = System will map the current date to the outbound envelope in CCYYMMDD format.

Current Time Start

A 5-position numeric field to define the starting position in the envelope of the field that contains the current time. The system maps the current time to the outbound envelope in HHMMSS format or HHMM format depending upon the length specified below. The system uses this field only during outbound processing. The Current Time Start field is valid only when the Current Time Length field also contains a value. Valid values are **1 – 2000**.

Current Time Length

A 2-position numeric field to define the length of the field that contains the current time. The system uses this field only during outbound processing. The Current Time Length field is valid only when the Current Time Start field also contains a value. Valid values are:

- 6** = The system will map the current time to the outbound envelope in HHMMSS format.
- 4** = The system will map the current time to the outbound envelope in HHMM format.

Current Date Format

A 2-position alphanumeric field to define the format of the current date. The system uses this field only during outbound processing and it is valid only when the Current Date Start field contains a value. Valid values are:

- MM** = Current date will be in MMDDYY format.
- DD** = Current date will be in DDMMYY format.
- YY** = Current date will be in:
YYMMDD format (if length is 6)
YYYYMMDD format (if length is 8).

Last Update (protected)

Displays the date of the last update of the envelope definition. Format is **MM/DD/YY**.

Time (protected)

Displays the time of the last update of the envelope definition. Format is **HH:MM:SS**.

User (protected)

Displays the initials of the last user to update the envelope definition.

Mapping Integration Subsystem

Overview

This section describes how the Mapping Integration subsystem supports Gentran:Structure.

Specifically, two mapping screens and the Transaction Maintenance – Gentran:Structure screen (EDIM516) allow the definition of fixed-format maps.

Fixed-Format Segment ID

The following rules apply to handling the fixed-format segment ID:

- If the segment ID starts in position 1, you do not need to code a data element for it in the standards.
- If the segment ID starts in a position after the last element of the segment, you do not need to code a data element for it in the standards.
- If the segment ID starts in the middle of a segment, you must code the segment ID as an element in the standards and map to it via transaction mapping. You should code a constant value that will write every time the segment writes.

In our example of the JASS standards in the Tutorial chapter of this guide, every EDI segment length is 80 bytes. The last three bytes are reserved for the segment ID. We set up the standards so the last data field would end in position 77. We did not code a specific element to fall in positions 78 – 80. The mapper automatically puts the segment ID in this position without an element for segment ID being coded in the standards.

See the *Gentran:Basic for zSeries Release 6.4 User's Guide* for more information concerning the Mapping feature.

Transaction Maintenance Screen**EDIM503***Purpose*

The Transaction Maintenance screen enables you to define and maintain the transaction map header information. The header information identifies the transaction map, establishes the EDI standard version being used, identifies the transaction set, lists the transaction status/use code/envelope type, and identifies the internal Application Data ID being translated to or from. You can only view, add, update, or delete those maps having a division code equal to your own, unless your Logon ID is defined with a division of "000."

Note: You cannot move to another screen or directory, or view, add, update, or delete a map whose division is not equal to your own, unless your division code is "000."

How to Access

You can access the Transaction Maintenance screen in any of these three ways:

- Type **2** to select Transaction Maintenance from the Transaction Mapping Menu, type **s** in the **A** (Action Code) field on the Transaction Mapping Directory screen, and press **PF5=Trans**.
- Type **5.2.2** in the jump code field.
- Select a transaction ID from the Transaction Mapping Directory and press **PF5**.

Screen Example (Gentran:Structure Not Installed)

The following illustrates the Transaction Maintenance screen when Gentran:Structure is not installed.

```

EDIM503 5.2.2_____      TRANSACTION MAINTENANCE                XXX  12/01/2005
                                                                12:00:00

Transaction ID.....: ANSI3030PO          Send or Receive(S/R)...: S
Division Code.....: 000
Description.....: ANSI_003030_OUTBOUND_POS_____
Standards Version.....: 003030_____      Agency:  X__
Transaction Set.....: 850_____
Transaction Set Release...: _ (0-9, ANA Tradacoms Only)
Transaction Status.....: P (D=Development, T=Test, P=Production)
Use Code.....: G (G=General, P=Partner Specific)
Envelope Type.....: X (E=Edifact, X=X12, U=UCS, G=GS, A=ANA)
Application Data ID.....: POFILE_____
Application Selection Field Values: _____
                                                                _____
                                                                _____

RSGRSG Level.....: _ (1/2/ ANA Tradacoms Only)
Underscore Character.....: _
Update Allowed.....: Y

                                                                Job Name: _____

Enter PF1=Help          PF3=Exit PF4=Dir          PF5=Segments  PF6=Copy
PF7=Rpt                 PF9=Add PF10=Updt PF11=Del      PF14=Info

```


Screen Example (Gentran:Structure Installed)

The following diagram illustrates the Transaction Maintenance screen with Gentran:Structure installed.

Gentran:Structure

```

EDIM503 5.2.2 _____ TRANSACTION MAINTENANCE          XXX 12/01/2005
                                                    12:00:00

Transaction ID.....: JASSIN _____ Send or Receive(S/R)...: R
Division Code.....: 000
Description.....: INVOICE_FOR_JASS_STANDARDS _____
Standards Version.....: JASS _____ Agency: SC_
Transaction Set.....: 0926 _____
Transaction Set Release...: _____ (0-9, ANA Tradacoms Only)
Transaction Status.....: T (D=Development, T=Test, P=Production)
Use Code.....: G (G=General, P=Partner Specific)
Envelope Type.....: D (E=Edifact, X=X12, U=UCS, G=GS, A=ANA, D=User)
Application Data ID.....: INVFILEF _____
Application Selection Field Values: _____

Standard Type.....: F (V=Variable, F=Fixed)
RSGRSG Level.....: _____ (1/2/ ANA Tradacoms Only)
Underscore Character.....: _____
Update Allowed.....: Y

Job Name: _____

Enter PF1=Help PF2=Fixed PF3=Exit PF4=Dir PF5=Segments PF6=Copy
PF7=Rpt PF9=Add PF10=Updt PF11=Del PF12=NuMap PF14=Info

```

Gentran:Structure

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

To view an existing transaction map header definition, type the transaction ID and corresponding send or receive code, and press **Enter**.

- PF2=Fixed** Displays the Transaction Maintenance — Fixed Format screen (only if Gentran:Structure has been installed on your system). This screen enables you to update the fields associated with fixed standard support at the transaction level.
- PF4=Dir** Returns to the Transaction Directory.
- PF5=Segments** Advances to the Segments screen. This screen lists each segment defined in the transaction map specified.
- PF6=Copy** Advances to the Copy Transaction screen. This screen allows you to choose the source from which the transaction map may be built. The transaction map definition may be copied and duplicated from an existing transaction map, or segments may be copied from a specified EDI standard version.

PF7=Rpt	Allows you to submit the batch Mapping Reports for the transaction map displayed at the top of the screen.
Note:	Both the Standard and Application Sequence Reports are generated.
PF9=Add	To add a new transaction map header definition, type the required data (you can type over displayed data), and press PF9 . The system re-displays the screen with the added transaction map header definition.
PF10=Updt	To update the information for an existing transaction map header definition, type the changes over the existing data, and press PF10 . The system re-displays the screen with the changes.
PF11=Del	To delete an existing transaction map header definition and all of its associated segments and elements, press PF11 . The system displays a message prompting you to confirm the deletion.
PF14=Info	Displays the date, time and user initials on the message line, to indicate when the information on this screen was created or last changed.

Field Descriptions

Note: Fields that are display-only contain the statement (protected) next to the field name in the documentation.

Fields in which you *must* enter a value contain the statement (required) next to the field name in the documentation.

Jump Code

A 10–position alphabetic or numeric field containing the jump code for this screen. A screen’s jump code is displayed in the jump code field for that screen.

To *jump* to another screen, press **Home**, type the jump code of the screen to which you want to jump, and then press **Enter**.

Transaction ID (required)

A 10–position alphanumeric field used to name the transaction map being modified.

Send or Receive (S/R) (required)

A 1–position alphabetic field defining the send or receive code associated with the transaction ID. This code designates whether the transaction map is used to send data (outbound) or receive data (inbound). Valid values are **S** (send) – used for outbound data, and **R** (receive) – used for inbound data.

Division Code (required)

A 3–position alphanumeric field used to define your user–specific division code. This division code must match the assigned division code for the user, as specified in the Security file, unless the division code for the user is 000.

Description (required)

A 30–position alphanumeric field containing a description of the transaction map. The description provides additional information about the transaction map.

Standards Version (required)

A 12–position alphanumeric field that contains the version ID of the standard for this map.

Agency (required)

A 3–position alphabetic field that contains the agency associated with the version ID.

Transaction Set (required)

A 6–position alphanumeric field that contains the standards transaction set ID associated with this transaction map.

Transaction Set Release (ANA TRADACOMS version only)

A 1–position numeric field that indicates the release number for the Transaction Set ID.

Transaction Status (required)

A 1–position alphabetic field that indicates the status of the transaction map. Valid values are:

- D** = Map is in development.
- T** = Map is in testing process.
- P** = Map is in production status.

Use Code (required)

A 1–position alphabetic field that indicates whether transaction map may be used for general transaction purposes or is used only for translation for particular trading partners. Valid values are:

- G** = General – Map may be used with any trading partner
- P** = Partner – Map name specified on the partner file.

Envelope Type (required)

A 1–position alphabetic field that indicates the interchange envelope category to which this transaction map belongs. Valid values are:

- E** = EDIFACT
- X** = ASC X12
- U** = UCS
- G** = GS
- A** = ANA TRADACOMS
- D** = User defined (Gentran:Structure)

Application Data ID (required)

A 10–position alphanumeric field that contains the application data ID associated with this transaction map.

Application Selection Field Values

A set of six 10–position alphanumeric fields that may be used to define values for the application selection field, which results in the selection of this transaction map, if found in the application file. If any value is placed in any of the six Application Selection fields then all size values are used. Therefore, the last application selection value in the table of six should be repeated through all empty slots to avoid making blank spaces a valid application selection code.

Standard Type (required)

A 1-position alphanumeric field defining whether the Transaction map is associated with a fixed or variable standard. Valid values are:

F	=	Fixed format – Non-delimited (Requires Gentran:Structure)
V	=	Variable – Delimited EDI standards

Note: This field is not related to the application field type of fixed or variable.

RSGRSG Level (ANA TRADACOMS only)

A 1-position numeric field indicating the release of RSGRSG reconciliation message to use for this transaction map.

Underscore Character

A 1-position alphabetic field that contains the underscore substitution character that will be used in place of the actual underscore (`_`) on the screen display of selected fields for this transaction ID. Valid values are: `~`, `!`, `@`, `#`, `$`, `%`, `-`, `&`, `*`, `(`, `)`, `-`, `=`, `+`, `{`, `}`, `:`, `;`, `<`, `>`, `/`, `?`, `|`, `\`, and space.

See the topic “Using Underscore Substitution Characters” in Chapter 7 of the *Gentran:Basic for zSeries Release 6.4 User’s Guide* for more information about this feature.

Update Allowed

A 1-position alphabetic field that indicates whether any records for this Transaction ID can be updated by any user. Valid values are:

Y	=	Yes, transaction map can be updated.
N	=	No, transaction map cannot be updated.

Job Name

An 8-position alphanumeric field used to designate a user-specified job name when printing a report using the **PF7** key. Valid values are any valid job name.

To select reports for printing, type the user-specified job name in the **Job Name** field and press **PF7**. If you do not type a value in the field, the system uses a default value, which was defined during installation customization of the JCL (**EDIRJCL**) file.

Transaction Maintenance – Gentran:Structure Screen**EDIM516***Purpose*

The Transaction Maintenance – Gentran:Structure screen enables you to view and maintain the segment start and length information necessary for fixed-format mapping.

Note: This Gentran:Structure screen will generate change audit records for Fixed Format Transaction header records if Mapping Transaction Change Audit is enabled. See chapter 7, “Tips and Techniques,” in the *Gentran:Basic User’s Guide* for more information about the Change Audit functionality.

How to Access

Access this screen from the Transaction Maintenance screen by pressing **PF2=Fixed**.

Screen Example

The following diagram illustrates the Transaction Maintenance – Gentran:Structure screen.

```

EDIM516 _____ TRANSACTION MAINTENANCE          XXX  12/01/2005
                      (Gentran:Structure)                12:00:00

Transaction ID.....:  JASSIN                S/R.....:  R
Division Code.....:   000
Description.....:    INVOICE FOR JASS STANDARDS
Standards Version.....:  JASS                Agency.....:  SC
Transaction Set.....:   0926
Transaction Set Release...:                (0-9, ANA Tradacoms Only)

Envelope Format.....:  F                    (V=Variable, F=Fixed)
Segment ID Start.....:  _78                (1 to 32743)
Segment ID Length.....:  _3                (1 to 10)

Last Update Date.....:  12/01/05
Time.....:             12:00:00
User.....:             XXX

Enter PF1=Help          PF3=Exit PF4=Maint          PF5=Segments
                        PF10=Updt
  
```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User’s Guide*.

Enter	Re-displays the screen.
PF3=Exit	Returns to the previous menu.
PF4=Maint	Returns to the Transaction Maintenance screen.

PF5=Segments	Advances to the Segments screen that lists each segment defined in the transaction map specified.
PF10=Updt	Updates an existing transaction ID. Change the desired fields and press PF10=Updt .

Field Descriptions

Transaction ID (protected)

Displays a transaction map.

S/R (Send or Receive) (protected)

Displays the send or receive code associated with the transaction map ID. This code designates whether the Transaction map is used to send data (outbound) or receive data (inbound). Valid values are:

S	=	Send data
R	=	Receive data

Division Code (protected)

Displays your user-specified division code. The transaction division code must match the user's assigned division code, as specified in the Security file, unless the user's division code is 000.

Description (protected)

Displays the transaction file description. The description provides additional text to describe the transaction map.

Standards Version (protected)

Displays the name of a particular version of an EDI standard to be used with this transaction map. A standards version table entry exists for the version entered in this field.

Agency (protected)

A 3-position alphabetic field that contains the agency associated with the Version ID.

Transaction Set (protected)

Displays the standards version of the transaction set associated with your internal application data ID. The transaction set identifies an EDI transaction (e.g., 850 identifies ASCX12 purchase orders). The transaction set and standards version combination exist in the Standards Table.

Transaction Set Release (protected)

Displays the release number of the standards version transaction set associated with your internal application data ID. Valid values are **0 – 9**. This field is for ANA TRADACOMS only.

Envelope Format (protected)

A 1-position alphabetic field to indicate whether the system should write non-user envelopes (e.g., 'ISA') as variable or fixed segments. Fixed segments have fixed-length elements with no delimiters or terminators. The system writes all user-defined envelopes as fixed segments. The system automatically sets this field to F when the Envelope Type value is D (user-defined). Valid values are

F	=	Fixed segment
V	=	Variable segment

Segment ID Start (required for fixed-format envelope)

A 5-position numeric field to define the start of the field that contains the segment ID for user-defined envelopes. Valid values are **1 – 32760**. The sum of the segment ID Start and Length fields cannot exceed 32761.

Segment ID Length (required for fixed-format envelope)

A 2-position numeric field to define the length of the field that contains the segment ID for user-defined envelopes. Valid values are **1 – 3**. The sum of the segment ID Start and Length fields cannot exceed 32761.

Note: Gentran:Basic Standards Maintenance supports segment ID lengths of up to three characters only.

Last Update Date (Protected)

An 8-position field that displays the date on which the information on this screen was created or last changed. The date format is MM/DD/YY.

Last Update Time (Protected)

An 8-position field that displays the time at which the information on this screen was created or last changed. The time format is HH:MM:SS.

Last Update User (Protected)

A 3-position field that displays the initials of the user who created or last changed the information on this screen.

Application Data ID Screen**EDIM552***Purpose*

The Application Data ID screen enables you to display and change the contents of an existing application data ID, add a new application data ID, or delete an existing one. The delete function allows you to delete the application data ID along with all associated records and fields.

How to Access

Access the Application Data ID screen either of the following two ways.

- Type **2** to select Application Data ID from the Application Definition Menu.
- OR
- Type an **s** in the A (Action Code) field on the Application Directory screen to select a specific application for processing, and press **PF5=Data Id**.

Screen Example

The following diagram illustrates the Application Data ID screen.

Gentran:Structure

```

EDIM552 5.1.2_____ APPLICATION DATA ID PRW 12/01/2005
                                           12:00:00

Application Data ID.....: INVFILEF__ Send or Receive: R
Division Code.....: 000
Description.....: INVOICE_MASTER_FILE_FIX_____
Functional Group.....: IN____ IG____ 0926__
                        _____
Fixed or Variable Length...: F (F/V)
Record Length.....: 00080
Record Type Start Pos.....: 00001 Length.....: 01
Inbound Pass-Thru.....: -
Underscore Character.....: -
Update Allowed.....: Y

Last Update User.....: SCI Date.....: 00/00/00
Time.....: 00:00:00

Enter PF1=Help PF2=Copy PF3=Exit PF4=Dir PF5=Records PF6=Refer
PF9=Add PF10=Updt PF11=Del PF12=NuMap PF13=Envel

```


Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

To display header information for an application data ID, type the application data ID and the corresponding send or receive code, and press **Enter**.

PF2=Copy	Advances to the Copy Application Definition screen, where you can create new application records and field definitions by copying them from an existing application.
PF4=Dir	Returns to the Application Directory Menu, where the system displays the application data IDs starting with the one displayed on this screen.
PF5=Records	Advances to the Application Records screen. This screen lists each record found in the application definition.
PF6=Refer	Displays the Application Partner Reference screen. This screen allows you to define user, partner, and application key fields.
PF9=Add	Adds a new application data ID, if it does not already exist.
PF10=Updt	Updates an existing application data ID.
PF11=Del	Deletes an application data ID AND ALL associated records and fields.
PF13=Envel	Displays the Application Envelope Definition screen. This screen is used to define application fields that are mapped directly to the EDI envelope data elements (outbound only).

Field Descriptions

For complete screen information, see the *Gentran:Basic for zSeries User's Guide*. This section only describes the field on this screen that is specific to Gentran:Structure functionality.

Inbound Pass-Thru

This field is used for inbound application definitions only. Valid values are:

Y = Yes
N = No

If you type a Y value, inbound mapping performs the following tasks:

- Examines the input file, from either the Inbound Editor (variable standards) or the Inbound Pre-Processing program (fixed standards).
- Removes the 15-byte key that is present on the front of each record.
- Eliminates the ###MAP, ###MP2, ###MP3, ###MP4, and ###MP5, and ###MP6 records.

The rest of the file is written unchanged.

This field option is intended for users with existing applications for processing the data in the format that it is in as it is passed to the Inbound Mapping program, but who want to use the functionality of the Gentran:Basic Databank subsystem.

Databank Maintenance Subsystem

Overview

This section describes how the Databank Maintenance subsystem supports Gentran:Structure.

The majority of system changes enable you to view Gentran:Structure documents from Gentran:Realtime or Gentran:Basic databanks.

Document Access

Once Gentran:Structure is installed, the system displays two options – 13 and 14 respectively – on the Databank Maintenance Main Menu. These options represent the following programs:

- Structure Document Directory (EDIM272)
- Structure Document Status (EDIM273)

Databank Maintenance Screen Example

The following example illustrates the Databank Maintenance Menu screen (EDIM250) after Gentran:Structure is installed.

See the *Gentran:Basic for zSeries Release 6.4 User's Guide* for more information about the Databank Maintenance screen.

```
EDIM250 3.0 _____ DATABANK MAINTENANCE MENU          XXX 12/01/2005
                                                    12:00:00

Type the number of your selection below and press ENTER,
or press the PF3 key to Exit.

      1. Interchange Directory
      2. Group Directory
      3. Interchange Status
      4. Group Status
      5. Transaction Status
      6. Document Directory
      7. Document Status
      8. Change Audit Directory
      9. Change Audit Status
     10. Log Display

      13. Structure Document Directory
      14. Structure Document Status

Enter PF1=Help          PF3=Exit          PF6=Refresh
                        PF15=Logoff
```

Gentran:Structure

Relationship Mode

```

Select
EDIM272 3.13 _____  STRUCTURE DOCUMENT DIRECTORY          XXX 12/01/2005
                                                                  12:00:00

User . . .  YOUR COMPANY _____ Partner  LAWNVEND _____
In/Outbound I              Databank G (Gentran, Realtime)

A  User           Partner           I/O   Dbk
  _ YOUR COMPANY  LAWNVEND          I     G
-
-
-
-
-
-
-
-
-
-
-
TO SELECT PROFILE ENTER AN "S" BESIDE THE ID
Enter PF1=Help     PF3=Exit         PF5=Doc
      PF7=Bwd    PF8=Fwd
    
```

Screen Actions

The system displays the screen actions on the top line of the Structure Document Directory screen. The following table describes the screen action function for this screen and gives instructions on how to perform the action.

To perform this action ...	Associated with this screen action ...	Do this ...
View the Structure Document Status screen for the Partner ID selected on the Structure Document Directory screen	Select	Type s in the A (Action Code) field next the selected Partner ID and press PF5 .

Function Key Description

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

PF5=Doc Displays the Structure Document Status screen.

Field Descriptions

Note: Display-only fields contain the statement (protected) next to the field name in the documentation.

Note: Fields in which you *must* enter a value contain the statement (required) next to the field name in the documentation.

Jump Code

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed in the jump code field for that screen.

To jump to another screen, press **Home**, type the jump code of the screen to which you want to jump, and press **Enter**.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
Partner ID (protected)	Displays the Partner ID that you have entered or selected. Note: The Partner ID and Qualifier make up the key for all associated records.	User (protected)	A 15-position alphabetic field displaying the User ID you have entered or selected.
Qual (protected)	Displays the Qualifier associated with the Partner ID, if applicable.	Partner (protected)	A 15-position alphabetic field that displays the Partner ID you have entered or selected.

In/Outbound

A 1-character alphabetic field to restrict the list to either inbound documents or outbound documents. If the field contains no value, the list includes both inbound and outbound documents. Valid values are:

- I** = Inbound documents only
- O** = Outbound documents only

Databank

A 1-character alphabetic field to restrict the list to documents from the Gentran:Basic for zSeries Databank, the Gentran:Realtime Databank, or both. Valid values are:

- G** = Gentran:Basic for zSeries databank only
- R** = Gentran:Realtime databank only
- blank** = Both Gentran:Basic and Gentran:Realtime databanks

A (Action Code)

A 1-character alphabetic field for entering an action to be performed against the selected list item. The top line of the screen lists the valid actions. To execute the action, type the letter next to the selected Partner ID, then press **PF5**.

Example

If you want to view the Document Status screen for a particular Partner ID on the Document Directory screen, type **s** in the A field corresponding to the partner whose document status you want to view, then press **PF5**.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
Partner (protected)	Displays the Partner ID that you have entered or selected. Note: The Partner ID and Qualifier make up the key for all associated records.	User (protected)	Displays the User ID that you have entered or selected.
Qual (protected)	Displays the Qualifier associated with the Partner ID, if applicable.	Partner (protected)	Displays the Partner ID you have entered or selected.

I/O

Displays the inbound or outbound code for the direction of the documents that belong to the Partner ID listed.

Dbk

Indicates whether the document is on the Gentran:Basic for zSeries databank or on the Gentran:Realtime databank. Valid values are:

- G** = Gentran:Basic for zSeries databank
- R** = Gentran:Realtime databank

Structure Document Status Screen

EDIM273

Purpose

The Structure Document Status screen displays a list of all documents for a profile ID. Various selection fields are available to you for selecting which documents should be listed. The “Field Descriptions” section contains details about each of these fields.

How to Access

Access the Structure Document Status screen in either of these two ways:

- Type **14** to select Structure Document Status from the Databank Maintenance Menu.
- OR
- Type **3.14** in the jump code field.

Screen Example

The following diagrams illustrate the Structure Document Status screen for both the Partner/Qualifier and Relationship (User/Partner) modes.

Partner/Qualifier Mode

```

Select Delete
EDIM273 3.14_____ STRUCTURE DOCUMENT STATUS          XXX 12/01/2005
                                                           12:00:00

Partner ID . . . : LAWNVEND_____ Qual _____
Version ID . . . : _____
User Reference : _____
In/Outbound. . . : _ Databank G
From Date . . . : _____ Time _____
To Date . . . . : _____ Time _____

  Rec Structure
A Stat Version ID  User Reference          Date      I/O Dbk
-      JASS        LAWN CARE VENDOR INC. 12/01/2005 I  G
-      JASS        LAWN CARE VENDOR INC. 12/01/2005 I  G
-      JASS        LAWN CARE VENDOR INC. 12/01/2005 I  G
-      JASS        REF:OA00010001        12/01/2005 O  G
-
-
-
-
END OF DOCUMENTS
Enter PF1=Help PF2=Data PF3=Exit PF4=Dir PF5=Detail PF6=Nx Pr ID
      PF7=Bwd  PF8=Fwd
    
```

Relationship Mode

```

Select Delete
EDIM273 3.14_____  STRUCTURE DOCUMENT STATUS          XXX  12/01/2005
                                                                12:00:00

User . . . . . : YOUR COMPANY_____  Partner  LAWNVEND_____
Version ID . . : _____
User Reference : _____
In/Outbound. . : I      Databank  G
From Date . . . : _____  Time  _____
To Date . . . . : _____  Time  _____

  Rec  Structure
A Stat Version ID   User Reference          Date      I/O Dbk
-      JASS        000000055              12/01/2005  I   G
-
-
-
-
-
-
-
-
-
END OF DOCUMENTS
Enter PF1=Help PF2=Data  PF3=Exit PF4=Dir          PF5=Detail  PF6=Nx Pr ID
      PF7=Bwd  PF8=Fwd

```

Screen Actions

The system displays the screen actions on the top line of the Structure Document Status screen. The following table describes each screen action function and gives instructions on how to perform those actions.

To perform this action ...	Associated with this screen action...	Do this ...
View the Structure Document Status Detail screen for the document displayed	Select	Type an s in the A (Action Code) field next to the document for which you want to view status detail, then press PF5 .
Delete a document	Delete	Type a d in the A (Action Code) field next to the document to delete and press Enter . To complete the request, respond to the system prompt.

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

- PF2=Data** Displays the Document Display screen, to display the application data for the document selected in the A (Action Code) field.
- PF4=Dir** Displays the Structure Document Directory screen.
- PF5=Detail** Displays the Document Status Detail screen. This screen displays all processing and status information regarding the selected document.
- PF6=Nx Pr ID** Displays documents for the next Profile ID on the databank.

Field Descriptions

Note: Display-only fields contain the statement (protected) next to the field name in the documentation.

Note: Fields in which you *must* enter a value contain the statement (required) next to the field name in the documentation.

Jump Code

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed in the jump code field for that screen.

To jump to another screen, press **Home**, type the jump code of the screen to which you want to jump, then press **Enter**.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
Partner ID	Displays the Partner ID that you have entered or selected. Note: The Partner ID and Qualifier make up the key for all associated records.	User	Displays the User ID you have entered or selected.
Qual	Displays the Qualifier associated with the Partner ID, if applicable.	Partner	Displays the Partner ID you have entered or selected.

Version ID

A 12-character, alphanumeric field enabling you to restrict the list to a specific Version ID associated with the Partner ID.

User Reference

A 45-character alphanumeric field to identify the user reference you want to list, depending on whether the document is inbound or outbound and how you have chosen to implement the User Reference option (the Application Key fields on the Application Partner Reference screen in data mapping). This field is created for the document by either Editor processing or Data Mapping processing.

For inbound processing, the User Reference is either the value of the field defined as the audit indicator in the Standards subsystem (located on the segment element) or an internal reference number when the audit indicator is not used. For outbound processing, the User Reference is either the concatenation of the application keys (defined on the Application Partner Reference screen) or an internal reference number.

In/Outbound

A 1-character alphabetic field to restrict the list to just inbound documents or outbound documents. If left blank the list includes both inbound and outbound documents. Valid values are:

- I** = Inbound documents only
- O** = Outbound documents only

Databank

A 1-character alphabetic field to restrict the list to documents from the Gentran:Basic Databank, the Gentran:Realtime Databank, or both. Valid values are:

- G** = Gentran:Basic for zSeries Databank only
- R** = Gentran:Realtime Databank only
- blank** = Both Gentran:Basic and Gentran:Realtime Databanks

From Date

A 10-character alphanumeric field that contains the date you want the list of documents to start with. Type the date in this format:
MM/DD/YYYY.

If you do not enter a date, all dates are selected. The value in the From Date field must be less than or equal to the current date.

Note: For inbound documents, the date used for the search is the output date. For outbound documents, the date used for the search is the date the document was loaded.

From Time

A 5-character alphanumeric field that contains the time you want the list of documents to start with. Type the time in this format:
HH:MM.

If you do not enter a time, all times are selected. The value in the From Time field must be less than or equal to the current time.

Note: For inbound documents, the time used for the search is the output time. For outbound documents, the time used for the search is the time the document was loaded.

To Date

A 10-character alphanumeric field containing the date with which you want the list of documents to end. Type the date in this format:
MM/DD/YYYY.

If you do not enter a date, all dates are selected. The value in the To Date field must be less than or equal to the current date.

To Time

A 5-character alphanumeric field that contains the time with which you want the list of documents to end. Type the time in this format:
HH:MM.

If you do not enter a time, all times are selected. The value in the To Time field must be less than or equal to the current date and time.

A (Action Code)

A 1-character alphabetic field to indicate an action to be performed against the corresponding list entry. The top line of the screen lists the valid actions. To execute the action, type the letter next to the selected document, then press **PF5**.

For example, if you want to view the Document Status Detail screen for the document displayed, type **s** in the A (Action Code) field for the document you want to view, then press **PF5**.

Rec Stat

Displays the last online action performed against the document. A value of **D** indicates that the document has been marked for delete.

Structure Version ID

Displays the Version ID for the document.

User Reference

Displays the User Reference for the document. Depending on whether the document is inbound or outbound and how you have chosen to implement the User Reference options in Data Mapping this field is created for the document by either Editor processing or Data Mapping processing.

Date

Displays the process date for inbound documents and the translated date for outbound documents.

I/O

Displays the inbound or outbound code for the direction of the documents that belong to the Partner ID being listed.

Dbk

Displays whether the document is on the Gentran:Basic for zSeries databank or on the Gentran:Realtime databank. Valid values are:

G	=	Gentran:Basic for zSeries databank
R	=	Gentran:Realtime databank

Structure Document Status Detail Screen**EDIM275***Purpose*

The Structure Document Status Detail screen displays detailed status and control information for a document on the databank.

How to Access

Access the Structure Document Status Detail screen in either of these two ways:

- Select the desired document from the Structure Document Status screen (EDIM273), and press **PF5=Detail**.

OR

- From the Structure Document Display screen (EDIM274), press **PF14=Dtl**.

Note: This screen has no jump code associated with it.

Screen Examples

The following diagrams illustrate the Structure Document Status Detail screen for both the Partner/Qualifier and Relationship (User/Partner) modes.

Partner/Qualifier Mode

```

EDIM275 _____ STRUCTURE DOCUMENT STATUS DETAIL      XXX 12/01/2005
                                                    12:00:00

Partner ID . . . : LAWNVEND                               Qual:
Version ID      : JASS                                   Agency..: SC  Division: 000
Transaction Set: 0926
User Reference  : LAWN CARE VENDOR INC.
Databank Run # : 00000001
Reference Tag   : IS00000001                             I/O: Inbound
Reported Status:                                         Databank: GENTRAN
Pre-Proc . . . : 12/01/2005 12:00                       Pre-Proc Status: 00
Int Env ID . . : PHD                                     SegID Length..: 03
Grp Env ID . . :                                         SegID Start Pos.: 00078
Trn Env ID . . : THD

                                                    Test/Prod: Prod
                                                    Envelope: Prod
                                                    User Dup. Ind.: N
                                                    Character Count: 000003215

Enter  PF1=Help  PF2=Data  PF3=Exit  PF4=Doc

```

Relationship Mode

```

EDIM275 _____ STRUCTURE DOCUMENT STATUS DETAIL      XXX 12/01/2005
                                                    12:00:00

User . . . . . : YOUR COMPANY                      Partner: LAWNVEND
Version ID   : JASS                               Agency..: SC   Division: 000
Transaction Set: 0926
User Reference : 000000055
Databank Run # : 00000027
Reference Tag : IS00000014                        I/O: Inbound
Reported Status:                                Databank: GENTRAN
Pre-Proc . . . : 12/01/2005 12:00                Pre-Proc Status: 00
Int Env ID . . : PHD                             SegID Length..: 03
Grp Env ID . . :                               SegID Start Pos..: 00078
Trn Env ID . . : THD

                                Test/Prod: Prod
                                Envelope: Prod
                                User Dup. Ind.: N
                                Character Count: 000003215

Enter PF1=Help PF2=Data  PF3=Exit PF4=Doc

```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran: Basic for zSeries Release 6.4 User's Guide*.

PF2=Data Displays the Structure Document Display screen (EDIM274). The system displays records for the current document.

PF4=Doc Returns to the Structure Document Status Screen (EDIM273).

Field Descriptions

Jump Code

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed in the jump code field for that screen.

To *jump* to another screen, press **Home**, type the jump code of the screen to which you want to jump, then press **Enter**.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
Partner ID (protected)	Displays the Partner ID that you have entered or selected. Note: The Partner ID and Qualifier make up the key for all associated records.	User (protected)	Displays the User ID you have entered or selected.
Qual (protected)	Displays the Qualifier associated with the Partner ID, if applicable.	Partner (protected)	Displays the Partner ID you have entered or selected.

Version ID (protected)

A 12-character, alphanumeric field that identifies the standard.

Agency (protected)

A 2-character, alphabetic field that contains the agency associated with the version ID.

Division (protected)

Displays the Division defined to the partner profile that was used to process the document displayed.

Transaction Set

A 6-character, alphanumeric field that identifies the transaction set associated with the Version ID and agency.

User Reference (protected)

Displays the user reference for the document. Depending on whether the document is inbound or outbound and how you have chosen to implement the user reference options in Data Mapping, this field is created for the document by either Editor processing or Data Mapping processing.

Databank Run #

Displays the databank run number, which was assigned to the document by Gentran:Basic at the time the document was last processed. The system uses the Databank Run number to identify the run that processed the document.

Reference Tag

Displays the reference tag that Gentran:Basic has assigned to the document.

Network (Outbound only)

Displays the network as defined on the partner ID used to process the document.

I/O

Indicates whether the document is inbound or outbound. Valid values are:

Inbound = Inbound documents only

Outbound = Outbound documents only

Reported Status

Displays the reported status value for inbound or outbound documents. This value indicates whether the Application Databank Inquiry Report (EDID551) was run. Valid values are:

Y = Reported
N = Not reported
Space = (Blank) Not reported

Databank

Indicates whether the document is on the Gentran:Basic for zSeries databank or on the Gentran:Realtime databank. Valid values are:

GENTRAN = Gentran:Basic for zSeries databank
Realtime = Gentran:Realtime databank

Mapped (Outbound only)

Displays the date and time the document was last mapped.

Mapping Status (Outbound only)

Displays the status that resulted from the Inbound Mapper for the document. Valid values are:

00 = The system encountered no errors during the mapping process for the document.
04 = The system detected one or more requirement or relational condition errors.
08 = The system detected one or more unknown or unexpected segment errors.
12 = The system could not translate an inbound document.

Pre-Proc (Inbound only)

Displays the date and time the pre-processor was executed.

Pre-Proc Status (Inbound only)

Displays the status associated with the pre-processed run. Valid values are:

00 = The system encountered no errors.
04 = The system detected one or more condition errors.
08 = The system detected one or more unknown errors.
12 = A fatal error occurred, program terminated.

Int Env ID

The segment ID used at the interchange level.

SegID Length (required for fixed-format envelope)

A 2-position, numeric field that defines the length of the field containing the Segment ID for user-defined envelopes. Valid values are **1** – **10**. The sum of the Segment ID Start and Length fields cannot exceed 32743.

Grp Env ID

The segment ID used at the group level.

SegID Start Pos (required for fixed-format envelope)

A 5-position, numeric field that defines the start of the field containing the segment ID for user-defined envelopes. Valid values are **1 – 32743**. The sum of the Segment ID Start and Length fields cannot exceed 32743.

Trn Env ID

The segment ID used at the transaction level.

Test/Prod

Displays the test/production status of the transaction. This value is defined in the partner profile that was used to process the transaction.

Envelope

Displays the test/production status of the transaction. This value is determined from the interchange envelope that was received with the transaction from your partner.

User Dup. Ind.

Indicates whether this document is a duplicate of a document already on the databank. The duplicate check is based on the Partner and User Reference values. Valid values are:

N = No, is not a duplicate.

Y = Yes, is a duplicate.

Character Count

Displays the number of characters in the document.

Structure Document Display Screen**EDIM274***Purpose*

The Structure Document Display screen displays the data detail for all records for a document. The screen displays the first 75 characters of data for each record.

How to Access

Access the Structure Document Display screen in either of the following two ways:

- Select the desired document from the Structure Document Status screen (EDIM273), and press **PF2=Data**.

OR

- From the Structure Document Status Detail screen (EDIM275), press **PF2=Data**.

Note: This screen has no jump code associated with it.

Screen Examples

The following diagrams illustrate the Structure Document Display screen for both the Partner/Qualifier and Relationship (User/Partner) modes.

Partner/Qualifier Mode

```

Select
EDIM274 _____ STRUCTURE DOCUMENT DISPLAY XXX 12/01/2005
                                           12:00:00

Partner ID . . . : LAWNVEND                               Qual :
Name . . . . . : LAWN VENDOR FOR DEMONSTRATION
User Reference : LAWN CARE VENDOR INC.
I/O . . . . . : Inbound      Databank : Gentran      Search _____

A Record
- LAWNVEND          LAWNCUST          9307291432JASSGARDEN000000055
- 0926199307291432000000155
- IN-220PO-1552293201449320130
- LAWN CARE VENDOR INC. 1212 E. MAIN STREET CINCINNATI OH43015000
- 0001ITEM-100OR000005UOM1000012999900000000649995GRADE 100 LAWN SEED
- 0002ITEM-110OR000004UOM1000010999900000000439996GRADE 200 LAWN SEED
- 0003ITEM-120OR000009UOM10000119999000000001079991GRADE 300 LAWN SEED
- 0004ITEM-230OR000012UOM1000013999900000001679988GROW-A-LOT FERTILIZER
- 0005ITEM-240OR000010UOM1000013499900000001349990GROW-A-LOT-MORE FERTILIZER
- 0006ITEM-300OR000007UOM1000022999900000001609993#10 SHOVELS
- 0007ITEM-350OR000010UOM1000024999900000002499990#15 RAKES

Enter PF1=Help      PF3=Exit PF4=Doc      PF5=Record      PF6=Search
      PF7=Bwd      PF8=Fwd      PF14=Dt1

```

Relationship Mode

```

Select
EDIM274 _____ STRUCTURE DOCUMENT DISPLAY      XXX 12/01/2005
                                                    12:00:00

User . . . . . : YOUR COMPANY                      Partner : LAWNVEND
Name . . . . . : EXAMPLE OF A FIX FORMAT USER      EXAMPLE OF A FIX FORMAT PART
User Reference : 000000055
I/O . . . . . : Inbound      Databank : Gentran      Search _____

A Record
- LAWNVEND      LAWNCUST      9307291432JASSGARDEN000000055
- 0926199307291432000000155
- IN-220PO-1552293201449320130
- LAWN CARE VENDOR INC.      1212 E. MAIN STREET CINCINNATI      OH43015000
- 0001ITEM-100OR000005UOM1000012999900000000649995GRADE 100 LAWN SEED
- 0002ITEM-110OR000004UOM1000010999900000000439996GRADE 200 LAWN SEED
- 0003ITEM-120OR000009UOM10000119999000000001079991GRADE 300 LAWN SEED
- 0004ITEM-230OR000012UOM10000139999000000001679988GROW-A-LOT FERTILIZER
- 0005ITEM-240OR000010UOM10000134999000000001349990GROW-A-LOT-MORE FERTILIZER
- 0006ITEM-300OR000007UOM10000229999000000001609993#10 SHOVELS
- 0007ITEM-350OR000010UOM10000249999000000002499990#15 RAKES

Enter PF1=Help      PF3=Exit PF4=Doc      PF5=Record      PF6=Search
      PF7=Bwd      PF8=Fwd      PF14=Dtl

```

Screen Action

The system displays the screen actions on the top line of the Structure Document Display screen. The following table describes the function for this screen and gives instructions on how to perform the function.

To perform this action ...	Associated with this screen action ...	Do this ...
View the record display screen for the record selected	Select	Type an s in the A (Action Code) field next to the record for which you want to view the record display, then press PF5=Record .

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran: Basic for zSeries Release 6.4 User's Guide*.

PF5=Record	Displays the Structure Record Display screen (EDIM276) for the selected EDI record.
PF6=Search	Used with a value entered in the Search field, to search for the specified value in the EDI data records.
PF4=Doc	Re-displays the Structure Document Status Detail screen (EDIM273).
PF14=Dtl	Displays the Structure Document Status Detail screen for the document displayed.

Field Descriptions

Note: Display-only fields contain the statement (protected) next to the field name in the documentation.

Note: Fields in which you *must* enter a value contain the statement (required) next to the field name in the documentation.

Jump Code

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed in the jump code field for that screen.

To *jump* to another screen, press **Home**, type the jump code of the screen to which you want to jump, then press **Enter**.

Partner/Qualifier Mode		Relationship Mode	
Field	Description	Field	Description
Part ID (protected)	Displays the Partner ID that you have entered or selected. Note: The Partner ID and Qualifier make up the key for all associated records.	User (protected)	Displays the User ID you have entered or selected.
Qual (protected)	Displays the Qualifier associated with the Partner ID, if applicable.	Partner (protected)	Displays the Partner ID you have entered or selected.
Name (protected)	A 35-position alphanumeric field to display the partner name as found on the Name and Address record. The partner name can help to further identify the Partner ID.	Name (User) (protected)	An alphabetic field displaying the user name, if it exists on file for the User/Partner ID.
		Name (Partner) (protected)	An alphabetic field displaying the partner name, if it exists on file for the User/Partner ID.

User Reference

Displays the User Reference for the document. Depending on whether the document is inbound or outbound and how you have chosen to implement the User Reference options in Data Mapping, this field is created for the document by either Editor processing or Data Mapping processing.

I/O

Indicates whether the document is inbound or outbound. Valid values are:

- Inbound** = Inbound documents only
- Outbound** = Outbound documents only

Databank

Indicates whether the document is in the Gentran:Basic for zSeries databank or in the Gentran:Realtime databank. Valid values are:

GENTRAN= Gentran:Basic for zSeries databank

Realtime = Gentran:Realtime databank

Search

A 14-character alphanumeric field that contains a specified value to search for in the records. Following the search, the record containing the value is the first record displayed. This field is used in conjunction with the **PF6** key.

A (Action Code)

A 1-character alphabetic field to indicate an action to be performed against the corresponding list entry. The top line of the screen lists the valid actions. To execute the action, type the letter next to the selected record, then press **PF5**.

For example, if you want to view the Structure Record Display screen for a particular record on the Document Display screen, type **s** in the A (Action Code) field for the record you want to view, then press **PF5**.

Record

Displays up to the first 75 characters of data as found in the record. You can view the complete record from the Record Display screen.

Structure Record Display Screen

EDIM276

Purpose

The Structure Record Display screen displays a record selected from a document.

How to Access

Access the Structure Record Display screen by typing an **s** in the A (Action code) field next to the desired record on the Structure Document Display screen (EDIM274), and pressing **PF5**.

Note: This screen has no jump code associated with it.

Screen Example

The following diagram illustrates the Structure Record Display screen.

```

Select
EDIM276 _____          STRUCTURE RECORD DISPLAY          XXX 12/01/2005
                                                                    12:00:00

Version ID. . . . : JASS                      Agency. . . . : SC
Transaction Set : 0926                      SegID . . . . : IDT
I/O . . . . . : Inbound                      Databank. . . : Gentran

  Fld
A  Seq  Description                          Field Data
-  002  LINE ITEM NUMBER                     0001
-  004  ITEM NUMBER                          ITEM-100
-  006  QUANTITY TYPE                        OR
-  008  QUANTITY                             000005
-  010  UNIT OF MEASURE                      UOM1
-  012  PRICE                                0000129999
-  014  EXTENDED PRICE                       00000000649995
-  016  ITEM DESCRIPTION                     GRADE 100 LAWN SEED
-  018  RESERVE ELEMENT 2
-

Enter  PF1=Help  PF3=Exit PF4=Doc          PF5=Field
        PF7=Bwd  PF8=Fwd
    
```

Screen Action

The system displays the screen actions on the top line of the Structure Record Display screen. The following table describes the screen function for this screen and gives instructions on how to perform the function.

To perform this action ...	Associated with this screen action ...	Do this ...
View the Field Display screen for the field selected	Select	Type s in the A (Action Code) field next to the field sequence number for which you want to view the field display data, then press PF5 .

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

PF4=Doc Returns to the Structure Document Display screen (EDIM274).
PF5=Field Displays the Structure Field Display screen (EDIM277) for the selected EDI data.

Field Descriptions

Jump Code

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed in the jump code field for that screen.

To *jump* to another screen, press **Home**, type the jump code of the screen to which you want to jump, then press **Enter**.

Version ID (protected)

A 12-character, alphanumeric field that identifies the standard.

Agency (protected)

A 2-character, alphabetic field that contains the agency associated with the version ID.

Transaction Set

A 6-character, alphanumeric field that identifies the transaction set associated with the version ID and agency.

SegID

A 4-character, alphanumeric field that identifies the segment ID used in the standards for the record displayed.

I/O

Indicates whether the document is inbound or outbound. Valid values are:

Inbound = Inbound documents only
Outbound = Outbound documents only

Databank

Indicates whether the document is in the Gentran:Basic for zSeries databank or in the Gentran:Realtime Databank. Valid values are:

Gentran = Gentran:Basic for zSeries databank
Realtime = Gentran:Realtime databank

A (Action Code)

A 1-character alphabetic field that contains an action to be performed against the corresponding list entry. The top line of the screen lists the valid actions. To execute the action, type the letter next to the selected field sequence number, then press **PF5=Field**.

For example, if you want to view the Field Display screen for a particular field, type an **s** in the A (Action Code) field next to the field sequence number you want to view, then press **PF5=Field**.

Fld Seq

Displays the field sequence number of the field within the record.

Description

Displays a text description of the field as defined in the Standards file.

Field Data

Displays up to the first 31 characters of data as found in the record's field. You can view the complete field from the Structure Field Display screen (EDIM277).

Structure Field Display Screen**EDIM277***Purpose*

The Structure Field Display screen enables you to view a field selected from a record.

How to Access

Access the Structure Field Display screen by typing an **s** in the A (Action Code) field next to the desired record on the Structure Record Display screen (EDIM276), and pressing **PF5=Field**.

Note: This screen has no jump code associated with it.

Screen Example

The following diagram illustrates the Structure Field Display screen.

```

EDIM277 _____          STRUCTURE FIELD DISPLAY          XXX 12/01/2005
                                                                12:00:00

I/O . . . . . : Inbound          Databank . . : Gentran
Version ID . . . . . : JASS          Agency . . . : SC

Field Description . . : LINE ITEM NUMBER

Field Sequence . . . : 002

Field Type . . . . . : N0

Field Position . . . : 0001

Field Length . . . . : 00004

Field Data . . . . . 0001

Enter      PF1=Help      PF3=Exit PF4=Record
  
```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran: Basic for zSeries Release 6.4 User's Guide*.

PF4=Record Displays the Structure Record Display screen (EDIM276).

*Field Descriptions***Jump Code**

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed in the jump code field for that screen.

To *jump* to another screen, press **Home**, type the jump code of the screen to which you want to jump, then press **Enter**.

I/O

This field indicates whether the document is inbound or outbound. Valid values are:

Inbound = Inbound documents only
Outbound = Outbound documents only

Databank

Displays whether the document is in the Gentran:Basic for zSeries Databank or in the Gentran:Realtime Databank. Valid values are:

GENTRAN= Gentran:Basic for zSeries Databank
Realtime = Gentran:Realtime Databank

Version ID (protected)

A 12-character, alphanumeric field that identifies the standard.

Agency (protected)

A 2-character, alphabetic field that contains the agency associated with the Version ID.

Field Description

Displays a text description of the field as defined in the Standards file.

Field Sequence

Displays the sequence number of the field in the record.

Field Type

Displays the data type of the field. Valid values are:

CM = Date format = MMDDYYYY
CY = Date format = YYYYMMDD
DD = Date format = DDMMYY
JD = Date format = Julian YYDDD
J8 = Date format = Julian YYYYDD
MM = Date format = MMDDYY
PD = Date format = Packed DDMMYY
PJ = Date format = Packed Julian YYDDD
PM = Date format = Packed MMDDYY
PY = Date format = Packed YYMMDD
Pn = Signed Packed with n implied decimal positions
Sn = Signed numeric with n implied decimal positions
YY = Date format = YYMMDD
ZD = Date format = Packed DDMMYYYY
ZJ = Date format = Packed Julian YYYYDDD
ZM = Date format = Packed MMDDYYYY
ZY = Date format = Packed YYYYMMDD

Valid values for standards version of all envelope types are the following:

AN = String type = alphanumeric
CD = Date format = DDMMYYYY
DT = Date format = YYMMDD or YYYYMMDD

D8	=	Date format = YYYYMMDD
FS	=	Fixed string = alphanumeric-pad with spaces
ID	=	Identifier type = element has code list
Nn	=	Numeric with n decimal places implied
R	=	Decimal = data contains explicit decimal point
Rn	=	Decimal where n indicates the maximum number of decimal positions.
TM	=	Time format = HHMM
T6	=	Time format = HHMMSS, where SS = seconds
T8	=	Time format = HHMMSSss, where ss = hundredths of seconds
B	=	Binary

Field Position

Displays the offset of the field from the start of the record. The record starts at 1.

Field Length

Displays the fixed length of the field.

Field Data

Displays up to 100 characters (2 lines of 50 each) for the field's data value.

Structure Envelope Display Screen

EDIM192

Purpose

The Structure Envelope Display screen displays data fields that can be defined for specific user envelopes.


How to Access

Access this screen by typing an **S** in the A (Action Code) field next to the desired envelope record on the Structure Document Display (EDIM274) screen, and pressing **PF5=Record**.

Note: The Structure Envelope Display screen (EDIM192) is only available for selected records in which SegID fields are associated with envelope headers and trailers as defined in user defined envelopes.

Screen Example

The following diagram illustrates the Structure Envelope Display screen.



Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

- Enter** Re-displays the current screen.
- PF3=Exit** Returns to the Databank Maintenance menu.
- PF4=Doc** Returns to the previous screen.

Field Descriptions

Segment ID (protected)

Displays the characters that identify the segment ID of the envelope that is processed.

Modifier (protected)

Displays the segment ID modifier of the envelope that is processed.

Length

A 5-position numeric field that defines the length of the envelope record. The default value is 80. Valid values are **1 – 2000**.

Default Version ID

A 12-position alphanumeric field to define what standard version should be used for processing when this user envelope is received. The field is intended to be used for proprietary, fixed-format standards, where the version is not specified on the envelope. This field is used by the Inbound Pre-Processing program for version determination. It is not used by the outbound process.

Default Transaction ID

A 6-position alphanumeric field to define what transaction set should be used for processing purposes when this user envelope is received. The field is intended to be used for proprietary, fixed-format standards where the transaction set is not specified on the envelope. This field is used by the Inbound Pre-Processing program for transaction determination. It is not used by the outbound process.

Version ID

A 12-position numeric field that contains the standard version.

Transaction ID

A 6-position alphanumeric field that contains the transaction set ID.

Sender ID

A 15-position alphanumeric field that contains the sender ID.

Receiver ID

A 15-position alphanumeric field that contains the receiver ID.

Reference Number

An 8-position numeric field that contains the reference number. This number is also referred to as the control number.

Generic Elements 1 to 10

A 16-position, alphanumeric field that displays the data associated with the generic elements as defined in the partner profile.

Current Date

An 8-position numeric field that contains the current date.

Current Time

A 6-position numeric field that contains the current time.

Current Date Format

A 2-position, alphanumeric field that defines the format of the current date. This field is only used during outbound processing and is only valid when the Current Date Start field contains a valid value. Valid values are:

- MM** = Current date will be in MMDDYY format.
- DD** = Current date will be in DDMMYY format.
- YY** = If length is 6, the current date will be in YYMMDD format.
If length is 8, the current date will be in YYYYMMDD format.

Standards Change Audit Subsystem

Overview

This section describes the special Standards Change Audit screens that are used to view Gentran:Structure User Envelope Change Audit records.

The Standards Change Audit subsystem allows you to view changes that have been applied to the online standards files. For Gentran:Structure, there is an additional Standards File—the User Envelope file. It contains the information, along with the other 13 standards files from Gentran:Basic, to describe the layout of the inbound and outbound fixed format documents. The User Envelope file contains values used to build outbound Fixed Format envelopes and contains information used to split inbound fixed format data from Delimited (variable-format) EDI data.

Note: See the *Gentran:Basic for zSeries Release 6.4 User's Guide* for more information about the Standards Maintenance and Standards Change Audit subsystems.

Standards Change Audit Director

EDIM181

Purpose

The Standards Change Audit Directory lists all of the Version IDs that currently exist in the Standards Change Audit file. Standards change audit records are written whenever an add, update, or delete occurs in a record of the online standards files via the online screens, the batch standards copy utility (EBDI032), or the batch standards merge utility (EBDI039).

How to Access

Access the Standards Change Audit Directory screen in one of the following ways:

- On the Change Audit Main Menu, type **3** to select the Standards Change Audit Directory screen and press **Enter**.
- Type **4 . 8 . 3** in the Jump Code field of any screen and press **Enter**.

Screen Example

The following diagram illustrates the Standards change Audit Directory:

```

Select
EDIM181 4.8.3_____ STANDARDS CHANGE AUDIT DIRECTORY          XXX 12/01/2005
                                                                12:00:00

Version ID . . : _____ Agency . . : ____

A Version ID   Agency
-  ACHG02      A
-  ANA001      A
-  CARG3              * Association *
-  CARG5              * Association *
-  CARG6              * Association *
-  D 01B         UN
-  D 03AGMI041   UN
-  EQUIFAX       EQ
-
-              * User Envelope *   JOY
-              * User Envelope *   PRW          1
-  TEST1              * Association *
-  TST1              * Association *

TO SELECT VERSION ENTER AN "S" BESIDE THE ID
Enter PF1=Help      PF3=Exit          PF5=Chg Aud
      PF7=Bwd   PF8=Fwd
  
```

Structure Fields

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran: Basic for zSeries Release 6.4 User's Guide*.

PF5=Chg Aud

Select a version ID by entering **s** next to the selected version ID and pressing **PF5** to branch to the Standards Change Audit Status screen for that ID. This screen displays standards change audit records for the selected version ID.

Field Descriptions

(Jump Code)

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed automatically in the Jump Code field for that screen. To jump to another screen, press **Home**, type the jump code of the screen to which you want to jump, and press **Enter**.

See "Jump Codes" in Chapter 1 of this guide for further information about using jump codes.

(Starting) Version ID

A 12-position alphanumeric field used to specify the version you want the display list to start with. If you type a partial Version ID in this field, the system displays ten Version IDs, starting with the closest matching Version ID. If you leave this field blank, the version list begins with the first version found in the Standards change audit file.

(Starting) Agency

A 3-position alphanumeric field used to specify the agency that, when combined with the (Starting) Version ID, positions the display list.

A (Action Code)

A 1-position alphabetic field used to select a Version ID. Type **s** next to a Version ID and press **Enter**.

Version ID (protected)

Displays the Version ID.

Note: Structure User Envelope change audit records will have spaces in this field.

Agency (protected)

Displays the agency associated with the Version ID.

Note: Structure User Envelope change audit records will have spaces in this field.

(Record Type) (protected)

This field identifies Association and User Envelope Change records. Valid values:

* Association *

* User Envelope*

Segment Id (protected)

Displays the Segment ID associated with the User Envelope records.

Mod (protected)

Displays the Segment ID modifier associated with the User Envelope records.

Standards Change Audit Status - Structure**EDIM184***Purpose*

The Standards Change Audit Status - Structure screen displays all of the records that currently exist in the Standard Change Audit file for the indicated Segment ID/ Mod. This screen only displays User Envelope Change audit records.

How to Access

Access the Standards Change Audit Status - Structure screen as follows:

- On the Standards Change Audit Directory screen, type **S** to select the desired Version ID/Agency and press **PF5**.

Screen Example

The following diagram illustrates the Standards Change Audit Status for Structure screen:

```

Select
EDIM184 _____ CHANGE AUDIT STATUS - STANDARDS          XXX 12/01/2005
                                                                12:00:00

Segment ID : XXX _____ Mod . . . : 1
From Date   _____ Time   _____
To Date     _____ Time   _____

A  Record Type   Update   Date
   Code
-  User Envelope   A       12/01/05
-  User Envelope   U       12/01/05
-  User Envelope   U       12/01/05
-  User Envelope   U       12/01/05
-  User Envelope   U       12/01/05
-  User Envelope   U       12/01/05
-  User Envelope   U       12/01/05
-  User Envelope   U       12/01/05
-  User Envelope   U       12/01/05
-  User Envelope   U       12/01/05
-  User Envelope   D       12/01/05

Enter PF1=Help          PF3=Exit PF4=Dir          PF5=Detail
      PF7=Bwd   PF8=Fwd

```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran: Basic for zSeries Release 6.4 User's Guide*.

PF5=Detail

Select a record by entering **S** next to the selected record type and pressing **PF5** to branch to the Standards Change Audit Detail screen for that record. This screen displays the change audit details for the selected record.

Field Descriptions

(Jump Code)

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed automatically in the Jump Code field for that screen. To jump to another screen, press **Home**, type the jump code of the screen to which you want to jump, and press **Enter**.

See "Jump Codes" in Chapter 1 of this guide for further information about using jump codes.

Segment ID

A 10-position alphanumeric field used to enter or display the Segment Id for the User Envelope records.

Mod

A 1-position alphanumeric field used to enter or display the modifier that is associated with the Segment ID.

From Date

A 10-character alphanumeric field used to enter the date you want the list to start with. Type the date in the following format: MM/DD/YYYY. If a date is not entered for this field, all dates are selected. The value in the From Date field must be less than or equal to the current date.

Time

A 5-character alphanumeric field used to enter the time you want the list to start with. Type the time in the following format: HH:MM. If a time is not entered for this field, all times are selected.

To Date

A 10-character alphanumeric field used to enter the date you want the list to end with. Type the date in the following format: MM/DD/YYYY. The value in the To Date field must be greater than or equal to the From Date.

Time

A 5-character alphanumeric field used to enter the time you want the list to end with. Type the time in the following format: HH:MM. If a time is not entered for this field, all times are selected.

A (Action Code)

A 1-position alphabetic field used to select a record type. Type S next to a record type and press Enter.

Record Type (protected)

The record type identifies the type of standards record that was modified. Valid value is User Envelope.

Update code (protected)

Displays the type of modification that caused the generation of this standards change Audit record. Valid values are:

Update

Add

Delete

Date (protected)

Displays the date that this change audit record was created.

Standards Change Audit Detail - Structure**EDIM185***Purpose*

The Standards Change Audit Detail screen displays the detail information for the standards change audit record.

How to Access

Access the Standards Change Audit Status - Structure screen as follows:

- On the Standards Change Audit Status screen, type **s** to select the desired record and press **PF5**.

Screen Example

The following diagram illustrates the Standards Change Audit Detail for Structure screen:

```

EDIM185 _____ STANDARDS- CHANGE AUDIT DETAIL          XXX  12/01/2005
                                                                12:00:00

Segment ID. . . : XXX                Mod   : 1
Record Type . . : User Envelope

Function: Update  Date: 12/01/2005 Time: 12:00:00 User: XXX Source: EDIX190

Description. . . SEG-STRT
Before . . . . . 00001

After. . . . . 00003

Enter PF1=Help          PF3=Exit PF4=Chg Aud          PF6=Next CA
  
```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

PF5=Next CA

Displays the next record in the Standards Change Audit file for the indicated Segment ID/Mod.

*Field Descriptions***(Jump Code)**

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen's jump code is displayed automatically in the Jump Code field for that screen. To

jump to another screen, press **Home**, type the jump code of the screen to which you want to jump, and press **Enter**.

See "Jump Codes" in Chapter 1 of this guide for further information about using jump codes.

Segment ID

A 10-position alphanumeric field used to enter or display the Segment Id for the User Envelope records.

Mod

A 1-position alphanumeric field used to enter or display the modifier that is associated with the Segment ID.

Record Type (protected)

The record type identifies the type of standards record that was modified. Valid

Value is User Envelope.

Function (protected)

Displays the type of modification that caused the generation of this standards change Audit record. Valid values are:

Update

Add

Delete

Date (protected)

Displays the date that this change audit record was created.

Time (protected)

Displays the time that this change audit record was created.

User (protected)

Displays the initials of the user who created the record.

Source (protected)

This field indicates which screen or batch program generated the change audit record.

Description (protected)

Displays the description of the field that was updated. This field is only displayed when Function is Update.

Before (protected)

Displays the value that was in the partner record before the update. This field is Only displayed when Function is Update.

After (protected)

Displays the value that resulted from the update. This field is only displayed when Function is Update.

Gentran:Realtime Screens

Overview

Gentran:Realtime supports the features added to Gentran:Basic for zSeries for Gentran:Structure processing. The Gentran:Realtime system runs all of its processes under CICS.

The Gentran:Structure for Realtime screens are described in this section.

Fixed Format Pre-Processor Path Maintenance

EDIM840

Purpose

The Fixed Format Pre-Processor Path Maintenance screen provides the parameters that the Pre-Processor program will use during processing. The purpose of the Pre-Processor program is to duplicate some of the critical functionality that is present in the Inbound Editor program. This program replaces the Inbound Editor program in the inbound processing flow for fixed-format standards.

How to Access

Access the Fixed Format Pre-Processor Path Maintenance screen by typing **6** in the “Transfer to” field on the Additional Shell Steps Maintenance screen (EDIM84F) and pressing **PF5=Transfer**.

See the *Gentran:Realtime for zSeries Release 6.3 User's Guide* for information about the Additional Shell Steps Maintenance screen.

Screen Example

The following diagram illustrates the Fixed Format Pre-Processor Path Maintenance screen.

```

EDIM840 _____ FIXED FORMAT PRE-PROCESSOR PATH MAINTENANCE XXX 12/01/2005
                                                    12:00:00

Path ID.....: 302P  STRUCTURE_INBOUND_PRE-PROCESSOR_____
Record Format..... 0          0 = Fixed 1 = Variable
Record Length..... 00080      Max of 32760
Partner ID / Qual..... _____ / _____
User ID / Qual..... _____ / _____
Version ID..... _____ Agency...: _____
Transaction ID..... _____
Envelope Level..... 2          0 = Trans 1 = Group 2 = Interchange
Application By..... 0          0 = None 1 = User 2 = Partner
User Reference Segment ID..... IRN_____
Segment ID Starting Position.... 00078
Segment ID Length..... 03      Dbk Proc. Level...: 1 0=No,1=Full
User Reference Starting Position. 00001          2=Dir
User Reference Length..... 23      Report Print Sw...: 0 0=No 1=Print
Detail Report..... 0          0=No 1=Yes
Data Envelope..... _          0=No 1=Yes
Last Update Date: 12/01/05 Time: 12:00:00 User: PRW

Enter PF1=Help          PF3=Exit PF4=Dir          PF6=Shell
                        PF9=Add PF10=Updt PF11=Del

```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User's Guide*.

PF4=Dir	Returns to the Path Options Directory screen.
PF6=Shell	Displays the General Shell Path Maintenance screen.
PF9=Add	Adds a new Pre-Processor path. Enter the appropriate parameters values and press PF9=Add .

Copies a current path. First, enter the current path ID and press **Enter**. Type over the path ID and any other fields that need to be changed and press **PF9=Add**. The system will re-display the screen and display a message to indicate the information was added.

PF10=Updt

Updates the current Pre-Processor path. Enter the new data over the existing data and press **PF10=Updt**. A message will be displayed to indicate the information was updated.

PF11=Del

Deletes a current Pre-Processor path. Press the **PF11=Del** key to delete the data. The system will prompt you to confirm the delete by again pressing **PF11=Del**.

*Field Definitions***Path ID**

A 4-position alphanumeric field to identify the path containing the Pre-Processor parameters to be used for processing. The first three numeric digits are the Path ID. The Path ID is used to tie the Mapper and Pre-Processor parameters to the Shell parameters. The suffix is always P.

(Path ID Description)

A 40-character alphanumeric field containing the description for the processing of these parameters. The system displays this description on the Path Options Directory screen.

Record Format

A 1-digit numeric field that identifies the record format of the fixed-format data. Valid values are:

0	=	Data is in fixed-length records.
1	=	Data is in variable-length records.

Record Length

A 5-digit numeric field that is the length of the fixed-format data. For fixed-length records, the length is from 10 to 32760; for variable-length records, the length is from 10 to 32752.

Partner ID

A 35-position alphanumeric field (15 positions if the trading profile mode is "Relationship") used to specify the partner ID of the fixed-format data being processed. This partner ID is used for all envelopes. The system ignores the partner information on the envelopes.

Partner Qual

A 4-position alphanumeric field that identifies the partner ID qualifier to use for all data processed through this path. The system ignores any partner information contained on the envelopes. You must complete the Partner ID field if the you are specifying the qualifier in this field.

User ID

A 35-position alphanumeric field (15 positions if the trading profile mode is "Relationship") used to specify the user ID to use for all data received in this run. The system ignores any user information contained on the envelopes.

Note: The system does not access the Partner Cross-Reference file during the lookup logic for the user ID and the partner ID. Code your partner IDs exactly as they appear on the partner profile.

User Qual

A 4-position alphanumeric field that identifies the user ID qualifier to use for all data processed through this path. Any user information contained on the envelopes is ignored. You must complete the User ID field if you specify the qualifier in the User Qual field.

Version ID

A 12-position field that identifies the version being used to process the inbound fixed standard data.

Agency

A 3-position field that identifies the agency associated with the version ID.

Transaction ID

A 6-position alphanumeric field that identifies which transaction set ID to use for all data processed through this path. The system ignores any transaction information contained in the envelopes.

Envelope Level

A 1-digit numeric field used to specify the level of enveloping that the fixed-format (non-delimited) standard uses. Valid values are:

0	=	Transaction level (default value)
1	=	Group level
2	=	Interchange level

The Pre-Processor program clears hold areas when an envelope at the specified level is received.

Application By

A 1-position numeric field used to specify to the program where to look for inbound transaction-level data separation records. Valid values are:

0	=	None
1	=	User
2	=	Partner

This information is used to specify the application to be loaded by the Inbound Mapper so that the instream option can be used.

User Reference Segment ID

A 15-position alphanumeric field used to specify the segment ID of the record from which the Application User-Reference field can be found.

Segment ID Starting Position

A 5-digit numeric field used to specify the starting position of the Segment ID field in the record where the Application User-Reference field can be found.

Segment ID Length

A 2-digit numeric field used to specify the length of the Segment ID field in the record where the Application User-Reference field can be found.

Dbk Proc. Level

A 1-position numeric field used to designate the databank processing level switch. Valid values are:

0	=	No databank
1	=	Full databank
2	=	Directory-only databank

The processing level switch defines the lowest level of databank processing required for the Mapper. However, trading partner requests at a higher level are performed. If there is a request for a databank operation at a higher level than the configuration switch setting (in the Databank Config. Sw. field), an error is generated and processing terminates.

User Reference Starting Position

A 5-digit numeric field used to specify the starting position of the Application User-Reference field in the EDI data record.

User Reference Length

A 2-digit numeric field used to specify the length of the Application User-Reference field in the EDI data record.

Report Print SW

A 1-position field that specifies whether to print reports generated from the Pre-Processor program. When the field is set to 1, reports are printed. When the field is set to spaces or 0, reports are not printed. The default value is 0.

Detail Report

A 1-character numeric field that indicates whether to print the first 80 characters of each record read and written. Valid values are:

0	=	No, do not print the records.
1	=	Yes, print the records.

Data Envelope

A 1-position field that instructs the Pre-Processor program to write the envelope segments as data segments. This allows elements in these segments to be mapped to application fields when data is processed by the Inbound Mapper (EDIR041). Valid values are:

0	=	No, do not write envelopes as data segments.
1	=	Yes, write the envelopes as data segments.

Last Update Date (Protected)

An 8-position field that displays the date on which the information on this screen was created or last changed. The date format is MM/DD/YY.

Last Update Time (Protected)

An 8-position field that displays the time at which the information on this screen was created or last changed. The time format is HH:MM:SS.

Last Update User (Protected)

A 3-position field that displays the initials of the user who created or last changed the information on this screen.

Fixed/Variable Splitter Path Maintenance**EDIM841***Purpose*

The Fixed/Variable Splitter Path Maintenance screen enables you to specify the options used by the Splitter program when splitting the fixed-format EDI data from the variable-format EDI data.

How to Access

Access the Fixed/Variable Splitter Path Maintenance screen by typing **7** in the ‘Transfer to’ field on the Additional Shell Steps Maintenance screen (EDIM84F) and pressing **PF5=Transfer**.

See the *Gentran:Realtime for zSeries Release 6.3 User’s Guide* for information about the Additional Shell Steps Maintenance screen.

Screen Example

The following diagram illustrates the Fixed/Variable Splitter Path Maintenance screen.

```

EDIM841 _____ FIXED/VARIABLE SPLITTER PATH MAINTENANCE   XXX  12/01/2005
                                                    12:00:00

Path ID.....: 301F  STRUCTURE INBOUND SPLITTER_____

Compord Dest.....: 000  Immediate Option or Queue File Number
EDI Variable Dest.....: 000  Immediate Option or Queue File Number
Fixed Gencod Dest.....: 000  Immediate Option or Queue File Number
Fixed GM Dest.....: 000  Immediate Option or Queue File Number
Other Fixed Dest.....: 302  Immediate Option or Queue File Number
Report Print Sw.....: 0    0 = No, 1 = Print

Last Update Date.....: 12/01/05
      Time.....: 12:00:00
      User.....: XXX

NO PATH RECORD FOUND
Enter PF1=Help          PF3=Exit PF4=Dir          PF6=Shell
                        PF9=Add PF10=Updt PF11=Del
  
```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF15=Logoff**, and **Enter** are defined in Chapter 1 of the *Gentran:Basic for zSeries Release 6.4 User’s Guide*.

- PF4=Dir** Returns to the Path Options Directory screen.
- PF6=Shell** Displays the General Shell Path Maintenance screen.
- PF9=Add** Adds a new Pre-Processor path. Enter the appropriate parameters values and press **PF9=Add**.
- Copies a current path. First, enter the current path ID and press **Enter**. Type over the path ID and any other fields that need to be changed and

	press PF9=Add . The system will re-display the screen and display a message to indicate the information was added.
PF10=Updt	Updates the current Splitter path. Enter the new data over the existing data and press PF10=Updt . A message will be displayed to indicate the information was updated.
PF11=Del	Deletes a current Splitter path. Press PF11=Del to delete the data. The system will prompt you to confirm the delete by again pressing PF11=Del .

Field Definitions

Path ID

A 4-position alphanumeric field designating the path for which the Shell parameters are used. The suffix is always "F" and the three-digit path number is used to match the Shell with the Splitter parameters.

(Path ID Description)

A 40-character alphanumeric field containing the description for the processing of these parameters. The system displays this description on the Path Options Directory screen.

Compord Dest

A 3-digit numeric field used to specify the destination option to be used in processing the COMPORD fixed-format data. Valid values are **000** for no option or any 3-digit number that specifies any immediate or queue option.

The Splitter program processes any COMPORD data through this option number.

EDI Variable Dest

A 3-digit numeric field used to specify the destination option to be used in processing the variable-format EDI data. Valid values are **000** for no option or any 3-digit number that specifies any immediate or queue option.

The Splitter program processes any variable data through this option number.

Fixed Gencod Dest

A 3-digit field used to specify the destination option to be used in processing the GENCOD fixed-format data. Valid values are **000** for no option or any 3-digit number that specifies any immediate or queue option.

The Splitter program processes any GENCOD data through this option number.

Fixed GM Dest

A 3-digit field used to specify the destination option to be used in processing the GM fixed-format data. Valid values are **000** for no option or any 3-digit number that specifies any immediate or queue option.

The Splitter program processes any GM fixed-format data through this option number.

Other Fixed Dest

A 3-digit field used to specify the destination option to be used in processing all other fixed-format data. Valid values are **000** for no option or any 3-digit number that specifies any immediate or queue option.

The Splitter program processes all other fixed-format data through this option number.

Report Print Sw (Optional)

A 1-digit field that instructs the Splitter program whether to print reports. Valid values are:

0 = Do not print reports.

1 = Print reports.

Last Update Date (Protected)

An 8-position field that displays the date on which the information on this screen was created or last changed. The date format is MM/DD/YY.

Last Update Time (Protected)

An 8-position field that displays the time at which the information on this screen was created or last changed. The time format is HH:MM:SS.

Last Update User (Protected)

A 3-position field that displays the initials of the user who created or last changed the information on this screen.

NCPDP Outbound Parms Maintenance Screen

EDIM84G

Purpose

The NCPDP Outbound Parms Maintenance screen allows you to designate the processing options that will be in effect when the NCPDP Outbound Post-Processor program runs. You need to indicate the maximum record size for the output records being generated, as well as the compression level.

How to Access

Access the NCPDP Outbound Parameters screen from the Additional Shell Steps Maintenance screen, by typing **6** in the "Transfer to" field and pressing **PF5=Transfer**.

Screen Example

The following example illustrates the NCPDP Outbound Parameters screen.

```

EDIM84G _____ NCPDP OUTBOUND PARMS MAINTENANCE          XXX 12/01/2005
                                                    12:00:00

Path ID.....: 001N  OUTBOUND TO MAILBOX EXAMPLE
Outbound Flow

NCPDP Reformat Parameters:

Record Length..: 00000
Compress.....: T      (F=Full, T=Transmission)

Last Update Date: 12/01/05
                Time: 12:00:00
                User: XXX

Enter PF1=Help          PF3=Exit PF4=Dir          PF6=Shell
                PF9=Add PF10=Updt PF11=Del
  
```

Function Key Descriptions

Note: Standard function keys, such as **PF1=Help**, **PF3=Exit**, **PF7=Bwd**, **PF8=Fwd**, **PF9=Add**, **PF10=Updt**, **PF11=Del**, **PF12=Cancel**, and **PF15=Logoff**, as well as the **Enter** key, are defined in Chapter 1 of this guide, *Getting Started*.

Enter	Refreshes the NCPDP Outbound parameters screen display with the saved field values for the Shell path designated in the Path ID field.
PF4=Dir	Displays the Path Options Directory screen.
PF6=Shell	Displays the General Shell Path Maintenance screen.

Field Descriptions

Note: Fields that are display-only contain the statement “(Protected)” next to the field name in the documentation. Fields in which you *must* type a value contain the statement “(Required)” next to the field name in the documentation.

(Jump Code)

A 10-position alphabetic or numeric field containing the jump code for this screen. A screen’s jump code is displayed automatically in the Jump Code field for that screen.

To *jump* to another screen, press **Home**, type the jump code of the screen to which you want to jump, and press **Enter**.

See the “Jump Codes” section in Chapter 1 of this guide for further information on using jump codes.

Path ID

A 4-position alphanumeric field designating the path number and suffix for the parameters defined. The suffix is always N and the three-digit path number corresponds to the numeric value in the Path ID field on the General Shell Path Maintenance screen.

(Path ID Description)

A 40-character alphanumeric field containing the description for this path.

NCPDP Reformat Parameters

Record Length

A 5-position numeric field that designates the maximum record size for the outbound data. Valid values are **00001 – 32760**.

Compress

A 1-position alphabetic field that designates the level of compression to be applied to the outbound data. Valid values are:

F = Full compression includes batch envelopes.

T = Transmission compression does not include batch envelopes.

Last Update Date (Protected)

An 8-position field that displays the date on which the information on this screen was created or last changed. The date format is MM/DD/YY.

Last Update Time (Protected)

An 8-position field that displays the time at which the information on this screen was created or last changed. The time format is HH:MM:SS.

Last Update User (Protected)

A 3-position field that displays the initials of the user who created or last changed the information on this screen.

Program Descriptions

Overview

This chapter contains detailed descriptions of Gentran:Structure files, processing, programs, and reports. Its purpose is to enable you to familiarize yourself with the system, its terminology, and its functionality. This chapter contains the following topics:

Topic	Page
Inbound Flow	4-3
Introduction	4-3
Illustration	4-3
Inbound Pre-Processing Program EBDI083	4-6
Purpose	4-6
Files Used	4-7
Parameter Descriptions	4-9
Processing Description	4-12
Partner Determination (Partner/Qualifier and Mixed Modes)	4-14
Partner Determination (Relationship Mode)	4-16
Inbound Mapping Program	EBDI041
Purpose	4-19
Inbound Mapping Program Flow	4-19
Files Used	4-20
Inbound Fixed/Variable Split Program	EBDI094
Purpose	4-24
Inbound Fixed/Variable Split Program Flow	4-25
Files Used	4-26
Processing Description	4-27
Outbound Flow	4-28
Overview	4-28
Outbound Flow with Fixed-Format Standards	4-29
Outbound Mapping Program	EBDI042
Purpose	4-30
Outbound Mapping Program Flow	4-31
Files Used	4-32
Mapping Parameter Records (SYS001)	4-34

NCPDP Inbound Pre-Processing Program	NCPDP51I	4-39
Purpose		4-39
Inbound Pre-Processing Program Flow		4-39
Files Used		4-40
Parameter Layout		4-40
NCPDP Outbound Post-Processing Program	NCPDP51O	4-42
Purpose		4-42
NCPDP Outbound Post-Processing Program Flow		4-42
Files Used		4-43
Parameter Layout		4-44
Structure Application Databank Inquiry Report Program EDID553		4-46
Purpose		4-46
Files Used		4-46
Reports		4-47
Control Card Options		4-47
Sample Reports		4-51

Inbound Flow

Introduction

This section illustrates and describes the inbound flow through Gentran:Structure, to provide context for the program descriptions that follow.

Illustration

Figure 4.1 illustrates the inbound flow through Gentran:Structure system components. It shows fixed-format, mixed-format and variable format EDI data. The numbers in the illustration correspond to the steps below the figure that describe the flow.




Figure 4.1 Inbound Flow Through Gentran:Structure System Components

The following table describes the inbound flow through Gentran:Basic using **Gentran:Structure**.

Stage	Description		
	Variable Format Data	Mixed-Format Data	Fixed-Format Data
1	The system sends the data from Communications to the Inbound editor.	The system sends the data from Communications to the Inbound Fixed/Variable Splitter to be separated by format type.	The system sends the data from Communications to the Format Specific Compliance Checker, if used, or directly to the Inbound Pre-processor.
2	If the Inbound Splitter is used, the system passes the data to the Splitter, and then to the Inbound Mapper. If the Splitter is not used, the system passes the data directly to the Inbound Mapper.	<ul style="list-style-type: none"> The Inbound Fixed/Variable Splitter: Sends the variable-format data to the Inbound editor. The data continues on the variable format data path. Sends the fixed-format data to the Compliance Checker, if used, or directly to the Inbound Pre-processor. The data continues on the fixed-format path. 	The system sends the data from the Pre-processor to the data router, if used, or directly to the Inbound Mapper.
3	The Inbound Mapper sends the file to the Application or to the Inbound Application databank (if used – See step 3A).		The Inbound Mapper sends the file to the Application or to the Inbound Application databank (if used; see Stage 3A).
3A	(Optional) The Inbound Application Databank Extract program sends the data to the Application.		(Optional) The Inbound Application Databank Extract program sends the data to the Application.

Inbound Pre-Processing Program

EBDI083

Purpose

The Inbound Pre-Processing Program (EBDI083) supports mapping from fixed-format standards by duplicating some of the critical functionality that is present in the Inbound Editor Program (EBDI001). This program replaces the Inbound Editor Program in the inbound processing flow for fixed-format standards.

The Inbound Pre-Processing Program processes as input a fixed-format standard that the user has received from a trading partner or internal division. It is the responsibility of the user to determine that all of the data presented to this program is a fixed-format standard that is defined to the Gentran:Basic online standards files. The Inbound Fixed/Variable Split program (EBDI094) can be used to segregate some types of this data.

The Pre-Processing program allows databanking of fixed-format data. The system stores the records on the Inbound Application Databank; you can view them using screens accessible via the Databank Menu.

The program generates an output file that contains the original input data with ####MAP, ####MP2, ####MP4, ####MP5, and ####MP6 records inserted into it. The format and placement of these special records is explained later.

The Inbound Mapping program (EBDI041) processes the output file.

The system writes data that cannot be processed to a suspense file.

Files Used

Input

The system uses the following files as input.

Filename	Description
SYS003	Fixed-Format EDI Data file This file contains the user's fixed-format EDI data. It can be fixed-blocked or variable-blocked and can have a logical record length up to 32760 bytes.
USRENV	User-Envelope Definition file This VSAM KSDS file contains definitions for all of the user-defined envelopes that the program might encounter while processing the input data. The program loads information from this file for all envelopes that are defined for inbound processing.
SYS030	Parameters file This file contains the parameters used for processing the data through the program. The program treats an invalid or unidentified parameter input card as a fatal error.
SYS095	Partner Profile Cross-Reference (Partner/Qualifier mode ONLY) The system uses this VSAM KSDS file to obtain a valid Partner ID and User ID when the partner and user information is being extracted from the incoming data.
SYS090	Partner Profile The system uses this VSAM KSDS file to obtain the processing parameters for a specific trading partner or user.
EDICFG	System Configuration file The program uses this file to determine system level processing options for base and add-on features of Gentran:Basic.
ERRCTL	Error Message and Control file Obtains the message text for error report processing.
EDIPREL	Partner Relationship Cross Reference file (Relationship mode ONLY) The program cross-references EDI IDs to User/Partner IDs.
EDISVER	Standard Version file This file is used to obtain standard version agency.

Output

The system uses the following files as output.

Filename	Description
SYS004	Intermediate file This file contains the data that was in the original input file, as well as ####MAP, ####MP2, ####MP3, ####MP4, ####MP5, and ####MP6 records. It is a variable-blocked file with a logical record length of 32760 bytes. The lengths of the actual records are the lengths of the records read.
SYS099	Suspense file This file contains data that could not be processed because of incomplete Partner, Version, User, or Transaction Set information. The file should have the same DCB information as the input file.
SYS005	Audit Trail This file is a report that lists all errors encountered during processing.
SYS006	Summary report This file is a report that shows all of the parameters used for processing and provides the following counts: <ul style="list-style-type: none"> • Input records read • Output records written • Map records written (includes MAP, MP2, MP3, MP4, MP5, and MP6 records) • Interchange headers read • Group headers read • Transaction headers read The system also prints the return code for the program.
EDIIAA	Inbound Application Directory This file stores incoming fixed-format data audit information.
EDIIAS	Inbound Application Message Store This file stores incoming fixed-format data.
EDIIEL	Inbound EDI/Application Link file This file stores link information for fixed-format and Application data generated from the mapper.
EDILOG	Log Report file.

Parameter Descriptions

Record Format (Mandatory)

FIXED The input file is fixed-block format.

VARIABLE The input file is variable-block format.

Record Length (Mandatory)

A 5-character numeric field to indicate the record length of the input file. The RDW (record descriptor word) for variable-blocked files should not be included in the length value. Valid values are up to **32760** for fixed-format files and **32752** for variable-format files.

Partner ID (Optional)

A 1- to 35-character field (15-character for Relationship mode) that identifies the Partner ID to use for all data received in this run. The system ignores any partner information contained on the envelopes. When this parameter card is supplied, a Partner value is required.

Note: The Partner Cross-Reference file is not accessed during the Partner ID Look-Up when it is supplied as an input parameter.

Partner Qualifier (Optional)

A 1- to 4-character field that identifies the Partner ID Qualifier to use for all data received in this run. Any partner information contained on the envelopes is ignored. The Partner ID parameter is required if the Partner Qualifier is supplied.

User ID (Optional)

A 1- to 35-character field (15-character if trading profile mode is Relationship) that identifies the User ID to use for all data received in this run. The system ignores any user information contained on the envelopes. When this parameter card is supplied, the User ID field must not contain spaces. The Partner Cross-Reference file is not accessed during the User ID Look-Up logic when the User ID field is supplied as an input parameter.

User Qualifier (Optional)

A 1- to 4-character field that identifies the User ID Qualifier to use for all data received in this run. The system ignores any user information contained on the envelopes. The User ID parameter is required if the User Qualifier is supplied.

Version ID (Optional)

A 1- to 12-character field followed by the three-character Agency, that identifies the Standard Version ID to use for all data received in this run. The system ignores any version information contained on the envelopes. If this parameter card is supplied, the Version ID field and agency field must not contain spaces.

Transaction ID (Optional)

A 1- to 6-character field that identifies the Transaction Set ID to use for all data received in this run. The system ignores any transaction information contained on the envelopes. If this parameter card is supplied as input, the Transaction Set ID field must not contain spaces.

Envelope Level (Optional)

This parameter specifies the level of enveloping that the fixed-format standard uses. Hold areas are cleared when an envelope at the specified level is received. Valid values are:

TRANSACTION (Default)
GROUP
INTERCHANGE

Application By (Optional)

This parameter instructs the program where to look for Inbound Transaction Level Data Separation records. The system uses these records to specify the application to be loaded by the Inbound Mapper so that the 'In-stream' option can be used.

NONE Data Separation is not defined (Default).
USER Data Separation is established underneath the User.
PARTNER
Data Separation is established underneath the Partner.

Data Envelope (Optional)

This parameter instructs the program to write the envelope segments as envelopes and data segments. This allows elements in these segments to be mapped to application fields when you execute the Inbound Mapper (EBDI041). Valid values are:

YES Write the envelopes as data segments.
NO Do not write envelopes as data segments (this is the default value).

Databank (optional)

This parameter instructs the program on the level of databanking to use for the incoming Fixed-Format data. Valid values are:

NO No Databanking (this is the default value).
DIR Only the directory portion of the databanking is used.
FULL The directory and message store facilities are used.

Note: The default value is no Databanking.

Detail Reports (optional)

This parameter instructs the program on the level of detail to print in the Audit Trail report. Valid values are:

ON Echo the incoming and outgoing data.
OFF Only print error messages (this is the default value).

User Reference (Optional)

This parameter is for use in conjunction with the Inbound Pass-Thru feature on the Inbound Mapper program. The User-Reference parameter specifies the user-reference key for the application document on the Application Databanks.

Position	Segment	Description
1 – 15	User Reference	A 15-position field that contains the value 'User Reference.'
16 – 25	Segment ID	A 10-position field to specify the segment ID of the record from which the application user-reference field can be found.
26 – 30	Segment ID Starting Position	A 5-position numeric field used to define the starting position of the segment ID field in the record where the application user-reference field can be found.
31 – 32	Segment ID Length	A 2-position numeric field used to define the length of the segment ID field in the record where the application user-reference field can be found.
33 – 37	User Reference Starting Position	A 5-position numeric field used to define the starting position of the application user-reference field in the EDI data record.
38 – 39	User Reference Length	A 2-position numeric field used to define the length of the application user-reference field in the EDI data record.

Processing Description

Initial Tasks

The following table describes the initial phase of inbound processing.

Stage	Description
1	The system opens the Audit Trail file, the Summary Report file, the Error Message file, and the Parameter file and validates all parameters. If the system detects any errors, it issues an error message, sets the return code to 16, and terminates the program.
2	The system opens the rest of the files. If it detects any errors, it issues an error message, sets the return code to 16, and terminates the program.
3	The system reads all of the User-Envelope Definition records and stores the information contained in the records in an internal table. The system loads the records into the table if the Envelope Level is set to 'Begin-Interchange,' 'Begin-Group,' or 'Begin-Transaction,' 'End-Interchange,' 'End-Group,' 'End-Transaction,' AND the Direction-Indicator is <i>not</i> set to 'O' (outbound). Note: If no defined envelope records match the selection criteria, the system issues an error message, sets the return code to 16, and terminates the program.
4	The system reads the first input record. If it finds no input, it issues an error message, sets the return code to 8, and terminates the program.

Envelope Processing

Stage	Description
1	<ul style="list-style-type: none"> If the system reads the record that is a beginning envelope (search against the Envelope Definition Table), the system moves the record to a hold area. <p>Note: No special processing occurs at this time for ending (trailer) envelopes.</p> <ul style="list-style-type: none"> The system defines multiple hold areas (at this time there are five). A counter describes the number of envelopes currently held. The system associates a length field to each hold area, which describes the length of the record that was read. The system also associates a flag with each hold area to indicate whether the held envelope has been written to the output file.
2	The system saves the input envelope Segment ID in the envelope hold table. If the system receives another envelope having the same Segment ID, it replaces the previous envelope in the table. At the same time, the system resets the 'Write Flag' for this segment.

Stage	Description
3	If the envelope is a beginning envelope that matches the level specified in the parameter file or the default level, the system clears hold areas associated with User, Partner, Version, and Transaction Set IDs. The system also clears all envelope records being held at this time.
4	<ul style="list-style-type: none"> • If the user-envelope definition record has a defined User ID, Partner ID, Version ID, or Transaction Set ID, the system extracts appropriate fields from the current envelope and moves them to hold areas associated with this field. • If a default version or transaction set is associated with the envelope definition, the system holds it also. Since there is only one level of hold areas, values extracted from lower-level envelopes overlay those from higher-level envelopes. If the extracted value is spaces, it does not overlay a previously extracted value. <p>Note: The system extracts values from the input segment only when the value was not supplied as an input parameter or defined as a default value on the user-envelope definition record.</p>
5	If the user-envelope definition record has defined Sender ID, Receiver ID, Reference Number, or Generic Element 1 through 10 fields, the system extracts these and stores them in the corresponding areas of the ###MP4, ###MP5, and ###MP6 records.
6	If a user-reference parameter has been specified, the system pulls the application user-reference key from the input data and puts it on a ###MP2 record.
7	If this envelope is a beginning interchange envelope, the system increments the Interchange Header counter. The system increments the group and transaction header counters when the respective envelopes are received. Processing continues until the system reads a record that is not defined as a beginning envelope.
8	The system writes the type of envelope to the “key” portion of the output record; otherwise, the system performs no special processing for ending envelopes.

Post-Envelope Processing – User/Partner Look-Up

The first thing to determine is what field the system will use for the key on the Partner Profile Look-Up. Depending on which of the partner profile fields are loaded, the system will perform the look-ups as described below.

Partner Determination (Partner/Qualifier and Mixed Modes)

The following describes the method Gentran:Structure uses to determine the partner when the trading profile mode is Partner/Qualifier or Mixed.

Method	Description
Partner supplied on input parameter	<p>The system uses the ID specified on the parameter to look up the partner directly on the partner profile. If the system does not find the partner's Header record, it issues a message, sets the return code to 16, and terminates processing. Because the partner specified on the parameter record applies to the entire run, a failed Look-Up implies that no partner ID will be found for any documents in the run. This is a fatal error.</p> <p>Note: The Partner Cross-Reference file is not used when the partner is specified on the parameter record.</p>
Extracted Partner from envelope	<p>If no ID is specified on the parameter, the system examines the partner hold area. If this area is spaces, the system suspends the input document. See "Suspending an Input Document" for more information. The system issues an error message and sets the return code to 4.</p>
Partner Header Record Look-Up	<p>If the Partner ID hold area is not spaces, the system uses this ID to access the Partner Cross-Reference file. If this access is successful, the system uses the Alias ID to access the Partner Profile Header record. If this access is not successful, the system reads the Partner Profile Header record using the original ID as the key. If the system finds an alias ID (including both Partner ID and Qualifier), it uses this ID in all subsequent partner profile reads as well as loading it into the ####MAP records.</p> <p>If the system does not find the Partner Profile Header record, it suspends the document, issues an error message, and sets the return code to 4.</p>
Partner Control Record Look-Up	<p>The system reads the Partner Profile Control record and moves the resolved Partner ID to the Partner ID portion of the key. If CFG-multiple envelope flag is set to Y, then the system moves GEN to the multiple envelope ID of the Control Record. If the Partner Lookup is unsuccessful, the system tries again, with spaces in the Multiple Envelope ID. If the system still doesn't find the Control Record, it suspends the document, issues an error message, and sets the return code to 4.</p>

Method	Description
Partner Transaction Record Look-Up	<p>The next step is to read the Partner Profile Transaction record. If the Transaction Set ID was specified on the parameter, the system uses that ID for the look-up key. If the ID was not supplied, the system uses the Transaction Set ID that was specified as the envelope default. Finally, if neither of the previous IDs are available, the system extracts the Transaction Set ID from the data if possible. If none of these values are loaded, the system suspends the document, issues an error message, and sets the return code to 4.</p> <p>Note: The Transaction Set ID record does not have to exist on the Partner Profile.</p> <p>The system reads the Partner Profile Transaction record at this time. If the read is successful, system saves the Inbound Translation ID, Functional Group ID, Inbound Application Databank Level, and the Test Transaction Indicator in a hold area. The default Transaction record does not need to be accessed if the specific Transaction record is not found. The system does not issue an error if the Transaction record is not found; the fields are merely loaded with spaces.</p>
Partner Data Separation Record Look-Up	<p>If the Application By parameter is set to Partner, an Inbound Data Separation record is accessed at the transaction level using the Transaction Set ID used above. If the read is successful, the Inbound Application field is saved in a hold area. If the Partner read is not successful or the Inbound Application field is not greater than spaces, the document is suspended, an error message issued, and the return code is set to 4.</p>

Partner Determination (Relationship Mode)

The following table describes the method Gentran:Structure uses to determine the partner when the trading profile mode is Relationship.

Note: If the trading profile mode is Relationship, the Partner Header record, with both user and partner on the key, must be on the partner profile.

Method	Description
Partner Profile Look-Up	The system performs the Partner Profile Look-Up in the same manner as the Partner Profile Look-Up for the sender. This action includes reading the Partner Relationship Cross-Reference file if the User/Partner ID was not supplied as an input parameter. If the system finds an alias, it uses it as the User/Partner ID for all subsequent partner profile reads and places it on the ####MAP records.
User/Partner ID supplied as an input parameter	If the system does not find the ID on the partner profile, it issues a message, sets the return code to 16, and terminates processing.
Partner Header Record Look-Up	If the User ID/Partner ID hold area is not spaces, the system uses this ID to access the Partner Cross-reference file. If this access is successful, the system uses the Alias ID to access the Partner Profile Header record. If this access is not successful, the system reads the Partner Profile Control record using the original ID as the key. If the system finds an alias ID, it uses this ID in all subsequent partner profile reads as well as loading it into the ####MAP records. If the system does not find the Partner Profile Header record, it suspends the document, issues an error message, and sets the return code to 4.
Partner Control Record Look-Up	The system reads the Partner Profile Control record and moves the resolved ID to the User ID/Partner ID portion of the key. If CFG-multiple envelope flag is set to Y, then the system moves GEN to the multiple envelope ID of the Control Record. If the Partner Lookup is unsuccessful, the system tries again, with spaces in the Multiple Envelope ID. If the system still doesn't find the Control Record, it suspends the document, issues an error message, and sets the return code to 4.

If the Application By parameter is set to User, an Inbound Data Separation record must exist for that user for the transaction set being processed. This Partner Profile Look-Up is independent of the trading profile mode setting.

If either record is required and not found, the system suspends the document, issues an error message, and sets the return code to 4.

If the system finds the Inbound Data Separation record but the Inbound Application field is not greater than spaces, the system suspends the document, issues an error message, and sets the program return code to 4.

Post-Envelope Processing – Suspending a Document

In the event that any required information is missing from the envelopes or the partner profile, the system must suspend the document. The system writes the document to the Suspense file exactly as it was read from the input file with the following exception: If multiple levels of envelopes are being held when the system determines to suspend a document, the system writes all of the held envelopes to the Suspense file with the document. This action allows the document to be reprocessed as a single entity.

###MAP records are not written to the Suspense file.

Post-Envelope Processing – Writing a Document

If the document is valid, the system writes it to the output file.

Formatting the MAP records. The system writes special ####MAP, ####MP2, ####MP3, ####MP4, ####MP5, and ####MP6 records to the output file. The Inbound Mapper uses these special format records. The ####MP4, ####MP5, and ####MP6 records contain information that is specific to inbound fixed-format processing.

Writing the data. The format of the output file is similar to that of the Inbound editor program, in that each record is prefixed with a 15-byte key. The record count is placed in the first 10 bytes of the key. The next two bytes contain the characters 01. The last three bytes are formatted as follows:

- If the output record is an envelope, a special designator indicates the type of envelope that is loaded in the field. For example, if the envelope is a beginning interchange envelope (type BI), the characters '#BI' are loaded.
- If the output record is any other type of record, '***' is loaded to the field.

Once the MAP records have been formatted, the data can be written to the output file. The system first writes envelopes that have been held. The system examines each of the hold area "write flags." If the system determines that the envelope has not been written, it writes it to the output file. The system sets the "write flag" at this time and sets the length of the envelope written to the hold area length value.

Once the envelopes have been written, the system writes the formatted ####MAP, ####MP2, ####MP3, ####MP4, ####MP5, and ####MP6 records. These records have a length of 400 bytes.

At this point, the program goes into a read/write mode until it encounters another beginning envelope. The program writes each record with the length of the record as read.

Note: The System writes ####Map records only when they contain significant information (blank or default records are not written).

Final Tasks

If the count of all of the records written is equal to zero, the system sets the return code to 8 and issues a message.

The system writes the summary report.

The system closes all files.

Inbound Mapping Program

EBDI041

Purpose

The Inbound Mapping program optionally processes fixed-format standard input in addition to variable-format standard input. A single execution of the mapper processes either fixed-format input that was generated by the Inbound Pre-Processing program (EBDI083) or variable-format data that was generated by the Inbound Editor program (EBDI001). A parameter instructs the mapper as to the format of the data. Regardless of format, the system reads the input data from the SYS004 dataset.

Data can be directed to the Application Data file and/or the Inbound Application databank regardless of input format.

Inbound Mapping Program Flow

Figure 4.2 illustrates the current file usage of the Inbound Mapping program.




Figure 4.2 File Usage of the Inbound Mapper

Files Used

The following files have been added or modified to support fixed-format standards.

See the *Gentran:Basic for zSeries Release 6.4 Technical Reference Guide* for complete information about this program.

Input

The following files are used as input.

Filename	Description
SYS001	<p>Parameters file</p> <p>This file contains the parameters that drive the Inbound Mapping process. Two parameters are specific to Gentran:Structure:</p> <ul style="list-style-type: none"> Input Format Type (Gentran:Structure only) This parameter describes whether the input file (SYS004) is variable-format and was generated by the Inbound Editor program (EBDI001) or is fixed-format and was generated by the Inbound Pre-Processing program (EBDI083). If the input is variable, nothing must be coded for the parameter. If the input is fixed, the character 'F' must be coded. This parameter starts in column 46 with a length of one character. Structure Databank Level The second parameter resides on mapping parameter record # 4. This parameter controls the databanking for Gentran:Structure data. This parameter indicates to the Mapper what level of databanking is desired. A value of '0' indicates that no databanking is desired. A value of '1' indicates directory and message store databanking is requested. A value of '2' indicates that directory-level only is desired. This parameter starts in column 3 of record 4, with a length of one character.
EDICFG	<p>System Configuration file</p> <p>This file is used by the program to determine system level processing options for base and add-on features of Gentran:Basic.</p>
SYS004	<p>Input file</p> <p>This file will contain either the data generated by the Inbound editor or the Inbound Pre-Processor. If the source of the data is the Inbound Pre-Processor, the Input Format Type parameter described above must be set to 'F.'</p>

Parameters File Layout – Inbound (SYS001)

The following tables describe the inbound parameters file layout.

Record 1

Position	Field Content	COBOL Picture	Format	Length	Description
001 – 010	Application Data ID	X(10)	AN	10	The name assigned to the definition of the Application Data file, or ##INSTREAM to specify application parameters.
011 – 011	EDI Data Print Switch	X(01)	AN	01	Y – Instructs the Mapper to print the first 125 characters of each record read and each record generated.
012 – 012	Forced Abend Switch	X(01)	AN	01	Y – Instructs the Mapper to abend if any errors are encountered during execution.
013 – 019	Start Process User Exit	X(07)	AN	07	The name of a user written program to be executed after all Gentran:Basic files have been opened.
020 – 026	End Process User Exit	X(07)	AN	07	The name of a user written program to be executed after all Gentran:Basic files have been closed.
027 – 027	Application Decimal Notation	X(01)	AN	01	A comma (,) instructs the Mapper to interpret a comma as a decimal point in the application file.
028 – 028	Application File Type	X(01)	AN	01	If using Instream application parameters, enter V in this field to indicate the application file is variable; enter F in this field to indicate a fixed format.
029 – 032	Application File Length	9(04)	N	04	If using Instream application parameters, code the maximum record length of the application file. Do not include 4 bytes for RDW for variable files.
033 – 033	Alternate Application Real Switch	X(01)	AN	01	Y – Instructs the Mapper to right justify application real numbers.
034 – 034	Return Code Switch	X(01)	AN	01	If = Y , generate return code.
035 – 035	NTE Float Switch	X(01)	AN	01	Y – instructs the Mapper to process all NTE segments received in a section with one definition.

Position	Field Content	COBOL Picture	Format	Length	Description
036 – 036	Databank Configuration Switch	X(01)	AN	01	0 – No Databank 1 – Full Databank 2 – Directory Only Databank.
037 – 037	Databank Processing Level Switch	X(01)	AN	01	0 – No Databank 1 – Full Databank 2 – Directory Only Databank. 3 – Partner Databank Level
038 – 039	Filler	X(02)	AN	02	Not used
040 – 040	Filler	X(01)	AN	01	Not used
041 – 041	Filler	X(01)	AN	01	Not used
042 – 042	Partner Print Switch	X(01)	AN	01	0 – Do not print user/partner information when partner is loaded 1 – Print partner information when partner is loaded.
043 – 043	Write to Output File Switch	X(01)	AN	01	0 – Write application to an output file in addition to the message store if requested. 1 – Do not write to the output file.
044 – 044	Document Tracking Switch	X(01)	AN	01	1 – Print an entry on the Audit Trail for each document in error in the run. 2 – Print an entry on the Audit Trail for each document processed in the run.
045 – 045	Support Quote Switch	X(01)	AN	01	Y – Execute additional program logic to allow a single quote in reserved word constants and literal constants.
046 – 046	Input Format Type	X(01)	AN	01	Used for Gentran:Structure only. F – Input to this program was generated by the inbound Structure pre-processor. V or blank – Input to this program was generated by the Inbound editor (default).
047 – 051	Filler	X(05)	AN	05	Not used
052 – 052	Mandatory Segment	X(01)	AN	1	Y – Indicates that the first segment of every loop received is mandatory and is present in the incoming EDI data. This aids in pulling the correct segment from the map when the map contains the same Segment ID multiple times (used mainly for 837 documents).

Position	Field Content	COBOL Picture	Format	Length	Description
053 – 054	Filler	X(02)	AN	02	Not used
055 – 055	User Exit Version	X(01)	AN	01	1 – Use the version 1 call blocks for user exits. 2 – Use the version 2 call block for user exits.
056 – 062	Filler	X(10)	AN	10	Not used
063 – 063	Viewpoint User Tracking (Gentran: Viewpoint Tracking Management only)	X(01)	AN	01	0 – Viewpoint tracking is not performed by a user application tracking program. 1 – Viewpoint tracking is performed by a user application tracking program.
064 – 076	Filler	X(13)	AN	13	Not used
077 – 077	Verify Map Version	X(01)	AN	01	Y – Instructs the Mapper to verify the Version ID used to compliance check the incoming document matches the version ID found on the selected partner-specific map. If the Versions IDs do not match, the document will be suspended.
078 – 080	Filler	X(03)	AN	03	Not used

For more information about the Inbound Mapping program, see the *Gentran:Basic for zSeries Release 6.4 Technical Reference Guide*.

Inbound Fixed/Variable Split Program**EBDI094****Purpose**

This program reads an EDI data file and splits it into the following categories:

- Fixed-format COMPORD data
- Fixed-format GM (CISCO) data
- Fixed-format GENCOD data
- Other fixed-format data
- Variable-format EDI data

The program writes all output as 80-byte fixed records.

This program processes as input 80-byte records. It determines the type of data and writes the records to the appropriate output file.

Either the Inbound Editor program (EBDI001 – variable-format data) or the Inbound Pre-Processor program (EBDI083 – fixed-format data) processes the output files.

Inbound Fixed/Variable Split Program Flow

Figure 4.3 illustrates the input and output files for this program.




Figure 4.3 Inbound/Variable Split Program Flow

Files Used

Input

The following files are input.

Filename	Description
SYS003	Fixed-Format and Variable-Format EDI Data file This file contains 80-byte fixed-input records wrapped with or without envelopes.
ERRCTL	Error Message file and Control file The system uses this VSAM file to obtain the message text for error report processing.
EDICFG	System Configuration file The program uses this file to determine system level processing options.

Output

The following files are output.

Filename	Description
COMPORD	Fixed COMPORD file This file will contain the 80-byte fixed records wrapped with COMPORD envelopes.
EDIDAT	EDI Variable Data This file will contain 80-byte fixed records of data wrapped with Standard EDI envelopes. Any GM headers wrapped around the input data are not written to the output file.
GENCOD	Fixed GENCOD file This file will contain 80-byte fixed records of data wrapped with GENCOD envelopes.
GMDATA	Fixed GM file This file will contain 80-byte fixed records wrapped with GM envelopes.
OTHFIX	User-Defined Fixed Data This file will contain 80-byte fixed records of data wrapped with user-defined envelopes.
SYS006	Summary Report This file is a report to show all of the parameters used for processing and will provide the following counts: <ul style="list-style-type: none"> • Input records read • Output records written to each output file The report also prints any error messages issued during processing and the final program return code.

Processing Description

Initial Tasks

The program opens all files. If it encounters an error, it issues a message, sets the return code to 16, and terminates the program.

The program reads the first input record. If there is no input, the program issues a message, sets the return code to 8, and terminates the program.

Envelope Processing

Once the program has read the first input record, it determines the type of data it has received. The following envelope types cause processing decisions to be made:

Standard	Segment	Position	Value	Occur
GM	Header	1 – 4	*THS	Single
GM	Trailer	1 – 4	*TTR	Multiple – (5 max)
Variable	Header	1 – 3	BG	Single
			GS	
			ICS	
			ISA	
			SCH	
			STX	
			UNA	
			UNB	
COMPORD	Header	1 – 2	20	Single
COMPORD	Trailer	1 – 2	99	Single
GENCOD	Header	1 – 3	035	Single
GENCOD	Trailer	1 – 3	199	Single

Once the program finds a match, it writes the data to the appropriate output file (through the corresponding trailer segments). After it has written all trailer segments, it queries the next record to determine the beginning envelope type, and the cycle starts over.

GM header and trailer segments may be wrapped around fixed or variable data. The system holds the header segments until it determines the type of data that is being processed. If the data is in a variable format, the system does not write the GM header and trailer records to the output file.

If there is no match against the envelope types, the system writes the data to the 'OTHFIX' output file.

Outbound Flow

Overview

The programs described in this section allow fixed-format standards to be processed. The following flow charts describe the outbound flow with fixed-format standards and the Outbound Mapping program.

Outbound Flow with Fixed-Format Standards

Figure 4.4 illustrates the outbound process.




Figure 4.4 Outbound Flow with Fixed-Format Standards

Outbound Mapping Program

EBDI042

Purpose

The Outbound Mapping Program optionally generates fixed-format standard output in addition to variable-format standard output. Both fixed-format data and variable-format data can be generated from a single application depending upon the receiver of the data. The program directs fixed-format output to a new dataset (SYS098). The program writes variable-format output to the SYS004 dataset.

Fixed-format data can be sent directly to communications for transmission to the trading partner, or it can be processed by optional envelope generation or compliance checking programs. These optional programs are not supplied with the system. If they are necessary for processing, they must be developed for the specific standard.

Outbound Mapping Program Flow

Figure 4.5 illustrates the outbound mapping process.




Figure 4.5 Outbound Mapping Program Flow

Files Used

Gentran:Structure includes the following files to support fixed-format standards.

See the *Gentran:Basic for zSeries Release 6.4 Technical Reference Guide* for complete information about this program.

Input

The following files are input.

Filename	Description
SYS001	<p>Parameters file</p> <p>This file contains the parameters that drive the Outbound Mapping process. There are four parameters specific to Gentran:Structure.</p> <p>Two parameters describe what the Fixed-Format Output file (SYS098) should look like. These parameters are:</p> <ul style="list-style-type: none"> • Fixed-Format File Type This parameter describes whether the Fixed-Format Output file will have fixed-length or variable-length records. Valid values are 'F' to indicate fixed-length records and 'V' to indicate variable-length records. If this parameter is used, the length parameter described below is mandatory. If both of these parameters are correctly specified, the program opens the Fixed-Format Output file using the information specified in the parameters. This parameter starts in column 46 with a length of one character. • Fixed-Format File Record Length This parameter describes the length of the records to be generated in the Fixed-Format Output file (SYS098). For fixed-length files, it describes the record length, and for variable-length files, it describes the maximum record length. Valid values are '00010' through '32760' for fixed-length files, and '00010' through '32752' for variable-length files. If this parameter is used, the type parameter described above is mandatory. If both of these parameters are correctly specified, the program opens the Fixed-Format Output file using the information specified in the parameters. This parameter starts in column 47 with a length of five characters. All characters must be valid numeric digits.

Filename	Description
	<p>The third parameter instructs the Mapper how to initialize numeric fields that are not mapped to.</p> <ul style="list-style-type: none"> Initialize Numerics This parameter tells the outbound mapper to set to zero non-packed dates and numeric data with types N0-N9 and S0-S9 if no valid value is mapped to the element. This parameter starts in column 53 with a length of one character. <p>The fourth parameter resides on the Mapping Parameter Record #4. This parameter controls the databanking for Gentran:Structure data.</p> <ul style="list-style-type: none"> Structure Databank Level This parameter indicates to the Mapper what level of databanking is desired. A value of '0' indicates that no databanking is desired. A value of '1' indicates directory and message store databanking is requested. A value of '2' indicates that directory-level only is desired. This parameter starts in column 3 of record 4, with a length of one character.

Output

The following files are used as output.

Filename	Description
SYS098	<p>Fixed-Format Output file</p> <p>This file contains data that has been mapped successfully to a fixed-format standard. The field description is based on the new Fixed-Format file type and Record Length parameters.</p> <p>Fixed-format data can be sent directly to communications for transmissions to the trading partner or it can be processed by optional envelope generation or compliance checking programs. These optional programs are not supplied with the system. If they are necessary for processing, they must be developed for the specific standard.</p>

Mapping Parameter Records (SYS001)

These record layouts are used by the Outbound Mapper to drive the outbound mapping process. The file is in a sequential format. The records are a fixed 80-byte length. Many of the options set in the parameter records have been described earlier in the processing section of this chapter.

Mapping Parameter Record Layout #1

The following table describes Mapping Parameter Record Layout #1.

Position	Field Content	COBOL Picture	Format	Length	Description
001 – 010	Application Data ID	X(10)	AN	10	The name assigned to the definition of the Application Data file, or ##INSTREAM to specify application parameters.
011 – 011	EDI Data Print Switch	X(01)	AN	01	Y – Instructs the Mapper to print the first 125 characters of each record read and each record generated.
012 – 012	Forced Abend Switch	X(01)	AN	01	Y – Instructs the Mapper to abend if any fatal errors are encountered during execution.
013 – 019	Start Process User Exit	X(07)	AN	07	The name of a user-written program to be executed after all Gentran:Basic files have been opened.
020 – 026	End Process User Exit	X(07)	AN	07	The name of a user-written program to be executed after all Gentran:Basic files have been closed.
027 – 027	Application Decimal Notation	X(01)	AN	01	A comma (,) instructs the Mapper to interpret a comma as a decimal point in the Application file.
028 – 028	Application File Type	X(01)	AN	01	If instream application parameters are used V – Indicates the Application file is variable F – Indicates a fixed format.
029 – 032	Application File Length	9(04)	ZD	04	If instream application parameters are used, code the maximum record length of the Application file. For variable records, add 4 bytes.
033 – 033	Not used				Used for inbound only
034 – 034	Return Code Switch	X(01)	AN	01	If = Y , generate a return code.
035 – 035	Not used				Used for inbound only

Position	Field Content	COBOL Picture	Format	Length	Description
036 – 036	Databank Configuration Switch	X(01)	AN	01	0 – No Databank 1 – Full Databank 2 – Directory Only Databank
037 – 037	Databank Processing Level Switch	X(01)	AN	01	0 – No Databank 1 – Full Databank 2 – Directory Only Databank. 3 – Partner Databank Level
038 – 038	Databank Reprocess Switch	X(01)	AN	01	N – No reprocessing Y – Reprocess data from application Databank.
039 – 039	Partner Read Switch	X(01)	AN	01	0 – Read partner profile first, then check cross-reference 1 – Read cross-reference first, then get partner 2 – Read partner profile first, but pass the EDI IDs to the Outbound editor 3 – Read cross-reference first, but pass the EDI IDs to the to the Outbound editor
040 – 040	Not used	X(01)	AN	01	Not used.
041 – 041	Not used				Internal use only
042 – 042	Partner Print Switch	X(01)	AN	01	0 – Do not print user/partner information when partner is loaded 1 – Print partner information when partner is loaded.
043 – 043	Filler	X(01)	AN	01	Used for inbound only
044 – 044	Document Tracking Switch	X(01)	AN	01	1 – Print an entry on the Audit Trail for each document in error in the run. 2 – Print an entry on the Audit Trail for each document processed in the run.
045 – 045	Support Quote Switch	X(01)	AN	01	Y – Execute additional program logic to allow a single quote in reserved word constants and literal constants.
046 – 046	Standard Type	X(01)	AN	01	Used for Gentran:Structure only. F – Fixed-format standard. V or blank – Variable-format standard (default).
047 – 051	Maximum Length	X(05)	AN	05	Used for Gentran:Structure only. The maximum length of a segment in the defined standard.

Position	Field Content	COBOL Picture	Format	Length	Description
052 – 052	Not used				Used for inbound only
053 – 053	Initialize Numerics	X(01)	AN	01	Used for Gentran:Structure only. Y – Allows non-packed dates and numeric data with types N0-N9 and S0-S9 to be set to 0 if no valid value is mapped to the element.
054 – 054	Map Blank Subfield	X(01)	AN	01	Y – Subfields with spaces as values hold their places in the element. N or blank – (default) Spaces are compressed.
055 – 055	User Exit Version	X(01)	AN	01	1 or blank – Use version 1 of the User Exit Call Block 2 – Use version 2 of the User Exit Call Block
056 – 062	Outbound Envelope User Exit	X(07)	AN	07	The name of a user-written program to execute before writing the outbound envelopes.
063 – 063	Not used				
064 – 064	Blank Partner Error Switch	X(01)	AN	01	Used with application partner enveloping. Y or 1 – Issue an error message and suspend the application data when the application has a blank Partner ID. blank – (default value) If the application has a blank Partner ID, the partner is processed using the previous Partner ID.
065 – 076	Default Outbound Version	X(12)	AN	12	Default outbound version used for each application document to resolve functional groups and transactions with the partner profile.
077 – 079	Filler	X(02)	AN	02	Not used.
080 – 080	Application Reference Load	X (01)	AN	01	1 – Use new logic to load the Application Reference field on STX. 0 or blank – Use old logic to load the Application Reference field on STX.

Note: Determine databanking performance by using the combination of the Databank Configuration switch and Databank Processing Level switch.

Mapping Parameter Record Layout #2

The following table describes Mapping Parameter Record Layout #2.

Position	Field Content	COBOL Picture	Format	Length	Description
001 – 035	Default Partner ID (limited to 15 characters in the Relationship mode)	X(35)	AN	35	Partner ID used in processing all outbound data in this run. Application partner reference is ignored.
036 – 039	Default Partner ID Qualifier (not used in the Relationship mode)	X(04)	AN	04	Partner ID/Qualifier used in processing all outbound data in this run. Application partner reference is ignored.
040 – 074	Default User ID (limited to 15 characters in the Relationship mode)	X(35)	AN	35	User ID used in processing all outbound data in this run. Application User reference is ignored.
075 – 078	Default User ID Qualifier (not used in the Relationship mode)	X(04)	AN	04	User ID/Qualifier used in processing all outbound data in this run. Application User reference is ignored.
079 – 079	CNTL Record Pass Thru Switch	X(01)	AN	01	Y – Instructs the Mapper that the application contains CNTL records at the interchange, group, and transaction level. I – Instructs the Mapper that the application contains CNTL records at the interchange level.
080 – 080	Envelope Generation Switch	X(01)	AN	01	Y – Generate CNTL records N or blank – Generate envelopes

Mapping Parameter Record Layout #3

The following table describes Mapping Parameter Record Layout #3.

Position	Field Content	COBOL Picture	Format	Length	Description
001 – 003	Multiple Envelope ID	X(03)	AN	3	Interchange Envelope ID used in key of control, group, and transaction records on the partner profile. Note: GEN is the only valid value for Gentran: Structure.
004 – 015	Default Interchange Version	X(12)	AN	12	Default interchange version used for each application document to resolve the control partner profile. Note: This is not supported for Gentran: Structure.
016 – 080	Filler	X(65)	AN	65	Not used.

Mapping Parameter Record Layout #4

The following table describes Mapping Parameter Record Layout #4.

Position	Field Content	COBOL Picture	Format	Length	Description
001 – 001	Filler	X(01)	AN	1	Not used.
002 – 002	Spaces in UNB:07	X(01)	AN	12	Y – Always fill application reference (UNB:07) with spaces.
003 – 003	Structure Databank Level	X(01)	AN	1	0 – No databanking 1 – Full databanking 2 – Directory databanking only
004 – 004	Interchange Version Off	X(01)	AN	1	Y – Do not use interchange version for this run.
005 – 005	Group Version Off	X(01)	AN	1	Y – Do not use group version for this run.
006 – 006	Transaction Version Off	X(01)	AN	1	Y – Do not use transaction version for this run.
007 – 007	Multiple Envelope ID Off	X(01)	AN	1	Y – Do not use multiple envelope ID for this run.
008 – 008	Always Generate Group Envelope	X(01)	AN	1	Y – Always generate group envelope each time a transaction envelope is generated.

NCPDP Inbound Pre-Processing Program

NCPDP51I

Purpose

The NCPDP Inbound Pre-Processing program reformats inbound NCPDP data into a fixed-format structure that can be processed by the Gentran:Structure Pre-Processor program (EBDI083). This program is the first step in the processing flow for NCPDP data.

For more information about processing NCPDP data through Gentran:Structure, see Appendix B of this guide.

Inbound Pre-Processing Program Flow

Figure 4.6 illustrates the Inbound Pre-Processing program process.




Figure 4.6 NCPDP51I Program Flow

Files Used

Input

The following files are input.

Filename	Description
EDICFG	System Configuration file
ERRCTL	Error Message and Control file Contains the message text for error report processing.
SYS003	Inbound NCPDP Data file This file contains the user's EDI data. It can be fixed-blocked or variable-blocked and can have a logical record length up to 32760 bytes.
SYS030	Parameters file This file contains the parameters that are used for processing the data through the program.

Output

The following files are output.

Filename	Description
SYS004	Reformatted NCPDP Data file
SYS005	Error report
SYS006	Summary report
SYS099	Suspense file This file contains data that could not be processed due to an invalid NCPDP Version/Release being found on the header record.

Parameter Layout

Record Format Parameter – Required

The following table describes the Record Format parameter layout.

Position	Field Content	COBOL Picture	Format	Length	Description
01 – 14	RECORD FORMAT	X(14)	AN	14	Input record format Valid value is: RECORD FORMAT
15 – 22	Record Format Value	X(08)	AN	08	Record format Valid values are: FIXED VARIABLE

Record Length Parameter – Required

The following table describes the Record Length parameter layout.

Position	Field Content	COBOL Picture	Format	Length	Description
01 – 14	RECORD LENGTH	X(14)	AN	14	Input record length Valid value is: RECORD LENGTH
15 – 19	Record Length Value	X(05)	AN	05	Record length value. Valid values are: 00001-32760.

NCPDP Outbound Post-Processing Program

NCPDP510

Purpose

The NCPDP Outbound Post-Processing program reformats and compresses outbound NCPDP data from the Gentran-specific format into true NCPDP format. This program is the last step in the outbound processing flow for NCPDP data.

For more information about processing NCPDP data through Gentran:Structure, see Appendix B in this guide.

NCPDP Outbound Post-Processing Program Flow

Figure 4.7 illustrates the Outbound Post-Processing program process.




Figure 4.7 NCPDP510 Program Flow

Files Used

Input

The following files are input.

Filename	Description
EDICFG	System Configuration file
ERRCTL	Error Message and Control file Contains the message text for error report processing.
SYS003	Outbound NCPDP Data file This file contains the NCPDP data in the Gentran-specific NCPDP format as created by the Outbound Mapper (EBDI042).
SYS030	Parameters file This file contains the parameters that are used for processing the data through the program.

Output

The following files are output.

Filename	Description
SYS004	Compressed and Reformatted NCPDP data This file contains NCPDP data in true NCPDP format.
SYS005	Error report
SYS006	Summary report

Input/Output

The following files is used as input/output.

Filename	Description
NCPWRK	Work file Temporary work file used in processing.

Parameter Layout

Record Format Parameter – Required

The following table describes the Record Format parameter layout.

Position	Field Content	COBOL Picture	Format	Length	Description
01 – 14	RECORD FORMAT	X(14)	AN	14	Input record format Valid value is: RECORD FORMAT
15 – 22	Record Format Value	X(08)	AN	08	Record format Valid values are: FIXED VARIABLE

Record Length Parameter – Required

The following table describes the Record Length parameter layout.

Position	Field Content	COBOL Picture	Format	Length	Description
01 – 14	RECORD LENGTH	X(14)	AN	14	Input record length Valid value is: RECORD LENGTH
15 – 19	Record Length Value	X(05)	AN	05	Record length value. Valid values are: 00001- 32760.

Compression Parameter – Required

The following table describes the Record Length parameter layout.

Position	Field Content	COBOL Picture	Format	Length	Description
01 – 09	COMPRESS	X(09)	AN	09	Output compression level. Valid value is: COMPRESS
10 – 22	Compression level value	X(12)	AN	12	Indicates level of compression for output file. Valid values are: FULL – compression includes batch envelopes TRANSMISSION – compression does not include batch envelopes.

Structure Application Databank Inquiry Report Program

EDID553

Purpose

The Structure Application Databank Inquiry Report program is generated when the batch program EDID553 is executed. The report provides detailed information on Gentran:Structure data from the Inbound and Outbound Application databanks. The Structure Application Databank Inquiry Report program runs as a batch job step.

The report contains a detail-level inquiry, summary-level inquiry, and processing log, based on the report-type control card value specified. The wide range of selection criteria provides you with flexible control to produce reports that meet your specific requirements.

The Structure Application Databank Inquiry Report program also produces a Statistics file, if requested. The Statistics file is a data file containing statistical information on the inbound and outbound Gentran:Structure application data.

Files Used

Input

Input varies based on the databank control card criteria used. The following is a list of possible input files.

Filename	Description
EDIHAA	Inbound Application Databank Directory
EDIOAA	Outbound Application Databank Directory
EDICNTL	Control Card file
ERRCTL	Error Message and Control file
EDICFG	System Configuration file

Output

The following files may be updated when the reported control card selection criteria is used with a value of NO or All.

Filename	Description
EDIHAA	Inbound Application Databank Directory
EDIOAA	Outbound Application Databank Directory

Reports

Program EDID553 produces the following reports:

- EDIRPT – Structure Application Databank Inquiry report
- EDILOG – Processing Log
- EDISUM – Processing Summary report
- EDISTX – Structure Statistics file

Control Card Options

The following Databank Inquiry operations and selection criteria are specified by control cards:

Operations

SELECT (Default Operation)

Selection criteria

Defaults

AGE-DAYS	ALL
AGE-HOURS	ALL
AGENCY	ALL
DATABANK	ALL
DATABANK-RUN-NUMBER	ALL
DIVISION	ALL
FROM-DATE	01/01/1900
FROM-TIME	00:00
MAP-VALIDATION-STATUS	ALL
NETWORK	ALL
PARTNER	ALL
PARTNER-QUALIFIER	ALL
PRE-PROCESSING STATUS	ALL
REFERENCE-TAG	ALL
REPORTED	ALL
REPORT-TYPE	SUMMARY
STATISTICS-FILE	NO
STRUCTURE-VERSION-ID	ALL
TEST-PRODUCTION-STATUS	ALL
TO-DATE	12/31/2099
TO-TIME	23:59
TRADING-PROFILE-MODE	PARTNER-QUALIFIER
TRANSACTION-SET-ID	ALL
USER	ALL
USER-REFERENCE	ALL

Note: Date and time selection criteria are evaluated independently. Time-based selection criteria are used to limit the data selected using the specified time range for each day within the date range. For example, selecting data with time criteria of 9 a.m. to 5 p.m. equates to data processed between 9 and 5 on any day. Adding a date range further reduces the data selected to that which was processed between 9 and 5 on any day in the date range.

Valid Criteria Values

Age-Days

The age of the data in number of days. Enter a three-digit value to request documents that are the specified age or newer. Specify **000** to get only documents added on the current date. To request documents older than a specified age, enter a greater than sign and the age-days (for example, enter **>002** to select documents more than 2 days old). Valid values are:

ALL
nnn (where *nnn* is 000-999)
>nnn (where *nnn* is 000-999)

Age-Hours

The age of the data in hours. Enter a three-digit value to request documents that are a specified age or newer. To request documents older than the specified age, enter a greater than sign and the age-hours (for example, enter **>005** to select documents more than five hours old). Valid values are:

ALL
nnn (where *nnn* is 000-999)
>nnn (where *nnn* is 000-999)

Agency

The 2-character agency code associated with the Gentran:Structure version ID. You can specify either an agency code of **ALL** for all agency codes. Valid values are:

ALL
aaaaaaaaaaaa

Databank

Identifies which application databanks should be used for the inquiry. Valid values are:

ALL
INBOUND-APPLICATION
OUTBOUND-APPLICATION

Databank-Run-Number

An 8-digit number that identifies the run that last processed the document. Valid values are:

ALL
nnnnnnnn (must include leading zeros)

Division

Specifies the 3-character division code. You can specify either a division code or **ALL** for all division codes. Valid values are:

ALL
aaa (division code)

From-Date

For outbound Gentran:Structure data, this value specifies the last date the Outbound Mapper processed the data. For inbound Gentran:Structure data, this value specifies the date when the Gentran:Structure Pre-processor program processed the data. Valid format is **MM/DD/YYYY**.

From-Time

For outbound Gentran:Structure data, this value specifies the last time the Outbound Mapper processed the data. For inbound Gentran:Structure data, this value specifies the time when the Gentran:Structure Pre-processor program processed the data. Valid format is **HH:MM**.

Map-Validation-Status

Specifies the map validation status as assigned by the Outbound Mapper. Valid values are:

ALL
<08, <12, 00, 04, 08, 12, >00, >04, >08 (Outbound Application only)

Network

Specifies the 15-character network ID. This selection criteria is valid for outbound application data only. Valid values are:

ALL
aaaaaaaaaaaaaaaa (Outbound Application only)

Partner

Trading partner ID. Valid values are:

ALL
a 15- or 35- character partner ID

Note: The length of the field depends on the trading mode. For Relationship mode, the length is 15 characters. For Partner/Qualifier mode, the length is 35 characters.

Partner-Qualifier

The 4-character qualifier for the Partner ID. You can specify a partner qualifier or **ALL** for all partner qualifiers. This is valid only if the trading profile mode is Partner/Qualifier. Valid values are:

ALL
aaaa

Pre-Processing-Status

Specifies the pre-processing status as assigned by the Gentran:Structure Pre-processing program. Valid values are:

ALL
<08, <12, 00, 04, 08, 12, >00, >04, >08 (Outbound Application only)

Reference-Tag

The 10-character Reference Tag assigned to the document by Gentran:Basic. Valid values are:

ALL
aanntnnnnn This is a reference tag where **aa** = **IS** or **OS**. Leading zeroes must be specified for the 8-digit number.

Reported

This selection criteria is used to limit selection based on what has been reported previously by an Inquiry report. Valid values are:

ALL Select everything regardless of previous reports.
YES Select only what has been reported previously.
NO Select only what has not been reported previously.

Report-Type

Identifies the level at which the Inquiry should report. Valid values are:

FULL Detailed information for each document that is reports
SUMMARY Summary list of selected documents

Statistics-File

Specifies whether the Gentran:Structure Statistics file is to be created. Valid values are:

YES Create the Statistics file in addition to the inquiry reports.
NO Do not create the Statistics file.
ONLY Create the Statistics file only, and do not print the inquiry reports.

Structure-Version-ID

Specifies the 1- to 12-character version ID. You can specify either a version ID or ALL for all version IDs. Valid values are:

ALL
aaaaaaaaaaaa

Test-Production-Status

Specifies the test/production status as assigned by Gentran:Basic that should be used for selecting documents. Valid values are:

ALL
PRODUCTION
TEST

To-Date

For outbound Gentran:Structure data, this value specifies the last date the Outbound Mapper processed the data. For inbound Gentran:Structure data, this value specifies the date when the Gentran:Structure Pre-processor program processed the data. This control card ends the date range and is used with From-Date. Valid format is **MM/DD/YYYY**.

To-Time

For outbound Gentran:Structure data, this value specifies the last time the Outbound Mapper processed the data. For inbound Gentran:Structure data, this value specifies the time when the Gentran:Structure Pre-processor program processed the data. This control card ends the date range and is used with From-Date. Valid format is **HH:MM**.

Transaction-Set-ID

Specifies the 1- to 6-character transaction set ID. You can specify either a transaction set ID or **ALL** for all transaction sets. This selection criteria is only used for Inbound Application search. Valid values are:

ALL
aaaaaa (Inbound Application only)

User

This selection criteria is only valid if the trading profile mode is Relationship. Specifies a 15-character User ID. Valid values are:

ALL
aaaaaaaaaaaaaaaa

User-Reference

Specifies the 1- to 45-character user reference value. You can specify either a user reference or **ALL** for all user references. Valid values are:

ALL
45-character User Reference field

Sample Reports

This section contains sample reports from the Structure Application Databank Inquiry Report program.

Summary Report

```

PAGE : 00001
VERSION: 6.4

GENTRAN: BASIC
STRUCTURE APPLICATION DATABANK INQUIRY
SUMMARY REPORT

REPORT DATE: 12/01/2005
REPORT TIME: 12:00:00
REPORT ID : EDI156

OPTIONS USED THIS RUN
-----
REQUESTED-OPERATION = SELECT
AGE-DAYS = ALL
AGE-HOURS = ALL
AGENCY = ALL
DATABANK = ALL
DATABANK-RUN-NUMBER = ALL
DIVISION = ALL
FROM-DATE = 01/01/1999
FROM-TIME = 00:00
MAP-VALIDATION-STATUS = ALL
NETWORK = ALL
PARTNER = ALL
PARTNER-QUALIFIER = ALL
PRE-PROCESSING-STATUS = ALL
REALTIME-DATABANKS = NO
REFERENCE-TAG = ALL
REPORTED = ALL
REPORT-TYPE = FULL
STATISTICS-FILE = YES
STRUCTURE-VERSION-ID = ALL
TEST-PRODUCTION-STATUS = ALL
TO-DATE = 12/31/2009
TO-TIME = 23:59
TRADING-PROFILE-MODE = PARTNER-QUALIFIER
TRANSACTION-SET-ID = ALL
USER-REFERENCE = ALL
CONCURRENCY-ENABLED = NO

PROCESSING SUMMARY
-----
INBOUND DOCUMENTS : 28
OUTBOUND DOCUMENTS : 48
INBOUND DOCUMENTS SELECTED : 25
OUTBOUND DOCUMENTS SELECTED : 0
STATISTICS FILE RECORDS WRITTEN : 28
NUMBER OF ERRORS THIS RUN : 0
HIGHEST RETURN CODE THIS RUN : 0
    
```

Figure 4.8 EDID553 Summary Report

Processing Log

```

REPORT DATE: 12/01/2005
REPORT TIME: 12:00:00
REPORT IS  : EDI154

                                GENTRAN: BASIC
                                STRUCTURE APPLICATION DATABANK INQUIRY
                                PROCESSING LOG

                                PAGE  : 0001
                                VERSION: 6.4
                                COMPILE DATE: 12/01/2005

MESSAGES
-----
EDI-042301-I 00 APPLICATION DATABANK INQUIRY PROCESSING BEGINS . . . DATE: 12/01/2005 TIME: 12:00:00
EDI-042302-I 00 APPLICATION DATABANK INQUIRY PROCESSING ENDS. . . . DATE: 12/01/2005 TIME: 12:00:00
    
```

Figure 4.9 EDID553 Processing Log

Detail Inquiry Report

```

REPORT DATE: 12/01/2005
REPORT TIME: 12:00:00
REPORT ID : EDI155

                                GENTRAN:STRUCTURE
STRUCTURE APPLICATION DATABANK INQUIRY
DETAIL INQUIRY REPORT

                                PAGE : 00001
                                VERSION: 6.4

                                INBOUND APPLICATION DATABANK

PARTNER ID....: LAWNVEND
VERSION ID....: JASS
USER REFERENCE: LAWN CARE VENDOR INC.
DATABANK RUN #: 00000901
PRE-PROCESS DT: 12/01/2005 12:00
INTER ENV ID...: PHD
GROUP ENV ID...: GHD
TRANS ENV ID...: THD

QUAL.....: SC
AGENCY.....: SC
REFERENCE TAG...: IS000003032
PRE-PROC STATUS: 00

DIVISION.....: 001
TRANSACTION SET...: 0926
PREVIOUSLY REPORTED: NO
DATABANK.....: GENTRAN
NETWORK.....:
SEG ID LENGTH.....: 03
SEG ID START POS...: 00078
CHARACTER COUNT...: 000006117

PARTNER ID....: LAWNVEND
VERSION ID....: JASS
USER REFERENCE: LAWN CARE VENDOR INC.
DATABANK RUN #: 00000901
PRE-PROCESS DT: 12/01/2005 12:00
INTER ENV ID...: PHD
GROUP ENV ID...: GHD
TRANS ENV ID...: THD

QUAL.....: SC
AGENCY.....: SC
REFERENCE TAG...: IS000003052
PRE-PROC STATUS: 00

DIVISION.....: 001
TRANSACTION SET...: 0926
PREVIOUSLY REPORTED: NO
DATABANK.....: GENTRAN
NETWORK.....:
SEG ID LENGTH.....: 03
SEG ID START POS...: 00078
CHARACTER COUNT...: 000005862
    
```

Figure 4.10 EDID553 Detail Inquiry Report

Summary Inquiry Report

REPORT DATE: 12/01/2005		GENTRAN:STRUCTURE		PAGE : 00001			
REPORT TIME: 12:00:00		STRUCTURE APPLICATION DATABANK INQUIRY		VERSION: 6.4			
REPORT ID : EDI155		SUMMARY INQUIRY REPORT					
OUTBOUND APPLICATION DATABANK							
PARTNER	USER	QUAL REFERENCE	VERSION ID	REFERENCE TAG	DATE	MAPPING TIME	MAP ST
FIX-VENDOR		0000 REF:OA00010030	GENCOD4	OS00010030	12/01/2005	12:00	00
FIX-VENDOR2		0000 REF:OA00010022	GENCOD4	OS00010022	12/01/2005	12:00	00
FIX-VENDOR3		0000 REF:OA00010032	GENCOD4	OS00010034	12/01/2005	12:00	00
FIX-VENDOR4		0000 REF:OA00010023	GENCOD4	OS00010028	12/01/2005	12:00	00

Figure 4.11 EDID553 Summary Inquiry Report

Gentran:Realtime Program Descriptions

Overview

This chapter contains detailed descriptions of Gentran:Realtime files, processing, programs, and reports that are related to Gentran:Structure. Its purpose is to enable you to familiarize yourself with these programs and their functionality. This chapter contains the following topics:

Topic	Page
Inbound Flow	5-3
Introduction	5-3
Illustration	5-3
Inbound Fixed/Variable Split ProgramEDIR094	5-6
Purpose	5-6
Operation	5-6
Inputs	5-6
File Access	5-7
Reports	5-7
Inbound Pre-processing ProgramEDIR083	5-9
Purpose	5-9
Operation	5-9
Inputs	5-10
File Access	5-10
Reports	5-10
Inbound Mapping Program.....EDIR041	5-13
Purpose	5-13
Operation	5-13
Inputs	5-13
Gentran:Structure Subprograms Called	5-13
File Access	5-13
Parameter Descriptions	5-14
Reports	5-15

Inbound NCPDP Pre-processing Program.....EDIRNCPI	5-16
Purpose	5-16
Operation	5-16
Inputs	5-16
File Access	5-16
Reports	5-17
Outbound Flow	5-20
Overview	5-20
Outbound Flow with Fixed-Format Standards	5-21
Outbound Mapping Program.....EDIR042	5-22
Purpose	5-22
Operation	5-22
Inputs	5-22
Gentran:Structure Subprograms Called	5-22
File Access	5-22
Parameter Descriptions	5-23
Reports	5-24
Outbound NCPDP Post-Processing Program.....EDIRNCPO	5-25
Purpose	5-25
Operation	5-25
Inputs	5-25
File Access	5-25
Parameter Descriptions	5-26
Reports	5-27

Inbound Flow

Introduction

This section illustrates and describes the inbound flow through Gentran:Structure for Gentran:Realtime, to provide context for the program descriptions that follow.

Illustration

Figure 5.1 illustrates the inbound flow through Gentran:Structure system components. It shows fixed-format, mixed-format and variable format EDI data. The numbers in the illustration correspond to the steps below the figure that describe the flow.




Figure 5.1 Inbound Flow Through Gentran:Structure System Components

The following table describes the inbound flow through Gentran:Realtime using Gentran:Structure.

Stage		Description		
	Variable Format Data	Mixed-Format Data	Fixed-Format Data	
1	The system sends the data from Communications to the Inbound editor.	The system sends the data from Communications to the Inbound Fixed/Variable Split program to be separated by format type.		The system sends the data from Communications to the Format Specific Compliance Checker, if used, or directly to the Inbound Pre-Processor.
2	If the Inbound Splitter is used, the system passes the data to the Splitter, and then to the Inbound Mapper. If the Splitter is not used, the system passes the data directly to the Inbound Mapper.	The Inbound Fixed/Variable Splitter: <ul style="list-style-type: none"> Sends the variable-format data to the Inbound editor. The data continues on the variable format data path. Sends the fixed-format data to the Compliance Checker, if used, or directly to the Inbound Pre-processor. The data continues on the fixed-format path. 		The system sends the data from the Pre-processor to the Inbound Mapper.
3	The Inbound Mapper sends the file to the Application or to the Inbound Application databank (if used; See step 3A).			The Inbound Mapper sends the file to the Application or to the Inbound Application databank (if used; see Stage 3A).
3A	(Optional) The Inbound Application Databank Extract program sends the data to the Application.			(Optional) The Inbound Application Databank Extract program sends the data to the Application.

Inbound Fixed/Variable Split Program

EDIR094

Purpose

The Inbound Fixed/Variable Split program (EDIR094), or “Splitter,” is optional. If the incoming EDI data file contains data for different fixed-format standards and/or is mixed with variable-format standards, then this program should be executed as the first step of the inbound process.

This program reads the EDI data file and splits it into the following categories:

- Fixed-format COMPORD data
- Fixed-format GM (CISCO) data
- Fixed-format GENCOD data
- Other fixed-format data
- Variable-format EDI data

Operation

The Splitter reads input data from a temporary storage queue (TSQ) identified by the user. The data is written to one of five output TSQs based on data type (e.g., COMPORD, GENCOD).

Once all input data is read, the program processes each of the five output TSQs. The destination parameters entered on the Fixed/Variable Splitter Path Maintenance screen (EDIM841) determine the processing performed for each TSQ.

When the destination is a queue file, the Splitter passes the TSQname to the Online Output Gateway (EDIEOOG) via a 'LINK'. The Output Gateway writes the TSQ data to the queue file specified by destination.

Note: The queue files and immediate options entered for Destination should be set up to run either the Inbound Editor (EDIR001) for variable-format data, or the Inbound Pre-Processor (EDIR083) for fixed-format data.

Inputs

The Splitter reads 80-byte records from an input TSQ. The input TSQ may be created in one of the following ways:

- By a CICS user program that passes the TSQname to the Splitter via the Inbound Communications Gateway (EDIR103).
- By a CICS user program that writes data to a queue file. The queue file trigger levels initiate execution of the Online Queue Read (EDIEOQR) program. The EDIEOQR program writes a TSQ and passes the TSQname to the Splitter via the Inbound Communications Gateway (EDIR103).

File Access

File Description	DDname	File Access
Gentran System Configuration file	EDICFG	Read
Gentran Error Message and Control file	ERRCTL	Read
Gentran:Realtime Online Control file	EDIOCF	Read
Gentran:Realtime Report Control file	EDIRRC	Write
Gentran:Realtime Report Detail file	EDIRRD	Write

Reports

The Inbound Fixed/Variable Split program produces a summary report and an error report. You can view these reports using the Gentran:Realtime Online Reporting function. The following diagrams illustrate the reports.

Note: The Process Name for this report is SPLITR.

Report Selection

```

Select Print Log Exception Activity
EDIM310 8.3 _____ REPORT SELECTION          XXX   12/01/2005
                                                    12:00:00

Path ID.....: ____ Process.....: _____
Line Incrmt..: ____ Cond Code...: _ (Y)
From Date....: _____ To Date....: _____ (MM/DD/YYYY)
From Time....: _____ To Time....: _____ (HH:MM:SS)
Task #.....: _____ Max Srch...: 0450
Print Job Name: _____

  Generation      Path  Process   Con  Task      Control
  A  Date         Time  ID      Name  St Cd   #   Description  Address
  -  12/01/2005 12:00:00 000  OA-SUM  00  10330  OA DBK MAINT  361
  -  12/01/2005 12:00:00 000  OA-AUD  00  10330  OA DBK MAINT  362
  -  12/01/2005 12:00:00 000  AK-SUM  00  10339  EDID515-EDISUM  363
  -  12/01/2005 12:00:00 000  AK-REC  00  10339  EDID515-EDIRECN  364
  -  12/01/2005 12:00:00 000  AK-LOG  00  10339  EDID515-EDILOG  365
  -  12/01/2005 12:00:00 203  EDI01E  F 16  10595  ANSI I/B IVP  366
  -  12/01/2005 12:00:00 203  EDI01S  F 16  10595  ANSI I/B IVP  367
  -  12/01/2005 12:00:00 072  SPLITR  00  10616  FIX/VAR SPLIT  368
  -  12/01/2005 12:00:00 070  CMPORD  F 16  10617  COMPORD TEST  369

Enter PF1=Help          PF3=Exit          PF5=Action
      PF7=Bwd  PF8=Fwd
    
```

Inbound Fixed/Variable Splitter Report Display Screens

```

EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY   XXX   12/01/2005
                                                    12:00:00

Task ID: 0010616 Process Name: SPLITR
Search.: _____ Line Increment: ____ Job Name: _____

  EDIR094   RUN 12/01/2005   TIME 12:00   SUMMARY REPORT - FIXED/VARIA+
PROGRAM EDIR094   COMPILED ON 12/01/2005 AT 12.00.00   VERSION 6.4

DATA FORMAT                                     DESTINATION
COMPORD FIXED FORMAT----- 370
VARIABLE FORMAT EDI----- 113
GENCOD FIXED FORMAT----- 114
GM FIXED FORMAT----- 115
OTHER FIXED FORMAT----- 116

RTE PROCESSES STARTED
COMPORD IMMEDIATE OPTION STARTED
EDIDAT QUEUE FILE WRITTEN

Enter PF1=Help PF2=Sum   PF3=Exit           PF5=Print   PF6=NxtEr
      PF7=Bwd  PF8=Fwd           PF10=Left PF11=Rgt PF12=Top   PF13=Bot
    
```

```

EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY   XXX   12/01/2005
                                                    12:00:00

Task ID: 0010616 Process Name: SPLITR
Search.: _____ Line Increment: ____ Job Name: _____

  EDIDAT QUEUE FILE WRITTEN
  GENCOD QUEUE FILE WRITTEN
  OTHFIX QUEUE FILE WRITTEN
  PROCESSING BEGAN ON                               12/01/2005 AT 12:00 AM.
  INPUT RECORDS READ----- 223
  COMPORD RECORDS WRITTEN----- 46
  EDI VARIABLE RECORDS WRITTEN----- 4
  GENCOD RECORDS WRITTEN----- 125
  GM DATA RECORDS WRITTEN----- 0
  OTHER FIXED DATA RECORDS WRITTEN----- 48
  PROCESSING ENDED NORMALLY ON                       12/01/2005 AT 12:00 AM.
  PROGRAM RETURN CODE----- 0

END OF ONLINE REPORTS
Enter PF1=Help PF2=Sum   PF3=Exit           PF5=Print   PF6=NxtEr
      PF7=Bwd  PF8=Fwd           PF10=Left PF11=Rgt PF12=Top   PF13=Bot
    
```


Inbound Pre-processing Program

EDIR083

Purpose

The Inbound Pre-Processing Program (EDIR083) supports mapping from fixed-format standards by duplicating some of the critical functionality that is present in the Inbound Editor program (EDIR001). This program replaces the Inbound Editor Program in the inbound processing flow for fixed-format standards.

The Inbound Pre-Processing program processes as input a fixed-format standard that the user has received from a trading partner or internal division. The user is responsible for determining that all data presented to this program is a fixed-format standard defined to the Gentran:Basic/Realtime online standards files. The Inbound Fixed/Variable Split program (EDIR094) can be used to segregate some types of this data.

The Pre-Processing program supports databanking of the fixed-format data. The system stores the records on the Inbound Application Databank. You can view them using screens accessible via the Databank menu.

Operation

The following table describes Inbound Pre-Processing program operation.

Stage	Description
1	The Inbound Pre-Processor initiates when a user selects the program as an option on the Additional Shell Steps Maintenance screen (EDIM84F) by typing a value of 1 in the Pre-processor field.
2	The Pre-Processor reads input data from a TSQ identified by the user and writes the data to an output TSQ.
3	The system passes the TSQname to the Inbound Mapping program (EDIR041).
4	As the input data is written to the output TSQ, the Pre-Processor adds ###MAP, ###MP2, ###MP3, ###MP4, ###MP5, and ###MP6 records. See the program description for program EBDI083 in Chapter 4, "Program Descriptions," of this guide for an explanation of the format and placement of these special records.
5	The program processes according to the parameter values entered on the Fixed Format Pre-Processor Path Maintenance screen (EDIM840). See the program description for program EDIR840 in Chapter 3, "Screens," of this guide for an explanation of the parameters.
6	If any input data cannot be processed, the program writes all input data to a Suspended Data TSQ and stores it on the Exception Handler subsystem for re-processing.

Inputs

The Pre-Processor reads records from an input TSQ. The input TSQ may be created in either of the following ways:

- By a CICS user program that passes the TSQname to the Pre-Processor by means of the Inbound Communications Gateway (EDIR103).
- By a CICS user program that writes data to a queue file. The queue file trigger levels initiate execution of the Online Queue Read (EDIEOQR or EDIROQR) program. The Online Queue Read writes a TSQ and passes the TSQname to the Pre-Processor by means of the Inbound Communications Gateway (EDIR103).

File Access

File Description	DDname	File Access
Gentran:Structure User Envelope Definition file	EDIUENV	Read
Gentran Partner File	EDIPART	Read
Gentran Partner Cross-Reference file	EDIPREF	Read
Gentran Partner Relationship file	EDIPREL	Read
Gentran System Configuration file	EDICFG	Read
Gentran Error Message and Control file	ERRCTL	Read
Gentran Standard Version file	EDISVER	Read
Gentran:Realtime Online Control file	EDIOCF	Read
Gentran:Realtime Report Control file	EDIRRC	Write
Gentran:Realtime Report Detail file	EDIRRD	Write

Reports

The Inbound Pre-Processor program produces a summary report and an error report. You can view these reports using the Gentran:Realtime Online Reporting function.

Note: The Process Name for this report is PREPRO

Report Selection

```

Select Print Log Exception Activity
EDIM310 8.3 _____ REPORT SELECTION XXX 12/01/2005
                                           12:00:00

Path ID.....: _____ Process....: _____
Line Incrmt...: _____ Cond Code...: _ (Y)
From Date.....: _____ To Date....: _____ (MM/DD/YYYY)
From Time.....: _____ To Time....: _____ (HH:MM:SS)
Task #.....: _____ Max Srch...: 0450
Print Job Name: _____

  Generation      Path Process   Con Task      Control
  A  Date         Time   ID   Name   St Cd   #   Description Address
  _  12/01/2005 12:00:00 000 AK-SUM  00 00 10339 EDID515-EDISUM 363
  _  12/01/2005 12:00:00 000 AK-REC  00 00 10339 EDID515-EDIRECN 364
  _  12/01/2005 12:00:00 000 AK-LOG  00 00 10339 EDID515-EDILOG 365
  _  12/01/2005 12:00:00 203 EDI01E  F 16 10595 ANSI I/B IVP 366
  _  12/01/2005 12:00:00 203 EDI01S  F 16 10595 ANSI I/B IVP 367
  _  12/01/2005 12:00:00 072 SPLITR  00 00 10616 FIX/VAR SPLIT 368
  _  12/01/2005 12:00:00 070 CMPORD  F 16 10617 COMPORD TEST 369
  _  12/01/2005 12:00:00 067 NCPDPI  00 00 10675 INBND NCPDP 370
  _  12/01/2005 12:00:00 067 PREPRO  00 00 10675 INBND NCPDP 371

Enter PF1=Help          PF3=Exit          PF5=Action
      PF7=Bwd   PF8=Fwd
    
```

Inbound Pre-Processor Report Display Screens

Part 1

```

EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY XXX 12/01/2005
                                           12:00:00

Task ID: 0010675 Process Name: PREPRO
Search.: _____ Line Increment: _____ Job Name: _____

EDIR083 RUN 12/01/2005 TIME 12:00 GENTRAN:STRUCTURE DATA PRE-PRO+
PROGRAM EDIR083 COMPILED ON 12/01/05 AT 12.00.00 VERSION 6.4
ERROR **RECORD**
NUMBR NBR ID INFORMATION ERROR MESSAGE
NO ERRORS OCCURRED DURING PROCESSING
PROCESSING ENDED NORMALLY - PROCESSING COUNTS BELOW
                                INPUT RECORDS READ----- 64
                                INPUT RECORDS SUSPENDED----- 0
                                OUTPUT RECORDS WRITTEN----- 109
                                PROGRAM RETURN CODE----- 0

EDIR083 RUN 12/01/2005 TIME 12:00 PROCESSING OPTIONS - GENTRAN:S+
INPUT FILE ORGANIZATION IS-----VARIABLE
INPUT FILE RECORD LENGTH IS-----05100

Enter PF1=Help PF2=Sum PF3=Exit PF5=Print PF6=NxtEr
      PF7=Bwd PF8=Fwd PF10=Left PF11=Rgt PF12=Top PF13=Bot
    
```

Part 2

```
EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY   XXX   12/01/2005
                                                    12:00:00
```

Task ID: 0010675 Process Name: PREPRO

Search.: _____ Line Increment: _____ Job Name: _____

```
INPUT FILE RECORD LENGTH IS-----05100
TRADING PROFILE MODE IS-----PARTNER QUALIFIER
DATABANKING LEVEL IS-----DATABANK NO
DATA ENVELOPE SWITCH-----ON
ENVELOPE LEVEL IS-----INTERCHANGE
DATA SEPARATION IS-----NOT DEFINED
```

```
EDIR083   RUN 12/01/2005   TIME 12:00   SUMMARY REPORT - GENTRAN:STRUC+
PROCESSING BEGAN ON 12/01/2005 AT 12:00 AM.
```

```
INPUT RECORDS READ-----64
INTERCHANGE ENVELOPES READ-----4
GROUP ENVELOPES READ-----8
TRANSACTION ENVELOPES READ-----8
MAP RECORDS WRITTEN-----24
OUTPUT RECORDS WRITTEN-----109
```

```
Enter PF1=Help PF2=Sum   PF3=Exit           PF5=Print   PF6=NxtEr
      PF7=Bwd  PF8=Fwd           PF10=Left  PF11=Rgt  PF12=Top  PF13=Bot
```

Part 3

```
EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY   XXX   12/01/2005
                                                    12:00:00
```

Task ID: 0010675 Process Name: PREPRO

Search.: _____ Line Increment: _____ Job Name: _____

```
OUTPUT RECORDS WRITTEN-----109
DATABANK RUN NUMBER-----000000000
DIRECTORY RECORDS WRITTEN-----0
MESSAGE STORE RECORDS WRITTEN-----0
RECORDS SUSPENDED-----0
```

```
PROCESSING ENDED ON 12/01/2005 AT 12:00 AM.
```

END OF ONLINE REPORTS

```
Enter PF1=Help PF2=Sum   PF3=Exit           PF5=Print   PF6=NxtEr
      PF7=Bwd  PF8=Fwd           PF10=Left  PF11=Rgt  PF12=Top  PF13=Bot
```

Inbound Mapping Program

EDIR041

Purpose

The Inbound Mapping program (EDIR041), or “Mapper,” optionally processes fixed-format standard input in addition to variable-format standard input. A single execution of the Mapper processes either fixed-format input that was generated by the Inbound Pre-Processing program (EDIR083) or variable-format data that was generated by the Inbound Editor program (EDIR001). A parameter instructs the Mapper as to the format of the data.

Data can be directed to the Application Data File and/or the Inbound Application databank regardless of input format.

Note: This section contains only information pertaining to the use of this program for Gentran:Structure for Gentran:Realtime. For complete information about this program see the *Gentran:Basic for zSeries Release 6.4 Technical Reference Guide* and the *Gentran:Realtime for zSeries Release 6.4 Technical Reference Guide*.

Operation

The Inbound Pre-Processor program reads input data from a TSQ identified by the user. The program writes data to an output TSQ. The system passes the TSQname to the Inbound Mapping program (EDIR041).

The Gentran:Realtime Shell program initiates the Mapper after the Inbound Pre-Processor program has successfully completed. When finished, this program builds a TSQ that contains the application data.

Inputs

The Inbound Mapper reads EDI data from a TSQ.

Gentran:Structure Subprograms Called

EDID652 Inbound Application Databank Interface subroutine

File Access

No special file accesses for Gentran:Structure for Gentran:Realtime.

Parameter Descriptions

Two parameters for the Inbound Mapper, Standard Type and DBK level, are specific to Gentran:Structure for Gentran:Realtime. The Inbound Mapper-3 Path Maintenance screen (EDIM837) enables you to enter values for these parameters.

Field Descriptions

Standard Type

The Standard Type parameter indicates whether the Inbound Mapper will process fixed-format or variable-format input data. A value of F indicates to the Inbound Mapper that the input data is fixed-format.

DBK Level

The DBK level parameter indicates whether the Inbound Mapper will use Databanking for the fixed-format input data. Due to the structure of the fixed-format data, the Inbound Application databank stores the inbound fixed-format EDI data. Valid values are:

- | | | |
|----------|---|---|
| 0 | = | No databanking is requested. |
| 1 | = | Use full databanking (both directory and message store levels). |
| 2 | = | Use directory-level databanking. |

Screen Example

The following diagram illustrates the Inbound Mapper-3 Path Maintenance screen with the Standard Type and DBK Level fields highlighted.

```

EDIM837 _____ INBOUND MAPPER-3 PATH MAINTENANCE      XXX 12/01/2005
                                                    12:00:00

Path ID.....: 302M  STRUCTURE INBOUND TEST

Structure:
  Standard Type.....: F  (F=Fixed/V=Variable)
  DBK Level.....: 1  (0=No/1=Full/2=Dir)

Viewpoint:
  User Tracking.....: N  (Y/N)
  Exception Tracking.: N  (Y/N)
  Tracking Management: N  (Y/N)

                                                    Last Update Date: 12/01/05
                                                    Time: 12:00:00
                                                    User: XXX

Enter PF1=Help          PF3=Exit PF4=Dir          PF6=Shell
    PF7=Map2 PF8=Map1          PF10=Updt
  
```

Reports

Standard Mapper reports are generated during fixed-format processing.

See the *Gentran:Realtime for zSeries Release 6.4 Technical Reference Guide* for more information.

Inbound NCPDP Pre-processing Program

EDIRNCPI

Purpose

The NCPDP Inbound Pre-Processing program (EDIRNCPI) reformats inbound NCPDP data into a fixed format structure that the Gentran:Structure Pre-Processor program (EDIR083) can process. This program is the first step in the processing flow for NCPDP data.

See Appendix B, “Processing NCPDP Data,” for more information about processing NCPDP data through Gentran:Structure.

Operation

The Inbound NCPDP Pre-Processor reads data from a TSQ identified by the user. The program writes output to a TSQ that is passed to the Pre-Processor program (EDIR083).

The system writes unrecognized data to a suspended TSQ and stores it on the Exception Handler subsystem for re-processing.

The Inbound NCPDP Pre-Processor reformats the inbound NCPDP transactions into a format that can be processed by the Inbound Mapper program.

Note: This program is based on the NCPDP Telecommunications Standard Version 5 Release 1.

Inputs

The NCPDP Pre-Processor reads records from an input TSQ. The input TSQ can be created in the following ways:

- By a CICS user program that passes the TSQname to the NCPDP Pre-Processor via the Inbound Communications Gateway (EDIR103).
- By a CICS user program that writes data to a queue file. The queue file trigger levels initiate execution of the Online Queue Read (EDIEOQR) program. The EDIEOQR program writes a TSQ and passes the TSQname to the NCPDP Pre-Processor via the Inbound Communications Gateway (EDIR103).

File Access

File Description	DDname	File Access
Gentran System Configuration file	EDICFG	Read
Gentran Error Message and Control file	ERRCTL	Read
Gentran:Realtime Report Control file	EDIRRC	Write
Gentran:Realtime Report Detail file	EDIRRD	Write

Reports

The Inbound NCPDP Pre-Processor program produces a summary report and an error report. You can view these reports using the Gentran:Realtime Online Reporting function.

Note: The Process Name for this report is NCPDPI.

Report Selection Screen

```

Select Print Log Exception Activity
EDIM310 8.3_____ REPORT SELECTION          XXX  12/01/2005
                                                12:00:00

Path ID.....: ____ Process....: _____
Line Incrmt..: ____ Cond Code..: _ (Y)
From Date....: _____ To Date....: _____ (MM/DD/YYYY)
From Time....: _____ To Time....: _____ (HH:MM:SS)
Task #.....: _____ Max Srch...: 0450
Print Job Name: _____

  Generation      Path  Process   Con  Task          Control
A   Date         Time   ID   Name   St Cd   #   Description   Address
- 12/01/2005 12:00:00 000 AK-SUM  00 10339 EDID515-EDISUM 363
- 12/01/2005 12:00:00 000 AK-REC  00 10339 EDID515-EDIRECN 364
- 12/01/2005 12:00:00 000 AK-LOG  00 10339 EDID515-EDILOG 365
- 12/01/2005 12:00:00 203 EDI01E  F 16 10595 ANSI I/B IVP 366
- 12/01/2005 12:00:00 203 EDI01S  F 16 10595 ANSI I/B IVP 367
- 12/01/2005 12:00:00 072 SPLITR  00 10616 FIX/VAR SPLIT 368
- 12/01/2005 12:00:00 070 COMPORD F 16 10617 COMPORD TEST 369
- 12/01/2005 12:00:00 067 NCPDPI  00 10675 INBND NCPDP 370
- 12/01/2005 12:00:00 067 PREPRO  00 10675 INBND NCPDP 371

Enter PF1=Help          PF3=Exit          PF5=Action
      PF7=Bwd  PF8=Fwd

```

Gentran:Realtime *NCPDP Pre-Processor Report Display*

Part 1

```

EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY   XXX   12/01/2005
                                                    12:00:00

Task ID: 0010675 Process Name: NCPDPI
Search.: _____ Line Increment: ____ Job Name: _____

EDIRNCPI   RUN 12/01/2005   TIME 12:00   PROCESSING OPTIONS - GENTRAN+
PROGRAM EDIRNCPI COMPILED ON 12/01/2005 AT 12.00.00   VERSION 6.4

EDIRNCPI   RUN 12/01/2005   TIME 12:00   GENTRAN:STRUCTURE DATA PRE-P+
ERROR   **RECORD**

NUMBER   NBR ID   INFORMATION   ERROR MESSAGE
NO ERRORS OCCURRED DURING PROCESSING
PROCESSING ENDED NORMALLY - PROCESSING COUNTS BELOW
                                INPUT RECORDS READ----- 46
                                INPUT RECORDS SUSPENDED----- 0
                                OUTPUT RECORDS WRITTEN----- 64
                                PROGRAM RETURN CODE----- 0

EDIRNCPI   RUN 12/01/2005   TIME 12:00   SUMMARY REPORT - GENTRAN:STR+

Enter PF1=Help PF2=Sum   PF3=Exit   PF5=Print   PF6=NxtEr
      PF7=Bwd  PF8=Fwd   PF10=Left PF11=Rgt PF12=Top  PF13=Bot
    
```

Part 2

```

EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY   XXX   12/01/2005
                                                    12:00:00

Task ID: 0010675 Process Name: NCPDPI
Search.: _____ Line Increment: ____ Job Name: _____

EDIRNCPI   RUN 12/01/2005   TIME 12:00   SUMMARY REPORT - GENTRAN:STR+
PROCESSING BEGAN ON 12/01/05 AT 12:00 AM.
INPUT RECORDS READ----- 46
OUTPUT RECORDS WRITTEN----- 64
RECORDS SUSPENDED----- 0
00 SEGMENTS WRITTEN ----- 4
G1 SEGMENTS WRITTEN ----- 8
TH SEGMENTS WRITTEN ----- 0
RH SEGMENTS WRITTEN ----- 8
01 SEGMENTS WRITTEN ----- 0
02 SEGMENTS WRITTEN ----- 0
03 SEGMENTS WRITTEN ----- 0
04 SEGMENTS WRITTEN ----- 0
05 SEGMENTS WRITTEN ----- 0

Enter PF1=Help PF2=Sum   PF3=Exit   PF5=Print   PF6=NxtEr
      PF7=Bwd  PF8=Fwd   PF10=Left PF11=Rgt PF12=Top  PF13=Bot
    
```

Part 3

```

EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY   XXX   12/01/2005
                                                    12:00:00

Task ID: 0010675 Process Name: NCPDPI
Search.: _____ Line Increment: ____ Job Name: _____
05 SEGMENTS WRITTEN ----- 0
06 SEGMENTS WRITTEN ----- 0
07 SEGMENTS WRITTEN ----- 0
08 SEGMENTS WRITTEN ----- 0
09 SEGMENTS WRITTEN ----- 0
10 SEGMENTS WRITTEN ----- 0
11 SEGMENTS WRITTEN ----- 0
12 SEGMENTS WRITTEN ----- 0
13 SEGMENTS WRITTEN ----- 0
20 SEGMENTS WRITTEN ----- 8
21 SEGMENTS WRITTEN ----- 8
22 SEGMENTS WRITTEN ----- 8
23 SEGMENTS WRITTEN ----- 8
24 SEGMENTS WRITTEN ----- 0

Enter PF1=Help PF2=Sum   PF3=Exit           PF5=Print   PF6=NxtEr
      PF7=Bwd  PF8=Fwd           PF10=Left PF11=Rgt PF12=Top   PF13=Bot
    
```

Part 4

```

EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY   XXX   12/01/2005
                                                    12:00:00

Task ID: 0010675 Process Name: NCPDPI
Search.: _____ Line Increment: ____ Job Name: _____
24 SEGMENTS WRITTEN ----- 0
25 SEGMENTS WRITTEN ----- 8
26 SEGMENTS WRITTEN ----- 0
PROCESSING ENDED ON 12/01/05 AT 12:00 AM.

END OF ONLINE REPORTS
Enter PF1=Help PF2=Sum   PF3=Exit           PF5=Print   PF6=NxtEr
      PF7=Bwd  PF8=Fwd           PF10=Left PF11=Rgt PF12=Top   PF13=Bot
    
```

Outbound Flow

Overview

The programs described in the following sections allow the system to process fixed-format standards. The following flow charts describe the outbound flow with fixed-format standards and the Outbound Mapping program.

Outbound Flow with Fixed-Format Standards

Figure 5.2 illustrates the outbound process.




Figure 5.2 Outbound Flow with Fixed-Format Standards

Outbound Mapping Program

EDIR042

Purpose

The Outbound Mapping program (EDIR042), or “Mapper,” optionally generates fixed-format standard output in addition to variable-format standard output. Both fixed-format data and variable-format data can be generated from a single application depending upon the receiver of the data.

Fixed-format data can be sent directly to communications for transmission to the trading partner, or it can be processed by optional envelope generation or compliance checking programs. We do not supply these optional programs with Gentran:Structure. If you need them for processing, you must develop them for the specific standard.

Note: This section contains only information pertaining to the use of this program for Gentran:Structure for Gentran:Realtime. For complete information about this program, see the *Gentran:Basic for zSeries Release 6.4 Technical Reference Guide* and the *Gentran:Realtime for zSeries Release 6.4 Technical Reference Guide*.

Operation

The Gentran:Realtime Shell program initiates the Outbound Mapping program routine after the Outbound Application Gateway has been invoked. When finished, this program builds a TSQ that contains the EDI data.

Inputs

The Outbound Mapper reads application data from a TSQ created by the user application or the Queue File Read process. The system passes the TSQname through the Gentran:Realtime Gateway.

Gentran:Structure Subprograms Called

- EDID562 Outbound Application Databank Interface subroutine
- EDIR056B Outbound Structure Envelope Generation subroutine

File Access

File Description	DDname	File Access
Gentran:Structure User Envelope Definition file	EDIUENV	Read

Parameter Descriptions

The following parameters for the Outbound Mapper are specific for Gentran:Structure for Gentran:Realtime:

- Standard Type
- Maximum Len
- Initialize Numerics
- DBK Level
- Always Generate New Group per Tran

The Outbound Mapper-4 Path Maintenance screen (EDIM84J) enables you to enter values for these parameters.

Field Descriptions

Standard Type

The Standard Type parameter indicates to the Outbound Mapper whether fixed-format or variable-format output data is to be generated. A value of F indicates that the output data is fixed-format

Maximum Len

The Maximum Len parameter describes the maximum length of a segment in the defined standard. Valid values are:

00010 – 32760 for fixed-length segments

00010 – 32752 for variable-length segments

Initialize Numerics

The Initialize Numerics indicates to the Outbound Mapper whether to initialize non-packed dates and numeric data to zero. A value of Y tells the Mapper to set to zero any non-packed dates and numeric data with types N0 – N9 and S0 – S9 if no valid value is mapped to the element.

DBK Level

Indicates whether the Outbound Mapper should use Databanking for the fixed-format input data. Due to the structure of the fixed-format data, the Outbound Application databank is used to store the outbound fixed-format EDI data. Valid values are:

0 = No databanking.

1 = Use full databanking (both directory and message store levels).

2 = Use directory-level databanking.

Always Generate New Group per Tran

For NCPDP processing, this indicates to the Outbound Mapper to always generate a group envelope when the system generates a transaction envelope. A value of Y directs the Mapper to generate a group envelope for each transaction.

Screen Example

The following diagram illustrates the Outbound Mapper-4 Path Maintenance screen with the parameters fields highlighted.

```
EDIM84J _____ OUTBOUND MAPPER-4 PATH MAINTENANCE      XXX 12/01/2005
                                           12:00:00

Path ID.....: 300M  STRUCTURE OUTBOUND - FIXED GENTEST

Structure:
Standard Type.....: F (F/V/blank)
Maximum Len.....: 00080
Initialize Numerics.....: _ (Y/Blank)
DBK Level.....: 1 (0=No/1=Full/2=Dir)
Always Generate New Group per Tran.: _ (Y/Blank)

Viewpoint:
Exception Tracking.....: N (Y=ON/N=OFF)
Tracking Management.....: N (Y=ON/N=OFF)

                                           Last Update Date: 12/01/05
                                           Time: 12:00:00
                                           User: XXX

Enter PF1=Help          PF3=Exit PF4=Dir          PF6=Shell
      PF7=Map3 PF8=Env          PF10=Updt
```

Reports

The system generates Standard Mapper reports during fixed-format processing.

See the *Gentran:Realtime for zSeries Release 6.4 Technical Reference Guide* for more information.

Outbound NCPDP Post-Processing Program

EDIRNCPO

Purpose

The Outbound NCPDP Post-Processing program (EDIRNCPO) reformats and compresses outbound NCPDP data from Gentran-specific format into true NCPDP format. This program is the last step in the outbound processing flow for NCPDP data.

See Appendix B, “Processing NCPDP Data,” for more information about processing NCPDP data through Gentran:Structure.

Operation

The NCPDP Post-Processor reads data from a TSQ created by the Outbound Mapper program (EDIR042). When finished, this program builds a TSQ that contains the EDI data.

Note: This program is based on the NCPDP Telecommunications Standard Version 5 Release 1.

Inputs

The NCPDP Post-Processor reads records from an input TSQ. The input TSQ is created by the Outbound Mapper program (EDIR042).

File Access

File Description	DDname	File Access
Gentran System Configuration file	EDICFG	Read
Gentran Error Message and Control file	ERRCTL	Read
Gentran:Realtime Report Control file	EDIRRC	Write
Gentran:Realtime Report Detail file	EDIRRD	Write

Parameter Descriptions

Two parameters, Record Format and Compress, are specific to the NCPDP Post-Processor. The NCPDP Outbound Parms Maintenance screen (EDIM84G) enables you to enter values for these parameters.

Field Descriptions

Record Length

The Record Length parameter indicates the maximum record length the Outbound NCPDP Post-Processor will use when compressing and wrapping the outgoing NCPDP EDI data. Valid values are **00001 – 32760**.

Compress

The Compress parameter indicates the level of compression and wrapping the Outbound NCPDP Post-Processor will use for the outgoing NCPDP EDI data. Valid values are:

- F** = Include the batch envelopes when compressing and wrapping the NCPDP EDI data.
- T** = The transaction envelope should start a new record. The batch envelopes are not compressed and wrapped.

Screen Example

The following diagram illustrates the NCPDP Outbound Parms Maintenance screen with the Record Length and Compress fields highlighted.

```

EDIM84G _____ NCPDP OUTBOUND PARMS MAINTENANCE      XXX 12/01/2005
                                                    12:00:00
Path ID.....: 300N  OUTBOUND STRUCTURE - FIXED ENV TEST
Outbound Flow

NCPDP Reformat Parameters:

Record Length....: 00000
Compress.....: _      (F=Full, T=Transmission)

Last Update Date.: 12/01/05
                Time.: 12:00:00
                User.: XXX

Enter PF1=Help          PF3=Exit PF4=Dir          PF6=Shell
                PF9=Add PF10=Updt PF11=Del
    
```

Reports

The Outbound NCPDP Post-Processor program produces a summary report and an error report. You can view these reports using the Gentran:Realtime Online Reporting function.

Note: The Process Name for this report is NCPDPO.

Report Selection

```

Select Print Log Exception Activity
EDIM310 8.3 _____ REPORT SELECTION XXX 12/01/2005
                                                    12:00:00

Path ID.....: ____ Process....: _____
Line Incrmt..: ____ Cond Code...: _ (Y)
From Date.....: _____ To Date....: _____ (MM/DD/YYYY)
From Time.....: _____ To Time....: _____ (HH:MM:SS)
Task #.....: _____ Max Srch...: 0450
Print Job Name: _____

  Generation      Path Process    Con Task      Control
A   Date         Time   ID   Name     St Cd   #   Description  Address
- 12/01/2005 12:00:00 000 IA-AUD   00 10711 IA DBK MAINT 376
- 12/01/2005 12:00:00 414 OEXAUD   01 10710 EDID255-EDIAUDT 377
- 12/01/2005 12:00:00 414 OEXSUM   01 10710 EDID255-EDISUM 378
- 12/01/2005 12:00:00 068 NCPDPO   F 16 10837 POFILE 379
- 12/01/2005 12:00:00 068 NCPDPO   F 16 10839 POFILE 380
- 12/01/2005 12:00:00 068 EDI42E   W 04 10874 POFILE 381
- 12/01/2005 12:00:00 068 EDI42S   W 04 10874 POFILE 382
- 12/01/2005 12:00:00 068 NCPDPO   F 16 10874 POFILE 383
- 12/01/2005 12:00:00 068 NCPDPO   00 10922 POFILE 384

Enter PF1=Help          PF3=Exit          PF5=Action
      PF7=Bwd   PF8=Fwd
    
```

Outbound NCPDP Post-Processor Report Display Screens

Part 1

```

EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY   XXX   12/01/2005
                                                    12:00:00

Task ID: 0010922 Process Name: NCPDPO
Search.: _____ Line Increment: ____ Job Name: _____

EDIRNCPO  RUN 12/01/2005   TIME 12:00   GENTRAN:STRUCTURE DATA POST-+
ERROR  **RECORD**
NUMBR    NBR ID          INFORMATION          ERROR MESSAGE
*****
NO ERRORS OCCURRED DURING PROCESSING
PROCESSING ENDED NORMALLY - PROCESSING COUNTS BELOW
                                INPUT RECORDS READ-----          52
                                OUTPUT RECORDS WRITTEN-----        32
                                PROGRAM RETURN CODE-----            0
EDIRNCPO  RUN 12/01/2005   TIME 12:00   PROCESSING OPTIONS - GENTRAN+
OUTPUT RECORD FORMAT IS -----VARIABLE
OUTPUT RECORD LENGTH IS -----00100
OUTPUT FILE COMPRESSION IS -----TRANSACTION

Enter PF1=Help PF2=Sum   PF3=Exit           PF5=Print   PF6=NxtEr
      PF7=Bwd  PF8=Fwd   PF10=Left PF11=Rgt PF12=Top  PF13=Bot
    
```

Part 2

```

EDIM311 _____ GENTRAN:Realtime EDI REPORT DISPLAY   XXX   12/01/2005
                                                    12:00:00

Task ID: 0010922 Process Name: NCPDPO
Search.: _____ Line Increment: ____ Job Name: _____
OUTPUT FILE COMPRESSION IS -----TRANSACTION
EDIRNCPO  RUN 12/01/2005   TIME 12:00   SUMMARY REPORT - GENTRAN:STR+
PROCESSING BEGAN ON 12/01/2005 AT 12:00 AM.
INPUT RECORDS READ-----          52
OUTPUT RECORDS WRITTEN-----        32
PROCESSING ENDED ON 12/01/2005 AT 12:00 AM.

END OF ONLINE REPORTS
Enter PF1=Help PF2=Sum   PF3=Exit           PF5=Print   PF6=NxtEr
      PF7=Bwd  PF8=Fwd   PF10=Left PF11=Rgt PF12=Top  PF13=Bot
    
```

Appendix

A

Jump Codes

Jump Codes by Screen Title

The following tables list the jump codes for the Gentran:Structure menus and screens. The screens are listed by title in the order in which they are displayed on the Gentran:Structure menus.

For a listing of jump codes listed by screen name, see “Jump Codes by Screen Name” on page A-2.

Screen Title	Screen	Jump Codes	
	Name	Numeric	Alphabetic
Control Information (Screen 1 with Generic Header Option)	EDIM015	1.2.2.1	PART.CNTL PART.CTL
Control Information (Screen 2 with Generic Options)	EDIM011		
Group Information (Generic)	EDIM034	1.2.3.1	PART.GRP
Transaction Information (Generic)	EDIM044	1.2.4.1	PART.TRN
Standards Maintenance Menu	EDIM100	2.0 2	STD
Version	EDIM110	2.2	STD.VER
Data Element Definition	EDIM160	2.9	STD.DD STD.ELE
User Envelope Specification	EDIM190	2.12	STD.ENV STD.UENV
Version/Outbound Specification	EDIM191		
Structure Envelope Display	EDIM192		
Databank Maintenance Menu	EDIM250	3.0 3	DB
Structure Document Directory	EDIM272	3.13	DB.SDIR
Structure Document Status	EDIM273	3.14	DB.SSTAT
Structure Document Display	EDIM274		
Structure Document Status Detail	EDIM275		
Structure Record Display	EDIM276		
Structure Field Display	EDIM277		
Transaction Maintenance	EDIM503	5.2.2	TRN.DEF TRN.ID

Screen Title	Screen	Jump Codes	
	Name	Numeric	Alphabetic
Transaction Maintenance – Gentran:Structure	EDIM516		
Application Data ID	EDIM552	5.1.2	APP.DEF APP.ID
Fixed Format Pre-processor Path Maintenance	EDIM840		
Fixed/Variable Splitter Path Maintenance	EDIM841		
NCPDP Outbound Parms Maintenance	EDIM84G		

Jump Codes by Screen Name

The following tables list the jump codes for the Gentran:Plus menus and screens. The screens are listed by screen name (EDIMXXX) and are arranged strictly in alphanumeric order, regardless of the menu arrangement.

For a listing of jump codes listed by screen title, in the order in which they are displayed on Gentran:Plus menus, see “Jump Codes by Screen Title” on page A-1.

Screen Name	Screen Title	Jump Codes	
		Numeric	Alphabetic
EDIM015	Control Information (Screen 1 with Generic Header Option)	1.2.2.1	PART.CNTL PART.CTL
EDIM011	Control Information (Screen 2 with Generic Options)		
EDIM034	Group Information (Generic)	1.2.3.1	PART.GRP
EDIM044	Transaction Information (Generic)	1.2.4.1	PART.TRN
EDIM100	Standards Maintenance Menu	2.0 2	STD
EDIM110	Version	2.2	STD.VER
EDIM160	Data Element Definition	2.9	STD.DD STD.ELE
EDIM190	User Envelope Specification	2.12	STD.ENV STD.UENV
EDIM191	Version/Outbound Specification		
EDIM192	Structure Envelope Display	3.0 3	DB
EDIM250	Databank Maintenance Menu		
EDIM272	Structure Document Directory	3.13	DB.SDIR

Screen		Jump Codes	
Name	Screen Title	Numeric	Alphabetic
EDIM273	Structure Document Status	3.14	DB.SSTAT
EDIM274	Structure Document Display		
EDIM275	Structure Document Status Display		
EDIM276	Structure Record Display		
EDIM277	Structure Field Display		
EDIM503	Transaction Maintenance	5.2.2	TRN.DEF TRN.ID
EDIM516	Transaction Maintenance – Gentran:Structure		
EDIM552	Application Data ID	5.1.2	APP.DEF APP.ID
EDIM840	Fixed Format Pre-Processor Path Maintenance		
EDIM841	Fixed/Variable Splitter Path Maintenance		
EDIM84G	NCPDP Outbound Parms Maintenance		

Processing NCPDP Data

Overview

This appendix explains how to process NCPDP data using Gentran:Basic/Realtime/Structure.

Note: For batch processing of inbound and outbound NCPDP transactions, Gentran:Structure supports only version 5 release 1 transactions. Version 1 release 1 batch envelopes must be used with these transactions.

Assumptions

This appendix assumes that you are familiar with:

- Batch NCPDP data and its implementation requirements.
- Setting up maps and partners in Gentran.
See the Gentran:Basic for zSeries Release 6.4 documentation if you need more information about these processes.

This appendix contains the following topics.

Topic	Page
Processing NCPDP Data in Gentran:Structure	B-2
Key Terms	B-2
The Gentran NCPDP51 Standard	B-3
Processing Outbound NCPDP Data.....	B-8
Define and Build Your Application Definition	B-10
Define and Build Your Transaction Map	B-10
Defining User Envelopes (Optional).....	B-15
Setting Up Partner Profiles	B-25
Preparing to Run Outbound Processing	B-29
Processing Inbound NCPDP Data.....	B-34
Define and Build your Application Definition	B-36
Define and Build your Transaction Map.....	B-36
Defining User Envelopes	B-39
Setting Up Your Partner Profile	B-49
Preparing to Run Inbound Processing.....	B-49
NCPDP Data Examples.....	B-51
Inbound Example Data.....	B-51
Outbound Example Data	B-52

Processing NCPDP Data in Gentran:Structure

The Gentran system requires file formats (record and field information) to be defined in the Gentran standards files for processing. Because the NCPDP standard does not conform with the Gentran standard format, it must be modified. For this reason, the Gentran Standards Cartridge contains a special Gentran version of the NCPDP Version 5.1 standard. You will build your NCPDP maps using this version of NCPDP Version 5.1.

The version ID is NCPDP51. The agency is SC.

Note: For information on how to load a standard to your system, see the “Standards Maintenance” section of Chapter 4 of the *Gentran:Basic for zSeries Release 6.4 Technical Reference Guide*.

For outbound processing, the Mapper translates your application data into the Gentran-specified format. A special Gentran:Structure program has been created to reformat this NCPDP data into the true outgoing NCPDP format. The program is NCPDP51O for Gentran:Basic and EDIRNCPO for Gentran:Realtime.

For inbound processing, another special program reformats the incoming NCPDP data into the Gentran-specified format. This program is NCPDP51I for Gentran:Basic for zSeries and EDIRNCPI for Gentran:Realtime. Once reformatted, the NCPDP data can be processed through the Structure Pre-Processor and then the Mapper to be translated into your application data.

Key Terms

NCPDP requires some different terminology than Gentran. The following table describes terms you need in order to understand the rest of the information in this appendix.

Term	Description
NCPDP51	The version ID to define the Gentran-specific NCPDP layout in Gentran standards files.
Batch envelopes	Envelopes that surround an NCPDP transmission. Valid batch envelopes are: Batch Transaction Header – segment ID = 00 Batch Transaction Detail – segment ID = G1 Batch Transaction Trailer – segment ID = 99
Transaction header	The first segment of a request transmission. It contains the transaction code that identifies the type of request.
Response header	The first segment of a response transmission. It contains the transaction code that identifies the type of response.
NCPDP transmission	A group of segments starting with either a transaction header segment or a response header segment, and including all of the segments associated with that NCPDP document.
NCPDP file	An NCPDP transmission with its surrounding batch envelopes.

Term	Description
NCPDP transaction	A group of segments that together contain the detail information about the request or response. Up to four transactions can make up a transmission, except for the eligibility request. (NCPDP restricts the eligibility request, transaction code E1, to one request per transaction.)
Gentran transaction ID	In Gentran, this is the field used to identify the transaction being processed or generated.

The Gentran NCPDP51 Standard

This section describes the Gentran-specific NCPDP standard, including transaction level, segment and segment element requirements for processing NCPDP data. In addition to reviewing the information provided here, we recommend you use the Online Standards Subsystem or run the EXEC036 Standards Print job found in Gentran:Basic to review the Gentran NCPDP51 standard.

In NCPDP terminology, a transmission is the highest level of data file. The transmission contains information that pertains to the entire file. A transaction occurs within a transmission, and there can be up to four transactions per transmission. In the Gentran NCPDP51 standard, all of the segments required for an NCPDP transmission are found in a single NCPDP51 transaction. The batch header envelopes (00, G1, transaction header, and response header) and transmission level segments appear in the header section of the Gentran transaction. The NCPDP transaction level segments appear in the detail section of the transaction in a loop that occurs a maximum of four times. The batch trailer envelope (99 segment) appears in the summary section of the Gentran transaction.

Transaction Level Information

Fourteen request type transactions exist in the NCPDP51 version. The first two characters of the transaction ID match its corresponding NCPDP transaction code, and the third character is the letter Q, which designates that the transaction is a request type transaction. (The table below provides a list of transactions.)

Because all responses are essentially built from the same segments, the NCPDP51 standard needs only a single transaction ID for translating all response type transactions. The NCPDP51 transaction ID for responses is R1.

The following table describes the transaction IDs in Gentran Standard Version NCPDP51.

Gentran Transaction ID	NCPDP Transaction Code	Description
B1Q	B1	Billing request
B2Q	B2	Reversal request
B3Q	B3	Rebill request
C1Q	C1	Controlled substance reporting request

Gentran Transaction ID	NCPDP Transaction Code	Description
C2Q	C2	Controlled substance reporting reversal request
C3Q	C3	Controlled substance reporting rebill request
E1Q	E1	Eligibility request
N1Q	N1	Information reporting request
N2Q	N2	Information reporting reversal request
N3Q	N3	Information reporting rebill request
P1Q	P1	Prior authorization request and billing
P2Q	P2	Prior authorization reversal request
P3Q	P3	Prior authorization inquiry request
P4Q	P4	Prior authorization request only
R1	B1, B2, B3, C1, C2, C3, E1, N1, N2, N3, P1, P2, P3, P4	Generic response transaction – The R1 transaction ID should be used to build maps for all response type documents

Segment Information

Because NCPDP does not define a segment ID for the transaction header and response header segments, Gentran uses the values TH and RH, respectively, to refer to these segments.

Each NCPDP51 transaction includes the version 1 release 1 batch envelopes (segment IDs 00, G1 and 99). This enables you to map data from your application data to the NCPDP fixed format structure when processing outbound NCPDP data, just as you would map any other segment in the transaction. For inbound processing, the presence of the envelopes in each transaction also allows you to map data from the envelopes directly to your application data, just as you would map any other segment.

In the following diagram, the 00, G1, and TH envelopes appear as a part of the B1Q transaction. The envelopes and the transmission level segments (01 and 04) are defined in the header section of the B1Q transaction.

```

Add Delete Update Select Info
EDIM130 2.6_____ SEGMENTS          XXX      12/01/2005
                                           12:00:00

Version Id.....: NCPDP51_____ Agency...: SC_
Transaction ID..: B1Q___

*****Segment*****   Man ***Use***  **Loop***  DE   Seg  Loop  LP Act
A  No  Id  Ver Ty Req Cde Min  Max  Min  Max  Count Grp  Id  B/E Cnt
-  --  --  --  --  --  --  --  --  --  --  --  --  --  --
0001 00  00  00  H  _  M  1  _  1  _  _  _  _  _  _
      BATCH_TRANSACTION_HEADER_DEFINITION
0002 G1  00  00  H  _  M  1  _  1  _  _  _  _  _  _
      BATCH_TRANSACTION_DETAIL_DEFINITION
0003 TH  00  00  H  _  M  1  _  1  _  _  _  _  _  _
      TRANSACTION_HEADER_SEGMENT
0004 01  00  00  H  _  O  _  _  _  1  _  _  _  _  _
      PATIENT_SEGMENT
0005 04  00  00  H  _  M  1  _  1  _  _  _  _  _  _
      INSURANCE_SEGMENT

Enter PF1=Help          PF3=Exit PF4=Trans      PF5=Elements  PF6=Nxt Tran
      PF7=Bwd  PF8=Fwd
    
```

In the following diagram, the transaction level segments (07, 02, 03, 05, 06) are defined in the detail section of the B1Q transaction in a loop (loop ID = 1000) that occurs four times.

```

Add Delete Update Select Info
EDIM130 2.6_____ SEGMENTS          XXX      12/01/2005
                                           12:00:00

Version Id.....: NCPDP51_____ Agency...: SC_
Transaction ID..: B1Q___

*****Segment*****   Man ***Use***  **Loop***  DE   Seg  Loop  LP Act
A  No  Id  Ver Ty Req Cde Min  Max  Min  Max  Count Grp  Id  B/E Cnt
-  --  --  --  --  --  --  --  --  --  --  --  --  --  --
0006 07  00  00  D  _  M  1  _  1  _  76  _  1000  B  _
      CLAIM_SEGMENT
0007 02  00  00  D  _  O  _  _  _  1  _  _  _  1000  _  _
      PHARMACY_PROVIDER
0008 03  00  00  D  _  O  _  _  _  1  _  _  _  1000  _  _
      PRESCRIBER
0009 05  00  00  D  _  O  _  _  _  1  _  _  _  1000  _  _
      COB/OTHER_PAYMENTS
0010 06  00  00  D  _  O  _  _  _  1  _  _  _  1000  _  _
      WORKERS_COMP

Enter PF1=Help          PF3=Exit PF4=Trans      PF5=Elements  PF6=Nxt Tran
      PF7=Bwd  PF8=Fwd
    
```

In the following diagram, the Batch Transaction Trailer (99 segment) appears as a part of the B1Q transaction, defined in the summary section of the transaction.

```

Add Delete Update Select Info
EDIM130 2.6_____ SEGMENTS          XXX      12/01/2005
                                           12:00:00

Version Id.....: NCPDP51_____ Agency...: SC_
Transaction ID...: B1Q_____

*****Segment*****  Man ***Use***  **Loop***  DE  Seg  Loop  LP  Act
A  No  Id  Ver Ty Req Cde Min  Max  Min  Max  Count Grp  Id  B/E  Cnt
-  -  -  -  -  -  -  -  -  -  -  -  -  -  -
0013 09__ 00  D  _  O  _  _  1  _  _  _  8  _  1000  _  _  _
      COUPON
-  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -
0014 10__ 00  D  _  O  _  _  1  _  _  _  260  _  1000  _  _  _
      COMPOUND
-  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -
0015 12__ 00  D  _  O  _  _  1  _  _  _  28  _  1000  _  _  _
      PRIOR_AUTHORIZATION
-  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -
0016 13__ 00  D  _  O  _  _  1  _  _  _  84  _  1000  _  E  _
      CLINICAL
-  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -
0017 99__ 00  S  _  M  1  _  1  _  _  _  5  _  _  _  _  _
      BATCH_TRANSACTION_TRAILER_DEFINITION

```

Enter PF1=Help PF3=Exit PF4=Trans PF5=Elements PF6=Nxt Tran
PF7=Bwd PF8=Fwd

Segment Element Information

The segment ID for each segment is a 2-character field that begins in the third position of each segment.

The field tags, where applicable, are defined in each segment prior to the actual segment field.

Note: There are no field tags in the envelope segments.

The NCPDP51 standard in Gentran has taken the segments used in each NCPDP version 5 release 1 transaction and expanded them to their maximum possible length with each element (field) in a fixed position.

Note: All possible field repeats and group repeats are defined in each segment, with the exception of the Compound segment (segment ID = 10). The NCPDP version 5 release 1 implementation guide allows 99 ingredients to be present in the Compound segment. Due to the limitation of the number of elements allowed per segment, Gentran will only support 98 occurrences of the ingredient component group.

The following diagram illustrates:

- The segment ID as the second element for each segment.
- The element/field tags as every other element (see sequence numbers 0001, 0003, 0005, 0007, 0009) within the segment.

```

Add Update Delete Select Info
EDIM140 2.7_____ SEGMENT ELEMENT          XXX      12/01/2005
                                                12:00:00

Version Id...: NCPDP51_____ Agency...: SC_
Segment Id...: 07__   Segment Version...: 00

Seq  Ele  Sub  Man  Com  Ad  Element          **Group**
A  Num  Seq  Ele  Ele  Ele  In  Id  Ver  R  Dsg  Ty  Description          C
-  -    -    -    -    -    -  -  -  -  -    -  -
-  0001 001 000  M   M   -   001__ 00 0001  -    -  ELEMENT TAG
-  0002 002 000  M   M   -   111__ 00 0001  -    -  SEGMENT IDENTIFICATIO
-  0003 003 000  M   M   -   001__ 00 0001  -    -  ELEMENT TAG
-  0004 004 000  M   M   -   455__ 00 0001  -    -  PRESCRIPTION/SERVICE
-  0005 005 000  M   M   -   001__ 00 0001  -    -  ELEMENT TAG
-  0006 006 000  M   M   -   402__ 00 0001  -    -  PRESCRIPTION/SERVICE
-  0007 007 000  M   M   -   001__ 00 0001  -    -  ELEMENT TAG
-  0008 008 000  M   M   -   436__ 00 0001  -    -  PRODUCT/SERVICE ID QU
-  0009 009 000  M   M   -   001__ 00 0001  -    -  ELEMENT TAG
-  0010 010 000  M   M   -   407__ 00 0001  -    -  PRODUCT/SERVICE ID

Enter PF1=Help PF2=Actvty PF3=Exit PF4=Segment PF5=Elem Def PF6=Nxt Seg
      PF7=Bwd  PF8=Fwd
    
```

If you are in the online Standards Subsystem and press **PF8=Fwd** to scroll through a segment, you will see that all possible elements for the segment (mandatory and optional) appear in the segment.

Processing Outbound NCPDP Data

This section describes the system flow for translating data into batch NCPDP version 5 release 1 data, and details the proper setup required to process the data.

Before Gentran:Structure can process NCPDP data, the data must be translated into a fixed-format composition as defined in the standards files. For outbound processing, Gentran:Structure translates your application data into Gentran-specified fixed format records, and then runs the data through a program to compress the data into true outgoing NCPDP data.

Note: See the Gentran online standards files under version NCPDP51, agency SC, for the layout of the Gentran fixed format structure for NCPDP data.

Processing outbound NCPDP data through Gentran:Structure requires extra set-up in addition to normal Gentran procedures. You must complete the following tasks according to the information provided in the next section of this chapter:

- Define and build your application definition.
- Define and build your transaction map.
- Define user envelopes (optional).
- Set up your partner profile.
- Prepare to run outbound processing.

Figure B.1 illustrates the system flow for translating your application data into batch NCPDP version 5 release 1 data. The requirements for the tasks listed above follow the diagram.




Figure B.1 System Flow – Translating Application Data into Batch NCPDP Data

Define and Build Your Application Definition

You will use the online mapping subsystem to enter your application definition.

On the Application Data ID screen (EDIM552), the value in the Functional Group field should match the NCPDP51 transaction ID to which this application data will be translated. The following diagram illustrates the screen.

```

EDIM552 5.1.2_____ APPLICATION DATA ID          XXX 12/01/2005
                                                12:00:00

Application Data ID.....: RAENCPDP1_  Send or Receive:  S
Division Code.....:      000
Description.....:      NCPDP_APPLICATION_DEFINITION__
Functional Group.....:  B1Q_____
Fixed or Variable Length...:  F   (F/V)
Record Length.....:      00255
Record Type Start Pos.....:  00001          Length.....:  03
Inbound Pass-Thru.....:      -
Underscore Character.....:  -
Update Allowed.....:      Y

Last Update User.....:      XXX          Date.....:  12/01/05
                                                Time.....:  12:00:00

Enter PF1=Help PF2=Copy  PF3=Exit PF4=Dir          PF5=Records  PF6=Refer
          PF9=Add PF10=Updt PF11=Del PF12=NuMap PF13=Envel
    
```

Define and Build Your Transaction Map

You use two initial screens to add a new Gentran:Structure map using the online mapping subsystem.

Set up the first screen, the Transaction Maintenance screen (EDIM503), with the following information:

In This Field...	Enter This Value
Standards Version	NCPDP51
Agency	SC
Transaction Set	(A transaction ID found in version NCPDP51)
Envelope Type	D (this indicates that this is a user-defined standard)
Standard Type	F (indicates a fixed-format standard)

The following diagram illustrates the screen.

```

EDIM503 5.2.2_____ TRANSACTION MAINTENANCE XXX 12/01/2005
                                           12:00:00

Transaction ID.....: NCPDPB1Q__          Send or Receive(S/R) ...: S
Division Code.....: 000
Description.....: BILL REQ. ENVELOPES MAPPED
Standards Version.....: NCPDP51_____ Agency: SC_
Transaction Set.....: B1Q__
Transaction Set Release...: _ (0-9, ANA Tradacoms Only)
Transaction Status.....: T (D=Development, T=Test, P=Production)
Use Code.....: G (G=General, P=Partner Specific)
Envelope Type.....: D (E=Edifact, X=X12, U=UCS, G=GS, A=ANA, D=User)
Application Data ID.....: RAENCPDP1_
Application Selection Field Values: _____

Standard Type.....: F (V=Variable, F=Fixed)
RSGRSG Level.....: _ (1/2/ ANA Tradacoms Only)
Underscore Character.....: _
Update Allowed.....: Y Job Name: _____

Enter PF1=Help PF2=Fixed PF3=Exit PF4=Dir PF5=Segments PF6=Copy
PF7=Rpt PF9=Add PF10=Updt PF11=Del PF12=NuMap PF14=Info
    
```

When you press **PF9=Add** to add the new map, the system displays the Transaction Maintenance – Gentran:Structure screen (EDIM516). Enter the following information on this screen:

In This Field...	Enter This Value
Segment ID Start	3
Segment ID Length	2

The following diagram illustrates the screen.

```

EDIM516 _____ TRANSACTION MAINTENANCE                XXX 12/01/2005
              (Gentran:Structure)                          12:00:00

Transaction ID.....: NCPDPB1Q                S/R.....: S
Division Code.....: 000
Description.....: BILL REQ. ENVELOPES MAPPED
Standards Version.....: NCPDP51                Agency....: SC
Transaction Set.....: B1Q
Transaction Set Release....: (0-9, ANA Tradacoms Only)

Envelope Format.....: F                (V=Variable, F=Fixed)
Segment ID Start.....: 3                (1 to 32743)
Segment ID Length.....: 2                (1 to 10)

Last Update Date.....: 12/01/05
Time.....: 12:00:00
User.....: XXX

Enter PF1=Help                PF3=Exit PF4=Maint        PF5=Segments
                                PF10=Updt

```

Once the transaction map definition is complete, copy the desired segments for the transaction you will be processing from the NCPDP51 version, and proceed with mapping the data as you would with any other Gentran map.

Keep in mind the following specifics when mapping NCPDP data.

- Because the segment ID is a part of each segment, you must map the segment ID for each segment.

Normally, the Outbound Mapper populates the segment ID for you when processing ASC X12, EDIFACT, and Tradacoms type data through Gentran. This is not the case for NCPDP data. Specifically, you must map the segment ID value into the segment ID element for each segment that you map.

In the following diagram, the literal value 00 is being mapped to the segment identifier element when mapping the 00 batch transaction header definition segment.

```

Extended-mapping Info Update Subfield Repeat
EDIM511 _____ ELEMENT MAPPING OUTBOUND XXX 12/01/2005
                                           12:00:00

Transaction ID.....: NCPDPB1Q__ Send or Receive..: S
Segment Sequence.....: 00100 Segment ID.....: 00 Ver: 00
Segment Description..: BATCH TRANSACTION HEADER DEFIN

A Mapping Table Ext Alt-Element- Repeat Md T C
  Constant/Field ID Map Map No ID No. Cd P Desc R
-----
'00' _____ 00010 001 0001 O AN ELEMENT_TAG
'00' _____ 00020 701 0001 M AN SEGMENT_IDENTIFIE
N00-TRAN-TYPE__ 00030 880K6 0001 M AN TRANSMISSION_TYPE
N00-SENDER-ID__ 00040 880K1 0001 C AN SENDER_ID
N00-BATCH-NBR__ 00050 806 0001 C NO BATCH_NUMBER
N00-CREATE-DATE 00060 880K2 0001 C DT CREATION_DATE
N00-CREATE-TIME 00070 880K3 0001 C TM CREATION_TIME
N00-FILE-TYPE__ 00080 702 0001 C AN FILE_TYPE
N00-VERSION_____ 00090 102 0001 C ID VERSION/RELEASE_N
N00-RECEIVER-ID _____ 00100 880K7 0001 C AN RECEIVER_ID

Enter PF1=Help PF2=Appl PF3=Exit PF4=Segments PF5=Codes PF6=Next Seg
      PF7=Bwd PF8=Fwd PF13=Relat
    
```

- You must map the NCPDP field tags (Gentran will not handle this for you).

If your application data contains the field tag values, you can map them from your application data. Otherwise, you can map literal values into the field tag fields. The following diagram illustrates literal values being mapped to the NCPDP fields tags.

```

Extended-mapping Info Update Subfield Repeat
EDIM511 _____ ELEMENT MAPPING OUTBOUND XXX 12/01/2005
                                           12:00:00

Transaction ID.....: NCPDPB1Q__ Send or Receive..: S
Segment Sequence.....: 00500 Segment ID.....: 04 Ver: 00
Segment Description..: INSURANCE SEGMENT

A Mapping Table Ext Alt-Element- Repeat Md T C
  Constant/Field ID Map Map No ID No. Cd P Desc R
-----
'AM' _____ 00010 001 0001 M AN ELEMENT_TAG
'04' _____ 00020 111 0001 M ID SEGMENT_IDENTIFIC
'C2' _____ 00030 001 0001 M AN ELEMENT_TAG
N04-CARD-ID_____ 00040 302 0001 M AN CARDHOLDER_ID
'CC' _____ 00050 001 0001 O AN ELEMENT_TAG
N04-FIRST-NAME__ 00060 312 0001 O AN CARDHOLDER_FIRST_
'CD' _____ 00070 001 0001 O AN ELEMENT_TAG
N04-LAST-NAME___ 00080 313 0001 O AN CARDHOLDER_LAST_N
_____ 00090 001 0001 O AN ELEMENT_TAG
_____ 00100 314 0001 O AN HOME_PLAN

Enter PF1=Help PF2=Appl PF3=Exit PF4=Segments PF5=Codes PF6=Next Seg
      PF7=Bwd PF8=Fwd PF13=Relat
    
```

- The Gentran transaction IDs do not match the NCPDP transaction codes, so you must map the NCPDP transaction code on the transaction header (TH) and response header (RH) segments.

You can either map the transaction code value from your application, or map a literal value into the transaction code element.

Example

If you are sending a billing request transaction to a trading partner, you are responsible for mapping the true NCPDP transaction code value (in this case B1) to the transaction code field on the TH segment. Gentran processes as if it is processing a B1Q transaction and therefore can not map the Gentran transaction ID into the Transaction Code field.

- If your application data has the information available, you may map the transaction count field on the TH and RH segment from your application. However, if your application data does not have the number of transactions in the transmission available, the Outbound NCPDP Reformat program (NCPDP51O) will calculate this value for you.

The following diagram illustrates the NCPDP Transaction Code and the NCPDP Transaction Count being mapped to the TH segment from the application data.

```

Extended-mapping Info Update Subfield Repeat
EDIM511 _____ ELEMENT MAPPING OUTBOUND XXX 12/01/2005
                                           12:00:00

Transaction ID.....: NCPDPB1Q__ Send or Receive...: S
Segment Sequence.....: 00300 Segment ID.....: TH Ver: 00
Segment Description...: TRANSACTION HEADER SEGMENT

A Mapping Table Ext Alt-Element- Repeat Md T C
  Constant/Field ID Map Map No ID No. Cd P Desc R
-----
- 'TH' _____ 00010 001 0001 O AN ELEMENT_TAG _____
- NTH-BIN-NBR _____ 00020 111 0001 M ID SEGMENT_IDENTIFIC _____
- NTH-VERSION _____ 00030 101 0001 C NO BIN_NUMBER _____
- NTH-TRANS-CODE _____ 00040 102 0001 C ID VERSION/RELEASE N _____
- NTH-CONTROL-NBR _____ 00050 103 0001 C ID TRANSACTION_CODE _____
- NTH-TRANS-COUNT _____ 00060 104 0001 C AN PROCESSOR_CONTROL _____
- NTH-PRV-ID-QUAL _____ 00070 109 0001 C ID TRANSACTION_COUNT _____
- NTH-PRV-ID _____ 00080 202 0001 C ID SERVICE-PROVIDER _____
- NTH-DATE-SVC _____ 00090 201 0001 C AN SERVICE-PROVIDER _____
- _____ 00100 401 0001 C DT DATE_OF_SERVICE _____

Enter PF1=Help PF2=Appl PF3=Exit PF4=Segments PF5=Codes PF6=Next Seg
      PF7=Bwd PF8=Fwd PF13=Relat
    
```

Defining User Envelopes (Optional)

For outbound processing, Gentran:Structure allows you to pull information from the partner profile when you build your envelope segments.

You can accomplish this by identifying special user envelopes. The envelope segments (00, G1, TH, RH, 99) are a part of each Gentran NCPDP51 transaction, so you can map to these segments from your application data. All of the information you need to map all of the fields in the envelope segments may be in your application data. If this is the case, you do not need to define user envelopes for NCPDP51 outbound processing. However, if you want certain information to be pulled from the Gentran partner profile to populate some of the envelope fields (e.g., the batch number on the 00 envelope), you must define special user envelopes in the Gentran:Structure User Envelope file.

Note: If you are not defining user envelopes, you can skip this section and proceed to the next section, *Setting Up Partner Profiles*.

Because the envelopes in the User Envelope file can not have the same segment IDs as the envelope segments found in the transactions themselves (00, G1, TH, RH, 99), you must use X versions of the envelopes in the User Envelope file. The values for the special segment IDs that you will use for your outbound user envelopes in the User Envelope file have already been pre-determined by Gentran.

The following table describes how the X versions of the envelopes relate to the NCPDP51 batch envelopes.

Envelope Segment ID found in NCPDP51 Transactions	Corresponding "X" version of the Envelope to be used in User Envelope File	Description
00	0X	Batch Transaction Header Definition
G1	GX	Batch Transaction Detail Definition
TH	TX	Transaction Header Segment
RH	RX	Response Header Segment
99	9X	Batch Transaction Trailer Definition

The X versions of the envelopes have a fixed record layout that may or may not match their corresponding NCPDP envelopes. You may not modify these layouts. You must enter all of the X envelopes on the User Envelope Specification screen (EDIM190). The following tables describe the layouts for the X envelopes. You will use this information in the EDIM190 screen for user and partner, and EDIM191 for other fields.

See the example later in this section for a more detailed explanation.

0X – Batch Transaction Header Definition User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Sender ID	AN	5	24
Batch Number	N	29	7
Creation Date	N	36	8
Creation Time	N	44	4
File Type	AN	48	1
Version Release	AN	49	2
Receiver ID	AN	51	24
GX – Batch Transaction Detail Definition User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Transaction Reference Number	AN	5	10
TX – Transaction Header Segment User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
BIN Number	N	5	6
Version Release	AN	11	2
Transaction Code	AN	13	2
Control Number	AN	15	10
Service Provider ID Qualifier	AN	25	2
Service Provider ID	AN	27	15
Date of Service	N	42	8
Vendor Certification ID	AN	50	10

RX – Response Header Segment User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Version Release	AN	5	2
Service Provider ID Qualifier	AN	7	2
Service Provider ID	AN	9	15
Date of Service	N	24	8
9X – Batch Transaction Trailer Definition User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Batch Number	N	5	7

Note: The X versions of the envelopes do not contain all fields found in the actual NCPDP envelopes. Only that information that can be pulled from the partner profile is included. For example, the Transmission Type field on the 00 envelope, which indicates whether the batch of data is a transaction, response, or an error, must come from the application since that field will change each time you send a batch of data to a particular partner.

When you use the X envelopes, the Outbound Mapper generates these segments and writes them to the fixed output file. The NCPDP510 Reformat program merges the information from the X envelopes with the actual NCPDP envelopes (00, G1, TH, RH, 99) mapped to from your application data. If a field on an actual NCPDP batch envelope (00, G1, TH, RH, 99) is spaces, NCPDP510 checks to see if there is an X version of the envelope and moves any field from the X envelope to the actual envelope.

See Chapter 4, “Program Descriptions,” for a description of the NCPDP510 program.

To use the X envelopes to pull information from the partner profile, you must define all of the X envelopes (0X, GX, TX, RX, 9X) in the User Envelope file.

Note: Trying to pass data that has the 0X and TX segment but no GX or 9X to the NCPDP510 reformat program will not work. You do not necessarily have to pull information from the partner profile for all of the X envelopes, but you must define all of them in the User Envelope file so that they will be generated by the Outbound Mapper.

The following diagram illustrates how to set up your X envelopes on the Version Envelope Specification screen. Note the following requirements.

- The 0X envelope must have a Level of BI to denote a beginning interchange envelope.
- The 0X envelope must have an Associated Trailer of 9X.
- The GX envelope must have a Level of BG to denote a beginning group envelope.
- The TX and RX envelopes must have a Level of BT to denote a beginning transaction envelope.
- The 9X envelope must have a Level of EI to denote an ending interchange envelope.
- The 9X envelope must have an Associated Header of 0X.
- All X envelopes must have a Segment ID Start value of 3 and a Segment ID Length value of 2.

```

Add Delete Update Version/outbound-specification
EDIM190 2.12_____ USER ENVELOPE SPECIFICATION          XXX  12/01/2005
                                                              12:00:00

Starting Segment ID.: 0X_____

A ---Segment-- -Seg ID- -Env- -Usr ID- -Prt ID- -Associated- Ver  Last Updt
   ID   Mod  Start Ln Lvl D  Start Ln  Start Ln Hdr/Trl  Mod Spc  Date User
-----
GX     _   _   3  2  BG B  _   _   _   _   _   _   Y  062801 XXX
PHD    _   _   78  3  BI B  _   _   1 15   _   _   Y  010698 XXX
RX     _   _   3  2  BT B  _   _   _   _   _   _   Y  071101 XXX
THD    _   _   78  3  BT B  _   _   _   _   _   _   Y  042897 XXX
TX     _   _   3  2  BT B  _   _   _   _   _   _   Y  071101 XXX
0X     _   _   3  2  BI B  _   _   _   _   9X   _   Y  071101 XXX
20     _   _   1  3  BI B  _   _   8  9  99   _   Y  041796 XXX
20G    _   _   1  3  BG B  _   _   _   _   99G  _   N  041796 XXX
20T    _   _   1  3  BT B  _   _   _   _   99T  _   N  041796 XXX
9X     _   _   3  2  EI B  _   _   _   _   0X   _   Y  062801 XXX

STATUS..ADD: 1 DEL: 0 UPD: 0

Enter PF1=Help          PF3=Exit
      PF7=Bwd   PF8=Fwd
    
```

Version/Outbound Specifications

This section contains diagrams to illustrate how to enter your Version/Outbound Specifications for each of the X envelopes. Please note that these are only examples. How you build your X envelopes depends on which elements on the envelope segments you want to pull from the partner profile.

Example 1: 0X Segment

The following diagram illustrates the Version/Outbound Specification screen for the 0X segment.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: 0X          Modifier:          Length:  ___74
Default Version ID...: _____ Agency...:  ___ Transaction ID: _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....:  ___49        _2          Transaction ID.....: _____
Sender ID.....:   ___5         15          Receiver ID.....:  ___51         15
Reference Number...:  ___29        _7          Generic Element 1...:  ___48         _1
Generic Element 2...: _____
Generic Element 4...: _____
Generic Element 6...: _____
Generic Element 8...: _____
Generic Element 10...: _____
Current Time.....:  ___44         _4          Current Date.....:  ___36         _8
Current Date Format: YY
Last Update Date: 12/01/05 Time: 12:00:00 User: XXX

Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                        PF10=Updt
    
```

These values are described below.

Note the following when reviewing this example:

- The segment length is 74; the length of the 0X segment will always be 74.
- If you review the record layout for the 0X segment in the following table, you will see that the following elements will be populated on the 0X segment:
 - Version release (version ID)
 - Sender ID
 - Receiver ID
 - Batch number (reference number)
 - File type (generic element 1)
 - Creation date (current date)
 - Creation time (current time)

0X – Batch Transaction Header Definition User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Sender ID	AN	5	24
Batch Number	N	29	7
Creation Date	N	36	8
Creation Time	N	44	4
File Type	AN	48	1
Version Release	AN	49	2
Receiver ID	AN	51	24

- If you want to pull the sender and receiver IDs from the partner profile for the 0X segment, you must take one limitation into account. The length of the sender and receiver IDs on the 0X /00 segment is 24 characters. The maximum length you can enter in the Sender ID and Receiver ID fields on the EDIM191 screen is 15. Therefore, if you use these fields, your sender and receiver IDs can only have 15 characters. The Mapper pads the right-most nine positions with spaces.
- You can use a generic element to pull the receiver and sender IDs from the partner profile, but the maximum length allowed for a generic element is 20. Therefore, if you need to send a full 24 character sender or receiver ID on the outgoing 00 segment, you must map the value from your application data.

Example 2: GX Segment

The following diagram illustrates the Version/Outbound Specification screen for the GX segment.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: GX          Modifier:          Length:  __14
Default Version ID...: _____ Agency...:  __ Transaction ID: _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....: _____ Transaction ID.....: _____
Sender ID.....: _____ Receiver ID.....: _____
Reference Number...: 5         10         Generic Element 1...: _____
Generic Element 2...: _____ Generic Element 3...: _____
Generic Element 4...: _____ Generic Element 5...: _____
Generic Element 6...: _____ Generic Element 7...: _____
Generic Element 8...: _____ Generic Element 9...: _____
Generic Element 10...: _____ Current Date.....: _____
Current Time.....: _____ Current Date Format:  __

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX

Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                        PF10=Updt
    
```

These values are described below.

Note the following when reviewing this example:

- The segment length is 14; the length of the GX segment will always be 14.
- If you review the record layout for the GX segment in the following table, you will see that the following element will be populated on the GX segment.
- Transaction Reference Number (Reference Number)

GX – Batch Transaction Detail Definition User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Transaction Reference Number	AN	5	10

Example 3: TX Segment

The following diagram illustrates the Version/Outbound screen for the TX segment.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: TX          Modifier:          Length:  __59
Default Version ID...: NCPDP51_____ Agency...: SC_ Transaction ID: _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....:  __11        __2          Transaction ID.....: _____
Sender ID.....:  _____ Receiver ID.....:  _____
Reference Number...:  __15        __10         Generic Element 1...:  __5         __6
Generic Element 2...:  __13        __2          Generic Element 3...:  __50        __10
Generic Element 4...:  _____ Generic Element 5...:  _____
Generic Element 6...:  _____ Generic Element 7...:  _____
Generic Element 8...:  _____ Generic Element 9...:  _____
Generic Element 10...: _____ Current Date.....:  _____
Current Time.....: _____ Current Date Format:  __

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX
USER ENVELOPE RECORD UPDATED
Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                        PF10=Updt
    
```

These values are described below.

Note the following when reviewing this example:

- The segment length is 59; the length of the TX segment will always be 59.
- If you review the record layout for the TX segment in the following table, you will see that the following elements will be populated on the TX segment.
 - Version release (version ID)
 - Control number (reference number)
 - BIN number (generic element 1)
 - Transaction code (generic element 2)
 - Vendor certification ID (generic element 3)

TX – Transaction Header Segment User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
BIN Number	N	5	6
Version Release	AN	11	2
Control Number	AN	15	10
Service Provider ID Qualifier	AN	25	2
Service Provider ID	AN	27	15
Date of Service	N	42	8
Vendor Certification ID	AN	50	10

Example 4: RX Segment

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....:  RX                      Modifier:          Length:  ___31
Default Version ID...: _____ Agency...:  ___ Transaction ID: _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....:  ___5          ___2          Transaction ID.....:  _____
Sender ID.....:  _____ Receiver ID.....:  _____
Reference Number...:  _____ Generic Element 1...:  _____
Generic Element 2...:  _____ Generic Element 3...:  _____
Generic Element 4...:  _____ Generic Element 5...:  _____
Generic Element 6...:  _____ Generic Element 7...:  _____
Generic Element 8...:  _____ Generic Element 9...:  _____
Generic Element 10...:  _____ Current Date.....:  _____
Current Time.....:  _____ Current Date Format:  ___

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX
USER ENVELOPE RECORD UPDATED
Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                        PF10=Updt
    
```

These values are described below.

Note the following when reviewing this example:

- The segment length is 31; the length of the RX segment will always be 31.

- If you review the record layout for the RX segment in the following table, you will see that the following element will be populated on the RX segment.
- Version release (version ID)

RX – Response Header Segment User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Version Release	AN	5	2
Service Provider ID Qualifier	AN	7	2
Service Provider ID	AN	9	15
Date of Service	N	24	8

Example 5: 9X Segment

The following diagram illustrates the Version/Outbound Specification screen for the 9X segment.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: 9X                Modifier:                Length:  __11
Default Version ID...: _____  Agency...:  __ Transaction ID: _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....: _____
Sender ID.....: _____
Reference Number...:  __5          7
Generic Element 2..: _____
Generic Element 4..: _____
Generic Element 6..: _____
Generic Element 8..: _____
Generic Element 10.: _____
Current Time.....: _____

Transaction ID.....: _____
Receiver ID.....: _____
Generic Element 1..: _____
Generic Element 3..: _____
Generic Element 5..: _____
Generic Element 7..: _____
Generic Element 9..: _____
Current Date.....: _____
Current Date Format:  __

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX

Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                        PF10=Updt
    
```

These values are described below.

Note the following when reviewing this example:

- The segment length is 11; the length of the 9X segment will always be 11.

- If you review the record layout for the 9X segment in the following table, you will see that the Batch number (reference number) element will be populated on the 9X segment.

9X – Batch Transaction Trailer Definition User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Batch Number	N	5	7

Setting Up Partner Profiles

Partner Profile set-up is different for sending outbound NCPDP data depending on whether you have defined user envelopes in the User Envelope file for outbound processing.

See the “Defining User Envelopes” section previously in this appendix for more information about user envelopes.

If you are mapping all fields of the envelopes (00,G1, TH, RH, 99) from your application (if you are not using the X envelopes), you must **NOT** define any outbound envelope IDs at the control (interchange), group or transaction levels on your partner profile. The following three diagrams illustrate an example of how to set up a partner that will not be using the X envelopes.

- Note:** On these screens, the value in the Envelope field must be spaces. If you enter a value other than spaces, the system attempts to generate envelopes.

```

EDIM011 _____ CONTROL INFORMATION XXX 12/01/2005
                                           12:00:00

      NCPDP PARTNER WITHOUT USER ENVELOPE
Part ID: RAENCPDPWO                               Qual:
Multiple Envelope Id:
Outbound envelope information for Generic Interchange:

Envelope ID...: _____ Modifier.....: _
Sender ID.....: _____
Receiver ID...: _____
Version ID...: _____
Transaction ID: _____
Reference.....: _____
Gen Element 1.: _____ Gen Element 2.: _____
Gen Element 3.: _____ Gen Element 4.: _____
Gen Element 5.: _____ Gen Element 6.: _____
Gen Element 7.: _____ Gen Element 8.: _____
Gen Element 9.: _____ Gen Element 10.: _____

Enter PF1=Help          PF3=Exit PF4=Ctrl      PF5=GDir
                        PF10=Updt      PF14=Info
    
```

```

EDIM034 1.2.2_____ GROUP INFORMATION XXX 12/01/2005
                                           12:00:00

      NCPDP PARTNER WITHOUT USER ENVELOPE
Part ID: RAENCPDPWO                               Qual:
Group ID: B1Q_____ Multiple Env Id:
Outbound envelope information for Generic Group:

Envelope ID...: _____ Modifier.....: _
Sender ID.....: _____
Receiver ID...: _____
Version ID...: NCPDP51_____
Transaction ID: B1Q_____ Reference.....: _____
Gen Element 1.: _____ Gen Element 2.: _____
Gen Element 3.: _____ Gen Element 4.: _____
Gen Element 5.: _____ Gen Element 6.: _____
Gen Element 7.: _____

Enter PF1=Help          PF3=Exit PF4=Ctrl      PF5=TDir      PF6=Next Grp
                        PF9=Add PF10=Updt PF11=Del      PF14=Info
    
```

```

EDIM044 1.2.3_____ TRANSACTION INFORMATION          XXX  12/01/2005
                                                    12:00:00

          NCPDP PARTNER WITHOUT USER ENVELOPE
Part ID: RAENCPDPWO                               Qual:
Transaction ID: B1Q___ Multiple Env Id:

Translation Map ID Inbound..: _____ Outbound: _____
Application Databank Inbound: D (F/D/N) Outbound: D (F/D/N)

Outbound envelope information for Generic Transaction:
Envelope ID..: _____ Modifier.....: -
Sender ID....: _____ Receiver ID...: _____
Version ID...: NCPDP51_____ Reference.....: _____
Gen Element 1: _____ Gen Element 2.: _____
Gen Element 3: _____ Gen Element 4.: _____
Gen Element 5: _____

Enter PF1=Help          PF3=Exit PF4=Group          PF5=Name          PF6=Nxt Tran
PF9=Add PF10=Updt PF11=Del          PF14=Info

```

If you plan to pull information from the partner profile to by using the X envelopes, you must define the outbound envelope IDs at the control (interchange), group and transaction levels on the partner profile. Enter the OX envelope at the control (interchange) level, the GX envelope at the group level, the TX envelope at the transaction level for request transactions, and the RX envelope at the transaction level for the response transaction.

The following diagrams illustrate an example of a partner that will be building the X envelopes to pull information from the partner profile.

Note: The outbound Envelope ID must be 0X on the following screen.

```

EDIM011 _____ CONTROL INFORMATION XXX 12/01/2005
                                           12:00:00

      NCPDP PARTNER WITH USER ENVELOPES
Part ID: RAENCPDPW                               Qual:
Multiple Envelope Id:
Outbound envelope information for Generic Interchange:

Envelope ID...: 0X                               Modifier.....: _
Sender ID.....: TESTSENDER_____
Receiver ID...: TESTRECEIVER_____
Version ID....: 11_____
Transaction ID: _____
Reference.....: 000000000000000012
Gen Element 1.: T_____ Gen Element 2.: _____
Gen Element 3.: _____ Gen Element 4.: _____
Gen Element 5.: _____ Gen Element 6.: _____
Gen Element 7.: _____ Gen Element 8.: _____
Gen Element 9.: _____ Gen Element 10: _____

Enter PF1=Help          PF3=Exit PF4=Ctrl    PF5=GDir
                        PF10=Updt  PF14=Info
    
```

Note: The outbound Envelope ID must be GX on the following screen.

```

EDIM034 1.2.2 _____ GROUP INFORMATION XXX 12/01/2005
                                           12:00:00

      NCPDP PARTNER WITH USER ENVELOPES
Part ID: RAENCPDPW                               Qual:
Group ID: B1Q_____ Multiple Env Id:
Outbound envelope information for Generic Group:

Envelope ID...: GX                               Modifier.....: _
Sender ID.....: _____
Receiver ID...: _____
Version ID....: NCPDP51_____
Transaction ID: B1Q_____ Reference.....: 000000000000000012
Gen Element 1.: _____ Gen Element 2.: _____
Gen Element 3.: _____ Gen Element 4.: _____
Gen Element 5.: _____ Gen Element 6.: _____
Gen Element 7.: _____

Enter PF1=Help          PF3=Exit PF4=Ctrl    PF5=TDir    PF6=Next Grp
                        PF9=Add  PF10=Updt PF11=Del    PF14=Info
    
```

Note: The outbound Envelope ID must be TX or RX on the following screen.

```

EDIM044 1.2.3_____ TRANSACTION INFORMATION          XXX  12/01/2005
                                                    12:00:00

          NCPDP PARTNER WITH USER ENVELOPES
Part ID:  RAENCPDPW                               Qual:
Transaction ID:  B1Q___ Multiple Env Id:

Translation Map ID Inbound...: _____ Outbound:  NCPDPB1QE_
Application Databank Inbound:  D (F/D/N)      Outbound:  D (F/D/N)

Outbound envelope information for Generic Transaction:
Envelope ID...:  TX_                               Modifier.....:  _
Sender ID....:  _____ Receiver ID...:  _____
Version ID...:  51_____ Reference.....:  000000000000000012
Gen Element 1:  606BIN_____ Gen Element 2.:  B1_____
Gen Element 3:  3333333333_____ Gen Element 4.:  _____
Gen Element 5:  _____

Enter PF1=Help          PF3=Exit PF4=Group          PF5=Name          PF6=Nxt Tran
                        PF9=Add PF10=Updt PF11=Del          PF14=Info
    
```

Preparing to Run Outbound Processing

Preparations for Gentran:Basic

Note: If you are not using Gentran:Basic, skip this section and proceed to the next section, Preparations for Gentran:Realtime.

Once you have set up your application definition, transaction map, user envelopes (optional), and partner profile, you are ready to run your outbound flow. This involves two Gentran:Basic/Structure programs, the Outbound Mapper (EBDI042) and the Outbound NCPDP Reformat program (NCPDP510).

Specific parameters are required to run the NCPDP data through the Outbound Mapper.

See Chapter 4, “Program Descriptions,” for detailed information about the program.

Record #1 of the SYS001 parameter file

Field	Start Position	End Position	Value	Notes
Standard Type	46	46	V	Variable length SYS098 output file.
Maximum Length	47	51	05100	The SYS098 output file maximum record length.

Record #2 of the SYS001 parameter file

Field	Start Position	End Position	Value	Notes
Envelope Generation Suppression Switch	80	80	<space>	Instructs the Outbound Mapper to generate envelopes. This field must contain a space value whether or not you use the X envelopes.

Record #4 of the SYS001 parameter file

Field	Start Position	End Position	Value	Notes
Group Envelope Always Switch	8	8	Y	Instructs the Outbound Mapper to generate a group level envelope (GX) whenever a transaction level envelope (TX or RX) is generated. This field must be set to Y only if the X envelopes are in use.

Following the Outbound Mapper (EBDI042), you must run the NCPDP510 program. This program reformats the output of the Mapper into true NCPDP format. The NCPDP510 program:

- Suppresses leading zeros in numeric fields.
- Removes trailing spaces from alphanumeric fields.
- Places text indicators, field separators, and group separators in the appropriate locations.
- Compresses data and wraps it according to the provided parameters.

See Chapter 4, “Program Descriptions,” for the detailed program description information.

Preparations for Gentran:Realtime

Once you have set up your application definition, transaction map, user envelopes (optional), and partner profile, you are ready to run your outbound flow through Gentran:Realtime. You must set up a Shell Path to execute the Outbound Mapper (EDIR042) and the Outbound NCPDP Post-Processing program (EDIRNCPO).

See the Gentran:Realtime for zSeries Release 6.4 *User's Guide* for information about the screens used to set up a shell path.

Specific parameters are required to run the NCPDP data through the Outbound Mapper.

You must enter the following parameter into the Outbound Mapper-2 Path Maintenance screen (EDIM84I).

Field	Value	Notes
Envelope GEN Switch	N	Generate envelopes

See Chapter 5, “Gentran:Realtime Program Descriptions,” for detailed information about the program.

```

EDIM84I _____ OUTBOUND MAPPER-2 PATH MAINTENANCE XXX 12/01/2005
                                                    12:00:00

Path ID.....: 300M STRUCTURE OUTBOUND - FIXED GENTEST

Document Tracking.....: _ (1=Print Error Audit/2=Print Audit for all)
Support Quote Switch.....: _ (Y/Blank)
Map blank Subfield.....: _ (Y/N)
CNTL Pass Thru ind.....: _ (Y/I/Blank)
Application Reference Load.: _ (0/1/Blank)
Envelope GEN Switch.....: N (Y=CNTLrecs/N=Env)
Interchange Version OFF....: _ (Y/Blank)
Group Version OFF.....: _ (Y/Blank)
Trans Version OFF.....: _ (Y/Blank)
Multi Env enable Override..: _ (Y/Blank)
Multiple Envelope id.....: _____
Default Interchange Ver....: _____

                                                    Last Update Date: 12/01/05
                                                    Time: 12:00:00
                                                    User: XXX

Enter PF1=Help          PF3=Exit PF4=Dir          PF6=Shell
      PF7=Map1 PF8=Map3          PF10=Updt PF11=Del
    
```

You must enter the following parameters into the Outbound Mapper-4 Path Maintenance screen (EDIM84J).

Field	Value	Notes
Standard Type	F	Fixed Format standard
Maximum Len	05100	Maximum record length
Always Generate New Group per Tran	Y	Generate group envelope for each transaction

```

EDIM84J _____ OUTBOUND MAPPER-4 PATH MAINTENANCE      XXX 12/01/2005
                                                    12:00:00

Path ID.....: 300M  STRUCTURE OUTBOUND - FIXED GENTEST

Structure:
Standard Type.....: F (F/V/blank)
Maximum Len.....: 05100
Initialize Numerics.....: _ (Y/Blank)
DBK Level.....: 1 (0=No/1=Full/2=Dir)
Always Generate New Group per Tran.: Y (Y/Blank)

Viewpoint:
Exception Tracking.....: N (Y=ON/N=OFF)
Tracking Management.....: N (Y=ON/N=OFF)

Last Update Date: 12/01/05
Time: 12:00:00
User: XXX

Enter PF1=Help          PF3=Exit PF4=Dir          PF6=Shell
      PF7=Map3 PF8=Env          PF10=Updt
    
```

Following the Outbound Mapper (EDIR042), the Outbound Post-Processor (EDIRNCPO) executes. This program reformats the output of the Mapper into true NCPDP format. The EDIRNCPO program:

- Suppresses leading zeros in numeric fields.
- Removes trailing spaces from alphanumeric fields.
- Places text indicators, field separators, and group separators in the appropriate locations.
- Compresses data and wraps it according to the provided parameters.

See Chapter 5, “Gentran:Realtime Program Descriptions,” for detailed information about the program.

You must enter the following parameters into the NCPDP Outbound Parm Maintenance screen (EDIM84G). The values shown here are examples. The specific values you enter will differ according to your business requirements.

Field	Value	Notes
Record Length		The maximum record length for compressed and wrapped NCPDP records.
Compress		Compression Level


```
EDIM84G _____ NCPDP OUTBOUND PARMS MAINTENANCE      XXX 12/01/2005
                                                    12:00:00
Path ID.....: 300N  OUTBOUND STRUCTURE - FIXED ENV TEST
Outbound Flow

NCPDP Reformat Parameters:

Record Length....: 00100
Compress.....: F      (F=Full, T=Transmission)

Last Update Date.: 12/01/05
                  Time.: 12:00:00
                  User.: XXX

Enter PF1=Help          PF3=Exit PF4=Dir          PF6=Shell
PF9=Add PF10=Updt PF11=Del
```

Processing Inbound NCPDP Data

This section describes inbound system flow for translating data into batch NCPDP version 5 release 1 data.

Before Gentran:Structure can process NCPDP data, the data must be translated into a fixed-format composition defined in the standards files. For inbound processing, Gentran:Structure reformats incoming data into a Gentran-specified fixed format structure that can be processed through Gentran:Structure and ultimately be translated to your application data.

Note: See the Gentran online standards files under version NCPDP51, agency SC, for the layout of the Gentran fixed format structure for NCPDP data.

Processing inbound NCPDP data through Gentran:Structure requires extra set-up in addition to normal Gentran procedures. You must complete the following tasks according to the information provided in the next section of this chapter:

- Define and build your application definition.
- Define and build your transaction map.
- Define user envelopes.
- Set up your partner profile.
- Prepare to run the inbound process.

Figure B.2 illustrates the system flow that you will use to translate your incoming batch NCPDP version 5 release 1 data into your application data. The requirements for the above tasks can be found following the diagram.




Figure B.2 System Flow – Translating Batch NCPDP Data into Application Data

Define and Build your Application Definition

You use the online mapping subsystem to enter your application definition.

On the Application Data ID screen (EDIM552), the value in the functional group field must match the NCPDP51 transaction ID to which this application data will be translated. The following diagram illustrates the screen.

```

EDIM552 5.1.2 _____ APPLICATION DATA ID          XXX 12/01/2005
                                                    12:00:00

Application Data ID.....: RAENCPDP2_  Send or Receive: R
Division Code.....: 000
Description.....: NCPDP_APPLICATION_DEFINITION__
Functional Group.....: B1Q  _____

Fixed or Variable Length..: F (F/V)
Record Length.....: 00255
Record Type Start Pos....: 00001          Length.....: 03
Inbound Pass-Thru.....: _
Underscore Character.....: _
Update Allowed.....: Y

Last Update User.....: XXX          Date.....: 12/01/05
                                                    Time.....: 12:00:00

Enter PF1=Help PF2=Copy  PF3=Exit PF4=Dir          PF5=Records  PF6=Refer
PF9=Add PF10=Updt PF11=Del PF12=NuMap PF13=Envel
  
```

Define and Build your Transaction Map

You use two initial screens to add a new Gentran:Structure map using the online mapping subsystem.

Set up the first screen, the Transaction Maintenance screen (EDIM503), with the following information:

In This Field...	Enter This Value
Standards Version	NCPDP51
Agency	SC
Transaction Set	(A transaction ID found in version NCPDP51)
Envelope Type	D (this indicates that this is a user-defined standard)
Standard Type	F (indicates a fixed-format standard)

The following diagram illustrates the screen.

```

EDIM503 5.2.2_____      TRANSACTION MAINTENANCE      XXX 12/01/2005
                                                                12:00:00

Transaction ID.....: NCPDPB1Q__      Send or Receive(S/R)...: R
Division Code.....: 000
Description.....: BILL REQ. INBOUND_____
Standards Version.....: NCPDP51_____ Agency: SC_
Transaction Set.....: B1Q__
Transaction Set Release...: _ (0-9, ANA Tradacoms Only)
Transaction Status.....: T (D=Development, T=Test, P=Production)
Use Code.....: G (G=General, P=Partner Specific)
Envelope Type.....: D (E=Edifact, X=X12, U=UCS, G=GS, A=ANA, D=User)
Application Data ID.....: RAENCPDP2
Application Selection Field Values: _____

Standard Type.....: F (V=Variable, F=Fixed)
RSGRSG Level.....: _ (1/2/ ANA Tradacoms Only)
Underscore Character.....: _
Update Allowed.....: Y Job Name: _____

Enter PF1=Help PF2=Fixed PF3=Exit PF4=Dir PF5=Segments PF6=Copy
      PF7=Rpt PF9=Add PF10=Updt PF11=Del PF12=NuMap PF14=Info
    
```

When you press **PF9=Add** to add the new map, the system displays the Transaction Maintenance – Gentran:Structure screen (EDIM516). Enter the following information on this screen:

In This Field...	Enter This Value
Segment ID Start	3
Segment ID Length	2

The following diagram illustrates the screen.

```

EDIM516 _____ TRANSACTION MAINTENANCE                XXX 12/01/2005
              (Gentran:Structure)                          12:00:00

Transaction ID.....: NCPDPB1Q                S/R.....: R
Division Code.....: 000
Description.....: BILL REQ. INBOUND
Standards Version.....: NCPDP51                Agency....: SC
Transaction Set.....: B1Q
Transaction Set Release...: (0-9, ANA Tradacoms Only)

Envelope Format.....: F                (V=Variable, F=Fixed)
Segment ID Start.....: 3                (1 to 32743)
Segment ID Length.....: 2                (1 to 10)

Last Update Date.....: 12/01/05
Time.....: 12:00:00
User.....: XXX

Enter PF1=Help                PF3=Exit PF4=Maint        PF5=Segments
                                PF10=Updt

```

Once the transaction map definition is complete, copy the desired segments for the transaction you will be processing from the NCPDP51 version and map the data as you would with any other Gentran map.

Because the envelope segments (00, G1, TH, RH, 99) are a part of the Gentran transaction, you can map fields from the envelope segments to your application just as you would for any other segment.

The following diagram illustrates the concept.

```

Copy Delete Info Loop-end Select Update
EDIM504 5.2.5_____ SEGMENTS XXX 12/01/2005
                                     12:00:00

Transaction Id...: NCPDPB1Q__ S/R...: R Trans Set: B1Q
Version ID.....: NCPDP51 Agency: SC
Starting Seg ID..: _____ Area...: _ Sequence.: _____

A Seq  A Segment M  Max  Loop  Max  Description  User  W
No  C  ID  Ver C  Use  ID  Loop  User  Exit  F
- 00100 H 00 00 M 1 1 1 BATCH_TRANSACTION_HEADER
- 00200 H G1 00 M 1 1 1 BATCH_TRANSACTION_DETAIL
- 00300 H TH 00 M 1 1 1 TRANSACTION_HEADER_SEGMEN
- 00500 H 04 00 M 1 1 1 INSURANCE_SEGMENT
- 00600 D 07 00 M 1 1000 4 CLAIM_SEGMENT
- 00605 D 11 00 M 1 1000 PRICING
- 01700 S 99 00 M 1 1 1 BATCH_TRANSACTION_TRAILER
-
-
-

END OF SEGMENTS
Enter PF1=Help PF3=Exit PF4=Trans PF5=Elem Map PF6=Ext Map
PF7=Bwd PF8=Fwd
    
```

Defining User Envelopes

The Gentran:Structure Inbound Pre-processor (EBDI083) requires certain information about the envelope segments that appear in the incoming NCPDP data be available to Gentran so that it will recognize them as envelopes. These envelopes provide trading partner, version and transaction ID information.

User envelopes in the Gentran:Structure User Envelope file provide EBDI083 with required information about the envelope segments. Because the data sent to EBDI083 is in the Gentran NCPDP51 fixed-format structure, you must define the header envelope segments that will be presented to EBDI083 (00, G1, TH and RH) in the User Envelope file. There is no need to define the transaction definition trailer (99) segment as a user envelope.

00 – Batch Transaction Header Definition User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Transmission Type	AN	5	1
Sender ID	AN	6	24
Batch Number	N	30	7
Creation Date	N	37	8
Creation Time	N	45	4
File Type	AN	49	1

Version Release	AN	50	2
Receiver ID	AN	52	24
G1 – Batch Transaction Detail Definition User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Transaction Reference Number	AN	5	10
TH – Transaction Header Segment User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
BIN Number	N	5	6
Version Release	AN	11	2
Transaction Code	AN	13	2
Control Number	AN	15	10
Transaction Count	AN	25	1
Service Provider ID Qualifier	AN	26	2
Service Provider ID	AN	28	15
Date of Service	N	43	8
Vendor Certification ID	AN	51	10
Gentran Transaction ID	AN	61	3
Gentran Version	AN	64	12
Gentran Agency	AN	71	2
RH – Response Header Segment User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Version Release	AN	5	2
Transaction Code	AN	7	2
Transaction Count	AN	9	1
Header Status	AN	10	1

Service Provider ID Qualifier	AN	11	2
Service Provider ID	AN	13	15
Date of Service	N	28	8
Gentran Transaction ID	AN	36	3
Gentran Version	AN	39	12
Gentran Agency	AN	46	2

Transaction Header Definition Segment (00)

The transaction header definition segment (00) provides the trading partner (sender and receiver) information to EBDI083. When defining the 00 segment as an envelope in the User Envelope file, you must provide information indicating where in the 00 segment the trading partner information can be found.

The following diagram illustrates the User Envelope Specification screen for the 00 segment.

```

Add Delete Update Version/outbound-specification
EDIM190 2.12_____ USER ENVELOPE SPECIFICATION          XXX  12/01/2005
                                                              12:00:00

Starting Segment ID...: 00_____

A ---Segment-- -Seg ID- -Env- -Usr ID- -Prt ID- -Associated- Ver  Last Updt
   ID   Mod  Start Ln Lvl D  Start Ln  Start Ln Hdr/Trl  Mod Spc  Date User
-----
  00           3  2  BI  I    52 24     6 24           N 120104 XXX
  20           1  3  BI  B           8 9 99           Y 120104 XXX
  20G          1  3  BG  B           99G           N 120104 XXX
  20T          1  3  BT  B           99T           N 120104 XXX
  9X           3  2  EI  B           0X           Y 120104 XXX
  99           1  3  EI  B           20           N 120104 XXX
  99G          1  3  EG  B           20G           N 120104 XXX
  99T          1  3  ET  B           20T           N 120104 XXX
-----
END OF USER ENVELOPE RECORDS
Enter PF1=Help          PF3=Exit
      PF7=Bwd  PF8=Fwd
    
```

These values are described below.

Refer to the following information when you define the 00 segment in User Envelope file:

- The Segment ID Starting Position must have a value of 3.
- The Segment ID Length must have a value of 2.
- The 00 segment must be set up as a beginning interchange (BI) level envelope because it is the highest level of envelope present in the data.

- Because the 00 segment will only be used as an envelope for inbound processing, the Envelope Direction field should be set to I for inbound.
- For inbound data, the User ID Start and Length fields refer to the receiver ID. On the 00 segment, the receiver ID is located in position 52 for a length of 24.
- For inbound data, the Partner ID Start and Length fields refer to the sender ID. On the 00 segment, the sender ID is located in position 6 for a length of 24.

00 – Batch Transaction Header Definition User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Transmission Type	AN	5	1
Sender ID	AN	6	24
Batch Number	N	30	7
Creation Date	N	37	8
Creation Time	N	45	4
File Type	AN	49	1
Version Release	AN	50	2
Receiver ID	AN	52	24

Transaction Detail Definition Segment (G1)

Even though the transaction detail definition (G1) segment does not provide trading partner, version or transaction ID information, you must define it as a user envelope.

The following diagram illustrates the User Envelope Specification screen for the G1 segment.

```

Add Delete Update Version/outbound-specification
EDIM190 2.12_____ USER ENVELOPE SPECIFICATION      XXX   12/01/2005
                                                    12:00:00

Starting Segment ID...: G1_____

A ---Segment-- -Seg ID- -Env-  -Usr ID-  -Prt ID-  -Associated- Ver  Last Updt
   ID      Mod  Start Ln Lvl D  Start Ln  Start Ln  Hdr/Trl  Mod  Spc  Date User
-----
G1          3  2  BG  I          _____  _____  _____  _____  _____  Y  120104 XXX
PHD          78  3  BI  B          _____  _____  _____  _____  _____  Y  120104 XXX
RH          3  2  BT  I          _____  _____  _____  _____  _____  Y  120104 XXX
RX          3  2  BT  B          _____  _____  _____  _____  _____  Y  120104 XXX
TH          3  2  BT  I          _____  _____  _____  _____  _____  Y  120104 XXX
THD         78  3  BT  B          _____  _____  _____  _____  _____  Y  120104 XXX
TX          3  2  BT  B          _____  _____  _____  _____  _____  Y  120104 XXX
OX          3  2  BI  B          _____  _____  _____  9X          _____  Y  120104 XXX
OO          3  2  BI  I          52  24  _____  6  24  _____  N  120104 XXX
20          1  3  BI  B          _____  _____  _____  8  9  99          _____  Y  120104 XXX

Enter PF1=Help          PF3=Exit
      PF7=Bwd  PF8=Fwd
    
```

These values are described below.

Note the following when defining the G1 segment in the User Envelope file:

- The Segment ID Starting Position must have a value of 3.
- The Segment ID Length must have a value of 2.
- You must set up the G1 segment as a beginning group (BG) level envelope even though, in the NCPDP definition, it is truly a transaction level envelope. This is because we can not define two transaction level envelopes for the same document, and the TH and RH envelopes are the lowest level envelopes received in the data. Therefore, they must be defined as beginning transaction envelopes.
- Because the G1 segment will only be used as an envelope for inbound processing, set the envelope direction field should to I for inbound.

G1 – Batch Transaction Detail Definition User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Transaction Reference Number	AN	5	10

Databanking Feature (Optional)

If you are going to use the Gentran Databanking feature for your inbound NCPDP data, you may want to use the transaction reference number found on the G1 segment as the reference number on the databank directory file.

When you fill in the Reference Number field on the Version/Outbound Specification screen, EBDI083 pulls the transaction reference number from the G1 segment and uses it as the reference number for that document on the databank directory file. The transaction reference number on the G1 segment starts in position 5 and has a length of 10.

The following diagram illustrates the screen.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: G1          Modifier:          Length:  __14
Default Version ID...: NCPDP51_____ Agency...: SC_ Transaction ID: _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....: _____ Transaction ID.....: _____
Sender ID.....: _____ Receiver ID.....: _____
Reference Number...:  __ 5      10 Generic Element 1...: _____
Generic Element 2...: _____ Generic Element 3...: _____
Generic Element 4...: _____ Generic Element 5...: _____
Generic Element 6...: _____ Generic Element 7...: _____
Generic Element 8...: _____ Generic Element 9...: _____
Generic Element 10...: _____ Current Date.....: _____
Current Time.....: _____ Current Date Format:  __

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX

Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                        PF10=Updt
    
```

The following diagram illustrates an example of the User Reference on the databank being pulled from the Transaction Reference number on the G1 segment.

```

Select Delete
EDIM273 3.14_____  STRUCTURE DOCUMENT STATUS          XXX 12/01/2005
                                                                12:00:00

Partner ID . . . : RAENCPDPWO_____ Qual _____
Version ID . . . : _____
User Reference : _____
In/Outbound. . . : I      Databank G
From Date . . . : _____ Time _____
To Date . . . . : _____ Time _____

  Rec  Structure
A Stat Version ID   User Reference          Date      I/O Dbk
-      NCPDP51      0000000001             12/01/2005 I    G
-
-
-
-
-
-
-
-
-
END OF DOCUMENTS
Enter PF1=Help PF2=Data  PF3=Exit PF4=Dir          PF5=Detail  PF6=Nx Pr ID
      PF7=Bwd  PF8=Fwd
    
```

Transaction Header (TH) and Response Header (RH) Segments

The transaction header (TH) and response header (RH) segments provide the version and transaction ID information to EBDI083.

The following diagram illustrates the User Envelope Specification screen for the RH segment.

```

Add Delete Update Version/outbound-specification
EDIM190 2.12_____ USER ENVELOPE SPECIFICATION      XXX  12/01/2005
                                                    12:00:00

Starting Segment ID.: RH_____

A ---Segment-- -Seg  ID- -Env-  -Usr ID-  -Prt ID-  -Associated- Ver  Last Updt
   ID    Mod  Start Ln Lvl D  Start Ln  Start Ln  Hdr/Trl  Mod  Spc  Date  User
-----
RH      -    -    3  2  BT  I  -    -    -    -    -    -    Y  120104  XXX
RX      -    -    3  2  BT  B  -    -    -    -    -    -    Y  120104  XXX
TH      -    -    3  2  BT  I  -    -    -    -    -    -    Y  120104  XXX
THD     -    -    8  3  BT  B  -    -    -    -    -    -    Y  120104  XXX
TX      -    -    3  2  BT  B  -    -    -    -    -    -    Y  120104  XXX
OX      -    -    3  2  BI  B  -    -    -    -    9X  -    Y  120104  XXX
00      -    -    3  2  BI  I  52  24  6  24  -    -    N  120104  XXX
20      -    -    1  3  BI  B  -    -    8  9  99  -    Y  120104  XXX
20G     -    -    1  3  BG  B  -    -    -    -    99G  -    N  120104  XXX
20T     -    -    1  3  BT  B  -    -    -    -    99T  -    N  120104  XXX

Enter PF1=Help          PF3=Exit
      PF7=Bwd  PF8=Fwd
  
```

These values are described below.

Note the following requirements when you define the TH and RH segments in User Envelope file:

- The Segment ID Starting Position must have a value of 3.
- The Segment ID Length must have a value of 2.
- The TH and RH segments must be set up as beginning transaction (BT) level envelopes because they are the lowest level of envelope present in the data.
- Because the TH and RH segments will only be used as an envelope for inbound processing, set the envelope direction field to I for inbound. Because the User Envelope Specification screen does not have version and transaction ID information, you must use the Version/Outbound Specification screen to provide the version and transaction ID information to EBDI083.

The following diagrams illustrate the Version/Outbound Specification screen for the RH and TH segments.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: (RH)          Modifier:          Length:   __53
Default Version ID...: _____ Agency...:   ___ Transaction ID: _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....:   __39          12          Transaction ID.....: __36          _3
Sender ID.....:   _____          Receiver ID.....:   _____
Reference Number...: _____          Generic Element 1...: _____
Generic Element 2...: _____          Generic Element 3...: _____
Generic Element 4...: _____          Generic Element 5...: _____
Generic Element 6...: _____          Generic Element 7...: _____
Generic Element 8...: _____          Generic Element 9...: _____
Generic Element 10...: _____          Current Date.....:   _____
Current Time.....:   _____          Current Date Format:  _____

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX

Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                        PF10=Updt
    
```

These values are described below.

```

EDIM191 _____ VERSION/OUTBOUND SPECIFICATION          XXX 12/01/2005
                                                    12:00:00

Segment ID.....: (TH)          Modifier:          Length:   __78
Default Version ID...: _____ Agency...:   ___ Transaction ID: _____

Envelope Field      Start      Length      Envelope Field      Start      Length
-----
Version ID.....:   __64          12          Transaction ID.....: __61          _3
Sender ID.....:   _____          Receiver ID.....:   _____
Reference Number...: _____          Generic Element 1...: _____
Generic Element 2...: _____          Generic Element 3...: _____
Generic Element 4...: _____          Generic Element 5...: _____
Generic Element 6...: _____          Generic Element 7...: _____
Generic Element 8...: _____          Generic Element 9...: _____
Generic Element 10...: _____          Current Date.....:   _____
Current Time.....:   _____          Current Date Format:  _____

Last Update Date: 12/01/05 Time: 12:00:00 User: XXX

Enter PF1=Help          PF3=Exit PF4=User          PF6=Nxt Env
                        PF10=Updt
    
```

These values are described below.

Note the following when defining the version and transaction information for the RH and TH segments:

- The version ID to be used is the Gentran version ID (NCPDP51), which will be found in position 39 of the RH record and position 64 of the TH record. EBDI083 requires the actual version ID on the Gentran standards files that will be used to process the data.
- The transaction ID to be used is the Gentran NCPDP51 transaction ID (e.g. R1, B1Q, E1Q), which will be found in position 36 of the RH segment and position 61 of the TH segment. EBDI083 needs to know the actual Gentran transaction ID being used to process the data.

RH – Response Header Segment User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
Version Release	AN	5	2
Transaction Code	AN	7	2
Transaction Count	AN	9	1
Header Status	AN	10	1
Service Provider ID Qualifier	AN	11	2
Service Provider ID	AN	13	15
Date of Service	N	28	8
Gentran Transaction ID	AN	36	3
Gentran Version	AN	39	12
Gentran Agency	AN	46	2

TH – Transaction Header Segment User Envelope			
Field Description	Format	Starting Position	Length
Filler	AN	1	2
Segment ID	AN	3	2
BIN Number	N	5	6
Version Release	AN	11	2
Transaction Code	AN	13	2
Control Number	AN	15	10

Transaction Count	AN	25	1
Service Provider ID Qualifier	AN	26	2
Service Provider ID	AN	28	15
TH – Transaction Header Segment User Envelope			
Date of Service	N	43	8
Vendor Certification ID	AN	51	10
Gentran Transaction ID	AN	61	3
Gentran Version	AN	64	12
Gentran Agency	AN	71	2

Setting Up Your Partner Profile

Entering an NCPDP partner for inbound processing has no special requirements.

See the Gentran:Structure Tutorial for more information on entering Gentran:Structure partner information.

Preparing to Run Inbound Processing

Preparations for Gentran:Basic for zSeries

Note: If you are not using Gentran:Basic, skip this section and proceed to the next section, “Preparations for Gentran:Realtime.”

Once you have set up your application definition, transaction map, user envelopes, and partner profile, you are ready to run your inbound flow. This involves two Gentran:Structure programs, the Inbound NCPDP Reformat Program (NCPDP51I) and the Inbound Structure Pre-Processor (EBDI083).

First you must run the NCPDP51I program. This program reformats the inbound NCPDP data into the Gentran format of NCPDP data. Parameters provide the record length and format of the input.

Following NCPDP51I, you must run EBDI083. Specific parameters are required to run the NCPDP data through the Gentran:Structure Pre-processor.

Following the EBDI083 program, you must run the Inbound Mapper (EBDI041) to translate NCPDP data into your application data.

See Chapter 4, “Program Descriptions,” for detailed program descriptions for the Inbound Mapper for Gentran:Structure, the Inbound NCPDP Reformat Program (NCPDP51I), and the Inbound Structure Pre-Processor (EBDI083).

Setting up Parameters for Running the Structure Pre-Processor (EBDI083)

You must use the following parameters when processing NCPDP data \through EBDI083.

Parameter	Comments
RECORD FORMAT VARIABLE	The output file created by EBDI083 for NCPDP51 data will have variable record lengths.
RECORD LENGTH 05100	The maximum record length of the records is 5100 bytes.
ENVELOPE LEVEL INTERCHANGE	Since the 00 segment is set up as a beginning interchange (BI) envelope in the User Envelope file, you must instruct EBDI083 that interchange level envelopes are present in the data.
DATA ENVELOPE YES	You need EBDI083 to write the envelope (00,G1, TH and RH) segments out as true data segments. This will allow you to map all fields from these segments to your application file when the data is translated in the Inbound Mapper (EBDI041).

Preparations for Gentran:Realtime

Once you have set up your application definition, transaction map, user envelopes, and partner profile, you are ready to run your inbound flow through Gentran:Realtime.

You must set up a shell path to execute the Inbound NCPDP Pre-Processor (EDIRNCPI), the Inbound Structure Pre-Processor (EDIR083) and the Inbound Mapper (EDIR041).

See the Gentran:Realtime for zSeries Release 6.4 *User's Guide* for information about the screens used to set up a shell path.

Specific parameters are required to run the NCPDP data through the Inbound Structure PreProcessor.

You must enter the following parameters on the Fixed Format Pre-Processor Path Maintenance screen (EDIM840).

Field	Value	Notes
Record Format	1	Records are variable length
Record Length	05100	Maximum record length for NCPDP records
Envelope Level	2	Interchange level envelopes
Data Envelope	Y	Write envelopes as data segments

See Chapter 5, "Gentran:Realtime Program Descriptions," for detailed information about the program.

```

EDIM840 _____ FIXED FORMAT PRE-PROCESSOR PATH MAINTENANCE   XXX 12/01/2005
                                                    12:00:00

Path ID.....: 352P   STRUCTURE_INBOUND_PRE-PROCESSOR
Record Format..... 1           0 = Fixed 1 = Variable
Record Length..... 05100     Max of 32760
Partner ID / Qual..... /
User ID / Qual..... /
Version ID..... Agency...:
Transaction ID.....
Envelope Level..... 2           0 = Trans 1 = Group 2 = Interchange
Application By..... 0           0 = None 1 = User 2 = Partner
User Reference Segment ID.....
Segment ID Starting Position.....
Segment ID Length..... Dbk Proc. Level...: 1 0=No, 1=Full
User Reference Starting Position..... 2=Dir
User Reference Length..... Report Print Sw...: 0 0=No 1=Print
Detail Report..... 0=No 1=Yes
Data Envelope..... 1           0=No 1=Yes
Last Update Date: 12/01/05 Time: 12:00:00 User: XXX

Enter PF1=Help           PF3=Exit PF4=User           PF6=Nxt Env
                          PF10=Updt
    
```

NCPDP Data Examples

The following data examples illustrate how the NCPDP Reformat programs format the data.

Inbound Example Data

The following diagram illustrates raw batch inbound NCPDP data that is the input to the NCPDP51I reformat program.

```

00TNCDPSENDER           8976747199412011632T11NCPDPRECEIVER
G1100005432120000251B1   HDB 1120000240           0010202ABC   ? AM04 C298
7654321? AM01 C419620615 C51 C700 CAJOSEPH CBSMITH CM123 MAIN STREET CNMY OWN CO
CO CP34567 CQ2014658923 CX01 CY123456789 CZ50Z123 1C2 ? AM07 EM1 D20000075 E103
D700006094228 C802 D300 D5030 D61 D80 DE20010202 DF05 DJ1 DK00 DT1 E70000030000
ET0000030000 28EA? AM11 D90000557{ DC0000100{ DN03 DQ0000807{ DU0000807{ DX00001
00{ H71 H801 H90000150{? AM02 EY02 E939359? AM03 EZ08 DB00G2345 2E01 DL123456 DR
JONES 1E10 H5101 4EWRIGHT PM2013639572
9998767470000000009TEST MESSAGE
    
```

The following diagram illustrates NCPDP Data in the Gentran fixed format as it looks after running through the NCPDP51I reformat program.

Note: This example displays only the first 120 bytes of each record.

```

00TNCPPDSENDER          8976747199412011632T11NCPDPRECEIVER
G11000054321
TH20000251B1      HDB  1120000240      0010202ABC      B1QNCPPDP51SC
AM01CX01CY123456789      C419620615C51CAJOSEPH      CBSMITH      CM123 MAIN STREET      CNMY OWN
AM04C2987654321      0      0
AM07EM1D20000075E103D700006094228      0000000  00000000  0      E70000000030D300D5030
AM02EY02E939359
AM03EZ08DB00G2345      1E10 DRJONES      PM20136395722E01DL123456      H51014EWRIGHT
AM11D90000005EDC0000001{ 0000000{DX0000001{ 0000000{H71H801H90000001E 0000000{ 0000000{ 0000000{ 0
9998767470000000009TEST MESSAGE

```

Outbound Example Data

The following diagram illustrates application data used as input to the Outbound Mapper.

```

N00T NCPDPSENDER          0001234200106271200T11NCPDPRECEIVER
NG10000000001
NTH60600151B100000000012XXPROVIDER      20010601VENDORID
N04288-12-345678      FIRST NAME  LAST NAME      FACILITY ID
N07X1122334ZZABCDEF      000000150001030C0000010000150
N1100020000000025000000250000002500000025000
N07X5544332ZZHIZJLMNOP      000000200001030C0000040000200
N110001000000002500000025000001000000015000
N9900012340000000000TEST MESSAGE

```

The following diagram illustrates application data that has been translated into the Gentran NCPDP fixed format by the Outbound Mapper. In this example, the X User Envelopes are not used.

Note: This example displays only the first 120 bytes of each record.

```

00TNCPPDSENDER          0001234200106271200T11NCPDPRECEIVER
G10000000001
TH60600151B100000000012XXPROVIDER      20010601VENDORID  B1Q
AM04C2288-12-345678      CCFIRST NAME  CDLAST NAME      8CFACILITY I
AM07EMXD21122334E1ZZD7ABCDEF      E70000001500D301D5030
AM11D90002000{DC0000250{BE0000250{DX0002500{
AM07EMXD25544332E1ZZD7HIZJLMNOP      E70000002000D301D5030
AM11D90001000{DC0000250{BE0000250{DX0001000{
9900012340000000000TEST MESSAGE

```

The following diagram illustrates application data that has been translated into the Gentran NCPDP fixed format by the Outbound Mapper. In this example, the X User Envelopes are used.

Note: This example displays only the first 120 bytes of each record.

```

OXTESTSENDER          0000016200108140913T11TESTRECEIVER
GX0000000016
TX606BIN51B10000000016          3333333333
00T
G1
TH          2XXPROVIDER          20010601VENDORID  B1Q
AM04C2288-12-345678          CCFIRST NAME  CDLAST NAME          8CFACILITY I
AM07EMXD21122334E1ZZD7ABCDEFG          E70000001500D301D5030
AM11D90002000{DC0000250{BE0000250{DX0002500{
AM07EMXD25544332E1ZZD7HIZJLMNOP          E70000002000D301D5030
AM11D90001000{DC0000250{BE0000250{DX0001000{
99          0000000000TEST MESSAGE
9X0000016

```

The following diagram illustrates NCPDP data that has been compressed by the NCPDP510 reformat program and is ready to be sent to your trading partner.

```

00TNCPDPSENDER          0001234200106271200T11NCPDPRECEIVER
G10000000000160600151B100000000012XXPROVIDER          20010601VENDORID  ? AM04 C2288-12-345678 CCFIRST
NAME CDLAST NAME 8CFACILITY I ? AM07 EMX D21122334 E1ZZ D7ABCDEF G E71500 D31 D530? AM11 D92000{ DC25
0{ BE250{ DX2500{ DU2500{ ? AM07 EMX D25544332 E1ZZ D7HIZJLMNOP E72000 D31 D530? AM11 D91000{ DC250{
BE250{ DX1000{ DU1500{
9900012340000000006TEST MESSAGE

```


Glossary

See the Glossary in the *Gentran:Basic for zSeries Release 6.4 User's Guide* or *Technical Reference Guide* for additional terms and definitions related to Gentran processing.

Definition of Terms

Fixed-Format Standard

A fixed-format standard is one that can be defined as multiple segment types with fixed-length elements within these segments. There are no element separators or segment terminators defined for these standards. A comparison and contrast between fixed- and variable-format standards is presented in Chapter 1 of this guide.

Gentran:Control

An add-on product to Gentran:Basic that enables you to automate the EDI processing stream and prioritize processing by trading partner and/or type of document. Gentran:Control enables you to organize processing and responsiveness based upon business criteria, not system limitations. In addition, the application and communications gateways expedite the movement of documents across the batch/CICS barrier.

Gentran:Plus

A comprehensive software system that provides a seamless application-to-EDI interface. Gentran:Plus can work in conjunction with Gentran:Basic, or as a stand-alone product. Gentran:Plus contains these three subsystems: Communications, Translation, and Communications Setup and Management. Gentran:Plus can accommodate an unlimited number of transactions while using an unlimited number of EDI standards versions. It supports multiple lines with different protocols for concurrent EDI sessions. This combination of translation, communications, and mailboxing represents a highly efficient EDI resource that can be used to automate your communications needs.

Gentran:Realtime

An add-on product to Gentran:Basic that facilitates the transmission of data processing in an operating mode when data is entered in an interactive session, as opposed to a batch session. Response time is drastically reduced over batch processing, providing the competitive benefits of online speed, flexible control, and universal EDI standards to many business applications.

Gentran:Structure

An add-on product to Gentran:Basic/Realtime that enables you to define proprietary fixed-format standards using the Standards subsystem, and map to and from these standards using the Inbound and Outbound Mapping programs.

Gentran:Viewpoint

A Gentran product that consists of these two modules: Exception Management and Tracking Management. Exception Management enables you to capture exception information, notify the appropriate user, and optionally take automated action for exceptions that are specific to their EDI business needs. Tracking Management is an optional module that enables you to query on the status and history of a document as it moves through the entire end-to-end EDI environment.

Partner/Qualifier Mode

This is trading partner processing method which defines your organization and each trading partner as separate and distinct entities on the partner profile. This mode permits each trading partner to be used in multiple relationships.

Proprietary Standard

A proprietary standard is one that is developed by one or more organizations for use among themselves. These standards are not supported by any national, international, or industry standards groups. Proprietary standards can be either fixed- or variable-format.

Relationship Mode

This is trading partner processing method provides uniqueness for identification purposes that would not be possible if the trading partner was defined using the Partner/Qualifier method. This mode requires you to first identify the inter- or intra- business relationships. Each identified relationship is then defined separately and distinctly on the partner profile. This method is ideal for defining multiple entities within your organization with shared (common) trading partners.

Variable-Format Standard

A variable-format standard is one that complies to either ANSCX12, EDIFACT, or TRADACOMS syntax rules. These standards have delimited elements and delimited segments. Only significant data is transmitted. Trailing spaces and leading zeroes are eliminated. Unused data elements are not sent. A comparison and contrast between fixed- and variable-format standards is presented in Chapter 1 of this guide.

Reserved Word Constants

The following reserved word constants are available for use during Inbound Mapping of a fixed-format standard. Data will be loaded to these constant values by the Inbound Pre-Processing program if the corresponding envelope elements have been defined for inbound envelopes.

See the descriptions for the User Envelope Specification screen and the Version Outbound Specification screen in Chapter 3 of this guide for more information.

GEN-INT-SNDR	Contains the value of the Sender Element defined on the Interchange level envelope.
GEN-GRP-SNDR	Contains the value of the Sender Element defined on the Group level envelope.
GEN-TRN-SNDR	Contains the value of the Sender Element defined on the Transaction level envelope.
GEN-INT-RCVR	Contains the value of the Receiver Element defined on the Interchange level envelope.
GEN-GRP-RCVR	Contains the value of the Receiver Element defined on the Group level envelope.
GEN-TRN-RCVR	Contains the value of the Receiver Element defined on the Transaction level envelope.
GEN-INT-REF	Contains the value of the Reference Number (Control Number) Element defined on the Interchange level envelope.
GEN-GRP-REF	Contains the value of the Reference Number (Control Number) Element defined on the Group level envelope.
GEN-TRN-REF	Contains the value of the Reference Number (Control Number) Element defined on the Transaction level envelope.
GEN-INT-ELE-01	Contains the value of the Generic Element 1 defined on the Interchange level envelope.
GEN-INT-ELE-02	Contains the value of the Generic Element 2 defined on the Interchange level envelope.
GEN-INT-ELE-03	Contains the value of the Generic Element 3 defined on the Interchange level envelope.
GEN-INT-ELE-04	Contains the value of the Generic Element 4 defined on the Interchange level envelope.
GEN-INT-ELE-05	Contains the value of the Generic Element 5 defined on the Interchange level envelope.
GEN-INT-ELE-06	Contains the value of the Generic Element 6 defined on the Interchange level envelope.

GEN-INT-ELE-07	Contains the value of the Generic Element 7 defined on the Interchange level envelope.
GEN-INT-ELE-08	Contains the value of the Generic Element 8 defined on the Interchange level envelope.
GEN-INT-ELE-09	Contains the value of the Generic Element 9 defined on the Interchange level envelope.
GEN-INT-ELE-10	Contains the value of the Generic Element 10 defined on the Interchange level envelope.
GEN-GRP-ELE-01	Contains the value of the Generic Element 1 defined on the Group level envelope.
GEN-GRP-ELE-02	Contains the value of the Generic Element 2 defined on the Group level envelope.
GEN-GRP-ELE-03	Contains the value of the Generic Element 3 defined on the Group level envelope.
GEN-GRP-ELE-04	Contains the value of the Generic Element 4 defined on the Group level envelope.
GEN-GRP-ELE-05	Contains the value of the Generic Element 5 defined on the Group level envelope.
GEN-GRP-ELE-06	Contains the value of the Generic Element 6 defined on the Group level envelope.
GEN-GRP-ELE-07	Contains the value of the Generic Element 7 defined on the Group level envelope.
GEN-TRN-ELE-01	Contains the value of the Generic Element 1 defined on the Transaction level envelope.
GEN-TRN-ELE-02	Contains the value of the Generic Element 2 defined on the Transaction level envelope.
GEN-TRN-ELE-03	Contains the value of the Generic Element 3 defined on the Transaction level envelope.
GEN-TRN-ELE-04	Contains the value of the Generic Element 4 defined on the Transaction level envelope.
GEN-TRN-ELE-05	Contains the value of the Generic Element 5 defined on the Transaction level envelope.

Index

Symbols

###MAP record 3-63, 4-6, 4-8, 4-14, 4-16, 4-17
###MP2 record 3-63, 4-6, 4-8, 4-13, 4-17
###MP3 record 3-63, 4-8, 4-17
###MP4 record 3-63, 4-6, 4-8, 4-13, 4-17
###MP5 record 3-63, 4-6, 4-8, 4-13, 4-17
###MP6 record 3-63, 4-6, 4-8, 4-13, 4-17
##INSTREAM 4-21
#BI envelope (beginning interchange) 4-17
&GRPCNT 3-18
&SEGCNT 3-18, 3-24, 3-30
&SEGCNT2 3-18, 3-30
&TRNCNT 3-18

Numerics

0909 Purchase Order Layout 2-8, 2-9
0926 Invoice Layout 2-10, 2-11

A

acknowledgment, expecting
 TA1, ACI or UCI 3-13
add-on products
 see GENTRAN:Control, GENTRAN:Dataguard,
 GENTRAN:Plus, GENTRAN:Realtime,
 GENTRAN:Structure,
 GENTRAN:Viewpoint in Glossary
Agency field 3-60, 3-76, 3-84, 3-87
AISI COMPORD standard 1-9
Alias ID 4-14, 4-16
Application By parameter 4-10, 4-15, 4-16
Application Data file 4-19, 4-21
Application Data ID field 3-57
Application Data ID screen (EDIM552) 3-62
 Inbound Pass-Thru field 3-63
Application Databank Inbound field 3-28

Application Databank Outbound field 3-29
application definition
 building 2-40
 sharing 1-2
Application Definition INVFILE 2-4
Application Definition POFILE 2-4
application definitions 1-4
Application Extract file 1-8
Application file 1-13
Application Selection Field Values field 3-57
Application User-Reference Key 4-13
ASCX12 1-2, 2-4
ASCX12 purchase order 3-60
Associated Hdr/Trl field 3-43
Associated Modifier field 3-43
Audit Trail file 4-12
Audit Trail file (SYS005) 4-8

B

Backup of User Envelope file 2-39
batch communications, user envelope specifications 1-2
batch programs
 EDID553 4-46
batch translation services 1-4
Begin-Group 4-12
Begin-Group envelope level 4-12
Begin-Interchange 4-12
Begin-Interchange envelope level 4-12
Beginning Group envelope level 3-42
beginning interchange envelope 4-17
Beginning Interchange envelope level 3-42
Beginning Transaction envelope level 3-42
Begin-Transaction envelope level 4-12
business requirements, determining 2-3

C

CFG-multiple envelope flag 4-14, 4-16
Character Count field 3-78
CICS user programs
 creating input TSQs 5-6, 5-10
code translation tables
 sharing 1-2
communications, EDI 1-2
compliance-checker, user-written 1-8
COMPORD data 1-12, 4-24, 5-6
COMPORD file 4-26
Compressed and Reformatted NCPDP Data file (SYS004) 4-43
Compression parameter 4-45
Configuration file
 exception management partner default indicator 3-13
configuration strategy
 developing 2-27
 mapping configuration 2-35
Control Card file (EDICNTL) 4-46
control card options
 EDID553 4-47
Control file 4-26
Control Information - Screen 1 with Generic Header Option (EDIM015) 3-9
Control Information - Screen 2 with Generic Options (EDIM011) 3-14
 Envelope ID field 3-16
 Generic Element 1 field 3-17
 Generic Element 10 field 3-18
 Generic Element 2 field 3-17
 Generic Element 3 field 3-18
 Generic Element 4 field 3-18
 Generic Element 5 field 3-18
 Generic Element 6 field 3-18
 Generic Element 7 field 3-18
 Generic Element 8 field 3-18
 Generic Element 9 field 3-18
 Modifier field 3-17
 Multiple Envelope ID field 3-16
 Receiver ID 3-17
 Reference field 3-17
 Sender ID field 3-17
 Transaction ID 3-17
 Version ID field 3-17
control number 3-47, 3-90
creating a standard 2-12
Current Date field 3-90
Current Date Format field 3-52, 3-91

Current Date Length field 3-52
Current Date Start field 3-51
Current Time field 3-90
Current Time Length field 3-52
Current Time Start field 3-52

D

D type envelope for user-defined standard 3-38
Data Element Definition screen (EDIM160) 3-36
 Element Type field 3-37
data element listing
 JASS standard 2-21
data elements
 JASS standard 2-7
Data Envelope parameter 4-10
data extraction
 trailer envelopes 3-39
data translation tables, sharing 1-2
Databank Configuration switch 4-36
databank control card criteria 4-46
databank facility 1-4
Databank field 3-67, 3-72, 3-77, 3-82, 3-84, 3-87
Databank Inquiry operations 4-47
Databank Inquiry selection criteria 4-47
Databank Maintenance 2-39
Databank Maintenance subsystem 3-64
Databank parameter 4-10
Databank Processing Level switch 4-36
Databank Run # field 3-76
databanking performance 4-36
Date field 3-73
Dbk field 3-68, 3-73
Default Agency field 3-45
default group record 3-19
Default Transaction ID field 3-45, 3-90
Default Version ID field 3-45, 3-90
Description field 3-60, 3-85
Detail Reports parameter 4-10
developing a configuration strategy 2-11
Direction-Indicator 4-12
Division Code field 3-56, 3-60
Division field 3-76

E

-
- EBDI001 4-6, 4-19, 4-24
 - EBDI011M 1-8
 - EBDI041 1-12, 4-6, 4-19
 - EBDI042 2-39, 4-30
 - mapping parameter records (SYS001) 4-34
 - EBDI083 1-12, 2-39, 4-6, 4-19, 4-24
 - output
 - Audit Trail file 4-8
 - Intermediate file (SYS004) 4-8
 - Suspense file (SYS099) 4-8
 - parameters
 - Envelope Level GROUP 4-10
 - Envelope Level INTERCHANGE 4-10
 - Envelope Level TRANSACTION 4-10
 - Record Format FIXED 4-9
 - Record Format VARIABLE 4-9
 - Summary report (SYS006) 4-8
 - EBDI094 1-12, 2-39, 4-6, 4-24
 - EDI
 - communications 1-2
 - communications configuration 1-2
 - EDI Variable Data file 4-26
 - EDICFG 4-7, 4-20, 4-26, 4-40, 4-43, 4-46
 - EDICNTL file 4-46
 - EDID553 4-46, 4-47
 - EDIDAT file 4-26
 - EDIFACT 1-2
 - EDIIAA 4-8, 4-46
 - EDIIAA file 4-46
 - EDIIAS 4-8
 - EDIIEL 4-8
 - EDILOG 4-8
 - Processing log report 4-47
 - EDIM011 3-14
 - EDIM015 3-9
 - EDIM034 3-19
 - EDIM044 3-25
 - EDIM100 3-32
 - EDIM110 3-33
 - EDIM160 3-36
 - EDIM190 3-39
 - EDIM191 3-44
 - EDIM192 3-89
 - EDIM272 3-65
 - EDIM273 3-69
 - EDIM274 3-79
 - EDIM275 3-74
 - EDIM276 3-83
 - EDIM277 3-86
 - EDIM503 3-54
 - EDIM516 3-59
 - EDIM552 3-62
 - EDIM84G 3-108
 - EDIOAA file 4-46
 - EDIPREL 4-7
 - EDIR041 5-13
 - EDIR042 5-22
 - EDIR083 1-12
 - EDIR094 5-6
 - EDIRNCPI 5-16
 - EDIRNCPO 5-25
 - EDIRPT
 - Structure Application Databank Inquiry report 4-47
 - EDISTX
 - Structure Statistics file 4-47
 - EDISUM
 - Processing Summary report 4-47
 - EDISVER 4-7
 - EDIUENV 4-7
 - element separator 1-3
 - element type
 - D8 3-38
 - T6 3-38
 - T8 3-38
 - Element Type field 3-37
 - End-Group 4-12
 - End-Group envelope level 4-12
 - Ending Envelopes 4-12
 - ending envelopes (trailer envelope) 4-12
 - Ending Group envelope level 3-42
 - Ending Interchange envelope level 3-42
 - Ending Transaction 3-42
 - End-Interchange envelope level 4-12
 - End-Transaction 4-12
 - Env D (Direction) field 3-42
 - envelope
 - information 1-2
 - segments defined as 1-6
 - sending at interchange level 3-14
 - structures 1-2
 - user-defined 1-8
 - Envelope Definition Table 4-12
 - Envelope Direction field
 - inbound and outbound processing value 3-42
 - inbound-only value 3-42
 - outbound-only value 3-42
 - Envelope field 3-78
-

- envelope format
 - fixed segment 3-60
 - variable segment 3-60
- Envelope Format field 3-60
- envelope generation process, failure 3-14
- Envelope Generation program (EBDI011M) 1-8
- Envelope Generator routine 1-8
- Envelope Hold Table 4-12
- Envelope ID field 3-16, 3-22, 3-29
- Envelope ID, differentiating 3-17, 3-29
- Envelope Level 4-12
 - Begin-Group 4-12
 - Begin-Interchange 4-12
 - Begin-Transaction 4-12
 - Direction-Indicator 4-12
 - End-Group 4-12
 - End-Interchange 4-12
 - End-Transaction 4-12
- Envelope Level field 3-42
 - Beginning Group value 3-42
 - Beginning Interchange value 3-42
 - Beginning Transaction 3-42
 - Ending Group value 3-42
 - Ending Interchange value 3-42
 - Ending Transaction value 3-42
- Envelope Level parameter 4-10
- envelope processing 4-12, 4-27
- envelope requirement, for fixed-format standards 1-9
- envelope requirements
 - fixed-format data 3-61
- envelope segments, requirements 1-6
- envelope structure, illustration 2-6
- envelope structures 3-7
- envelope type
 - D 3-36, 3-38
 - user-defined 3-33, 3-34
- Envelope Type field 3-34, 3-57
- ERRCTL 4-7, 4-26, 4-40, 4-43, 4-46
- Error Message and Control file (ERRCTL) 4-40, 4-43, 4-46
- Error Message file 4-12
- Error report (SYS005) 4-40, 4-43
- error report processing 4-7
- Exception Management Partner Default Indicator 3-13
- Exception Management, GENTRAN:Viewpoint 3-13

F

- fictitious standard (for tutorial) 2-3
- Field Data field 3-85, 3-88
- Field Description field 3-87
- Field Length field 3-88
- Field Position field 3-88
- Field Sequence field 3-87
- Field Type field 3-87
- Fixed- and Variable-Format EDI Data file 4-26
- Fixed COMPORD file 4-26
- Fixed GENCOD file 4-26
- Fixed GM file 4-26
- fixed segment 3-60
- Fixed Standard 1-3
- fixed-block format 4-9
- fixed-format
 - COMPORD data 1-12, 4-24
 - envelope requirement 3-61
 - GENCOD data 1-12, 4-24
 - GM (CISCO) data 1-12, 4-24
 - mapping 3-59
 - output 1-8
- Fixed-Format and Variable-Format EDI Data file (SYS003) 4-26
- fixed-format data 4-24
 - databanking 4-6
 - example 1-4
 - miscellaneous 1-12
 - restrictions 1-6
- Fixed-Format EDI Data file (SYS003) 4-7
- Fixed-Format File Record Length parameter 4-32
- Fixed-Format File Type parameter 4-32
- Fixed-Format Input file 1-13
- Fixed-Format Output file 4-32
- Fixed-Format Output file (SYS098) 4-32, 4-33
- fixed-format processing, inbound 4-17
- fixed-format segment ID 3-31
- fixed-format standard
 - creating 2-12
 - example (JASS) 2-3
- fixed-format standards 1-2, 1-3
 - auditing and tracking data 1-2
 - default standard version for processing 3-90
 - defining generic envelope structures for 3-39
 - defining in Standards Maintenance 3-7
 - generic interchange envelope 3-14
 - output 1-13
 - partner look-up function 1-12
 - see Glossary G-1

segment ID rules 3-53
 setting up 2-1
 specifications 1-3
 Fld Seq field 3-85
 Format Specific Compliance Checker 4-5, 5-5
 Format Specific Envelope Generator 2-39
 format-specific
 compliance checking 1-9
 enveloping 1-8
 formatting the MAP records 4-17
 From Date field 3-72
 From Time field 3-72
 Functional Group ID 4-15

G

GEN (generic) Interchange Header Option 3-9
 GEN header option 3-7
 GEN-(INT/GRP)-ELEMENT-04 3-49
 GEN-(INT/GRP)-ELEMENT-05 3-49
 GEN-(INT/GRP)-ELEMENT-06 3-49
 GEN-(INT/GRP)-ELEMENT-07 3-50
 GEN-(INT/GRP)-ELEMENT-08 3-50
 GEN-(INT/GRP)-ELEMENT-09 3-51
 GEN-(INT/GRP/TRN)-ELEMENT-01 3-47
 GEN-(INT/GRP/TRN)-ELEMENT-02 3-47, 3-48
 GEN-(INT/GRP/TRN)-ELEMENT-03 3-48
 GEN-(INT/GRP/TRN)-ELEMENT-04 3-48
 GENCOD data 1-12, 4-24, 5-6
 GENCOD Envelope 4-26
 GENCOD file 4-26
 GEN-ELEMENT-01 3-47
 Generic Element 1 field 3-17, 3-23, 3-30
 Generic Element 1 Length field 3-47
 Generic Element 1 Start field 3-47
 Generic Element 10 field 3-18
 Generic Element 10 Length field 3-51
 Generic Element 10 Start field 3-51
 Generic Element 2 field 3-17, 3-23, 3-30
 Generic Element 2 Length field 3-48
 Generic Element 2 Start field 3-47
 Generic Element 3 field 3-18, 3-23, 3-30
 Generic Element 3 Length field 3-48
 Generic Element 3 Start field 3-48
 Generic Element 4 field 3-18, 3-23, 3-30
 Generic Element 4 Length field 3-48
 Generic Element 4 Start field 3-48
 Generic Element 5 field 3-18, 3-23, 3-30

Generic Element 5 Length field 3-49
 Generic Element 5 Start field 3-49
 Generic Element 6 field 3-18, 3-23
 Generic Element 6 Length field 3-49
 Generic Element 6 Start field 3-49
 Generic Element 7 field 3-18, 3-24
 Generic Element 7 Length field 3-50
 Generic Element 7 Start field 3-50
 Generic Element 8 field 3-18
 Generic Element 8 Length field 3-50
 Generic Element 8 Start field 3-50
 Generic Element 9 field 3-18
 Generic Element 9 Length field 3-51
 Generic Element 9 Start field 3-50
 Generic Elements 1 to 10 field 3-90
 generic envelope 3-16, 3-22, 3-29, 3-39
 definition of structure 3-39
 generic group 3-22
 generic group envelope 3-19
 generic interchange 3-16
 generic interchange envelope 3-14
 Generic Interchange Header Option 3-9
 generic transaction 3-29
 GEN-GRP-ELE-01
 see Glossary G-4
 GEN-GRP-ELE-02
 see Glossary G-4
 GEN-GRP-ELE-03
 see Glossary G-4
 GEN-GRP-ELE-04
 see Glossary G-4
 GEN-GRP-ELE-05
 see Glossary G-4
 GEN-GRP-ELE-06
 see Glossary G-4
 GEN-GRP-ELE-07
 see Glossary G-4
 GEN-GRP-RCVR 3-46
 see Glossary G-3
 GEN-GRP-REF 3-47
 see Glossary G-3
 GEN-GRP-SNDR 3-46
 see Glossary G-3
 GEN-INT- RCVR 3-46
 GEN-INT-ELE-01
 see Glossary G-3
 GEN-INT-ELE-02
 see Glossary G-3
 GEN-INT-ELE-03
 see Glossary G-3

- GEN-INT-ELE-04
 - see* Glossary G-3
- GEN-INT-ELE-05
 - see* Glossary G-3
- GEN-INT-ELE-06
 - see* Glossary G-3
- GEN-INT-ELE-07
 - see* Glossary G-4
- GEN-INT-ELE-08
 - see* Glossary G-4
- GEN-INT-ELE-09
 - see* Glossary G-4
- GEN-INT-ELE-10
 - see* Glossary G-4
- GEN-INT-ELEMENT-09 3-51
- GEN-INT-ELEMENT-10 3-51
- GEN-INT-RCVR 3-46
 - see* Glossary G-3
- GEN-INT-REF 3-47
 - see* Glossary G-3
- GEN-INT-SNDR 3-46
 - see* Glossary G-3
- GENTRAN:Basic
 - batch and realtime interaction 1-5
- GENTRAN:Basic Application Databank facility 1-2
- GENTRAN:Control
 - see* Glossary
- GENTRAN:Plus
 - network ID field 3-13
 - remote ID field 3-13
 - see* Glossary
- GENTRAN:Realtime
 - see* Glossary
- GENTRAN:Realtime programs
 - Inbound Fixed/Variable Split program (EDIR094) 5-6
 - Inbound Mapping program (EDIR041) 5-13
 - Inbound NCPDP Pre-Processing program (EDIRNCPI) 5-16
 - Inbound Pre-Processing program (EDIR083) 5-9
 - outbound flow 5-20
 - Outbound Mapping program (EDIR042) 5-22
 - Outbound NCPDP Post-Processing program (EDIRNCPO) 5-25
- GENTRAN:Structure
 - application definitions 1-4
 - batch and realtime illustration 1-5
 - batch translation services 1-4
 - Databank Maintenance 2-39
 - databanking 2-39
 - features 1-2
 - implementation 2-38
 - inbound flow 4-3, 5-3
 - inbound flow illustration 1-9
 - install tape 2-38
 - limitations, AISI COMPORD standard 1-9
 - map definitions 1-4
 - mapping features 1-2
 - online services 1-4
 - outbound flow 4-28
 - outbound flow, illustration 1-6
 - overview 1-1
 - product description
 - outbound flow 4-29, 5-21
 - realtime translation services 1-4
 - screen descriptions 3-1
 - see* Glossary
 - supporting subsystems 3-7
 - system components 1-4
 - system flow 1-6
 - trading partner profiles 1-4
 - Tutorial 2-40
 - viewing documents from databanks 3-7
- GENTRAN:Structure Pre-Processor program (EBDI083)
 - processing NCPDP data 4-39
- GENTRAN:Structure Tutorial
 - inbound mapping integration 2-56
 - outbound mapping integration 2-51
 - partner maintenance 2-61
 - standards maintenance 2-41
- GENTRAN:Viewpoint
 - field on Parameters file (Inbound) 4-23
 - see* Glossary
- GEN-TRN-ELE-01
 - see* Glossary G-4
- GEN-TRN-ELE-02
 - see* Glossary G-4
- GEN-TRN-ELE-03
 - SEE also GLOSSARY - G-4
- GEN-TRN-ELE-04
 - see* Glossary G-4
- GEN-TRN-ELE-05
 - see* Glossary G-4
- GEN-TRN-RCVR 3-46
 - see* Glossary G-3
- GEN-TRN-REF 3-47
 - see* Glossary G-3
- GEN-TRN-SNDR 3-46
 - see* Glossary G-3
- global parameters
 - Partner Databank 3-28
- GM (CISCO) data 1-12, 4-24, 5-6

GM Envelope 4-26
 GM header segment 4-27
 GM trailer segment 4-27
 GMDATA file 4-26
 group envelope header, segment IDs 3-12
 GROUP Envelope Level parameter 4-10
 Group Information Screen – Generic (EDIM034) 3-19
 Envelope ID field 3-22
 Generic Element 1 field 3-23
 Generic Element 2 field 3-23
 Generic Element 3 field 3-23
 Generic Element 4 field 3-23
 Generic Element 5 field 3-23
 Generic Element 6 field 3-23
 Generic Element 7 field 3-24
 Modifier field 3-22
 Receiver ID field 3-22
 Reference field 3-23
 Sender ID field 3-22
 Transaction ID field 3-23
 Version ID field 3-23
 Grp Env ID field 3-78

H

header envelope 3-17
 Hold Area 4-10, 4-12, 4-13
 hold area write flag 4-17
 How GENTRAN:Structure Relates with GENTRAN:Basic Features 3-7

I

I/O field 3-68, 3-73, 3-76, 3-81, 3-84, 3-87
 identify
 standards information to create 2-12
 trading partner to do business with 2-27
 implementation
 business requirements 2-3
 creating a plan 2-3
 developing a configuration strategy 2-11
 GENTRAN:Structure Tutorial 2-40
 overview 2-3
 processing daily business 2-39
 trading partner business requirements 2-3
 In/Outbound field 3-67, 3-72
 Inbound and Outbound Application databanks 4-46

inbound application
 databank 4-19
 definition 1-13
 Inbound Application databank 4-5, 5-5
 records stored 5-9
 Inbound Application Databank Directory (EDI-IAA) 4-46
 Inbound Application Databank Extract program 4-5, 5-5
 Inbound Application Databank Level 4-15
 Inbound Application directory (EDIIAA) 4-8
 Inbound Application field 4-15
 Inbound Application Message Store (EDIIAS) 4-8
 Inbound Communications Gateway (EDIR103) 5-6
 Inbound Data Separation record 4-15, 4-16
 Inbound EDI/Application Link file (EDIIEL) 4-8
 Inbound Editor program (EBDI001) 1-12, 1-13, 3-63, 4-6, 4-19, 4-20, 4-24
 Inbound Editor program (EDIR001)
 functionality shared with Inbound Pre-Processing program (EDIR083) 5-9
 Inbound Fixed/Variable Split program (EBDI094) 1-12, 4-6, 4-24, 4-25
 EDI Variable Data file (EDIDAT) 4-26
 envelope processing 4-27
 Error Message and Control file (ERRCTL) 4-26
 files used 4-26
 Fixed COMPORD file (COMPORD) 4-26
 Fixed GENCOD file (GENCOD) 4-26
 Fixed GM file (GMDATA) 4-26
 Fixed-Format and Variable-Format EDI Data file (SYS003) 4-26
 initial processing tasks 4-27
 input files 4-26
 output files 4-26
 processing description 4-27
 Summary report (SYS006) 4-26
 Summary report input records read 4-26
 Summary report output records written 4-26
 System Configuration file (EDICFG) 4-26
 user-defined fixed data (OTHFIX) 4-26
 Inbound Fixed/Variable Split program (EDIR094) 4-5, 5-5, 5-6
 file access 5-7
 inputs 5-6
 report display screens 5-8
 reports 5-7
 Inbound Fixed/Variable Splitter 4-5, 5-5
 inbound fixed-format processing 4-17

- inbound fixed-format standards
 - segment requirements 1-6
 - inbound flow 2-39
 - Inbound Mapping program (EBDI041) 1-12, 4-19
 - Inbound Pre-Processing program (EBDI083) 4-6
 - Inbound Pre-Processing program (EDIR083) 1-12
 - related programs 1-12
 - through GENTRAN:Structure using
 - GENTRAN:Realtime 5-3, 5-5
 - with fixed-format standards 1-10, 4-3, 5-3
 - Inbound Mapper 4-5, 5-5
 - see Inbound Mapping program 4-17
 - Inbound Mapping program (EBDI041) 1-12, 1-13, 4-6, 4-19
 - EDICFG 4-20
 - files used 4-20
 - input files 4-20
 - System Configuration file 4-20
 - Input Format Type parameter 4-20
 - mapping status values 3-77
 - Parameters file 4-20
 - Parameters file layout – inbound 4-21
 - Structure Databank Level parameter 4-20, 4-33
 - SYS001 4-20
 - Inbound Mapping program (EDIR041) 5-13
 - file access 5-13
 - inputs 5-13
 - parameter descriptions 5-14
 - reports 5-15
 - Inbound NCPDP Data file (SYS003) 4-40
 - Inbound NCPDP Pre-Processing program (EDIRNCPI) 5-16
 - file access 5-16
 - inputs 5-16
 - reports 5-17
 - Inbound Pass-Thru field 3-63
 - Inbound Pre-Processing program (EBDI083) 1-12, 3-39, 3-42, 3-63, 3-90, 4-5, 4-19, 4-20, 4-24, 5-5
 - envelope processing 4-12
 - files used 4-7
 - input
 - Error Message and Control file (ERRCTL) 4-7
 - Fixed-Format EDI Data file (SYS003) 4-7
 - Parameters file (SYS030) 4-7
 - partner profile (SYS090) 4-7
 - Partner Profile Cross-Reference file (SYS095) 4-7
 - Partner Relationship Cross Reference file (EDIPREL) 4-7
 - Standard Version file (EDISVER) 4-7
 - System Configuration file (EDICFG) 4-7
 - User-Envelope Definition file (EDIUENV) 4-7
 - input files 4-7
 - output
 - Audit Trail (SYS005) file 4-8
 - Intermediate file (SYS004) 4-8
 - Summary report 4-8
 - Suspense file (SYS099) 4-8
 - parameter descriptions 4-9
 - parameters
 - Application By 4-10
 - Data Envelope 4-10
 - Databank 4-10
 - Detail Reports 4-10
 - Envelope Level 4-10
 - Envelope Level GROUP 4-10
 - Envelope Level INTERCHANGE 4-10
 - Envelope Level TRANSACTION 4-10
 - Partner ID 4-9
 - Partner Qualifier 4-9
 - Record Format 4-9
 - Record Format FIXED
 - FIXED Record Format parameter 4-9
 - Record Format VARIABLE 4-9
 - Record Length 4-9
 - Transaction ID 4-9
 - User ID 4-9
 - User Qualifier 4-9
 - User Reference 4-11
 - Version ID 4-9
 - partner determination 4-14
 - processing description 4-12
 - version determination 3-45
- Inbound Pre-Processing program (EDIR083) 4-6, 5-9
 - file access 5-10
 - inputs 5-10
 - reports 5-10
 - summary report display 5-11
- Inbound Splitter 4-5, 5-5
- Inbound Transaction Level Data Separation records 4-10
- Inbound Translation ID 4-15
- INFILEF 2-56
- Input Envelope Segment ID value 4-12
- input file
 - format fixed-block 4-9
 - inbound mapping 4-20
 - variable-block 4-9
- Input Format Type parameter 4-20

In-Stream option 4-10
 Int Env ID field 3-77
 interchange envelope header, segment IDs 3-12
 INTERCHANGE Envelope Level parameter 4-10
 interchange header option
 GEN 3-7, 3-9
 interchange header options
 ISA, ICS, BG, GS, UNA, UNB, SCH, STX, GEN 3-12
 interchange level
 Exception Management 3-13
 Tracking Management 3-13
 interchange reference number 3-17, 3-23
 interchange trailer segments 3-18
 Intermediate file 1-12
 INVFILE 2-4
 INVFILEF 2-4, 2-56
 invoice (0926) 2-4
 segments 2-7
 ISA
 delete 3-15
 ISA parameters
 deleting 3-15
 updating 3-15

J

JASS Standard
 0909 Purchase Order Segment Element Structure 2-18
 JASS standard 2-3, 2-4
 data element listing 2-21
 data elements 2-7
 document types 2-7
 guide to using 2-7, 2-12
 inbound flow 2-39
 partner configuration 2-27
 segment element structures 2-18
 JASSIN 2-4, 2-40
 JASSPO 2-4, 2-40
 map 2-51
 jump codes 3-3, A-1–A-2
 alphabetic 3-4
 by screen name A-2
 by screen title A-1
 EXIT 3-4
 guidelines 3-5
 jumping between screens 3-3
 numeric 3-4

special character 3-4
 SWAP 3-4, 3-6
 types 3-3
 User-Defined Jump Code table 3-5
 jumping between screens 3-3

L

Last Update Date field 3-52
 Last Update User field 3-52
 LAWNVEND 2-4
 accessing 2-27
 modifying 2-40
 Length field 3-45, 3-90
 Log Report file (EDILOG) 4-8

M

maintenance procedures 2-39
 mandatory/optional code
 for output records and fields 1-13
 for output segments and elements 1-8
 map definitions 1-4
 MAP record 4-8
 Map records
 ###MAP record 3-63, 4-6, 4-8, 4-14, 4-16, 4-17
 ###MP2 record 3-63, 4-6, 4-8, 4-13, 4-17
 ###MP3 record 3-63, 4-8, 4-17
 ###MP4 record 3-63, 4-6, 4-8, 4-13, 4-17
 ###MP5 record 3-63, 4-6, 4-8, 4-13, 4-17
 ###MP6 record 3-63, 4-6, 4-8, 4-13, 4-17
 MAP record 4-8
 MP2 record 4-8
 MP3 record 4-8
 MP4 record 4-8
 MP5 record 4-8
 MP6 record 4-8
 Mapped (Outbound Only) field 3-77
 mapping
 configuration 2-35
 directly from standards 2-56
 features 1-2
 fixed-format 3-59
 from user-defined envelopes 1-13
 Mapping Integration
 Application Data ID screen (EDIM552) 3-62
 inbound 2-56
 outbound 2-51

- Transaction Maintenance - GENTRAN:Structure screen (EDIM516) 3-59
- Transaction Maintenance screen (EDIM503) 3-54
- Mapping Integration subsystem 3-53
- Mapping Parameter Record Layout #1 4-34
- Mapping Parameter Record Layout #2 4-37
- Mapping Parameter Record Layout #3 4-38
- Mapping Parameter Record Layout #4 4-38
- Mapping Status (Outbound Only) field 3-77
- Modifier field 3-17, 3-22, 3-29, 3-41, 3-45, 3-90
- MP2 record 4-8
- MP3 record 4-8
- MP4 record 4-8
- MP5 record 4-8
- MP6 record 4-8
- Multiple Envelope ID field 3-16

N

- navigation
 - how to jump from screen to screen 3-3
- NCPDP data
 - compressed and reformatted 4-43
 - compressing 5-25
 - reformatting 4-39, 5-16
- NCPDP Inbound Pre-Processing program (NCPDP51I)
 - flow illustration 4-39
- NCPDP Inbound Pre-Processing program (NCPDP51I) 4-39
 - EDICFG file 4-39
 - ERRCTL file 4-40
 - input files used 4-40
 - output files 4-40
 - record format parameter 4-40
 - record length parameter 4-41
 - SYS003 file 4-40
 - SYS004 file 4-40
 - SYS005 file 4-40
 - SYS006 file 4-40
 - SYS030 file 4-40
 - SYS099 file 4-40
- NCPDP Outbound Parms Maintenance screen (EDIM84G) 3-108
- NCPDP Outbound Post-Processing program (NCPDP51O)
 - flow illustration 4-42

- NCPDP Outbound Post-Processing program (NCPDP51O) 4-42
 - compression parameter 4-45
 - EDICFG 4-43
 - ERRCTL file 4-43
 - files used 4-43
 - input files 4-43
 - input/output work file 4-43
 - NCPWRK file 4-43
 - output files 4-43
 - parameter layout 4-44
 - record format parameter 4-44
 - record length parameter 4-44
 - SYS003 file 4-43
 - SYS004 file 4-43
 - SYS005 file 4-43
 - SYS006 file 4-43
 - SYS030 file 4-43
- NCPDP Version/Release, invalid 4-40
- NCPDP51I 4-39
- NCPDP51O 4-42
- NCPDPI report 5-17
- NCPDPO report 5-27
- NCPWRK file 4-43
- Network (Outbound only) field 3-76

O

- Online Output Gateway (EDIEOOG) 5-6
 - online services 1-4
- ONT segment 2-41, 2-42, 2-51
- Order Notes (ONT) segment 2-40
- OTHFIX file 4-26, 4-27
- Outbound Application databank 1-8
- Outbound Application Databank Directory (EDIOAA) 4-46
- outbound documents, sending 3-14
- Outbound Editor 1-9
- outbound envelopes, creating 3-14
- outbound flow 4-28, 4-29, 5-20, 5-21
 - description 1-7
 - format-specific compliance checking 1-9
 - format-specific enveloping 1-8
 - processing daily business 2-39
 - with fixed-format standards 1-7, 4-28, 4-29, 5-20, 5-21
- Outbound Mapping program (EBDI042) 2-39, 3-22, 4-28, 4-30, 4-31, 5-20
 - Envelope Generator routine 1-8
 - files used 4-32

Fixed-Format File Record Length parameter 4-32
 Fixed-Format File Type parameter 4-32
 Fixed-Format Output file (SYS098) 4-33
 generating generic envelopes 3-39
 input files used 4-32
 mapping parameter record layout #1 4-34
 mapping parameter record layout #2 4-37
 mapping parameter record layout #3 4-38
 mapping parameter record layout #4 4-38
 mapping parameter records (SYS001) 4-34
 outbound flow description 1-8
 output files 4-33
 Parameters file (SYS001) 4-32
 User-Envelope Generation facility 1-8, 1-9
 Outbound Mapping program (EDIR042) 5-22
 file access 5-22
 GENTRAN:Structure subprograms called 5-22
 inputs 5-22
 parameter descriptions 5-23
 reports 5-24
 Outbound NCPDP Data file (SYS003) 4-43
 Outbound NCPDP Post-Processing program (EDIRNCPO) 5-25
 file access 5-25
 inputs 5-25
 parameter descriptions 5-26
 reports 5-27
 outbound transaction, labeling 3-12

P

parameters

Application By 4-10, 4-15, 4-16
 Data Envelope 4-10
 Databank 4-10
 Detail Reports 4-10
 Envelope Level 4-10
 Fixed-Format File Type 4-32
 Partner ID 4-9
 Partner Qualifier 4-9
 Record Format 4-9
 Record Length 4-9
 Transaction ID 4-9
 User ID 4-9
 User Qualifier 4-9
 User Reference 4-11
 Version ID 4-9
 Parameters file 4-12
 Parameters file (SYS030) 4-7, 4-40, 4-43
 Parameters file layout – inbound (SYS001) 4-21

Partner Profile Cross-Reference file (SYS095) 4-7
 partner configuration 2-27
 identify trading partner to do business with 2-27
 JASS standard 2-27
 Partner Control record 3-19
 added 3-25
 Partner Control Record Look-Up 4-14, 4-16
 Partner Cross-Reference file 4-9, 4-14, 4-16
 Partner Data Separation Record Look-Up 4-15
 Partner Determination
 methods
 partner extracted from envelope 4-14
 partner supplied on input parameter 4-14
 Partner Control Record Look-Up 4-16
 Partner Data Separation Record Look-Up 4-15
 Partner Header Record Look-Up 4-14, 4-16
 Partner Transaction Record Look-Up 4-15
 partner determination 4-14
 Relationship mode 4-16
 Partner file 3-43, 4-16
 Partner File Control record 4-16
 Partner File Look-Up 4-13, 4-16
 Partner File Transaction record 4-15
 Partner Header record
 with Relationship mode 4-16
 Partner Header Record Look-Up 4-14, 4-16
 Partner ID Look-Up 4-9
 Partner ID parameter 4-9
 partner IDs
 listed for documents on databank 3-65
 Partner Maintenance 2-61, 3-8
 Control Information - Screen 1 with Generic Header Option (EDIM015) 3-9
 Control Information - Screen 2 with Generic Options (EDIM011) 3-14
 Group Information Screen – Generic (EDIM034) 3-19
 Transaction Information Screen – Generic (EDIM044) 3-25
 partner profile
 (SYS090) 4-7
 with multiple EDI standards 3-22
 Partner Profile Control record 4-14
 Partner Profile Header record 4-14
 Partner Profile Transaction record 4-15
 Partner Qualifier parameter 4-9
 Partner Relationship Cross Reference file (EDIPREL) 4-7
 Partner Relationship Cross-Reference file 4-16
 Partner Transaction Record Look-Up 4-15

Partner/Qualifier mode
 see Glossary
POFILE 2-4
POFILEF 2-4, 2-35, 2-51
post-envelope processing
 suspending a document 4-17
 User/Partner Look-Up 4-13
 writing a document 4-17
 formatting the MAP records 4-17
 writing the data 4-17
PREPRO report 5-10
Pre-Proc (Inbound Only) field 3-77
Pre-Proc Status (Inbound Only) field 3-77
processing daily business 2-39
 inbound flow 2-39
 maintenance procedures 2-39
 outbound flow 2-39
processing description
 initial tasks 4-12
 post-envelope processing
 User/Partner Look-Up 4-13
profile ID, documents listed 3-69
program descriptions 4-1, 5-1
proprietary standard
 see Glossary G-2
Prt ID Ln field 3-43
Prt ID Start field 3-43
purchase order (0909) 2-4
 segments 2-7
Purchase Order Notes segment (ONT) 2-42

R

RDW (record descriptor word) 4-9
real-time communications
 user-envelope specifications 1-2
realtime translation services 1-4
Rec Stat field 3-73
Receiver ID 3-17
Receiver ID field 3-22, 3-29, 3-90
Receiver ID Length field 3-46
Receiver ID Start field 3-46
record descriptor word (RDW) 4-9
Record field 3-82
Record Format parameter 4-9, 4-40, 4-44
record length
 for variable-blocked segments 1-6
 of output files 1-8
Record Length parameter 4-9, 4-41, 4-44

reference
 interchange reference number 3-17, 3-23
Reference field 3-17, 3-23, 3-29
 transaction reference number 3-29
Reference Number field 3-90
Reference Number ID Start field 3-47
Reference Number Length field 3-47
Reference Tag field 3-76
Reformatted NCPDP Data file (SYS004) 4-40
Relationship mode 4-9, 4-16
 partner determination 4-16
 see Glossary
 user ID for processing 3-42
reported control card selection criteria 4-46
Reported Status field 3-77
reserved word constants 1-13
 GEN-(INT/GRP)-ELEMENT-04 3-49
 GEN-(INT/GRP)-ELEMENT-05 3-49
 GEN-(INT/GRP)-ELEMENT-06 3-49
 GEN-(INT/GRP)-ELEMENT-07 3-50
 GEN-(INT/GRP)-ELEMENT-08 3-50
 GEN-(INT/GRP)-ELEMENT-09 3-51
 GEN-(INT/GRP/TRN)-ELEMENT-01 3-47
 GEN-(INT/GRP/TRN)-ELEMENT-02 3-47, 3-48
 GEN-(INT/GRP/TRN)-ELEMENT-03 3-48
 GEN-(INT/GRP/TRN)-ELEMENT-04 3-48
 GEN-ELEMENT-01 3-47
 GEN-GRP-RCVR 3-46
 GEN-GRP-REF 3-47
 GEN-GRP-SNDR 3-46
 GEN-INT-ELEMENT-09 3-51
 GEN-INT-ELEMENT-10 3-51
 GEN-INT-RCVR 3-46
 GEN-INT-REF 3-47
 GEN-INT-SNDR 3-46
 GEN-TRN-RCVR 3-46
 GEN-TRN-REF 3-47
 GEN-TRN-SNDR 3-46
 see Glossary G-3
reserved words 3-18, 3-24, 3-30
 &GRPCNT 3-18
 &SEGCNT 3-18, 3-24, 3-30
 &SEGCNT2 3-18, 3-30
 &TRNCNT 3-18
RSGRSG Level field 3-58

S

- S/R (Send or Receive) field 3-60
- sample reports
 - EDID553 4-51
- Search field 3-82
- Seg ID field 3-84
- SegID Length field 3-77
- SegID Start field 3-78
- segment
 - defining data elements within 3-36
- segment element structures
 - JASS standard 2-18
- segment ID
 - and mapping integration 3-7
 - for fixed-format data 1-6
 - length 3-61
 - modifier 3-45
 - rules for fixed-format standards 3-53
 - used at group level 3-78
 - used at interchange level 3-77
 - used at transaction level 3-78
- Segment ID field 3-41, 3-45
- Segment ID Length field 3-61
- Segment ID Ln field 3-41
- Segment ID Start field 3-41, 3-61
- segment IDs
 - defining an envelope in different standards 3-43
 - group envelope header 3-12
 - interchange envelope header 3-12
- segment terminator 1-3
- Sender ID field 3-17, 3-22, 3-29, 3-90
- Sender ID Length field 3-46
- Sender ID Start field 3-46
- SPLITR report 5-7
- Standard Code Directory Screen (EDIM171) 2-23
- standard definitions, sharing 1-2
- Standard Type field 3-58
- Standard Version file (EDISVER) 4-7
- standards
 - configuration 2-12
 - configuration overview 2-12
 - display, add, change 3-32
 - overview 2-12
 - records 3-33
- standards definitions 1-4
- Standards file 3-85
- Standards Maintenance 2-41
 - Data Element Definition screen (EDIM160) 3-36
 - Structure Envelope Display screen (EDIM192) 3-89
 - User Envelope Specification screen (EDIM190) 3-39
 - Version screen (EDIM110) 3-33
 - Version/Outbound Specification screen (EDIM191) 3-44
- Standards Maintenance Menu (EDIM100) 3-32
- Standards Maintenance subsystem 3-31
- Standards Version field 3-60
- Starting Segment ID field 3-41
- Statistics file 4-46
- STRINB 2-40
- STROUT 2-40
- Structure Application Databank Inquiry Report program (EDID553) 4-46
 - control card options 4-47
 - Detail Inquiry report 4-54
 - EDICFG file 4-46
 - EDICNTL file 4-46
 - EDIHAA file 4-46
 - EDIOAA file 4-46
 - ERRCTL file 4-46
 - files used 4-46
 - input files 4-46
 - output files 4-46
 - Processing Log report 4-53
 - reports 4-47
 - sample reports 4-51
 - Summary Inquiry report 4-55
 - Summary report sample 4-52
- Structure Databank Level parameter 4-20, 4-33
- Structure Document Directory screen (EDIM272) 3-65
 - Databank field 3-67
 - Dbk field 3-68
 - I/O field 3-68
 - In/Outbound field 3-67
- Structure Document Display screen (EDIM274) 3-79
 - Databank field 3-82
 - I/O field 3-81
 - Record field 3-82
 - Search field 3-82
 - User Reference field 3-81
- Structure Document Status Detail screen (EDIM275) 3-74
 - Agency field 3-76
 - Character Count field 3-78
 - Databank field 3-77
 - Databank Run # field 3-76
 - Division field 3-76

- Envelope field 3-78
- Grp Env ID field 3-78
- I/O field 3-76
- Int Env ID field 3-77
- Mapped (Outbound Only) field 3-77
- Mapping Status (Outbound Only) field 3-77
- Network (Outbound only) field 3-76
- Pre-Proc (Inbound Only) field 3-77
- Pre-Proc Status (Inbound Only) field 3-77
- Reported Status field 3-77
- SegID Length field 3-77
- SegID Start field 3-78
- Test/Prod field 3-78
- Transaction Set field 3-76
- Trn Env ID field 3-78
- User Dup. Ind field 3-78
- User Reference field 3-76
- User Reference Tag field 3-76
- Version ID field 3-76
- Structure Document Status screen (EDIM273) 3-69
 - Databank field 3-72
 - Date field 3-73
 - Dbk field 3-73
 - From Date field 3-72
 - From Time field 3-72
 - I/O field 3-73
 - In/Outbound field 3-72
 - Rec Stat field 3-73
 - Structure Version ID field 3-73
 - To Date field 3-73
 - To Time field 3-73
 - User Reference field 3-72, 3-73
 - Version ID field 3-71
- Structure Envelope Display screen (EDIM192) 3-89
 - Current Date field 3-90
 - Current Date Format field 3-91
 - Current Time field 3-90
 - Default Transaction ID field 3-90
 - Default Version ID field 3-90
 - Generic Elements 1 to 10 field 3-90
 - Length field 3-90
 - Modifier field 3-90
 - Receiver ID field 3-90
 - Reference Number field 3-90
 - Segment ID field 3-90
 - Sender ID field 3-90
 - Transaction ID field 3-90
 - Version ID field 3-90
- Structure Field Display screen (EDIM277) 3-86
 - Agency field 3-87
 - Databank field 3-87
 - Field Data field 3-88
 - Field Description field 3-87
 - Field Length field 3-88
 - Field Position field 3-88
 - Field Sequence field 3-87
 - Field Type field 3-87
 - I/O field 3-87
 - Version ID field 3-87
- Structure Record Display screen (EDIM276) 3-83
 - Agency field 3-84
 - Databank field 3-84
 - Description field 3-85
 - Field Data field 3-85
 - Fld Seq field 3-85
 - I/O field 3-84
 - Seg ID field 3-84
 - Transaction Set field 3-84
 - Version ID field 3-84
- Structure Version ID field 3-73
- Summary report 4-26
 - group headers read 4-8
 - input records read 4-8
 - interchange headers read 4-8
 - map records written 4-8
 - output records written 4-8
 - transaction headers read 4-8
- Summary report (SYS006) 4-40, 4-43
- Summary Report file 4-12
- Summary report sample
 - EDID553 4-52
- suspending a document 4-17
- Suspense file 4-17
- Suspense file (SYS099) 4-40
- SYS001 4-20, 4-32
- SYS003 4-7, 4-26
- SYS003 file 4-40, 4-43
- SYS004 4-8, 4-19, 4-20, 4-30
- SYS004 file 4-40, 4-43
- SYS005 4-8
- SYS005 file 4-40, 4-43
- SYS006 4-8
 - input records read 4-26
 - output records written 4-26
- SYS006 file 4-26, 4-40, 4-43
- SYS030 4-7
- SYS030 file 4-40, 4-43
- SYS090 4-7
- SYS095 4-7
- SYS098 4-30, 4-32, 4-33
- SYS099 4-8
- SYS099 file 4-40

system components 1-4
 System Configuration file 4-20, 4-26
 System Configuration file (EDICFG) 4-7, 4-40,
 4-43, 4-46

T

Test Transaction Indicator 4-15
 Test/Prod field 3-78
 To Date field 3-73
 To Time field 3-73
 trading partner
 business requirements 2-3
 creating 2-40
 deleting ISA parameters 3-15
 LAWNVEND 2-4
 profiles 1-4
 sharing 1-2
 trading profile mode 4-9
 trailer envelope 3-17, 4-12
 JASS standard 2-41
 transaction
 outbound
 see outbound transaction
 reference number 3-29
 transaction definition
 (maps) sharing 1-2
 building 2-40
 TRANSACTION Envelope Level parameter 4-10
 Transaction ID 3-17
 Transaction ID field 3-23, 3-56, 3-60, 3-90
 Transaction ID Length field 3-46
 Transaction ID parameter 4-9
 Transaction ID Start field 3-46
 Transaction Information Screen – Generic (EDIM044) 3-25
 Application Databank Inbound field 3-28
 Application Databank Outbound field 3-29
 Envelope ID field 3-29
 Generic Element 1 field 3-30
 Generic Element 2 field 3-30
 Generic Element 3 field 3-30
 Generic Element 4 field 3-30
 Generic Element 5 field 3-30
 Modifier field 3-29
 Receiver ID field 3-29
 Reference field 3-29
 Sender ID field 3-29
 Translation Map ID Inbound field 3-28
 Translation Map ID Outbound field 3-28
 Version ID field 3-29
 Transaction Maintenance - GENTRAN:Structure screen (EDIM516) 3-59
 Agency field 3-60
 Description field 3-60
 Division Code field 3-60
 Envelope Format field 3-60
 S/R (Send or Receive) field 3-60
 Segment ID Length field 3-61
 Segment ID Start field 3-61
 Standards Version field 3-60
 Transaction ID field 3-60
 Transaction Set field 3-60
 Transaction Set Release field 3-60
 Transaction Maintenance screen (EDIM503) 3-54
 Application Data ID field 3-57
 Application Selection Field Values 3-57
 Division Code field 3-56
 Envelope Type field 3-57
 RSGRSG Level field 3-58
 Standard Type field 3-58
 Transaction ID field 3-56
 Transaction Set field 3-57
 Transaction Set Release field 3-57
 Transaction Status field 3-57
 Update Allowed field 3-58
 Use Code field 3-57
 transaction map
 defining header information 3-54
 JASSIN 2-4, 2-40
 JASSPO 2-4, 2-40
 maintaining header information 3-54
 transaction record
 default added with new Partner Control record 3-25
 transaction set
 not specified on envelope 3-90
 Transaction Set field 3-57, 3-60, 3-76, 3-84
 Transaction Set ID 4-15
 as look-up key 4-15
 Transaction Set ID field 4-9
 Transaction Set Release field 3-57, 3-60
 Transaction Status field 3-57
 Translation Map ID Inbound field 3-28
 Translation Map ID Outbound field 3-28
 Trn Env ID field 3-78

U

Update Allowed field 3-58
Use Code field 3-57
user determination
 final tasks 4-18
 post-envelope processing
 suspending a document 4-17
 writing a document 4-17
User Dup. Ind field 3-78
user envelope 3-41
 data fields 3-89
 defining 3-44
User Envelope Specification screen (EDIM190)
3-39
 Associated Hdr/Trl field 3-43
 Associated Modifier field 3-43
 Env D field 3-42
 Envelope Level field 3-42
 Modifier field 3-41
 Prt ID Ln field 3-43
 Prt ID Start field 3-43
 Segment ID 3-41
 Segment ID field 3-41
 Segment ID Ln 3-41
 Starting Segment ID field 3-41
 Usr ID Ln field 3-42
 Usr ID Start field 3-42
user exits field on Parameters file 4-21
User ID 4-9
User ID Look-Up 4-9
User ID parameter 4-9
User Qualifier parameter 4-9
User Reference field 3-72, 3-73, 3-76, 3-81
User Reference option 3-72
User Reference parameter 4-11
User/Partner ID
 as input parameter for partner determination 4-16
 not supplied as input parameter for partner
 determination 4-16
User/Partner Look-Up 4-13
user-defined envelope type 3-34
user-defined envelopes 1-8, 3-89, 4-7, 4-26
user-defined fixed data 4-26
User-Defined Jump Code table 3-5
 and CICS PPT table 3-5
 and Configuration file 3-5
user-defined standard 3-38
user-defined standards
 Standards Maintenance 3-31
User-Envelope Definition file (EDIUENV) 4-7

User-Envelope Definition record 4-12, 4-13
User-Envelope file 3-14, 3-19
User-Envelope Generation facility 1-9
user-envelope specifications 3-17, 3-22, 3-29
 sharing 1-2
user-written compliance checker 1-8, 1-9, 1-13
Usr ID Ln field 3-42
Usr ID Start field 3-42

V

variable blocked segments 1-6
VARIABLE Record Format parameter 4-9
variable segment 3-60
Variable Standard 1-3, 1-8, 3-63, 4-5, 5-5
variable-block format 4-9
variable-blocked files
 RDW 4-9
variable-format data 1-12, 4-24
variable-format standard
 see Glossary G-2
 specifications 1-3
version ID
 change, view, delete definition 3-33
Version ID field 3-17, 3-23, 3-29, 3-71, 3-76,
3-84, 3-87, 3-90
Version ID Length field 3-45
Version ID parameter 4-9
Version ID Start field 3-45
Version screen (EDIM110) 3-33
 Envelope Type field 3-34
Version/Outbound Specification screen
(EDIM191) 3-17, 3-44
 Current Date Format field 3-52
 Current Date Length field 3-52
 Current Date Start field 3-51
 Current Time Length field 3-52
 Current Time Start field 3-52
 Default Agency field 3-45
 Default Transaction ID field 3-45
 Default Version ID field 3-45
 Generic Element 1 Length field 3-47
 Generic Element 1 Start field 3-47
 Generic Element 10 Length field 3-51
 Generic Element 10 Start field 3-51
 Generic Element 2 Length field 3-48
 Generic Element 2 Start field 3-47
 Generic Element 3 Length field 3-48
 Generic Element 3 Start field 3-48
 Generic Element 4 Length field 3-48

Generic Element 4 Start field 3-48
Generic Element 5 Length field 3-49
Generic Element 5 Start field 3-49
Generic Element 6 Length field 3-49
Generic Element 6 Start field 3-49
Generic Element 7 Length field 3-50
Generic Element 7 Start field 3-50
Generic Element 8 Length field 3-50
Generic Element 8 Start field 3-50
Generic Element 9 Length field 3-51
Generic Element 9 Start field 3-50
Last Update Date field 3-52
Last Update User field 3-52
Length field 3-45
Modifier field 3-45
Receiver ID Length field 3-46
Receiver ID Start field 3-46
Reference Number ID Start field 3-47
Reference Number Length field 3-47
Segment ID field 3-45
Sender ID Length field 3-46
Sender ID Start field 3-46
Transaction ID Length field 3-46
Transaction ID Start field 3-46
Version ID Length field 3-45
Version ID Start field 3-45

W

Work file (NCPWRK) 4-43
Write Flag 4-12
write flag 4-17
writing a document 4-17

