



# **IBM® Sterling Connect:Express® for z/OS®**

## **Options Guide**

**Version 4.3**

## Copyright

This edition applies to the Version 4.3 of IBM® Sterling Connect:Express® for z/OS® and to all subsequent releases and modifications until otherwise indicated in new editions.

Before using this information and the product it supports, read the information in Notices on page N-1.

Licensed Materials - Property of IBM

ProductName

© Copyright IBM Corp. 1992,2011. All Rights Reserved.

US Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

## Preface

Chapter Overview .....	iii
Product Documentation.....	iii
Getting Support for Sterling Commerce Products .....	iv
Conventions Used in This Guide .....	iv
Implementing an Interface Option .....	v

## Chapter 1 CICS Interface

Overview .....	1-1
Installing the CICS Option.....	1-1
Updating the CICS Tables .....	1-2
Updating the T3B2ZSSN Table.....	1-3
Updating the CICS Start Procedure .....	1-4
CICS Interface Transactions .....	1-4
CICS Interface Initialization.....	1-4
CICS Interface Termination.....	1-4
CICS Interface Troubles .....	1-5
Using the Sterling Connect:Express for z/OS CICS Interface.....	1-5
Managing Files .....	1-5
L3B2ZALC: Dynamic File Allocation/De-allocation .....	1-6
L3B2ZUSJ: Selective Access to Sterling Connect:Express Journal File .....	1-10
Managing CICS to Sterling Connect:Express Communications .....	1-14
L3B2ZZ20: File Transfer Request to Sterling Connect:Express.....	1-14
Managing Sterling Connect:Express to CICS Communications .....	1-17
L3B2ZAPL: Transfer Notification Request .....	1-17

## Chapter 2 IMS Interface

Overview .....	2-1
Using the IMS Interface.....	2-1

Managing Files.....	2-2
L4B2ZALC: Dynamic File Allocation/Deallocation.....	2-2
L0B2ZUSJ: Access to Sterling Connect:Express Journal .....	2-8
Managing IMS to Sterling Connect:Express Communications .....	2-13
L4B2ZWAI: Set Program in Wait State .....	2-14
L0B2ZZ20: Transfer Request .....	2-15
Managing Sterling Connect:Express to IMS Communications .....	2-17
L0B2ZAPL: Transfer Notification Request.....	2-17
L4B2ZAP0: Initialize the ESTAE Environment for L0B2ZAPL.....	2-19

## Notices

Trademarks .....	N-3
------------------	-----

## Index

---

# Preface

The *Sterling Connect:Express for z/OS Options Guide* is for programmers and network operations staff who install and maintain the ProductName product.

This guide provides information about two options for the Sterling Connect:Express for z/OS product: the CICS interface and the IMS interface. These features enable you to better integrate file transfer operations in your environment by providing tools to integrate file transfer requests and controls in applications.

This guide assumes knowledge of the z/OS operating system, including its applications, network, and environment. If you are not familiar with the Platform operating system, refer to IBM documentation for more information.

---

## Chapter Overview

The *Sterling Connect:Express for z/OS Options Guide* is organized into the following chapters:

Chapter/Appendix	Description
Chapter 1 CICS Interface	This chapter describes the CICS interface option. This option provides the environment in which a CICS application can communicate with Sterling Connect:Express. Facilities enable a CICS application to request Sterling Connect:Express to perform certain functions on behalf of the application.
Chapter 2 IMS Interface	This chapter describes the IMS interface option which provides subroutine modules that can be called by an IMS application to communicate with Sterling Connect:Express. These subroutines enable an IMS application to request Sterling Connect:Express to perform certain functions on behalf of the application.

---

## Product Documentation

Sterling Connect:Express documentation consists of the following manuals:

- ❖ The *Sterling Connect:Express for z/OS 4.3.0 Release Notes* lists maintenance updates and any important notes.
- ❖ The *Sterling Connect:Express for z/OS 4.3 Installation Guide* describes the planning and installation of Sterling Connect:Express.

- ❖ The *Sterling Connect:Express for z/OS 4.3 User Guide* includes general information about using the TSO/ISPF interface, and serves as a reference of user and environment commands.
- ❖ The *Sterling Connect:Express for z/OS 4.3 Utilities Guide* describes the optional Utilities package that you can integrate with Sterling Connect:Express.
- ❖ The *Sterling Connect:Express for z/OS 4.3 FTP Guide* provides you with the information that you need to use Sterling Connect:Express with the FTP protocol.
- ❖ The *Sterling Connect:Express for z/OS 4.3 Administration Guide* provides detailed information about transfer operations for system administrators and other advanced users of Sterling Connect:Express.
- ❖ The *Sterling Connect:Express for z/OS 4.3 Options Guide* provides information about the CICS and IMS interfaces available for Sterling Connect:Express.
- ❖ The *Sterling Connect:Express for z/OS 4.3 PeSIT User Fields Guide* describes how you can exchange the PeSIT Pi37 and Pi99 fields with any PeSIT software.
- ❖ The *Sterling Connect:Express for z/OS 4.3 Etebac3 User Guide* provides you with the information that you need to use Sterling Connect:Express with the Etebac3 protocol.
- ❖ The *Sterling Connect:Express HTTP Option Implementation Guide* provides you with the information that you need to implement HTTP access to Sterling Connect:Express for z/OS repository.
- ❖ The *Sterling Connect:Express for z/OS 4.3 SSL Guide* includes general information on implementing secured file transfers.
- ❖ The *Sterling Connect:Express for z/OS 4.3 Sysplex Supervision Guide* includes general information on implementing a group of ProductName Plex managers under control of a ProductName Plex supervisor.

---

## Getting Support for Sterling Commerce Products

Sterling Commerce provides intuitive technical products and superior Help and documentation to enable you to work independently. However, if you have a technical question regarding a Sterling Commerce product, use the Sterling Commerce Customer Support Web site.

The Sterling Commerce Customer Support Web site at [www.sterlingcommerce.com](http://www.sterlingcommerce.com) is the doorway to Web support, information, and tools. This Web site contains several informative links, including a solutions database, an issue tracking system, fix information, documentation, workshop information, contact information, sunset and retirement schedules, and ordering information. Refer to the Customer Support Reference Guide at [www.sterlingcommerce.com/customer/tech\\_support.html](http://www.sterlingcommerce.com/customer/tech_support.html) for specific information on getting support for Sterling Commerce products.

---

## Conventions Used in This Guide

The *Sterling Connect:Express for z/OS Options Guide* uses certain notational conventions. This section describes the conventions used in this guide.

Convention	Description
UPPERCASE LETTERS	Uppercase letters in the command format indicate that you type in information as shown.

Convention	Description
Lowercase letters	Lowercase letters or words in commands or syntax boxes require substitution by the user. For example, index1.index2.PARMLIB indicates that you must provide the first and second indexes of the string. "PARMLIB" is mandatory.
Bold Letters	Bold print in syntax boxes indicates Sterling Connect:Express commands and required parameters. For example, PLEX=N indicates that the parameter PLEX must be set to N.
Underlined Letters	Underlining indicates default values for parameters and subparameters. For example, PLEX=Y N specifies that the default for PLEX is N.
Vertical Bars ( )	Vertical bars indicate that you can supply one of a series of values separated by the vertical bars. For example, RUN=H C specifies that H or C is valid.
Monospaced characters (characters of equal width)	Monospaced characters represent information for screens, commands, Processes, and reports.
Punctuation	Code all commas and parentheses as they appear.
£ or #	The Pound character (£) and the hash character (#) are equivalent.

---

## Implementing an Interface Option

Sterling Connect:Express options are interfaces that you can integrate into user applications. All optional feature objects are provided and enabled on the standard product tape.

Communication structures between applications and Sterling Connect:Express are described in the \*MACLIB\* product library. You should always use assembly Dsects or Cobol Copies in user programs.

---

**Note:** The \*ISPCLIB\* contains an ISPF EDIT MACRO that automatically converts an assembly-dsect to a cobol-copy (see M2COBASM).

---

### Updating the Product

Updating the product should not impact user application programs if you use product structures (Dsects and Copies). The user program should clear structures before the initial communication with the monitor. If a compilation or link-edit is necessary, the release notes will inform you. This may be the case if a new function has been added.





---

## CICS Interface

This chapter describes the CICS interface option. This option provides the environment in which a CICS application can communicate with Sterling Connect:Express for z/OS. Facilities enable a CICS application to request Sterling Connect:Express to perform certain functions on behalf of the application.

---

### Overview

The Sterling Connect:Express CICS interface includes load modules for integration into the CICS subsystem as well as implementation examples. This interface enables a CICS application to manage files and communications with Sterling Connect:Express.

Normally, a CICS application does not have access to file management, but this is possible with the features listed below:

- ❖ Dynamic allocation, de-allocation, catalog, de-catalog, delete, of QSAM data set
- ❖ Open/Close of extra partition destinations (French BSIT application only)
- ❖ Selective access to Sterling Connect:Express journal file

A CICS application can use Sterling Connect:Express services to send a parameter list to the monitor to initiate a transfer request. A CICS application can also connect to the monitor, and then Sterling Connect:Express sends the journal record to the application.

During CICS initialization, a transaction is called to create the environment within CICS to communicate with Sterling Connect:Express. After the environment has been created, any CICS application can call Sterling Connect:Express to perform any of the functions described below. During CICS shutdown, an additional transaction is called to clean up this environment before CICS terminates.

---

### Installing the CICS Option

The CICS option modules are provided and enabled on the standard product tape.

If an application uses the CICS interface, you must first initialize an environment in the CICS address space. This environment must then be released before CICS termination. Note that some programs are executed during CICS initialization and termination, while others are executed during communications between the

CICS application and Sterling Connect:Express. A table (T3B2ZSSN) is provided to establish the communication between the user application and Sterling Connect:Express subsystem.

The installation of the Sterling Connect:Express for z/OS CICS option includes the following 3 phases.

1. Updating the CICS tables
2. Updating the T3B2ZSSN communication table
3. Updating the starting procedure or JCL of CICS

## Updating the CICS Tables

To initialize the environment in the CICS address space, you must update the CICS tables, define programs from the Sterling Connect:Express product, and prepare for the initialization and termination processes.

### CICS PPT

The following programs must be defined in the PPT of CICS with the option ASSEMBLY LANGUAGE.

Program	Description
L3B2ZALC	Dynamic allocation
L3B2ZAPL	Notification at end of transfer
L3B2ZEND	Disconnection from Sterling Connect:Express
L3B2ZUSJ	Access to Sterling Connect:Express journal file
L3B2ZZ20	Transfer request
L3B2ZJNL	Access to Sterling Connect:Express journal file
P3B2Z001	Initialization (load T3B2ZSSN)
P3B2Z002	Initialization
P3B2Z003	Normal termination
P3B2Z009	Clear interface
T3B2ZSSN	Communication table

The following programs must be defined in the PPT of CICS with the option EXECKEY=CICS:

Program	Description
L3B2ZEND	Disconnect from Sterling Connect:Express
P3B2Z001	Initialization (load T3B2ZSSN)
P3B2Z002	Initialization
P3B2Z003	Normal termination
P3B2Z009	Clear interface

## CICS PCT

The following transactions must be defined in the PCT of CICS, and have the option TASKDATAKEY=CICS.

---

Transaction	Description
TCIS	First program - P3B2Z001
TCIN	First program - P3B2Z002
TCIE	First program - P3B2Z003

---

---

**Note:** You can change the transaction names.

---

## CICS PLTPI

For an automatic initialization of the Sterling Connect:Express for z/OS CICS interface, the P3B2Z001 program name must be added to the PLTPI list.

## CICS PLTSD

The P3B2Z003 program is used to stop the Sterling Connect:Express for z/OS CICS interface before terminating CICS. To automate this process, the P3B2Z003 program name must be added to the PLTSD list at the first stage.

The programs defined in the PLTSD do not run when an Immediate Shutdown request is made to CICS. The P3B2Z009 program is then used to clear the CICS interface.

## Updating the T3B2ZSSN Table

The T3B2ZSSn module is a table loaded by the P3B2Z001 program during CICS PLTPI initialization. The T3B2ZSSN table defines the following items.

- ❖ The Sterling Connect:Express subsystem name (SSN).
- ❖ The name of the initialization transaction which is automatically started by the P3B2Z001 program during PLTPI.

An example of the T3B2ZSSN table is provide in the \*SAMPOPT\* library of the product. The table T3B2ZSSN (see EX£T3SSN) supplied with the installation materials defines TOM1 as the subsystem name and TCIN as the initialization transaction name.

---

**Note:** Several CICS can use the same Sterling Connect:Express. In this case, each CICS must have a separate LOADLIB with its own T3B2ZSSN module. Each CICS can reference the same Sterling Connect:Express subsystem, but with a different application name.

---

The initialization transaction TCIN can be the same for all applications. You can check the list of applications through the Sterling Connect:Express TSO/ISPF option 2.5.

The P3B2Z009 program is used to clear the CICS interface. When several CICS are using the same Sterling Connect:Express subsystems, they must be coded with the 'APL=' parameter.

## Updating the CICS Start Procedure

The \*LOADLIB\* of Sterling Connect:Express must be concatenated to both STEPLIB and DFHRPL of the CICS step. The \*LOADLIB\* of Sterling Connect:Express is APF.

When using the L3B2ZUSJ program, you must add a DD statement referring to the Sterling Connect:Express journal file, as shown below.

```
//SYSJNL DD DSN=XXXX.TOMn.SYSJNL,DISP=SHR
```

You must also add a step to execute the P3B2Z009 clearing program after the CICS step to allow the interface to stop normally if this operation was not successfully completed by the P3B2Z003 program.

```
//CLEAR EXEC PGM=P3B2Z009,COND=EVEN
```

OR

```
//CLEAR EXEC PGM=P3B2Z009,COND=EVEN,PARM='SSN=TOM?,APL=xxxxxxxx'
```

---

## CICS Interface Transactions

Before running your application in the CICS environment, you must initialize the Sterling Connect:Express CICS interface. When CICS terminates, it must terminate the Sterling Connect:Express CICS interface. If problems occur when initializing the CICS interface, you can clean up the control blocks of the Sterling Connect:Express subsystem interface. Standard transactions and utilities are provided.

### CICS Interface Initialization

The installation of the environment is performed by a transaction called TCIN. TCIN can be activated either automatically by PLTPI or by the TCIS transaction. In both cases, the initialization process must be completed before starting the user application. This transaction remains active until the interface termination.

CICS applications connected to the monitor are displayed on the Sterling Connect:Express Application (CICS,IMS,...) screen. (TSO/ISPF option 2.5)

### CICS Interface Termination

The environment created by the TCIN transaction is released when this transaction terminates, either automatically by running the P3B2Z003 program declared in the PLTSD list during the first stage of Shutdown or by the TCIE transaction.

For an immediate shutdown, it is necessary to use the TCIE transaction to terminate the Sterling Connect:Express CICS interface before stopping CICS.

## CICS Interface Troubles

The control blocks of the Sterling Connect:Express subsystem interface may be altered in the following situations:

- ❖ The environment is not well initialized.
- ❖ CICS has been canceled without running the P3B2Z009 program.
- ❖ An error occurred while processing the interface (initialization, call, termination).

In these cases, it is recommended to execute the steps below:

1. Pass the '\$\$LOAD\$\$' command to Sterling Connect:Express or run 'P1B2Z9RL' program.
2. Stop both CICS and Sterling Connect:Express.
3. Restart both CICS and Sterling Connect:Express.

---

## Using the Sterling Connect:Express for z/OS CICS Interface

Once the Sterling Connect:Express for z/OS CICS environment has been initialized, a user program can call the interface to access Sterling Connect:Express services.

The modules provided are written in ASSEMBLY “COMMAND LEVEL” and can be called by any program written in COBOL, ASSEMBLY, or PL1 using the standard conventions of CICS COMMAND LEVEL, as shown below.

```
EXEC CICS LINK PROGRAM('L3B2Zxxx')
      COMMAREA(parmlist) LENGTH(parmlng)

L3B2Zxxx = called module name
parmlist = communication area acquired by the
          calling program and given to the called module
parmlng  = length of the communication area
```

For COBOL programs, communication areas are defined in the \*MACLIB\* provided with the installation material and can be inserted using COPY commands.

## Managing Files

Normally, a CICS application does not have access to file management. This is possible using L3B2ZALC for dynamic file allocation and de-allocation, and L3B2ZUSJ for selective access to the Sterling Connect:Express Journal File. These programs are discussed in the next two sections.

## L3B2ZALC: Dynamic File Allocation/De-allocation

The following COBOL example defines the communication area structure.

```
01 Sterling Connect:Express -ALC-PARMLIST.
03 ALCSSNA      PICTURE  X(4) .
03 ALCPARML.
05 ALCFUNC     PICTURE  X(1) .
05 ALCDDNM    PICTURE  X(8) .
05 ALCDSNM    PICTURE  X(44) .
05 ALCMEMB    PICTURE  X(8) .
05 ALCDISP    PICTURE  X(3) .

05 ALCVOLS    PICTURE  X(6) .
05 ALCUNIT    PICTURE  X(5) .
05 ALCSPAC    PICTURE  X(1) .
05 ALCPRIM    PICTURE  S9(2)    COMPUTATIONAL.
05 ALCSECD    PICTURE  S9(2)    COMPUTATIONAL.
05 ALCBLKS    PICTURE  S9(2)    COMPUTATIONAL.
05 ALCLREC    PICTURE  S9(2)    COMPUTATIONAL.
05 ALCRECF    PICTURE  X(2) .

05 ALCLRTCD   PICTURE  S9(2)    COMPUTATIONAL.
05 ALCLRSCD   PICTURE  X(4) .
```

The function to be processed determines the fields that you must complete. The tables below list the fields that you complete for each function.

### Allocate a sequential file already catalogued

Field	Value
ALCFUNC	A
ALCDDNM	DD name padded with blank
ALCDSNM	Data set name padded with blank
ALCDISP	SHR or OLD

### Deallocate a File

Field	Value
ALCFUNC	U
ALCDDNM	DD name padded with blank

### Delete/decatalog a file allocated by user program

Field	Value
ALCFUNC	D
ALCDDNM	DD name padded with blank

### Delete/decatalog of file

Field	Value
ALCFUNC	D
ALCDDNM	Blank
ALCDSNM	Data set name padded with blank

### Allocate a Member

Field	Value
ALCFUNC	A
ALCDDNM	DD name padded with blank
ALCDSNM	Data set name padded with blank
ALCDISP	SHR or OLD
ALCMEMB	Member name padded with blank

### Allocate a new Sequential File

Field	Value
ALCFUNC	A
ALCDDNM	DD name padded with blank
ALCDSNM	Data set name padded with blank
ALCDISP	NEW
ALCVOLS	Volume serial number
ALCUNIT	Unit name
ALCSPAC	Space type 'T' or 'C'
ALCPRIM	Primary allocation

Field	Value
ALCSECD	Secondary allocation
ALCBLKS	Block size
ALCLREC	Record length
ALCRECF	Record format

### Allocation Return Codes

The table below describes the possible allocation return codes.

ALCRTCD	Description
0	Request successfully executed
1	ALCFUNC not equal to A, U, or D
2	ALCDISP not equal to OLD, SHR, or NEW
3	ALCDDNM not given
4	ALCDSNM omitted
5	ALCSPAC not equal to C or T
6	ALCPRIM zero or < zero
7	ALCSECD zero or < zero
8	ALCVOLS omitted
9	ALCUNIT omitted
10	ALCBLKS zero or < zero
11	ALCLREC zero or < zero
12	ALCRECF zero or < zero
16	SVC99 return code given in field ALCRSCD
20	Internal error, see field ALCRSCD



## Reason Codes

The following table describes the possible reason codes with L3B2ZALC.

ALCRSCD	Description
9 302	Subsystem unknown or not started since last IPL
9 303	Sterling Connect:Express CICS notification interface not initiated
9 304	Request queue full
9 306	Invalid function
9 307	Notification interface (APL) already in WAIT state
9 308	Sterling Connect:Express CICS notification interface attach error
9 309	Notification interface (APL) request pending
9 310	Forced by user
9 311	Notification interface (APL) environment not initiated
9 312	Notification interface already attached
9 313	Notification interface (APL) queue full

## Abend Codes

The table below describes the possible abend codes with L3B2ZALC.

ALCRSCD	Description
T301	DFHCOMMAREA not found
T302	Invalid subsystem
T303	Sterling Connect:Express CICS Interface not initialized (L3B2Z040)
T304	Sterling Connect:Express CICS Interface table full (gm2- L3B2Z040)
T305	Request queue full

## L3B2ZUSJ: Selective Access to Sterling Connect:Express Journal File

The following COBOL example defines the communication area structure.

```

01 Sterling Connect:Express -USJ-PARMLIST.
   03 USJSSNA      PICTURE  X(4) .
   03 USJPARML.
      05 USJFUNC   PICTURE  X(1) .
      05 FILLER    PICTURE  X(3)      VALUE SPACES.
      05 USJRETC.
         07 USJRTCD PICTURE  X(1)      VALUE ZERO.
         07 USJRSCD PICTURE  X(3)      VALUE ZERO.
      05 USJNBRC   PICTURE  X(1)      VALUE ZERO.
      05 USJLIBE   PICTURE  X(3)      VALUE SPACE.
   03 USJSLECT.
      05 USJFILEN  PICTURE  X(8) .
      05 SCI-FUNC  PICTURE  X(1) .
      05 USJDSNAM  PICTURE  X(44) .
      05 USJDIREC  PICTURE  X(1) .
      05 USJSFCOD  PICTURE  X(5) .
      05 USJSFNAM  PICTURE  X(5) .
      05 USJPARID  PICTURE  X(8) .
      05 USJSORGT  PICTURE  X(1) .
      05 USJSORGN  PICTURE  X(5) .
      05 USJSDSTT  PICTURE  X(1) .
      05 USJSDSTN  PICTURE  X(5) .
      05 USJREQNB  PICTURE  X(8) .
      05 USJRDAT1  PICTURE  X(6) .
      05 USJRTIM1  PICTURE  X(6) .
      05 USJRDAT2  PICTURE  X(6) .
      05 USJRTIM2  PICTURE  X(6) .
      05 USJFILLR  PICTURE  X(9) .
   03 USJRECOR.
      05 FILLER    PICTURE  X(508)    VALUE SPACES.

```

The parameter area has the four sections listed below.

Section	Description
USJSSNA	Sterling Connect:Express subsystem name
USJPARML	Function codes and return codes
USJSLECT	Selection fields
USJRECOR	Journal record

The following table identifies the fields and possible values for each section.

Section	Field	Value
USJSSNA		Sterling Connect:Express subsystem name

Section	Field	Value
USJPARML	USJFUNC	O open SYSJNL file. <b>Note:</b> The O function must precede one or several calls with the D function. The C function must be called after the D function indicates there is no record corresponding to the specified selection criteria (USJNBRC = 0).
	Function code	D to obtain the first record at the first call, or the following records at successive calls. The records obtained successfully after each CALL with D function are placed in USJRECOR when they match the specified selection criteria. The field USJNBRC then is equal to 1. "C" Close SYSJNL file.
	FILLER	Reserved area
	USJRETC	Return code. If USJRETC is equal to zero this means that the request has been successfully completed. Otherwise, see the return codes list.
	USJNBRC	Can be equal to 0 or 1. <b>0</b> No or no more records of the Sterling Connect:Express journal file match the selection criteria. <b>1</b> One record is placed in the USJRECOR area.
	USJLIBE	Error message: blank means that the request has been successfully completed. Otherwise, see the error message list.
USJSLECT		Selection fields. It is possible to filter the journal file records by filling in the selection fields. A blank field means that any possible value is selected. The wild card * (asterisk) can be placed at the end of the selection string: for example, if DSNAM = SYST.BORDEAUX.*, then each record whose DSNAM field begins with "SYST.BORDEAUX" will be selected.
	USJFILEN	Symbolic name of the file
	USJDSNAM	Physical name of the file
	USJDIREC	Transfer direction, T for transmit, R for receive
	USJSFCOD	File type, for PeSIT only (used only in France)
	USJSFNAM	Logical file name, for PeSIT only
	USJPARID	Symbolic partner name
	USJSORGT	Origin type, for PeSIT only
	USJSORGN	Application ID, for PeSIT only
	USJSDSTT Journal record	Partner type
	USJSDSTN	Destination application ID, for PeSIT only
	USJREQNB	Request number

Section	Field	Value
	USJRDAT1, USJRTIM1, USJRDAT2, USJRTIM2	Date and time selection: the selected records correspond to any transfers starting after RDATE1 date and RTIME1 time and ending before RDATE2 date and RTIME2 time.
USJRECOR		Journal record. See the Sterling Connect:Express for z/OS User Guide for more information about the journal record and D1B2PJNL structure.

## Return Codes

USJRTCD	Description
0	Request successfully executed
not = 0	USJLIBE gives error message
9	Sterling Connect:Express CICS interface internal error USJLIBE = 'INV'USJFUNC not equal to O, D, C, or R USJLIBE = 'ACB'Generate ACB error USJLIBE = 'RPL'Generate RPL error USJLIBE = 'OPN'Open error USJLIBE = 'SHW'VSAM error USJLIBE = 'GET'READ error, USJRETC = RPL feed-back USJLIBE = 'CLS'Close error

## Reason Codes

USJRSCD	Description
9 302	Subsystem unknown or not started since last IPL
9 303	Sterling Connect:Express CICS notification interface not initiated
9 304	Request queue full
9 306	Invalid function
9 307	Notification interface (APL) already in WAIT state
9 308	Sterling Connect:Express CICS notification interface attach error
9 309	Notification interface (APL) request pending
9 310	Forced by user
9 311	Notification interface (APL) environment not initiated
9 312	Notification interface already attached
9 313	Notification interface (APL) queue full

## Abend Codes

USJRSCD	Description
T301	DFHCOMMAREA not found
T302	Invalid subsystem
T303	Sterling Connect:Express CICS Interface not initialized (L3B2Z040)
T304	Sterling Connect:Express CICS Interface table full (gm2- L3B2Z040)
T305	Request queue full

## Managing CICS to Sterling Connect:Express Communications

A CICS application can use Sterling Connect:Express services to send a parameter list to the monitor to initiate a transfer request. A CICS application can also connect to the monitor, and then Sterling Connect:Express sends the journal record to the application. You can use the L3B2ZZ20 program to send a file transfer request to Sterling Connect:Express.

### L3B2ZZ20: File Transfer Request to Sterling Connect:Express

The L3B2ZZ20 interface is based on the Application Program Interface described in Chapter 6 of the Sterling Connect:Express for z/OS User Guide. The following COBOL example shows the communication area structure.

```
01 Sterling Connect:Express -REQ-PARMLIST.
   03 REQSNA          PICTURE X(4) .

   03 REQ-SIT-PARML.
     05 SIT-FUNC      PICTURE X(1)    VALUE 'T' .
     05 SIT-TYPE      PICTURE X(1)    VALUE 'R' .
     05 SIT-REQN      PICTURE X(8)    VALUE '00000000' .
     05 FILLER        PICTURE X(2)    VALUE SPACES .
     05 SIT-RTCF      PICTURE X(1)    VALUE '0' .
     05 SIT-RSCF      PICTURE X(3)    VALUE '000' .
     05 SIT-EMSG      PICTURE X(80)   VALUE SPACES .

     05 SIT-PROT      PICTURE X(1)    VALUE 'A' .
     05 SIT-CLAS      PICTURE X(1) .
     05 SIT-PRTY      PICTURE 9(1) .
     05 SIT-RTYP      PICTURE X(1)    VALUE 'N'
     05 FILLER        PICTURE X(1)    VALUE SPACES .

     05 SIT-ORGT      PICTURE 9(1) .
     05 SIT-ORGN      PICTURE 9(5) .
     05 SIT-DSTT      PICTURE 9(1) .
     05 SIT-DSTN      PICTURE 9(5) .

     05 SIT-DATE      PICTURE 9(6) .
     05 SIT-TIME      PICTURE 9(6) .

     05 SIT-FCOD      PICTURE 9(5) .
     05 SIT-FNAM      PICTURE X(5) .
     05 SIT-DSNM      PICTURE X(44) .
     05 FILLER        PICTURE X(133) .

   03 REQ-SCI-PARML REDEFINES REQ-SIT-PARML.
     05 SCI-FUNC      PICTURE X(1) .
     05 SCI-TYPE      PICTURE X(1)    VALUE 'R' .
     05 SCI-REQN      PICTURE X(8)    VALUE '00000000' .
     05 FILLER        PICTURE X(2)    VALUE SPACES .
     05 SCI-RTCF      PICTURE X(1)    VALUE '0' .
     05 SCI-RSCF      PICTURE X(3)    VALUE '000' .
     05 SCI-EMSG      PICTURE X(80)   VALUE SPACES .

     05 SCI-PROT      PICTURE X(1)    VALUE 'S' .
     05 SCI-CLAS      PICTURE X(1) .
     05 SCI-PRTY      PICTURE 9(1) .
     05 SCI-RTYP      PICTURE X(1) .
     05 SCI-TDIR      PICTURE X(1) .
```

Continued

05	SCIFILNM	PICTURE	X(8).
05	SCIPARTN	PICTURE	X(8).
05	SCIDSNAM	PICTURE	X(44).
05	SCIMEMBR	PICTURE	X(8).
05	FILLER	PICTURE	X(144).

Two types of file transfer requests are supported. The PeSIT request which is only used in France, and the Standard request.

### PeSIT Transfer Requests

The following table describes the fields and possible values for a PeSIT request.

Field	Value
REQSSNA	Subsystem name
SIT-CLAS	APM effector class
SIT-PRTY	Priority (0,1,2)
SIT-ORGT	Origin type (1,2)
SIT-ORGN	Origin number
SIT-DSTT	Destination type
SIT-DSTN	Destination number
SIT-DATE	Creation date
SIT-TIME	Creation time
SIT-FCOD	File type
SIT-FNAM	File logical name
SIT-DSNM	Physical name of the file

### Standard Transfer Requests

The following table describes the fields and possible values for a standard transfer request.

Field	Value
SCI-CLAS	APM effector class
SCI-PRTY	Priority (0,1,2)
SCI-TDIR	Transfer direction (T,R)
SCIFILNM	Symbolic file name
SCIPARTN	Symbolic partner name

Field	Value
SCIDSNAM	Physical name of the file:edt.

### Return Codes

For PeSIT transfer requests, the return codes, reason codes, and messages are returned in the fields SIT-RTCF, SIT-RSCF, and SIT-EMSG.

For standard transfer requests, the return codes, reason codes, and messages are returned in the fields SCI-RTCF, SCI -RSCF, and SCI -EMSG.

The 'EMSG' fields contain the error message or 'OK'. See Sterling Connect:Express HELP TRC on the TSO/ISPF screen or consult *Appendix B Error Codes and Messages* in the User Guide for a list of error codes.

Internal errors in the Sterling Connect:Express CICS interface are identified in the following tables.

### Reason Codes (RTCF + RSCF)

Code	Description
9 302	Subsystem unknown or not started since last IPL
9 303	Sterling Connect:Express CICS notification interface not initiated
9 304	Request queue full
9 306	Invalid function
9 307	Notification interface (APL) already in WAIT state
9 308	Sterling Connect:Express CICS notification interface attach error
9 309	Notification interface (APL) request pending
9 310	Forced by user
9 311	Notification interface (APL) environment not initiated
9 312	Notification interface already attached
9 313	Notification interface (APL) queue full

### Abend Codes (RTCF + RSCF)

Code	Description
T301	DFHCOMMAREA not found
T302	Invalid subsystem
T303	Sterling Connect:Express CICS Interface not initialized (L3B2Z040)
T304	Sterling Connect:Express CICS Interface table full (gm2- L3B2Z040)
T305	Request queue full



## Managing Sterling Connect:Express to CICS Communications

You can use the L3B2ZAPL program to request transfer notifications from Sterling Connect:Express.

### L3B2ZAPL: Transfer Notification Request.

The L3B2ZAPL interface is based on the Application Program Interface described in Chapter 6 of the Sterling Connect:Express for z/OS User Guide.

There are three steps to implement a transfer notification request.

1. The user application connects to Sterling Connect:Express at initialization to be identified.
2. The user application waits to receive a notification each time a transfer is completed. At each event (transmit-receive completion, normal or abnormal), Sterling Connect:Express immediately transmits the elements recorded in its journal file to the waiting transaction.
3. The application issues a disconnect request to Sterling Connect:Express.

The following example shows the communication area structure.

```
01 Sterling Connect:Express -APL-PARMLIST.
03 APLSSNA PICTURE X(4).
03 APLPARML.
05 APLAPLNM PICTURE X(8).
05 APLREQST PICTURE X(1).
05 APLRSRVD PICTURE X(3).
05 APLREQRC PICTURE X(1).
05 APLREQRS PICTURE X(3).
03 APLANSWR.
05 FILLER PICTURE X(508).
03 APLANSW2 REDEFINES APLANSWR.
05 APLINTR-KEY PICTURE X(4).
05 APLINTR-COD PICTURE X(4).
05 FILLER PICTURE X(500).
```

The table below describes the fields in the communication area structure.

Field	Value
APLSSNA	Subsystem name of Sterling Connect:Express
APLAPLNM	Name of application
APLREQST	Function I, W, or T
APLRSRVD	Unused
APLREQRC	Return code
APLREQRS	Return code
APLANSWR	Reply area (see journal record format)
APLINTR-KEY	Reply key of journal for I and T
APLINTR-COD	Function key (INIT if it is OK, TERM if Sterling Connect:Express stops, FORC to force application stop)

## Reason Codes (RC + RS)

Code	Description
<b>9 302</b>	<b>Subsystem unknown or not started since last IPL</b>
9 303	Sterling Connect:Express CICS notification interface not initiated
9 304	Request queue full
9 306	Invalid function
9 307	Notification interface (APL) already in WAIT state
9 308	Sterling Connect:Express CICS notification interface attach error
9 309	Notification interface (APL) request pending
9 310	Forced by user
9 311	Notification interface (APL) environment not initiated
9 312	Notification interface already attached
9 313	Notification interface (APL) queue full

## Abend Codes (RC + RS)

Code	Description
T301	DFHCOMMAREA not found
T302	Invalid subsystem
T303	Sterling Connect:Express CICS Interface not initialized (L3B2Z040)
T304	Sterling Connect:Express CICS Interface table full (gm2- L3B2Z040)
T305	Request queue full

---

# IMS Interface

This chapter describes the IMS interface option which provides subroutine modules that can be called by an IMS application to communicate with Sterling Connect:Express for z/OS. These subroutines enable an IMS application to request Sterling Connect:Express to perform certain functions on behalf of the application.

---

### Overview

The IMS option of Sterling Connect:Express for z/OS enables an IMS application to manage files and communications with Sterling Connect:Express.

---

Note: The IMS option modules are provided and enabled on the standard product tape.

---

Normally an IMS application does not have access to file management, however this is possible using the features listed below:

- ❖ Dynamic allocation, deallocation, catalog, decatalog, delete - of QSAM files
- ❖ Selective access to the Sterling Connect:Express journal file

An IMS application can use Sterling Connect:Express services by sending a parameter list to the monitor to initiate a transfer request or place the program in a wait state. An IMS application can also connect to the monitor, and then Sterling Connect:Express sends the journal record to the application.

During initialization of the IMS region that issues requests to Sterling Connect:Express, you must call a module which initializes an ESTAE environment. This environment ensures that the application disconnects from Sterling Connect:Express if the IMS region or task ABENDs.

---

### Using the IMS Interface

After the Sterling Connect:Express IMS interface is enabled, a user program can use IMS services by calling one of the subroutine modules.

The modules are written in assembly and can be called by a user program running in a BMP or an MPP. The user program can be written in COBOL, ASSEMBLY, or PL1 using standard IBM conventions. For COBOL

programs, communication areas are defined in the \*MACLIB\* provided with the installation material and can be inserted using COPY commands.

Because BMP and MPP are user applications that use IMS statements, they can use the Sterling Connect:Express interface module to communicate with Sterling Connect:Express. Because they are IMS regions, they can communicate with IMS.

## Managing Files

Normally, an IMS application does not have access to file management. This is possible using L4B2ZALC for dynamic file allocation and de-allocation, and L0B2ZUSJ for selective access to the Sterling Connect:Express Journal File. These programs are discussed in the next two sections.

### L4B2ZALC: Dynamic File Allocation/Deallocation

A user program running in BMP or MPP can call this module to perform any of the following functions:

- ❖ Dynamic allocation DISP=SHR
- ❖ Dynamic allocation DISP=NEW
- ❖ Scratch/decatalog

The screen below shows the communication area structure.

```

DCL 1 ALLOCATION_PARM ,
    2 ALLOCATION_FUNCTION,
        5 ALCFNC CHAR(1),           /*A:ALLOCATION,U:UNALLOC,D:DELETE*/
    2 ALLOCATION_DDNAME,
        5 ALCDDN CHAR(8),           /*DDNAME */
    2 ALLOCATION_DSN,
        5 ALCDSN CHAR(44),          /*DSN */
    2 ALLOCATION_MEMBER,
        5 ALCMBR CHAR(8),           /* MEMBER NAME */
    2 ALLOCATION_DISP,
        5 ALCDSP1 CHAR(3),          /* OLD/SHR/NEW */
/*-----
NEXT PARMS: ONLY IF DISP=NEW
-----*/
    2 ALLOCATION_VOLUME,
        5 ALCVOL CHAR(6),           /*VOL=SER= */
    2 ALLOCATION_UNIT,
        5 ALCUNT CHAR(5),           /*UNIT= */
    2 ALLOCATION_SPACE,
        5 ALCSPC CHAR(1),           /* SPACE T:TRACKS,C:CYLINDER */
        5 ALCPRM BIN FIXED(15,0),   /* ALLOCATION PRIMAIRE */
        5 ALCSEC BIN FIXED(15,0),   /* ALLOCATION SECONDAIRE */
    2 ALLOCATION_DCB,
        5 ALCBLK BIN FIXED(15,0),   /* BLKSIZE= */
        5 ALCRCL BIN FIXED(15,0),   /* RECL= */
        5 ALCRFM CHAR(2),           /* RECFM= F/FB */
    2 ALLOCATION_CODE,
        5 ALCRTC BIN FIXED(15,0),   /* REASON CODE */
        5 ALCRSC CHAR(4);          /* RETURN CODE */

```

There are 5 functions that you can execute with this module. The following tables describe the values to enter for each function.

## Dynamic Allocation of a Catalogued File

Field	Value
ALCFNC	'A'
ALCDDN	DDNAME padded with blank
ALCDSN	Data set name padded with blank
ALCDSP1	SHR or OLD keywords

## Dynamic Allocation of a Member

The partitioned data set must be catalogued, and the user must fill in the following fields.

Field	Value
ALCFNC	'A'
ALCDDN	DDNAME padded with blank
ALCDSN	Data set name padded with blank
ALCDSP1	SHR or OLD keywords
ALCMBR	Member name padded with blank

## Dynamic Allocation of a New File

Field	Value
ALCFNC	'A'
ALCDDN	DDNAME padded with blank
ALCDSN	Data set name padded with blank
ALCDSP1	NEW keyword

All other parameters can be completed like a DD statement.

Note: The new data set is catalogued if the allocation was successful.

## Dynamic De-allocation

The request must be done after closing the file.

Field	Value
ALCFNC	'U'
ALCDDN	DD name padded with blank

### Scratch and de-catalog a file

The request must be done after closing the current file.

If the file has been previously allocated by a user program, complete the following fields.

---

Field	Value
ALCFNC	'D'
ALCDDN	DD name padded with blank

---

If the file was not previously allocated, complete the fields below.

---

Field	Value
FUNCTION	'D'
ALCDDN	Blank
ALCDSN	Data set name padded with blank

---

### Return Codes and Messages

If the request was successfully executed, the field ALCRTC is equal to zero. The other possible values for ALCRTC are listed below.

---

Note: The error codes 5 to 12 are used for dynamic allocation of new files.

---

## Execution Errors

Error Code	Description
1	FUNCTION not equal to A, U, or D
2	ALCDSP is invalid
3	ALCDDN is omitted
4	ALCDSN is omitted
5	ALCSPC not equal to T or C
6	ALCPRC equal or inferior to zero
7	ALCSEC equal or inferior to zero
8	ALCVOL is omitted
9	ALCUNT is omitted
10	ALCBLK equal to or less than zero
11	ALCRCL equal to or less than zero
12	ALCRFM equal to or less than zero

If ALCRTC = 16, the dynamic allocation or deallocation failed. In this case, the Return Code field contains the SVC99 return code, and a message appears on the screen.

```
L4B2ZALC dddddddd ffffffff ERR.CODE = xxxx
```

The table below describes each field.

Field	Description
Dddddddd	DD name
Fffffff	"ALLOCATE" or "DESALLOC"
Xxxx	SVC99 return code

## Example: Program Calling L4B2ZALC

The following screens show an example of an IMS application calling L4B2ZALC.

```
*PROCESS FLAG(I),A,S,GS,C,INC,NNUM,NEST;
SAMPLE1: PROCEDURE OPTIONS(MAIN) ;
/* *****
   SAMPLE PL/I PROGRAM calling L4B2ZALC
   ***** */
DCL PLIRETV BUILTIN;
DCL PLIRETC BUILTIN;
DCL L4B2ZALC EXTERNAL ENTRY OPTIONS (ASM,INTER,RETCODE) ;
DCL SYSPRINT FILE STREAM OUTPUT ;

DCL DDN FILE RECORD SEQUENTIAL INPUT ;
DCL DDN2 FILE RECORD SEQUENTIAL OUTPUT ;
DCL DDN3 FILE RECORD SEQUENTIAL OUTPUT ;

DCL ZONE CHAR(80);
DCL ZON2 CHAR(120);

DCL 1 ALLOCATION_PARM ,
    2 ALLOCATION_FUNCTION,
        5 ALCFNC CHAR(1),           /*A:ALLOCATION,U:UNALLOC,D=DLET */
    2 ALLOCATION_DDNAME,
        5 ALCDDN CHAR(8),           /*DDNAME */
    2 ALLOCATION_DSN,
        5 ALCDSN CHAR(44),         /*DSN */
    2 ALLOCATION_MEMBER,
        5 ALCMBR CHAR(8),          /* MEMBER NAME */
    2 ALLOCATION_DISP,
        5 ALCDSP1 CHAR(3),         /* OLD/SHR/NEW */
/*-----
NEXT PARM_: ONLY IF DISP=NEW
-----*/
    2 ALLOCATION_VOLUME,
        5 ALCVOL CHAR(6),          /*VOL=SER= */
    2 ALLOCATION_UNIT,
        5 ALCUNT CHAR(5),          /*UNIT= */
    2 ALLOCATION_SPACE,
        5 ALCSPC CHAR(1),          /* SPACE T:TRACKS,C:CYLINDER */
        5 ALCPRM BIN FIXED(15,0),  /* ALLOCATION PRIMAIRE */
        5 ALCSEC BIN FIXED(15,0),  /* ALLOCATION SECONDAIRE */
    2 ALLOCATION_DCB,
        5 ALCBLK BIN FIXED(15,0),  /* BLKSIZE= */
        5 ALCRCL BIN FIXED(15,0),  /* RECL= */
        5 ALCRFM CHAR(2),          /* RECFM= F/FB */
    2 ALLOCATION_CODE,
        5 ALCRTC BIN FIXED(15,0),  /* REASON CODE */
        5 ALCRSC CHAR(4);         /* RETURN CODE */
```

Continued



```

/*-----*/
PUT SKIP LIST(' ALLOCATION CATALOGUED FILE');
ALCFNC='A';
ALCDDN='DDN      ';
ALCDSN='PSR$TST.MNF.BBBB';
ALCDSP1='SHR';
CALL L4B2ZALC (ALLOCATION_PARM) ;

IF ALCRTC = 0 THEN GOTO ERROR;

OPEN FILE(DDN) ;
READ FILE(DDN) INTO(ZONE);
PUT SKIP LIST(' ZONE',ZONE) ;

/*-----*/
PUT SKIP LIST(' ALLOCATION NEW FILE');
ALCFNC='A';
ALCDDN='DDN2';
ALCDSN='PSR$TST.MNF.BBB2';
ALCDSP1='NEW';
ALCVOL='PSR002';
ALCUNT='3380';
ALCSPC='T';
ALCPRM=1;
ALCSEC=0;
ALCRCL=120;
ALCBLK=120;
ALCRFM=' F';
CALL L4B2ZALC (ALLOCATION_PARM) ;

IF ALCRTC = 0 THEN GOTO ERROR;

ZON2=ZONE;

OPEN FILE(DDN2) ;
WRITE FILE(DDN2) FROM(ZON2);

/*-----*/
PUT SKIP LIST(' ALLOCATION SECOND NEW FILE');
ALCFNC='A';
ALCDDN='DDN3';
ALCDSN='PSR$TST.MNF.BBB3';
ALCDSP1='NEW';
ALCVOL='PSR002';
ALCUNT='3380';
ALCSPC='C';
ALCPRM=1;
ALCSEC=1;

ALCRCL=120;
ALCBLK=1200;
ALCRFM=' F';
CALL L4B2ZALC (ALLOCATION_PARM) ;

IF ALCRTC = 0 THEN GOTO ERROR;

```

Continued

```

OPEN FILE (DDN3) ;
WRITE FILE (DDN3) FROM (ZON2) ;

/*-----*/
CLOSE FILE (DDN) ;
PUT SKIP LIST (' UNALLOC FILE BY DDN') ;
ALCDDN='DDN' ;
ALCFNC='U' ;
CALL L4B2ZALC (ALLOCATION_PARM) ;

IF ALCRTC = 0 THEN GOTO ERROR;
/*-----*/
PUT SKIP LIST (' DELETE NO CURRENTLY ALLOCATED DATA SET') ;
ALCDDN='      ' ;
ALCDSN='PSR$TST.MNF.BBBB      ' ;
ALCFNC='D' ;
CALL L4B2ZALC (ALLOCATION_PARM) ;

IF ALCRTC = 0 THEN GOTO ERROR;

/*-----*/
PUT SKIP LIST (' DELETE CURRENTLY ALLOCATED DATA SET') ;
CLOSE FILE (DDN3) ;
ALCDDN='DDN3      ' ;
ALCDSN='      ' ;
ALCFNC='D' ;
CALL L4B2ZALC (ALLOCATION_PARM) ;

IF ALCRTC = 0 THEN GOTO ERROR;

GOTO FIN;

ERROR:
PUT SKIP LIST (' FUNCTION ERROR: ' ||ALCFNC|| ',RETURN CODE='
||ALCRTC|| ',REASON CODE=' ||ALCRSC) ;

FIN:
END ;

```

## L0B2ZUSJ: Access to Sterling Connect:Express Journal

A user program running in BMP or MPP can call this module to access the Sterling Connect:Express Journal file. You can retrieve a record by record number or select a list of records with selection criteria.

---

**Note:** Assembler usage is recommended with this module, rather than COBOL or PL/I.

---

The following PL/I example defines the communication area structure.

```

DCL 01 JOURNAL-COMMUNICATION,
      03 JOURNAL-PARM,
          05 JNL-PRM-FNC      CHAR,
          05 JNL-PRM-FILLER CHAR(3),
          05 JNL-PRM-RTCOD  CHAR(4),
          05 JNL-PRM-NBR    CHAR(1),
          05 JNL-PRM-RSCOD  CHAR(3),
      03 JOURNAL-SELECTION,
          05 JNL-SLC-FILEN  CHAR(8),
          05 JNL-SLC-DSNAM  CHAR(44),
          05 JNL-SLC-DIREC  CHAR(1),
          05 JNL-SLC-PSFTY  CHAR(5),
          05 JNL-SLC-PSNAM  CHAR(5),
          05 JNL-SLC-PARTN  CHAR(8),
          05 JNL-SLC-LOTYP  CHAR,
          05 JNL-SLC-LOAPN  CHAR(5),
          05 JNL-SLC-PATYP  CHAR,
          05 JNL-SLC-PAAPN  CHAR(5),
          05 JNL-SLC-REQNB  CHAR(8),
          05 JNL-SLC-MNDAT  CHAR(6),
          05 JNL-SLC-MNTIM  CHAR(6),
          05 JNL-SLC-MXDAT  CHAR(6),
          05 JNL-SLC-MXTIM  CHAR(6),
          05 JNL-SLC-FILLR  CHAR(9),
      03 JOURNAL-ANSWER,
          05 JNL-ANS-RECORD CHAR(508);

```

The parameter area includes the following three sections:

- ❖ JOURNAL-PARM: function codes and return codes
- ❖ JOURNAL-SELECTION: Selection fields
- ❖ JOURNAL-ANSWER: Journal record

When a program calls L0B2ZUSJ, a DD statement must refer to the Sterling Connect:Express journal file. Then, the user program submits a request to open the journal file, enters a request for one or more records, and sends a request to close the journal file.

The parameter area, JOURNAL-PARM, has the following fields.

Field	Value
JNL-PRM-FNC	Function code. The following values are valid. <b>O</b> Request for opening the journal file. <b>D</b> To obtain the first record at the first call, or the following records at the next calls. The records obtained successfully after each call with the D function are placed in JNL-ANS-RECORD when they match the selection criteria. The field JNL-PRM-NBR is equal to 1. <b>R</b> To obtain directly the record number x, this number must be put in hexadecimal XL4 in USJFILEN first positions. <b>C</b> Request for closing the journal file. The C function must be called as soon as the D function indicates that no record matches the specified selection criteria. The field JNL-PRM-NBR is equal to zero.
JNL-PRM-FILLER	Reserved
JNL-PRM-RTCOD	Return code

Field	Value
JNL-PRM-NBR	This field is equal to 1 if the selection is successful and 0 if no matching record is found.
JNL-PRM-RSCOD	Error message or blank as listed next page

You can filter the journal file records by filling in the selection fields. Complete only the fields that you want to use as selection criteria. You can use the wild card \* (asterisk) at the end of the selection string. For example, if JNL-SLC-DSNAM = SYST.BORDEAUX.\*, then each record whose DSNAM field begins with “SYST.BORDEAUX” is selected. The selection area, JOURNAL-SELECTION, includes the following fields.

Field	Value
JNL-SLC-FILEN	Symbolic file name
JNL-SLC-DSNAM	Data set name of file
JNL-SLC-DIREC	Transfer direction (T for transmit, R for receive)
JNL-SLC-PSFTY	File type (PeSIT)
JNL-SLC-PSNAM	Logical file name (PeSIT)
JNL-SLC-PARTN	Symbolic partner name (PeSIT)
JNL-SLC-LOTYP	Origin type (PeSIT)
JNL-SLC-LOAPN	Origin application number (PeSIT)
JNL-SLC-PATYP	Destination type (PeSIT)
JNL-SLC-PAAPN	Destination application number (PeSIT)
JNL-SLC-REQNB	Number of the request
JNL-SLC-MNDAT	Date and time selection: The selected records
JNL-SLC-MNTIM	correspond to transfers starting after JNL-SLC-MNDAT
JNL-SLC-MXDAT	date and JNL-SLC-MNTIM time and ending before
JNL-SLC-MXTIM	JNL-SLC-MXDAT date and JNL-SLC-MXTIM time

The results of your record search display in the JOURNAL-ANSWER section.

### Return Codes

The JNL-PRM-RSCOD field indicates the error type. The table below lists the possible codes.

Code	Description
INV	Function code not equal to O, D, R or C
ACB	ACB generation failed
RPL	RPL generation failed

<b>Code</b>	<b>Description</b>
OPN	SYSJNL open error
SHW	VSAM error, SHOWCB failed
GET	Read error, RTCOD is equal to RPL "feedback"
CLS	Close error

## Example: Program Calling L0B2ZUSJ

```
*PROCESS FLAG(I),A,S,GS,C,INC,NNUM,NEST;
SAMPLE5: PROCEDURE OPTIONS(MAIN);

/*****
/** L0B2ZUSJ calling sample **/
/** to read all Sterling Connect:Express journal records **/
*****/

DCL L0B2ZUSJ EXTERNAL ENTRY OPTIONS (ASM,INTER,RETCODE);

DCL 01 JOURNAL-COMMUNICATION,
    03 JOURNAL-PARM,
        05 JNL-PRM-FNC CHAR, /* O:OPEN,D:DISPLAY,C:CLOSE */
        05 JNL-PRM-FILLER CHAR(3),
        05 JNL-PRM-RTCOD CHAR(4), /* BLANC:OK ERROR CODES */
        05 JNL-PRM-NBR CHAR(1), /*v0:NO MORE REC.,1:ONE REC.*
        05 JNL-PRM-RSCOD CHAR(3), /* BLANC:OK ERROR CODES */
    03 JOURNAL-SELECTION,
        05 JNL-SLC-FILEN CHAR(8),
        05 JNL-SLC-DSNAM CHAR(44),
        05 JNL-SLC-DIREC CHAR(1),
        05 JNL-SLC-PSFTY CHAR(5),
        05 JNL-SLC-PSNAM CHAR(5),
        05 JNL-SLC-PARTN CHAR(8),
        05 JNL-SLC-LOTYP CHAR,
        05 JNL-SLC-LOAPN CHAR(5),
        05 JNL-SLC-PATYP CHAR,
        05 JNL-SLC-PAAPN CHAR(5),
        05 JNL-SLC-REQNB CHAR(8),
        05 JNL-SLC-MNDAT CHAR(6),
        05 JNL-SLC-MNTIM CHAR(6),
        05 JNL-SLC-MXDAT CHAR(6),
        05 JNL-SLC-MXTIM CHAR(6),
    03 JOURNAL-ANSWER,
        05 JNL-ANS-RECORD CHAR(512);

/* criteria-selected fields filled by
   appropriate value or by blanks */

JNL-SLC-FILEN=' ';
JNL-SLC-DSNAM=' ';
JNL-SLC-DIREC=' ';
JNL-SLC-PSFTY=' ';
JNL-SLC-PSNAM=' ';
JNL-SLC-PARTN=' ';
JNL-SLC-LOTYP=' ';
JNL-SLC-LOAPN=' ';
JNL-SLC-PATYP=' ';
JNL-SLC-PAAPN=' ';
JNL-SLC-REQNB=' ';
JNL-SLC-MNDAT=' ';
JNL-SLC-MNTIM=' ';
JNL-SLC-MXDAT=' ';
JNL-SLC-MXTIM=' ';
```

Continued

```

/*-----OPEN SYSJNLP-----*/

        JNL-PRM-FNC='O';

        CALL LOB2ZUSJ (JOURNAL-PARM);

        IF JNL-PRM-RSCOD=' ' | JNL-PRM-RTCOD='0000' THEN GOTO ERROR;

/*-----DISPLAY-RECORDS -----*/

        JNL-PRM-FNC='D';

DISPLAY:

        CALL LOB2ZUSJ (JOURNAL-PARM);

        IF JNL-PRM-RSCOD=' ' | JNL-PRM-RTCOD='0000' THEN GOTO ERROR;
        IF JNL-PRM-NBR='0' THEN GOTO CLOSE;

        PUT SKIP DATA(JOURNAL-ANSWER);

        GOTO DISPLAY;

/*-----CLOSE SYSJNL -----*/
CLOSE:

        JNL-PRM-FNC='C';

        CALL LOB2ZUSJ (JOURNAL-PARM);

        IF JNL-PRM-RSCOD=' ' | JNL-PRM-RTCOD='0000' THEN GOTO ERROR;

ERROR:
        PUT SKIP LIST('ERROR FCT='||JNL-PRM-FNC||' RSCOD='||JNL-PRM-RSCOD);

FIN:

        END;

```

## Managing IMS to Sterling Connect:Express Communications

An IMS application can use Sterling Connect:Express services by sending a parameter list to the monitor to initiate a transfer request or place the program in a wait state. You can use the L4B2ZWAI program to give the program a Wait status, and the LOB2ZZ20 program to send a transfer request.

## L4B2ZWAI: Set Program in Wait State

A user program running in a BMP or MPP can call this module. The following screen shows the communication area structure.

```
DCL 1 WAIT_PARM,
    2 WAIT_SECOND,
    5 WAISCN BIN FIXED (31,0);
```

The value in the field WAISCN must be entered in seconds, and no return code is issued at the end of execution.

### Example: Program Calling L4B2ZWAI

The following screen shows an example of an IMS application calling L4B2ZWAI.

```
*PROCESS FLAG(I),A,S,GS,C,INC,NNUM,NEST;
  BSIT07 : PROCEDURE OPTIONS(MAIN) ;
  DCL PLIRETV BUILTIN;
  DCL PLIRETC BUILTIN;
  DCL L4B2ZWAI EXTERNAL ENTRY OPTIONS (ASM,INTER,RETCODE) ;
  DCL SYSPRINT FILE STREAM OUTPUT ;

  DCL CALLRC BIN FIXED (31,0);

  DCL 1 WAIT_PARM ,
    2 WAIT_SECONDE,
    5 WAISCN BIN FIXED(31,0); /*SECONDS */

/*-----*/
  PUT SKIP LIST(wait for 15 seconds);
  WAISCN=15;
  CALL L4B2ZWAI (WAIT_PARM) ;

  CALLRC = PLIRETV ;
  PUT SKIP LIST(' CALL-RC',CALLRC) ;

/*-----*/
  PUT SKIP LIST(wait for 20 seconds);
  WAISCN=20;
  CALL L4B2ZWAI (WAIT_PARM) ;

  CALLRC = PLIRETV ;
  PUT SKIP LIST(' CALL-RC',CALLRC) ;

  END;
```



## L0B2ZZ20: Transfer Request

The L0B2ZZ20 interface is based on the Application Program Interface described in Chapter 6 of the *Sterling Connect:Express for z/OS User Guide*.

A user program running in a BMP or MPP can call this module. The following COBOL example shows the communication area structure.

```
01  REQUEST-PARM.
    03  TOMMONN  PICTURE X(4) .
    03  TOMFUNC  PICTURE X(1)  VALUE 'T' .
    03  TOMTYPE  PICTURE X(1)  VALUE 'R' .
    03  TOMREQN  PICTURE X(8)  VALUE ZERO .
    03  TOMFIL1  PICTURE X(2) .
    03  TOMRTCF  PICTURE X(1)  VALUE ZERO .
    03  TOMRSCF  PICTURE X(3)  VALUE ZERO .
    03  TOMEMSG  PICTURE X(80) VALUE SPACES .

    03  TOMASIT  PICTURE X(1)  VALUE 'A' .
    03  TOM-CLAS PICTURE X(1) .
    03  TOM-PRTY PICTURE X(1)  VALUE '1' .
    03  TOM-RTYP PICTURE X(1)  VALUE 'N' .
    03  TOM-FIL1 PICTURE X(1)  VALUE ' ' .
    03  TOM-ORGT PICTURE X .
    03  TOM-ORGN PICTURE X(5) .
    03  TOM-DSTT PICTURE X .
    03  TOM-DSTN PICTURE X(5) .
    03  TOM-DATE PICTURE X(6) .
    03  TOM-TIME PICTURE X(6) .
    03  TOM-FCOD PICTURE X(5) .
    03  TOM-FNAM PICTURE X(5) .
    03  TOM-DSNM PICTURE X(44) .
    03  FILLER   PICTURE X(128) .
```

If the request is accepted, then TOMRTCF and TOMRSCF are equal to zero and the TOMREQN field contains the Sterling Connect:Express request number.

If the request is rejected, then TOMRTCF is equal to 2 and TOMRSCF contains the reason code. TOMEMSG contains an error message or 'OK'. Refer to Sterling Connect:Express HELP TRC on the TSO/ISPF screen or *Appendix B Error Codes and Messages* in the User guide for a list of error codes and messages.

## Example: Program Calling L0B2ZZ20 for a PeSIT Transfer Request

```
IDENTIFICATION DIVISION.
PROGRAM-ID. 'TOMUSER'.
ENVIRONMENT DIVISION.
CONFIGURATION SECTION.

INPUT-OUTPUT SECTION.
FILE-CONTROL.
    SELECT PRT ASSIGN TO UT-S-PRT.

DATA DIVISION.
FILE SECTION.
FD   PRT          LABEL RECORDS ARE OMITTED
                        DATA RECORD IS TOMLNE
                        RECORDING MODE IS F.

01   TOMLNE.
02   ASA          PICTURE X(1) VALUE '1'.
02   T1           PICTURE X(16) VALUE 'REQUEST NUMBER: '.
02   C1           PICTURE X(8).
02   T2           PICTURE X(13) VALUE 'RETURN CODE: '.
02   C2           PICTURE X(2).
02   T3           PICTURE X(13) VALUE 'REASON CODE: '.
02   C3           PICTURE X(2).

WORKING-STORAGE SECTION.

01   REQUEST-PARM.
03   TOMMONN PICTURE X(4).
03   TOMFUNC PICTURE X(1) VALUE 'T'.
03   TOMTYPE PICTURE X(1) VALUE 'R'.
03   TOMREQN PICTURE X(8) VALUE '00000000'.
03   TOMFIL1 PICTURE X(2) VALUE ' '.
03   TOMRTCF PICTURE X(2).
03   TOMRSCF PICTURE X(2).

03   TOMASIT PICTURE X(1) VALUE 'A'.
03   Sterling Connect:Express -CLAS PICTURE X(1) VALUE 'B'.
03   Sterling Connect:Express -PRTY PICTURE X(1) VALUE '1'.
03   Sterling Connect:Express -RTYP PICTURE X(1) VALUE 'N'.
03   Sterling Connect:Express -FIL1 PICTURE X(1) VALUE ' '.
03   Sterling Connect:Express -ORGT PICTURE X.

03   Sterling Connect:Express -ORGN PICTURE X(5).
03   Sterling Connect:Express -DSTT PICTURE X.
03   Sterling Connect:Express -DSTN PICTURE X(5).
03   Sterling Connect:Express -DATE PICTURE X(6).
03   Sterling Connect:Express -TIME PICTURE X(6).
03   Sterling Connect:Express -FCOD PICTURE X(5).
03   Sterling Connect:Express -FNAM PICTURE X(5).
03   Sterling Connect:Express -DSNM PICTURE X(44).
03   FILLER PICTURE X(144).
```

Continued

```

PROCEDURE DIVISION.

OPEN OUTPUT PRT.

NOTE **** SET Sterling Connect:Express SUBSYSTEM NAME *****.
MOVE 'TOM4' TO TOMMONN.

NOTE **** SET ORIGIN TYPE AND APPLICATION NUMBER *****.
MOVE '1' TO Sterling Connect:Express -ORGT.
MOVE '11111' TO Sterling Connect:Express -ORGN.

NOTE **** SET DEST. TYPE AND APPLICATION NUMBER *****.
MOVE '1' TO Sterling Connect:Express -DST.
MOVE '22222' TO Sterling Connect:Express -DSTN.

NOTE **** SET DATE AND TIME *****.
MOVE '010188' TO Sterling Connect:Express -DATE.
MOVE '081256' TO Sterling Connect:Express -TIME.

NOTE **** SET SYMBOLIC FILENAME AND DSNAME *****.
MOVE '12345' TO Sterling Connect:Express -FCOD.
MOVE '12345' TO Sterling Connect:Express -FNAM.
MOVE 'A.B.C' TO Sterling Connect:Express -DSNM.

CALL 'L0B2Z20' USING REQUEST-PARM.

NOTE **** WRITE RETURN CODE AND REQUEST NUMBER *****.
MOVE TOMREQN TO C1.
MOVE TOMRTCF TO C2.
MOVE TOMRSCF TO C3.
WRITE TOMLNE.

CLOSE PRT.

NOTE * * * * *
* * * * *

STOP RUN.

```

### Managing Sterling Connect:Express to IMS Communications

An IMS application can connect to the monitor, and then Sterling Connect:Express sends the journal record to the application. You use the L0B2ZAPL program to request transfer notifications, and the L4B2ZAPO program to initialize the ESTAE environment for L0B2ZAPL. The next two sections discuss these programs.

#### L0B2ZAPL: Transfer Notification Request

The L0B2ZAPL interface is based on the Application Program Interface described in Chapter 6 of the Sterling Connect:Express for z/OS User Guide.

A user program running in a BMP or an MPP calls this module and performs the functions listed below:

- ❖ The program connects to the Sterling Connect:Express interface
- ❖ The program waits for notification from Sterling Connect:Express about completed transfers
- ❖ The programs issues a disconnect request to Sterling Connect:Express

The following example shows the communication area structure.

```

01 REQUEST-L0B2ZAPL.

05 APLTOMS PICTURE X(4) VALUE 'TOMP'. ---- TO ----> L0B2ZAPL
05 APLNAME PICTURE X(8) VALUE 'BSIT-IMS'. -----> L0B2ZAPL
05 APLFUNC PICTURE X(1) VALUE 'I'. or 'W' or 'T' -> L0B2ZAPL
05 APLRSRV PICTURE X(3) VALUE LOW-VALUE.
05 APLRTCD PICTURE X(1) VALUE ZERO. <--- FROM ----L0B2ZAPL
05 APLRSCD PICTURE X(3) VALUE ZERO. <-----L0B2ZAPL
05 APLRJNL PICTURE X(512) VALUE SPACES. <-----L0B2ZAPL

```

For each call to the L0B2ZAPL module, the fields must be completed or initialized as follows.

Field	Value
APLTOMS	Subsystem name.
APLNAME	Eight-character name padded with spaces.
APLFUNC	Function requested: <b>I</b> - Initialization. This function connects the user application to the Sterling Connect:Express interface. <b>W</b> - Wait notification. This function puts the user program in wait event from Sterling Connect:Express. At each end-of-transfer (normal or abnormal transmit-receive completion), Sterling Connect:Express immediately transmits the elements recorded on its journal file. The wait function can be repeated as many times as necessary. <b>T</b> - Termination. This function disconnects the user application from the Sterling Connect:Express interface.
APLRSRV	Reserved. Initialized with blanks.
APLRTCD	Initialized with ZERO (Sterling Connect:Express return code).
APLRSCD	Initialized with ZERO (Sterling Connect:Express reason code).
APLRJNL	Initialized with space (Sterling Connect:Express journal area).

### Return Codes

Each time a user program calls the program L0B2ZAPL, the user program receives and processes a response. If the return code is not 0, the operation failed. A reason code may also be returned. The table below describes the (RTC) and reason (RSC) codes.

Code	Description
RTC = 0 RSC = 000	Function I, W or T Request successfully executed

Code	Description
RTC = 1	Subsystem error
RSC = 001	Subsystem not defined
RSC = 002	End of SSCVT chain
RSC = 003	TOMn not started since last IPL
RSC = 004	T1B2PAPL table not initialized
RTC = 2	Parameter error
RSC = 999	APLTOMSS is not valid
RSC = 888	APLNAME is not valid
RSC = 777	Function code not equal to I, W or T
RTC = 4	Initialization error
RSC = 666	T1B2PAPL table is not valid
RSC = 555	Maximum initialized applications number reached
RSC = 444	Interface error
RSC = 333	Application already initialized
RTC = 6	Sterling Connect:Express notification error
RSC = 008	Wait event error
RTC = 8	Termination error
RSC = 222	Requested application not connected
RSC = 111	Application not found in T1B2PAPL table

When an error occurs, you must stop the process and correct the parameters or the program.

### APLRJNL Field

Sterling Connect:Express returns information to the user into the APLRJNL field. This field is mapped by the D1B2PJNL structure in the \*MACLIB\*. Normally, this information is displayed as a journal record. You can use this information to tell the application that Sterling Connect:Express is initializing or terminating.

When the user application is started before Sterling Connect:Express, Sterling Connect:Express notifies the application when it is in active status by sending a message in the Z45FILEN field (D1B2PJNL). This message contains the last journal record number in the first four bytes and the keyword "INIT" in the last four bytes of data.

When Sterling Connect:Express is stopped before the user application, the application is notified by a message in the Z45FILEN field (D1B2PJNL). The message contains the last journal record number in the first four bytes and the keyword "TERM" in the last four bytes of data.

### L4B2ZAP0: Initialize the ESTAE Environment for L0B2ZAPL

The L4B2ZAP0 module initializes the ESTAE environment to disconnect the user application when a program ABENDs. You must write a CALL to the L4B2ZAP0 module before the first call to L0B2ZAPL with the 'I' function. The following example shows a call to L4B2ZAP0 with the same communication area as that used for L0B2ZAPL. Only APLTOMS and APLNAME fields are used by this module.

```
CALL L4B2ZAP0 USING REQUEST-L0B2ZAPL.

01 REQUEST-L0B2ZAPL.

05 APLTOMS PICTURE X(4) VALUE 'TOMP'. ----- TO ---> L0B2ZAPL
05 APLNAME PICTURE X(8) VALUE 'BSIT-IMS'. -----> L0B2ZAPL
```



---

# Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing

IBM Corporation

North Castle Drive

Armonk, NY 10504-1785

U.S.A.

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual

Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing

Legal and Intellectual Property Law

IBM Japan Ltd.

1623-14, Shimotsuruma, Yamato-shi

Kanagawa 242-8502 Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT**

WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation

J46A/G4

555 Bailey Avenue

San Jose, CA\_\_95141-1003

U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.



All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information is for planning purposes only. The information herein is subject to change before the products described become available. This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© IBM 2010. Portions of this code are derived from IBM Corp. Sample Programs.

© Copyright IBM Corp. 2010.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

## Trademarks

IBM, the IBM logo, and [ibm.com](http://ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "[Copyright and trademark information](http://www.ibm.com/legal/copytrade.shtml)" at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

IT Infrastructure Library is a registered trademark of the Central Computer and Telecommunications Agency which is now part of the Office of Government Commerce.

Intel, Intel logo, Intel Inside, Intel Inside logo, Intel Centrino, Intel Centrino logo, Celeron, Intel Xeon, Intel SpeedStep, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

ITIL is a registered trademark, and a registered community trademark of the Office of Government Commerce, and is registered in the U.S. Patent and Trademark Office.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Cell Broadband Engine is a trademark of Sony Computer Entertainment, Inc. in the United States, other countries, or both and is used under license therefrom.

Linear Tape-Open, LTO, the LTO Logo, Ultrium and the Ultrium Logo are trademarks of HP, IBM Corp. and Quantum in the U.S. and other countries.

Connect Control Center®, Connect:Direct®, Connect:Enterprise, Gentran®, Gentran:Basic®, Gentran:Control®, Gentran:Director®, Gentran:Plus®, Gentran:Realtime®, Gentran:Server®, Gentran:Viewpoint®, Sterling Commerce™, Sterling Information Broker®, and Sterling Integrator® are trademarks or registered trademarks of Sterling Commerce, Inc., an IBM Company.

Other company, product, and service names may be trademarks or service marks of others.

- A**
- Allocation 1-6, 2-2
- C**
- CICS 1-1
    - Initialization 1-4
    - Installing 1-1
    - PCT 1-3
    - PLTPI 1-3
    - PLTSD 1-3
    - PPT 1-2
    - Start procedure 1-4
    - Tables 1-2
    - Termination 1-4
    - Troubles 1-5
- E**
- ESTAE environment 2-19
    - Initialization 2-19
- F**
- File
    - Allocation 1-6, 2-2
    - Management 1-5, 2-2
- I**
- IMS 2-1
    - Initialization 2-19
- J**
- Journal file 2-8
- L**
- L0B2ZAPL 2-17
  - L0B2ZUSJ 2-8
    - Example 2-12
  - L0B2ZZ20 2-15
    - Example 2-16
  - L3B2ZALC 1-6
  - L3B2ZAPL 1-17
  - L3B2ZUSJ 1-10
  - L3B2ZZ20 1-14
  - L4B2ZALC 2-2
    - Example 2-6
  - L4B2ZAP0 2-19
  - L4B2ZWAI 2-14
    - Example 2-14
- P**
- PeSIT
    - Transfer request 2-16
    - Transfer requests 1-15
- T**
- T3B2ZSSN 1-3
- W**
- Wait Status 2-14

