

Program Directory for IBM WebSphere Screen Customizer Version 2.0.70

Version 2 Release 0, Modification Level 70

Program Number 5648-D76

FMID HCUT207

for Use with OS/390 V2R9 - V2R10 z/OS V1.1 and higher

Document Date: September 2002

Note!
Before using this information and the product it supports, be sure to read the general information under "Notices" on page v.
A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.
© Copyright International Business Machines Corporation 2000, 2002. All rights reserved. US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Noti Trad	cesemarks	
1.1	Introduction Screen Customizer Description Screen Customizer FMIDs	2
2.1 2.2 2.3 2. 2. 2.4	Program Materials Basic Machine-Readable Material Optional Machine-Readable Material Program Publications 3.1 Basic Program Publications 3.2 Optional Program Publications Program Source Materials Publications Useful During Installation	
3.1 3.2 3.3	Program Support Program Services Preventive Service Planning Statement of Support Procedures Program and Service Level Information	
4.1	Program Level Information	11
5.1 5.2 5.2 5.5 5.3	Installation Requirements and Considerations Driving System Requirements 1.1 Machine Requirements 1.2 Programming Requirements Target System Requirements 2.1 Machine Requirements 2.2 Programming Requirements 5.2.2.1 Mandatory Requisites 5.2.2.2 Functional Requisites 5.2.2.2 Functional Requisites 5.2.2.3 Toleration/Coexistence Requisites 5.2.2.4 Incompatibility (Negative) Requisites 2.3 DASD Storage Requirements FMIDs Deleted Special Considerations	13 13 14 14 14 15 15 18
	Installation Instructions Installing Screen Customizer	

6 6 6 6 6 6 6	.1.1 SMP/E Considerations for Installing Screen Customizer .1.2 SMP/E Options Subentry Values .1.3 Sample Jobs .1.4 Perform SMP/E RECEIVE .1.5 Allocate SMP/E Target and Distribution Libraries and Paths .1.6 Create DDDEF Entries .1.7 Allocate Screen Customizer HFS Data Set (CUSHFS) - Optional .1.8 Allocate HFS Mount Points and Paths (CUSISMKD) .1.9 Perform SMP/E APPLY .1.10 Perform SMP/E ACCEPT	21 23 23 23 24 24 25 26
	Activating Screen Customizer	
	.2.1 Post-SMP/E Installation Steps (Run shell script mvscli.sh)	
	.2.3 Executing Screen Customizer	
	· · · · · · · · · · · · · · · · · · ·	
Rea	der's Comments	33
1.	Basic Material: Program Tape	
2.	Program File Content	
3.	Basic Material: Unlicensed Publications	
4. 5.	Screen Customizer Supported Language Publication Availability with Prefix	5
5. 6.	Publications Useful During Installation	
7.	Component IDs	
8.	Driving System Software Requirements	
9.	Mandatory Requisites	
10.	Functional Requisites	
11.	Total DASD Space Required by Screen Customizer	
12.	Storage Requirements for SMP/E Work Data Sets	17
13.	Storage Requirements for SMP/E Data Sets	17
14.	Storage Requirements for Screen Customizer Target Libraries	18
15.	Screen Customizer HFS Paths	
16.	Storage Requirements for Screen Customizer Distribution Libraries	
17.	SMP/E Options Subentry Values	
18.	Sample Installation Jobs	22

Notices

References in this document to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe on any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, New York 10504-1785 USA

For online versions of this book, we authorize you to:

- Copy, modify, and print the documentation contained on the media, for use within your enterprise, provided you reproduce the copyright notice, all warning statements, and other required statements on each copy or partial copy.
- Transfer the original unaltered copy of the documentation when you transfer the related IBM product (which may be either machines you own, or programs, if the program's license terms permit a transfer). You must, at the same time, destroy all other copies of the documentation.

You are responsible for payment of any taxes, including personal property taxes, resulting from this authorization.

THERE ARE NO WARRANTIES, EXPRESS OR IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Some jurisdictions do not allow the exclusion of implied warranties, so the above exclusion may not apply to you.

Your failure to comply with the terms above terminates this authorization. Upon termination, you must destroy your machine readable documentation.

Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

CBPDO MVS IBM® RACF

Host On-Demand

RETAIN USS

SMP/E WebSphere

TSO

The following terms are trademarks of other companies as follows:

Java Sun Microsystems, Inc.

Microsoft Corporation
UNIX X/Open Company Limited
Windows Microsoft Corporation
Windows 95 Microsoft Corporation
Windows 98 Microsoft Corporation
Windows 2000 Microsoft Corporation
Windows NT Microsoft Corporation

1.0 Introduction

This program directory is intended for the system programmer responsible for program installation and maintenance. It contains information concerning the material and procedures associated with the installation of IBM WebSphere Screen Customizer V2.0.70. This publication refers to IBM WebSphere Screen Customizer V2.0.70 as Screen Customizer. You should read all of this program directory before installing the program and then keep it for future reference.

The program directory contains the following sections:

- 2.0, "Program Materials" on page 3 identifies the basic and optional program materials and documentation for Screen Customizer.
- 3.0, "Program Support" on page 9 describes the IBM support available for Screen Customizer.
- 4.0, "Program and Service Level Information" on page 11 lists the APARs (program level) and PTFs (service level) incorporated into Screen Customizer.
- 5.0, "Installation Requirements and Considerations" on page 13 identifies the resources and considerations for installing and using Screen Customizer.
- 6.0, "Installation Instructions" on page 21 provides detailed installation instructions for Screen Customizer. It also describes the procedures for activating the functions of Screen Customizer, or refers to appropriate publications.

Before installing Screen Customizer, read 3.2, "Preventive Service Planning" on page 9. This section tells you how to find any updates to the information and procedures in this program directory.

Do not use this program directory if you are installing Screen Customizer with a SystemPac or ServerPac. When using these offerings, use the jobs and documentation supplied with the offering. This documentation may point you to specific sections of the program directory as required.

If you are installing Screen Customizer using the Custom-Built Product Delivery Offering (CBPDO, 5751-CS3), a softcopy program directory is provided on the CBPDO tape which is identical to the printed copy shipped with your order. All service and HOLDDATA for Screen Customizer are included on the CBPDO tape.

This program directory is now being maintained as a 'living document' that contains up-to-date program and service level information. Please always reference the latest level of the Program Directory at the following web site (follow the library/documentation path):

http://www.ibm.com/software/network/screencustomizer/

Note: The external naming convention of Screen Customizer has changed to accommodate the dependency of working with IBM WebSphere Host On-Demand V7 only. Screen Customizer V2.0.70 will not function, nor install with any other release of Host On-Demand other than V7. Host On-Demand V7 (FMID HHOJ700) is a mandatory requisite for Screen Customizer. Subsequent service updates will be externally named, Screen Customizer V2.0.72, V2.0.73, to correspond with the service releases of Host

On-Demand (ie., V7.0.1, V7.0.2, etc). The previous level of Screen Customizer, V2.0.6 (FMID HCUT206) has been updated with its own line of service that corresponds with functioning with Host On-Demand V6 only. The V2.0.5 level (FMID HCUS200) has also been updated with its own line of service to correspond with functioning with Host On-Demand V5 only.

1.1 Screen Customizer Description

IBM WebSphere Screen Customizer V2.0.70 provides a graphical user interface for IBM WebSphere Host On-Demand sessions. Extensive customization capability is possible that does not require programming or modification of host applications. Screen Customizer is based on innovative screen recognition technology, requiring no access to source code.

The Client is integrated with a Host On-Demand session and runs as a Java applet in a browser.

Note: This level of Screen Customizer (V2.0.70 FMID HCUT207), will only execute with IBM Host On-Demand V7 (FMID HHOJ700). Host On-Demand V7 must be installed before the installation of Screen Customizer V2.0.70 or the installation will fail. Please see section 5.2.2, "Programming Requirements" on page 14, for more information on the requirements needed for a successful installation of Screen Customizer.

Note: The Administrator and Customization Studio components are not provided with Screen Customizer. The Administrator component lets you capture host screens and save them as maps that can be modified in the Customization Studio. The Administrator can also be used to set global defaults for font, colors, button styles, and attributes, and to save the defaults in a profile. The Customization Studio lets you create customized versions of host screens captured by the Administrator. Both the Administrator and Customization Studio can run only on a Windows 95, 98, or NT workstation. If you need Administrator or Customization capabilities, you must also separately order the IBM WebSphere Screen Customizer for Host Integration Administrator and Customization Studio components. Please contact your IBM Representative for more information.

1.2 Screen Customizer FMIDs

Screen Customizer consists of the following FMID:

HCUT207

2.0 Program Materials

An IBM program is identified by a program number and a feature number. The program number for Screen Customizer is 5648-D76.

Basic Machine-Readable Materials are materials that are supplied under the base license and feature code, and are required for the use of the product. Optional Machine-Readable Materials are orderable under separate feature codes, and are not required for the product to function.

The program announcement material describes the features supported by Screen Customizer. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is magnetic tape or downloadable files. It is installed using SMP/E, and is in SMP/E RELFILE format. See 6.0, "Installation Instructions" on page 21 for more information about how to install the program.

Figure 1 describes the physical tape. Figure 2 describes the file content.

Notes:

- 1. The data set attributes in these tables should be used in the JCL of jobs reading the data sets, but since the data sets are in IEBCOPY unloaded format, their actual attributes may be different.
- 2. If you are installing Screen Customizer using the Custom-Built Product Delivery Offering (CBPDO) (5751-CS3), some of the information in these figures may not be valid. Consult the CBPDO documentation for actual values.
- 3. If any RELFILEs are identified as PDSEs, ensure that SMPTLIB data sets are allocated as PDSEs.

Figure 1. Basic Material: Program Tape					
Medium	Feature Number	Physical Volume	External Label	R/M *	VOLSER
3480		1	IBM WebSpher Screen Customize V2.0.70		CUT207

^{*} R/M = Restricted Materials of IBM

Figure 2. Program File Content				
		R	L	
	0	E C	R E	
	R	F	Ċ	BLK
Name	G	М	L	SIZE
	-			
SMPMCS	PS	FB	80	6400
		FB VS	80 8816	6400 8820

2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for Screen Customizer.

2.3 Program Publications

The following sections identify the basic and optional publications for Screen Customizer.

2.3.1 Basic Program Publications

Figure 3 identifies the basic unlicensed program publications for Screen Customizer. The publications are in softcopy form and can be accessed by following the information below.

Note: PASS RULES must be added to your configuration file for your HTTP web server in order to view the documentation. Typically, the configuration file for your HTTP web server is named **httpd.conf** and is typically found in your **/etc** directory in UNIX System Services. Listed below are the complete set of **Pass** Rules that you should have to successfully execute both Host On-Demand V7 and Screen Customizer. You should have **all** the **Pass** rules as listed below in your **httpd.conf** file. You should have already added these statements with the installation of Host On-Demand V7. Please verify that the following **Pass** statements exist in your **httpd.conf** file and in the following order:

It is extremely important that the *Pass* statement "Pass /hod/* /usr/.." is the last Pass rule encountered. If this is not the last statement, problems will occur when trying to access both Host On-Demand V7 and Screen Customizer *htmls* and online publications.

Figure 3. Basic Material: Unlicensed Publications	
Publication Title	Form Number
IBM WebSphere Screen Customizer Getting Started	N/A
README	N/A

The main publication for Screen Customizer is Getting Started which covers installation (for non-OS/390 operating systems), configuration (all operating systems), and administration (all operating systems) for the Screen Customizer product. The README covers late breaking information about Screen Customizer. The publications are included in soft copy form (HTML) with the product and are viewable from your browser using the URL format listed below:

- · Getting Started:
 - http://<server name>/<webserver alias>/<language>/doc/custom/install/installation.html
- README:
 - http://<server name>/<webserver alias>/<language>/doc/custom/readme/readme.html

where <server name> refers to your OS/390 or z/OS server's TCP/IP host name, <webserver alias> refers to your web server's Pass Rule alias (look in your /etc/httpd.conf file in the 'Pass Rule' section default is **hod**), and **<language>** refers to your installed language prefix (ie., **en** for English, **de** for German, etc.). A table of all the supported languages, publication availability and their associated prefix is found after the table of basic publications. An example of a URL to point to the English language Screen Customizer Getting Started is:

http://mvs048/hod/en/doc/custom/install/installation.html

The publications are also available from the Screen Customizer product Web page at the following URL (following the library/ documentation path):

http://www.ibm.com/software/network/screencustomizer/

Figure 4 identifies the supported languages and the associated language prefix that you use in the URLs above to access the publications. If the table lists a 'Y', the document is provided in that language. If a 'N' is indicated, an English language document will be displayed instead of a translated version.

Figure 4 (Page 1 of 2). Screen Customizer Supported Language Publication Availability with Prefix			
Language	Language Prefix	README	Getting Started
Czech	CS	Υ	Υ
Danish	da	Υ	Υ
Dutch	nl	Υ	Υ
English	en	Υ	Υ

Language	Language Prefix	README	Getting Started
Finnish	fi	Υ	Υ
French	fr	Υ	Υ
German	de	Υ	Υ
Greek	el	Υ	Υ
Hungarian	hu	Υ	Υ
Italian	it	Υ	Υ
Japanese	ja	Υ	Υ
Korean	ko	Υ	Υ
Norwegian	no	Υ	Υ
Polish	pl	Υ	Υ
Portugese	pt_PT	Υ	Υ
Brazilian-Portugese	pt	Υ	Υ
Russian	ru	Υ	Υ
Slovenian	sl	N	Υ
Spanish	es	Υ	Υ
Swedish	sv	Υ	N
Simplified Chinese	zh	Υ	Υ
Traditional Chinese	zh_TW	Υ	Υ
Turkish	tr	Υ	Υ

Figure 5 identifies the basic licensed program publications for Screen Customizer.

Figure 5. Basic Material: Licensed Publications		
Publication Title	Form Number	Feature Number
There are no basic Licensed Publications	N/A	N/A

2.3.2 Optional Program Publications

2.4 Program Source Materials

No program source materials or viewable program listings are provided for Screen Customizer.

2.5 Publications Useful During Installation

The publications listed in Figure 6 on page 7 may be useful during the installation of Screen Customizer. To order copies, contact your IBM representative or visit the IBM Publications Center on the world wide web at: elink.ibmlink.ibm.com/applications/public/applications/publications/ cgibin/pbi.cgi on the Internet.

Figure 6. Publications Useful During Installation	
Publication Title	Form Number
IBM SMP/E for z/OS and OS/390 User's Guide	SA22-7773
IBM SMP/E for z/OS and OS/390 Commands	SA22-7771
IBM SMP/E for z/OS and OS/390 Reference	SA22-7772
IBM SMP/E for z/OS and OS/390 Messages, Codes, and Diagnosis	GA22-7770
UNIX System Services User's Guide	SC28-1891
UNXI System Services Command Reference	SC28-1892
UNXI System Services Planning	SC28-1890
UNXI System Services Messages & Codes	SC28-1908

3.0 Program Support

This section describes the IBM support available for Screen Customizer.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

If you obtained Screen Customizer as part of a CBPDO, there is HOLDDATA information included on the CBPDO.

If you obtained Screen Customizer on a product tape, or if the CBPDO is more than two weeks old when you install it, you should contact the IBM Support Center.

For access to RETAIN, visit http://www.ibmlink.ibm.com/ on the Internet.

Before installing Screen Customizer, you should also review the current support, product information, and Hints and Tips on the following Web sites:

- Support site: http://www.ibm.com/software/network/screencustomizer/support/
- Product information site: http://www.ibm.com/software/network/screencustomizer/
- Program Directory softcopy: http://www.ibm.com/software/network/screencustomizer/
- Hints and Tips site: http://www.ibm.com/support/

3.3 Statement of Support Procedures

Report any difficulties you have using this program to your IBM Support Center. If an APAR is required, the Support Center will provide the address to which any needed documentation can be sent.

Figure 7 identifies the component IDs (COMPID) for Screen Customizer.

Figure 7. Component IDs			
FMID	COMPID	Component Name	RETAIN Release
HCUT207	5648D0101	Screen Customizer V2.0.70	207

4.0 Program and Service Level Information

This section identifies the program and any relevant service levels of Screen Customizer. The program level refers to the APAR fixes incorporated into the program. The service level refers to the PTFs integrated.

4.1 Program Level Information

No APARs have been incorporated into Screen Customizer.

4.2 Service Level Information

No PTFs against this release of Screen Customizer have been incorporated into the product tape.

© Copyright IBM Corp. 2000, 2002

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating Screen Customizer. The following terminology is used:

- Driving system: the system used to install the program.
- · Target system: the system on which the program is installed.

In many cases, the same system can be used as both a driving system and a target system. However, you may want to set up a clone of your system to use as a target system by making a separate IPL-able copy of the running system. The clone should include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Some cases where two systems should be used include the following:

- When installing a new level of a product that is already installed, the new product will delete the old
 one. By installing onto a separate target system, you can test the new product while still keeping the
 old one in production.
- When installing a product that shares libraries or load modules with other products, the installation can
 disrupt the other products. Installing onto a test system or clone will allow you to assess these
 impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install Screen Customizer.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

Figure 8. Driving System Software Requirements			
Program Product Name and Number Minimum VRM/Service Level			
Any one of the foll	Any one of the following:		
5647-A01	OS/390 SMP/E Version 2 Release 9 or higher		
5694-A01	z/OS Version 1 Release 1 or higher		
5655-G44	IBM SMP/E for z/OS and OS/390 Version 3 Release 1 or higher		

© Copyright IBM Corp. 2000, 2002

5.2 Target System Requirements

This section describes the environment of the target system required to install and use Screen Customizer.

Screen Customizer installs in the MVS (Z038) SREL.

5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

5.2.2 Programming Requirements

5.2.2.1 Mandatory Requisites: A mandatory requisite is defined as a product that is required without exception; this product either will not install or will not function unless this requisite is met. This includes products that are specified as REQs or PREs.

Figure 9. Mandatory Requisites					
Program Number	Product Name and Minimum VRM/Service Level				
5733-A59	IBM WebSphere Host On-Demand V7 (FMID HHOJ700)				
Any one of the foll	lowing for base Operating System				
5647-A01	OS/390 V2R9 or higher				
5694-A01	z/OS V1.1 or higher				

It is recommended that you install Screen Customizer in the same SMP/E environment as you did for the mandatory requirement IBM WebSphere Host On-Demand (FMID HHOJ700). You can install into a different SMP/E environment, but this is not recommended.

5.2.2.2 Functional Requisites: A functional requisite is defined as a product that is **not** required for the successful installation of this product or for the basic function of the product, but is needed at run time for a specific function of this product to work. This includes products that are specified as IF REQs.

Figure 10 (Pag	ge 1 of 2). Functional Requisites		
Program Number	Product Name and Minimum VRM/Service Level	Function	
Any one of the	following for Browser Function:		
	Netscape Navigator 4.6 or higher	Browser Function	
	Netscape Navigator (OS/2) 4.61, IBM Web Browers for OS/2 V1.2	Browser Function	

Figure 10 (Pa	age 2 of 2). Functional Requisites		
Program Number	Product Name and Minimum VRM/Service Level	Function	
	Microsoft Internet Explorer 4.01 with SP1, V5.0, 5.1, 5.5, 6.0	Browser Function	
	Java Plugin 1.3 1.3.1, 1.4 (Sun, IBM)	Browser Function	

5.2.2.3 Toleration/Coexistence Requisites: A toleration/coexistence requisite is defined as a product which must be present on a sharing system. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD at different time intervals.

Screen Customizer has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites: A negative requisite identifies products which must not be installed on the same system as this product.

Screen Customizer has no negative requisites.

5.2.3 DASD Storage Requirements

Screen Customizer libraries can reside on all supported DASD types.

Figure 11 lists the total space required for each type of library.

Figure 11. T	otal DASD Space Required by Screen Customizer
Library Type	Total Space Required
Target	0.2 MB
Distribution	36.0 MB
HFS	150.0 MB

Notes:

- 1. IBM recommends use of system determined block sizes for efficient DASD utilization for all non-RECFM U data sets. For RECFM U data sets, IBM recommends a block size of 32760, which is the most efficient from a performance and DASD utilization perspective.
- 2. Abbreviations used for the data set type are:
 - U Unique data set, allocated by this product and used only by this product. To determine the correct storage needed for this data set, this table provides all required information; no other tables (or program directories) need to be referenced for the data set size.

- S Shared data set, allocated by this product and used by this product and others. To determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
- Existing shared data set, used by this product and others. This data set is NOT allocated by Ε this product. To determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other program directories). This existing data set must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old one and reclaim the space used by the old release and any service that had been installed. You can determine whether or not these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information on the names and sizes of the required data sets, please refer to 6.1.5, "Allocate SMP/E Target and Distribution Libraries and Paths" on page 23.

- 3. Abbreviations used for the HFS Path type are:
 - Ν New path, created by this product.
 - X Path created by this product, but may already exist from a previous release.
 - Ρ Previously existing path, created by another product.
- 4. All target and distribution libraries listed have the following attributes:
 - The default name of the data set may be changed
 - · The default block size of the data set may be changed
 - The data set may be merged with another data set that has equivalent characteristics
 - The data set may be either a PDS or a PDSE
- 5. All target libraries listed have the following attributes:
 - The data set may be SMS managed
 - It is not required for the data set to be SMS managed
 - · It is not required for the data set to reside on the IPL volume
 - The values in the "Member Type" column are not necessarily the actual SMP/E element types identified in the SMPMCS.
- 6. All target libraries listed which contain load modules have the following attributes:
 - The data set may be in the LPA
 - It is not required for the data set to be in the LPA
 - · The data set may be in the LNKLST
 - · It is not required for the data set to be APF authorized

Figure 12. Storage Requirements for SMP/E Work Data Sets							
Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR BIks	
SMPWRK1	S	PDS	FB	80	13	216	
SMPWRK2	S	PDS	FB	80	13	216	
SMPWRK3	S	PDS	FB	80	13	216	
SMPWRK4	S	PDS	FB	80	13	216	
SMPWRK6	S	PDS	FB	80	13	216	
SYSUT1	U	SEQ			30	0	
SYSUT2	U	SEQ			20	0	
SYSUT3	U	SEQ			20	0	
SYSUT4	U	SEQ			20	0	

Figure 13. Storage Requirements for SMP/E Data Sets						
Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR BIks
SMPLTS	Е	PDS	U	0	0	0
SMPMTS	Е	PDS	FB	80	75	5
SMPPTS	E	PDS	FB	80	2250	2
SMPSCDS	Е	PDS	FB	80	15	20
SMPSTS	Е	PDS	FB	80	75	5

The following figures describe the target and distribution libraries and HFS paths required to install Screen Customizer. The storage requirements of Screen Customizer must be added to the storage required by other programs having data in the same library or path.

Note: The data in these tables should be used when determining which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

Figure 14. Sto	orage Requirements for S	Screen Customize	er Targ	et Libraries				
Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR BIks
SCUSINST	Sample EXEC	TGTVOL	U	PDS	FB	80	3	2

Figure 15. Scr	een Cust	omizer HFS Paths
	Т	
	Y	
	Р	
DDNAME	E	Path Name
SCUS0001	N	/usr/lpp/customizer/IBM

Figure 16. Storage Requirements for Screen Custom	izer Distr	ibution Libra	aries			
Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR BIks
ACUSHFS1	U	PDS	VB	32600	1600	5
ACUSINST	U	PDS	FB	80	3	2

5.3 FMIDs Deleted

Installing Screen Customizer may result in the deletion of other FMIDs. To see what FMIDs will be deleted, examine the ++VER statement in the product's SMPMCS.

If you do not wish to delete these FMIDs at this time, you must install Screen Customizer into separate SMP/E target and distribution zones.

Note: These FMIDs will not automatically be deleted from the Global Zone. Consult the SMP/E manuals for instructions on how to do this.

5.4 Special Considerations

The distribution libraries are assumed to be contained in a single HFS data set whose mount point is /usr/lpp/customizer. Screen Customizer can be installed into an existing HFS, but if you wish to create your own HFS, the sample job CUSHFS can be used to allocate the HFS. It is recommended that you create your own HFS for Screen Customizer for serviceability. The CUSISMKD JCL sample is used to create the directory structure for your HFS.

After you finish with the SMP/E portion of your installation including running CUSAPPLY and CUSACCPT, you will have to run the shell script mvscli.sh to complete the installation. Refer to 6.2 Activating Screen Customizer for more details.

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of Screen Customizer.

Please note the following:

- If you want to install Screen Customizer into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMPCSI and the SMP/E control data sets.
- Sample jobs have been provided to help perform some or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries required for SMP/E execution have been defined in the appropriate zones.
- The SMP/E dialogs may be used instead of the sample jobs to accomplish the SMP/E installation steps.

6.1 Installing Screen Customizer

6.1.1 SMP/E Considerations for Installing Screen Customizer

This release of Screen Customizer is installed using the SMP/E RECEIVE, APPLY, and ACCEPT commands. The SMP/E dialogs may be used to accomplish the SMP/E installation steps.

6.1.2 SMP/E Options Subentry Values

The recommended values for some SMP/E CSI subentries are shown in Figure 17. Use of values lower than these may result in failures in the installation process. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. Refer to the SMP/E manuals for instructions on updating the global zone.

Figure 17. SM	Figure 17. SMP/E Options Subentry Values				
SUB-ENTRY	Value	Comment			
DSSPACE	(1000,500,350)	Specifies the primary and secondary space allocation (in Tracks) and the number of directory blocks to be allocated for each SMPTLIB dataset.			
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.			

6.1.3 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install Screen Customizer:

Figure 18. San	Figure 18. Sample Installation Jobs					
Job Name	Job Type	Description	RELFILE			
CUSRECVE	RECEIVE	Sample RECEIVE job	IBM.HCUT207.F1			
CUSALLOC	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.HCUT207.F1			
CUSDDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.HCUT207.F1			
CUSHFS	HFS	Sample job to define Screen Customizer HFS dataset (Optional)	IBM.HCUT207.F1			
CUSISMKD	MKDIR	Sample job to invoke the supplied CUSMKDIR EXEC to allocate HFS paths	IBM.HCUT207.F1			
CUSAPPLY	APPLY	Sample APPLY job	IBM.HCUT207.F1			
CUSACCPT	ACCEPT	Sample ACCEPT job	IBM.HCUT207.F1			

You may copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1
           EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN
           DD DSN=IBM.HCUT207.F1,UNIT=tunit,VOL=SER=CUT207,
           LABEL=(2,SL),DISP=(OLD,KEEP)
//FILEIN
           DD DSN=IBM.HCUT207.F1,UNIT=SYSALLDA,DISP=SHR,
           VOL=SER=filevol
//
//0UT
           DD DSNAME=jcl-library-name,
           DISP=(NEW, CATLG, DELETE),
//
//
           VOL=SER=dasdvol, UNIT=SYSALLDA,
           SPACE=(TRK,(3,2,1))
//SYSUT3
           DD UNIT=SYSALLDA, SPACE=(CYL, (1,1))
//SYSIN
           DD *
    COPY INDD=xxxxIN,OUTDD=OUT
```

where tunit is the unit value matching the product tape, filevol is the volume serial of the DASD device where the downloaded files reside, jcl-library-name is the name of the output data set where the sample jobs will be stored, dasdvol is the volume serial of the DASD device where the output data set will reside and **xxxxIN** on the SYSIN DD to either TAPEIN or FILEIN depending on your input DD statement.

You can also access the sample installation jobs by performing an SMP/E RECEIVE and then copying the jobs from the SMPTLIBs to a work data set for editing and submission. See Figure 18 on page 21 to find the appropriate SMPTLIB data set.

6.1.4 Perform SMP/E RECEIVE

Edit and submit sample job CUSRECVE to perform the SMP/E RECEIVE for Screen Customizer. Consult the instructions in the sample job for more information.

NOTE: If you obtained Screen Customizer as part of a CBPDO, you can use the RCVPDO job found in the CBPDO RIMLIB data set to RECEIVE the Screen Customizer FMIDs as well as any service, or HOLDDATA information included on the CBPDO tape. For more information, refer to the documentation included with the CBPDO.

Expected Return Codes and Messages:

This step should complete with Return Code = 0.

6.1.5 Allocate SMP/E Target and Distribution Libraries and Paths

Edit and submit sample job CUSALLOC to allocate the SMP/E target and distribution libraries for Screen Customizer. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages:

This step should complete with Return Code = 0.

6.1.6 Create DDDEF Entries

Edit and submit sample job CUSDDDEF to create DDDEF entries for the SMP/E target and distribution libraries for Screen Customizer. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages:

This step should complete with Return Code = 0.

This job should complete with a return code 0. However, if some or all of these DDDEF entries already exist, then the job will complete with a return code 8. You will have to examine the output and determine whether or not the existing entries should be replaced. you can change the 'ADD' to 'REP' in this job to replace existing entries.

You may receive the following message for the first change command in the DEFPATH step. This message is expected and can be ignored:

GIM26501W THE PATH SUBENTRY WAS NOT CHANGED.

If you receive this message, a return code of 4 is expected for the DEFPATH step.

6.1.7 Allocate Screen Customizer HFS Data Set (CUSHFS) - Optional

IBM WebSphere Screen Customizer V2.0.70 can be installed into any HFS. However, if you wish to create your own HFS for Screen Customizer, edit and submit sample job CUSHFS to allocate the HFS. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages:

This step should complete with Return Code = 0.

If you plan to create a new HFS for this product, you should consider updating the BPXPRMxx PARMLIB member to mount the new HFS at IPL time. This may be helpful if an IPL occurs before the installation is complete.

6.1.8 Allocate HFS Mount Points and Paths (CUSISMKD)

In this step you will create the HFS paths and the mount point for Screen Customizer. The instructions to create the mount point for Screen Customizer is detailed below as well as directions for running the CUSISMKD job which will create the paths.

The distribution libraries are assumed to be contained in a single HFS data set whose mount point is /usr/lpp/customizer. Screen Customizer can be installed into an existing HFS or a new one created using the CUSHFS sample job. Use the commands below and the CUSISMKD job as needed to create the paths and mount points for Screen Customizer. If you created a new HFS, you will need to complete all three (3) steps below. If you are installing into an existing HFS, you will only have to do step #3 (omit steps 1 and 2).

Note: The TSO MKDIR commands must be invoked using a RACF userid with root authority in the OS/390 UNIX System. Path as well as mount point specification in the OS/390 UNIX System is case sensitive.

Follow these steps to create the mount point and directories:

1. From TSO issue the following TSO MKDIR command to create the /usr/lpp/customizer mount point. TSO MKDIR '-PATHPREFIX-/usr/lpp/customizer' MODE (7,5,5)

Note: Change the occurrences of the string -pathprefix- to the appropriate high level directory name. For users installing in the root, this would be null. For others, the high level directory may be something like /service/ or a more meaningful name. Please note the replacement string is case sensitive.

2. Issue the following MOUNT command to mount the HFS on the /usr/lpp/customizer mount point. The HFS was previously allocated by the CUSHFS job.

Note: The mount command should be on one line.

Note: Change the **hfsprfx** qualifier to the name of the qualifier used in the CUSHFS installation job.

```
TSO MOUNT FILESYSTEM('hfsprfx.hfs')
MOUNTPOINT('-PATHPREFIX-/usr/lpp/customizer') TYPE(HFS)
```

Note: Change the occurrences of the string -pathprefix- to the appropriate high level directory name. For users installing in the root, this would be null. For others, the high level directory may be something like /service/ or a more meaningful name. Please note the replacement string is case sensitive.

3. Edit and submit sample job CUSISMKD to allocate the HFS paths for Screen Customizer. Consult the instructions in the sample job for more information.

This job calls CUSMKDIR which creates the directory structure for Screen Customizer. CUSMKDIR is a REXX script which is called by CUSISMKD. CUSMKDIR should not be invoked by itself.

Expected Return Codes and Messages:

This step should complete with Return Code = 0.

6.1.9 Perform SMP/E APPLY

Edit and submit sample job CUSAPPLY to perform an SMP/E APPLY CHECK for Screen Customizer. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do not bypass the following on the APPLY CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of ERRORS and not of WARNINGS (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

Once you have taken any actions indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E apply all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from APPLY CHECK:

This step should complete with Return Code = 0.

Expected Return Codes and Messages from APPLY:

This step should complete with Return Code = 0.

6.1.10 Perform SMP/E ACCEPT

Edit and submit sample job CUSACCPT to perform an SMP/E ACCEPT CHECK for Screen Customizer. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do not bypass the following on the ACCEPT CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of ERRORS and not of WARNINGS (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

Before using SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. This will cause entries produced from JCLIN to be saved in the distribution zone whenever a SYSMOD containing inline JCLIN is ACCEPTed. For more information on the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E manuals.

Once you have taken any actions indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accept all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK:

This step should complete with Return Code = 0.

Expected Return Codes and Messages from ACCEPT:

This step should complete with Return Code = 0.

If PTFs containing replacement modules are being ACCEPTed, SMP/E ACCEPT processing will linkedit/bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder may issue messages documenting unresolved external references, resulting in a return code of 4 from the ACCEPT step. These messages can be ignored, because the distribution libraries are not executable and the unresolved external references will not affect the executable system libraries.

6.2 Activating Screen Customizer

6.2.1 Post-SMP/E Installation Steps (Run shell script myscli.sh)

After the SMP/E installation steps have been completed for Screen Customizer, the mvscli.sh shell script must be run to properly configure Screen Customizer to Host On-Demand V7 for operation from a UNIX Systems Services command prompt.

There have been changes to the **mvscli.sh** shell script from past releases to accomodate the ability to install from one Screen Customizer directory (i.e., /Srvc/usr/lpp/customizer) and run from another

mountpoint (i.e., /usr/lpp/customizer). You are now required to input three (3) parameters to the initial shell script to indicate; 1) your current Screen Customizer mount point and where you are running the shell script from, 2) the path or mount point that indicates your Host On-Demand run-time, and 3) the path or mount point that indicates your Screen Customizer run-time.

One restriction that also needs to be met is that you must run the mvscli.sh shell script with your Host On-Demand run-time directory currently mounted as your mount point. This a restriction of the link command.

The **mvscli.sh** shell script is located by default in the /usr/lpp/customizer directory. If you changed the default path during your SMP/E install (ie., /Srvc/usr/lpp/customizer), you will find the shell script in this directory. You must invoke the shell script from the Screen Customizer directory where it was installed.

```
mvsclinew.sh <SC Install_Dir> <HOD Run_dir> <SC RunTime_dir>
  <SC Install_Dir> - your Screen Customizer installation directory.
  Typically this would be /usr/lpp/customizer. This is where
   you are running this shell script from.
  <HOD Run_dir> - the directory where you will run Host
  On-Demand. Typically this would be /usr/lpp/HOD
  <SC RunTime dir> - the directory where you will run Screen
  Customizer. Typically, this would be /usr/lpp/customizer
FOR EXAMPLE:
mvscli.sh /usr/lpp/customizer /usr/lpp/HOD /usr/lpp/customizer
                            -0R-
mvslic.sh /Srvc/usr/lpp/customizer /usr/lpp/HOD /usr/lpp/customizer
```

The mvscli.sh shell script creates the Screen Customizer directories and untars to the created HFS directories. The shell script also calls the HODSEDLink-UNIX shell script which creates symbolic links to Host On-Demand. You should not have to execute HODSEDLink-UNIX yourself. A HODLink-UNIX-errors file is created during the installation. If the shell script ran without errors, the last two lines in the file should be Linking HOD files and Done. with no error messages. If any errors occur during the execution of this shell script, the errors will be listed in this file and displayed to your USS console.

6.2.2 PASS RULES for Screen Customizer V2.0.70 Execution

Screen Customizer V2.0.70 requires that PASS RULES need to be added to your configuration file for your HTTP web server. Typically, this file is named httpd.conf and is typically found in your /etc directory in UNIX System Services. Listed below are the complete set of Pass Rules that you should have to successfully execute both Host On-Demand V7 and Screen Customizer. You should have all the Pass rules as listed below in your httpd.conf file. You should have already added these statements with the installation of Host On-Demand V7. Please verify that the following Pass statements exist in your httpd.conf file and in the following order:

```
# *** ADD NEW PASS RULES HERE ***
Pass /hod/*.html /usr/lpp/HOD/hostondemand/HOD/*.html.ascii
Pass /hod/*.HTML /usr/1pp/HOD/hostondemand/HOD/*.HTML.ascii
Pass /hod/*.js
                   /usr/lpp/HOD/hostondemand/HOD/*.js.ascii
Pass /hod/*.properties (continued on next line)
              /usr/1pp/HOD/hostondemand/HOD/*.properties.ascii
Pass /hod/*.props /usr/1pp/HOD/hostondemand/HOD/*.props.ascii
Pass /hod/* /usr/1pp/HOD/hostondemand/HOD/*
```

Note: It is extremely important that the Pass statement "Pass /hod/* /usr/.." is the last Pass rule encountered. If this is not the last statement, problems will occur when trying to access both Host On-Demand V7 and Screen Customizer htmls and online publications.

6.2.3 Executing Screen Customizer

The basic functions of Screen Customizer can be executed from one of the supported internet browsers via a Host On-Demand session. This will allow you to view default and any customized Screen Customizer screens. There are two ways to bring up a screen via your browser and a Host On-Demand session. One way is to enable an existing Host On-Demand User/Session to view Screen Customizer screens. The second way is to define a new Host On-Demand User, create enabled sessions for this new User for Screen Customizer and bring up a screen under this new User. Both methods are detailed below.

Enabling Screen Customizer with an existing Host On-Demand User/Session:

- 1. Enter the Host On-Demand Admin URL in your browser window to access Host On-Demand administrator functions
 - Log On to your Admin ID (requires Admin ID and Password)
- Select the Users tab
- 3. Expand the **Users** dropdown to reveal previously defined Users
- 4. Left click on an existing User ID to highlight
- 5. Select Sessions button to bring up a window with all configured sessions for that User
 - Right Click on selected session type (ie., 3270 Display) and select Properties
 - Under Screen tab, set Screen Customizer parameter to Enabled
 - Select the **OK** button
 - · Select the OK button
- 6. Log Off your Host On-Demand Admin ID
- 7. Log On to your enabled User/Session:
 - · Enter the Host On-Demand Client URL in your browser window
 - Enter your Screen Customizer enabled User ID and Password
- 8. Right click on your **enabled** defined session(s) (ie.,3270 Display)
 - Select Start Session to bring up your Screen Customizer screen(s)

Enabling Screen Customizer with a new Host On-Demand User - Create New User

1. Enter the Host On-Demand Admin URL in your browser window to access Host On-Demand administrator functions

- Log On to your Admin ID (requires Admin ID and Password)
- 2. Select the Users tab
- 3. Expand the **Users** dropdown to reveal defined users
- 4. Select the **New User** button and fill in the following:
 - User ID name
 - Description
 - · Password information
 - Add new User to a Group (Member of area)
 - Select **Apply** and then **Close** to add your new user to **Users** dropdown
- 5. Left click on your newly created User ID to highlight
- 6. Select **Sessions** button
 - Configure new session type (ie., 3270 Display) button
 - Under **Connection** tab, enter appropriate session information for your site
 - Under **Screen** tab, set Screen Customizer parameter to **Enabled**
 - Select the **OK** button and a new configured session will be created for the new User
 - Select the **OK** button
- 7. Log Off your Host On-Demand Admin ID
- 8. Log On to your newly created User/Session:
 - Enter the Host On-Demand Client URL in your browser window
 - Enter your new User ID and Password
- 9. Right click on your **enabled** defined session(s) (ie.,3270 Display)
 - Select Start Session to bring up your Screen Customizer screen(s)

Note: As mentioned previously, you must separately purchase the Administrator and Customization Studio components for administrative and customization capabilities with Screen Customizer. Screen Customizer provides the capability to view default and previously customized Screen Customizer screens. Contact your IBM representative to order the Administrator and Customization Studio.

Reader's Comments

Program Directory for IBM WebSphere Screen Customizer V2.0.70 September 2002

You may use this form to comment about this document, its organization, or subject matter with the understanding that IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

For each of the topics below please indicate your satisfaction level by circling your choice from the rating scale. If a statement does not apply, please circle N.

RATIN	G SCALE	i ———				
very satisfied 1	<===== 2	3	=====> 4	very dissatisfied 5	not applicable N	

	Satisfaction					
Ease of product installation	1	2	3	4	5	N
Contents of program directory	1	2	3	4	5	Ν
Installation Verification Programs	1	2	3	4	5	Ν
Time to install the product	1	2	3	4	5	Ν
Readability and organization of program directory tasks	1	2	3	4	5	Ν
Necessity of all installation tasks	1	2	3	4	5	Ν
Accuracy of the definition of the installation tasks	1	2	3	4	5	Ν
Technical level of the installation tasks	1	2	3	4	5	Ν
Ease of getting the system into production after installation		2	3	4	5	N

installatio	on
How did	d you order this product?
	CBPDO CustomPac ServerPac Independent Other
ls this t	he first time your organization has installed this product?
_	Yes No
Were th	ne people who did the installation experienced with the installation of z/OS products? Yes

	No	
If yes	, how many years?	
	have any comments to make about your ratings above, or any other asperm below:	ect of the product installation, please
-		
-		
-		
-		
-		
_		
-		
Pleas	e provide the following contact information:	
N	ame and Job Title	
ō -	rganization	
Ā	ddress	
_	elephone	

Thank you for your participation.

Please send the completed form to (or give to your IBM representative who will forward it to the IBM WebSphere Screen Customizer V2.0.70 Development group):

IBM Corporation Host Integration Installation Dept. DGYA/Bldg. 502 P.O. Box 12195 RTP, North Carolina 27709 USA

IBM

Printed in U.S.A.

