

Quick Start Guide

This guide gets you started with a typical installation for the AIX Version 6.1 operating system.

Product overview

Use these steps to install the Base Operating System (BOS) for AIX® from physical DVD media. The steps guide you through a new installation, also called an overwrite installation.

1 Step 1: Completing the prerequisites



Prepare for a new and complete overwrite:

- Ensure that you have at least 2 GB of memory and a minimum of 5 GB of physical disk space. For additional release information, see the AIX Release Notes that correspond to the level of your AIX operating system.
- Ensure that your hardware installation is complete, including all external devices. See the documentation that is provided with your system unit for installation instructions.
- Verify that your system is set to boot from the device in which the installation media is loaded. See the hardware documentation that accompanied your system for instructions about setting the boot device.
- If your system must communicate with other systems and access their resources, make sure that you have the following information before you proceed with the installation:
 - Network interface
 - Host name
 - IP address
 - Network mask
 - Name server
 - Domain name
 - Gateway

2 Step 2: Preparing your system for installation



Follow these steps to prepare your system for installation:

1. Insert the AIX Volume 1 media into the media device.
2. Shut down your system. If your system is running, turn it off by following these steps:
 - Log in as the root user.
 - Type the following command:

```
shutdown -F
```
 - If your system does not automatically turn off, place the power switch in the Off (0) position.

Do not turn on the system unit until instructed to do so in Step 4: Booting from your installation media.
3. Ensure that all external devices attached to the system (such as CD-ROM drives, tape drives, DVD drives, and terminals) are turned on. You must turn on the external devices first so that the system unit can identify each peripheral device during the startup (boot) process.

3 Step 3: Setting up an ASCII terminal



If you have not set up your ASCII terminal, set the communications, keyboard, and display options. Use the following criteria and your terminal reference documentation to set the communications, keyboard, and display options. The following settings are typical, but your terminal might have different option names and settings than these options:

Communication Options:

Options	Settings
Line speed (baud rate)	9600
Word Length (bits per character)	8
Parity	no (none)
Number of stop bits	1
Interface	RS-232C (or RS-422A)
Line control	IPRTS

Keyboard and display options:

Options	Settings
Screen	normal
Row and Column	24x80
Scroll	jump
Auto LF (line feed)	off
Line Wrap	on
Forcing Insert	line (or both)
Tab	field
Operating Mode	echo
Turnaround Character	CR
Enter	return
Return	new line
New Line	CR
Send	page
Insert	Character space

4 Step 4: Booting from your installation media



Follow this procedure for booting from your installation media:

1. Turn on the system unit power switch.
2. When the system beeps twice, press 5 on your ASCII terminal. The word keyboard is shown when the beeps occur.
3. If you have more than one console, each one might display a panel that directs you to press a key to identify your system console. A different key is specified for each console that is displayed on this panel. If this panel opens, press the specified key only on the console that you want to use for the installation. (The system console is the keyboard and display device that is used for installation and system administration.)
4. Select the language that you prefer to use during installation, and press Enter.

5 Step 5: Verifying the installation settings



Follow this procedure to verify your installation settings:

1. Display the installation settings before you install the BOS, by typing 2 in the **Choice** field to select 2 Change/Show Installation Settings and Install and press Enter.

```
Welcome to Base Operating System
Installation and Maintenance
Type the number of your choice and press Enter. Choice is indicated by >>>.
>>> 1 Start Install Now with Default Settings
2 Change/Show Installation Settings and Install
3 Start Maintenance Mode for System Recovery
4 Make Additional Disks Available
5 Select Storage Adapters
88 Help ?
99 Previous Menu
>>> Choice [1]:
```

2. Verify the default installation settings from the Overwrite Installation and Settings panel.
3. If the installation and system settings are correct, type 0 in the **Choice** field and press Enter. Confirm that the selections on the installation summary panel are correct, and press Enter to begin the BOS installation. The system automatically reboots after the system installation is complete. Go to Step 9: Finishing the BOS installation.

If your installation settings are not correct, or you want to change the installation settings, go to Step 6. Changing the installation settings.

6 Step 6: Optional: Changing the installation settings



To change the installation settings, complete the following steps:

1. In the Installation and Settings panel, type 1 in the **Choice** field to select the System Settings option.

Installation and Settings

Either type 0 and press Enter to install with current settings, or type the number of the setting you want to change and press Enter.

1 **System Settings:**

Method of Installation.....New and Complete Overwrite

Disk Where You Want to Install.....hdisk0

Choice [0]: 1

2. When the Change Method of Installation panel is displayed, type 1 New and Complete Overwrite Installation and press Enter.

When the Change Disk(s) Where You Want to Install panel is displayed, you can change the destination disk for the installation.

Change Disk(s) Where You Want to Install

Type one or more numbers for the disk(s) to be used for installation and press Enter. To cancel a choice, type the corresponding number and Press Enter.

At least one bootable disk must be selected. The current choice is indicated by >>>.

Name Location Code Size(MB) VG Status Bootable

>>> 1 hdisk0 04-B0-00-2,0 4296 none Yes

2 hdisk1 04-B0-00-5,0 4296 none Yes

3 hdisk2 04-B0-00-6,0 12288 none Yes

0 Continue with choices indicated above

55 More Disk Options

66 Disks not known to Base Operating System Installation

77 Display More Disk Information

88 Help ?

99 Previous Menu

>>> Choice [0]:

3. If the default settings shown are correct, type 0 in the **Choice** field and press Enter.

To change the destination disk, complete the following steps:

- a. Type the number for each disk where you want to install the BOS in the **Choice** field and press Enter. Do not press Enter a final time until you have finished selecting all disks. If you need to deselect a disk, type its number a second time and press Enter.
- b. To finish selecting disks, type 0 in the **Choice** field and press Enter. The Installation and Settings panel is displayed with the selected disks listed under System Settings.

7 Step 7: Changing Primary Language Environment



To change the primary language that is used by this installation:

1. Type 2 (Primary Language Environment Settings) in the **Choice** field on the Installation and Settings panel.
2. Select the appropriate set of cultural convention, language, and keyboard options. Most of the options are a predefined combination; however, you can define your own combination of options.
3. To select a predefined Primary Language Environment, type the corresponding number in the **Choice** field and press Enter.

To configure your own Primary Language Environment, complete the following steps:

- a. Select **More Choices**.
- b. Page through the choices and select the **Create Your Own Combination** option.
- c. On the Set Primary Cultural Convention panel, type the corresponding number in the **Choice** field and press Enter.
- d. On the Set Primary Language panel, type the number in the **Choice** field that corresponds to your choice for the primary language and press Enter.
- e. On the **Set Keyboard** panel, type the number in the **Choice** field that corresponds to the keyboard that is attached to the system and press Enter.

8 Step 8: Verifying BOS installation settings



To verify your BOS installation settings:

1. Verify that the selections are correct on the Overwrite Installation Summary panel.

```
Overwrite Installation Summary
Disks: hdisk0
Cultural Convention: en_US
Language: en_US
Keyboard: en_US
JFS2 File Systems Created: Yes
Graphics Software: Yes
System Management Client Software: Yes
Enable System Backups to install any system: Yes
Selected Edition: express
Optional Software being installed:
>>> 1 Continue with Install
88 Help ?
99 Previous Menu
>>> Choice [1]:
```

2. Press Enter to begin the BOS installation.

9 Step 9: Finishing the BOS installation



After the base runtime environment is installed, status information is displayed about other software that is being installed. The system automatically reboots.

The Installation Assistant guides you through the configuration tasks.

Related information



For more information, see the following resources:

- For additional release information, see the AIX Release Notes that corresponds to your level of the AIX operating system.
- For late-breaking information, which might include information about the configuration process and installed software, see the readme files.
- For more detailed installation notes, see the Installation and migration topic collection in the IBM® AIX 6.1 Information Center (<http://pic.dhe.ibm.com/infocenter/aix/v6r1/index.jsp>).

