

Security APIs (V5R2)

Network Security APIs

Table of Contents

[Network Security APIs](#)

- [Server Authentication Entry APIs](#)
 - [Add Server Authentication Entry](#) (QsyAddServerEntry)
 - [Change Server Authentication Entry](#) (QsyChangeServerEntry)
 - [Remove Server Authentication Entry](#) (QsyRemoveServerEntry)
 - [Retrieve Server Authentication Entries](#) (QSYRTVSE, QsyRetrieveServerEntries)
- [NetWare Authentication Entry APIs](#)
 - [Add NetWare Authentication Entry](#) (QfpzAddNtwAutE)
 - [Change NetWare Authentication Entry](#) (QfpzChgNtwAutE)
 - [End NetWare Connection](#) (QfpzEndNtwCnn)
 - [List NetWare Authentication Entries](#) (QfpzListNtwAutE)
 - [Remove NetWare Authentication Entry](#) (QfpzRmvNtwAutE)
 - [Start NetWare Connection](#) (QfpzStrNtwCnn)
 - [Verify Netware Authentication Entry](#) (QfpzVfyNtwAutE)

Network Security APIs

The network security APIs include:

- [Server Authentication Entry APIs](#)
- [NetWare Authentication Entry APIs](#)

[Security APIs](#) | [APIs by category](#)

Server Authentication Entry APIs

The Server Authentication Entry APIs can be used by a client requesting connection to a server.

The server authentication entry APIs are:

- [Add Server Authentication Entry](#) (QsyAddServerEntry) adds server authentication information for use by application requesters in connecting to application servers.
- [Change Server Authentication Entry](#) (QsyChangeServerEntry) changes server authentication information for use by application requesters in connecting to application servers.
- [Remove Server Authentication Entry](#) (QsyRemoveServerEntry) removes server authentication information for use by application requesters in connecting to application servers.
- [Retrieve Server Authentication Entries](#) (QSYRTVSE, QsyRetrieveServerEntries) returns a list of server authentication entries for a user profile.

[Top](#) | [Security APIs](#) | [APIs by category](#)

Add Server Authentication Entry (QsyAddServerEntry) API

Required Parameter Group:

1	User profile	Input	Char(10)
2	Server name	Input	Char(*)
3	Length of server name	Input	Binary(4)
4	User ID	Input	Char(*)
5	Length of user ID	Input	Binary(4)
6	Password	Input	Char(*)
7	Length of password	Input	Binary(4)
8	Error code	I/O	Char(*)

Default Public Authority: *USE

Service Program: QSYSVRFN

Threadsafe: No

The Add Server Authentication Entry (QsyAddServerEntry) API adds server authentication information for use by application requesters in connecting to application servers.

When adding a server authentication entry for a Distributed Relational Database Architecture (DRDA) application that uses TCP/IP, the server name must be entered in upper case.

Authorities and Locks

If the user profile parameter is not *CURRENT or the user profile currently running, then the user profile that calls this API must have *SECADM special authority and *OBJMGT and *USE authorities to the user profile.

Required Parameter Group

User profile

INPUT; CHAR(10)

The user profile for which the server authentication entry will be added. The special value *CURRENT may be specified to add an entry for the user profile that calls this API.

Server name

INPUT; CHAR(*)

The name of the application server.

Length of server name

INPUT; BINARY(4)

The length of the server name that is specified in the server name parameter. The length of the server name must be a value from 1 to 200.

User ID

INPUT; CHAR(*)

The user name for which requests will be made to the implementation server.

Length of user ID

INPUT; BINARY(4)

The length of the user ID that is specified in the user ID parameter. The length of the user ID must be a value from 0 to 1000. If the length is 0, the user ID will be the same as the name that is specified in the user profile parameter.

Password

INPUT; CHAR(*)

The password to be used to authenticate the user when the client attempts to connect to the server.

Length of password

INPUT; BINARY(4)

The length of the password that is specified in the password parameter. The length of the password must be a value from 0 to 696. If the length is 0, then no password is supplied on the connection request. If the retain server security data (QRETSVRSEC) system value is set to 0 (do not retain data), then the length of the password is assumed to be 0.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see [Error Code Parameter](#).

Error Messages

Message ID	Error Message Text
CPF2204 E	User profile &1 not found.
CPF2213 E	Not able to allocate user profile &1.
CPF2222 E	Storage limit is greater than specified for user profile &1.
CPF224F E	Server authentication entry already exists.
CPF225F E	Not all information stored.
CPF226C E	Not authorized to perform function.
CPF3CF1 E	Error code parameter not valid.
CPF3CF2 E	Error(s) occurred during running of &1 API.

CPF3C1D E Length specified in parameter &1 not valid.
CPF3C90 E Literal value cannot be changed.
CPF9872 E Program or service program &1 in library &2 ended. Reason code &3.

API Introduced: V4R2

[Top](#) | [Security APIs](#) | [APIs by category](#)

Change Server Authentication Entry (QsyChangeServerEntry) API

Required Parameter Group:

1	User profile	Input	Char(10)
2	Server name	Input	Char(*)
3	Length of server name	Input	Binary(4)
4	User ID	Input	Char(*)
5	Length of user ID	Input	Binary(4)
6	Password	Input	Char(*)
7	Length of password	Input	Binary(4)
8	Error code	I/O	Char(*)

Default Public Authority: *USE

Service Program: QSYSVRFN

Threadsafe: No

The Change Server Authentication Entry (QsyChangeServerEntry) API changes the server authentication information for use by application requesters in connecting to application servers.

Authorities and Locks

If the user profile parameter is not *CURRENT or the user profile currently running, then the user profile that calls this API must have *SECADM special authority and *OBJMGT and *USE authorities to the user profile.

Required Parameter Group

User profile

INPUT; CHAR(10)

The user profile for which the server authentication entry will be changed. The special value *CURRENT may be specified to change an entry for the user profile that calls this API.

Server name

INPUT; CHAR(*)

The name of the application server.

Length of server name

INPUT; BINARY(4)

The length of the server name that is specified in the server name parameter. The length of the server name must be a value from 1 to 200.

User ID

INPUT; CHAR(*)

The user name for which requests will be made to the implementation server.

Length of user ID

INPUT; BINARY(4)

The length of the user ID that is specified in the user ID parameter. The length of the user ID must be a value from -1 to 1000. If -1 is specified, the user ID value is not changed. If 0 is specified, the user ID will be the same as the name that is specified in the user profile parameter.

Password

INPUT; CHAR(*)

The password to be used to authenticate the user when the client attempts to connect to the server.

Length of password

INPUT; BINARY(4)

The length of the password that is specified in the password parameter. The length of the password must be a value from -1 to 696. If -1 is specified, the password value does not change. If 0 is specified, then no password is supplied on the connection request. If the retain server security data (QRETSVRSEC) system value is set to 0 (do not retain data), then the length of the password is assumed to be 0.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see [Error Code Parameter](#).

Error Messages

Message ID	Error Message Text
CPF2204 E	User profile &1 not found.
CPF2213 E	Not able to allocate user profile &1.
CPF225E E	Server authentication entry does not exist.
CPF225F E	Not all information stored.
CPF226C E	Not authorized to perform function.
CPF3CF1 E	Error code parameter not valid.
CPF3CF2 E	Error(s) occurred during running of &1 API.
CPF3C1D E	Length specified in parameter &1 not valid.

CPF3C90 E Literal value cannot be changed.

CPF9872 E Program or service program &1 in library &2 ended. Reason code &3.

API Introduced: V4R2

[Top](#) | [Security APIs](#) | [APIs by category](#)

Remove Server Authentication Entry (QsyRemoveServerEntry) API

Required Parameter Group:

1	User profile	Input	Char(10)
2	Server name	Input	Char(*)
3	Length of server name	Input	Binary(4)
4	Error code	I/O	Char(*)

Default Public Authority: *USE

Service Program: QSYSVRFN

Threadsafe: No

The Remove Server Authentication Entry (QsyRemoveServerEntry) API removes server authentication information for use by application requesters in connecting to application servers.

Authorities and Locks

If the user profile parameter is not *CURRENT or the user profile currently running, then the user profile that calls this API must have *SECADM special authority and *OBJMGT and *USE authorities to the user profile.

Required Parameter Group

User profile

INPUT; CHAR(10)

The user profile for which the server authentication entry will be removed. The special value *CURRENT may be specified to remove an entry for the user profile that calls this API.

Server name

INPUT; CHAR(*)

The name of the application server. The special value *ALL may be specified to indicate that all server authentication entries for the user profile that is specified in the user profile parameter are to be removed.

Length of server name

INPUT; BINARY(4)

The length of the server name that is specified in the server name parameter. The length of the server name must be a value from 1 to 200.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see [Error Code Parameter](#).

Error Messages

Message ID	Error Message Text
CPF2204 E	User profile &1 not found.
CPF2213 E	Not able to allocate user profile &1.
CPF225E E	Server authentication entry does not exist.
CPF226C E	Not authorized to perform function.
CPF3CF1 E	Error code parameter not valid.
CPF3CF2 E	Error(s) occurred during running of &1 API.
CPF3C1D E	Length specified in parameter &1 not valid.
CPF3C90 E	Literal value cannot be changed.
CPF9872 E	Program or service program &1 in library &2 ended. Reason code &3.

API Introduced: V4R2

[Top](#) | [Security APIs](#) | [APIs by category](#)

Retrieve Server Authentication Entries (QSYRTVSE, QsyRetrieveServerEntries) API

Required Parameter Group:

1	Receiver variable	Output	Char(*)
2	Length of receiver variable	Input	Binary(4)
3	Return records feedback information	Output	Char(12)
4	Format name	Input	Char(8)
5	Starting server name	Input	Char(*)
6	Length of starting server name	Input	Binary(4)
7	Starting server option	Input	Char(1)
8	User profile	Input	Char(10)
9	Error code	I/O	Char(*)

Default Public Authority: *USE

Service Program: QSYSVRFN

Threadsafe: No

The Retrieve Server Authentication Entries (OPM, QSYRTVSE; ILE, QsyRetrieveServerEntries) API returns a list of server authentication entries for a user profile.

Authorities and Locks

User Profile Authority

»*READ«

Required Parameter Group

Receiver variable

OUTPUT; CHAR(*)

The receiver variable that receives the information requested. You can specify the size of the area to be smaller than the format requested as long as you specify the length parameter correctly. As a result, the API returns only the data that the area can hold.

Length of receiver variable

INPUT; BINARY(4)

The length of the receiver variable provided. The length of receiver variable parameter may be specified up to the size of the receiver variable specified in the user program. If the length of receiver variable parameter specified is larger than the allocated size of the receiver variable specified in the user program, the results are not predictable.

Returned records feedback information

OUTPUT; CHAR(12)

Information about the entries that are returned in the receiver variable.

See [Format of Returned Records Feedback Information](#) for details.

Format name

INPUT; CHAR(8)

The name of the format that is used to retrieve server authentication entries for the user profile.

You can specify this format:

SVRE0100 For a detailed description of this format, see [SVRE0100 Format](#).

Starting server name

INPUT; CHAR(*)

The server name at which to start listing server authentication entries. The server authentication entries are listed in hexadecimal sort sequence by server name.

Possible values follow:

- *FIRST* Server authentication entries are returned starting with the server that has the smallest hexadecimal value.
- server name* If an exact match for the starting server name is found, the starting server option parameter indicates whether that server authentication entry is returned.

If an exact match for the starting server name is not found, the listing begins with the first existing server authentication entry for the server name whose hexadecimal value would follow the hexadecimal value of the specified starting server name.

Length of starting server name

INPUT; BINARY(4)

The length of the starting server name. The length of the starting server name may be from 1 to 200.

Starting server option

INPUT; CHAR(1)

This parameter indicates whether the starting server authentication entry is returned when an exact match for the starting server name is found.

Possible values follow:

- 0 Server authentication entries for server names whose hexadecimal value is greater than the hexadecimal value for the starting server name are returned.
- 1 Server authentication entries for server names whose hexadecimal value is equal to or greater than the hexadecimal value for the starting server name are returned.

User profile

INPUT; CHAR(10)

The name of the user profile for which the server authentication entries are returned.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see [Error Code Parameter](#).

Receiver Variable Description

The following tables describe the order and format of the data returned in the receiver variable. For detailed descriptions of the fields in the tables, see [Field Descriptions](#).

SVRE0100 Format

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Length of entry
4	4	BINARY(4)	Length of server name
8	8	BINARY(4)	CCSID of server name
12	C	CHAR(200)	Server name
212	D4	BINARY(4)	Displacement to user ID
216	D8	BINARY(4)	Length of user ID
220	DC	BINARY(4)	CCSID of user ID
224	E0	CHAR(1)	Password stored indicator
		CHAR(*)	User ID

Format of Returned Records Feedback Information

Offset		Type	Field
Dec	Hex		

0	0	BINARY(4)	Bytes returned
4	4	BINARY(4)	Bytes available
8	8	BINARY(4)	Number of server authentication entries

Field Descriptions

Bytes available. The number of bytes of data available to be returned to the user in the receiver variable. If all data is returned, bytes available is the same as the number of bytes returned. If the receiver variable was not large enough to contain all of the data, this value is estimated based on the total number of server authentication entries for the user profile and the format specified.

Bytes returned. The number of bytes of data returned to the user in the receiver variable. This is the lesser of the number of bytes available to be returned or the length of the receiver variable.

CCSID of server name. The CCSID of the server name. This will be the default job CCSID of the job that added the server authentication entry.

CCSID of user ID. The CCSID of the user ID. This will be the default job CCSID of the job that last changed the user ID field in the server authentication entry.

Displacement to user ID. The displacement in the entry to the start of the user ID.

Format name. The name of the format that is used to return server authentication entries for a user profile.

Length of entry. The length (in bytes) of the current entry. This length can be used to access the next entry.

Length of server name ID. The length (in bytes) of the server name.

Length of user ID. The length (in bytes) of the user ID.

Number of server authentication entries. The number of complete entries returned in the list of server authentication entries. A value of zero is returned if the list is empty.

Password specified. Indicates whether the server authentication entry has a password associated with it.

Possible values follow:

- 0* The server authentication entry does not have a password associated with it.
- 1* The server authentication entry does have a password associated with it.

Server name. The name of the server that the entry is for.

User ID. The user ID that is used on requests to the server.

User profile. The name of the user profile for which the list of server authentication entries is returned.

Error Messages

Message ID	Error Message Text
CPFA0AA E	Error occurred while attempting to obtain space.
CPF2204 E	User profile &1 not found.
CPF2213 E	Not able to allocate user profile &1.
CPF2217 E	Not authorized to user profile &1.
CPF2222 E	Storage limit is greater than specified for user profile &1.
CPF3CF1 E	Error code parameter not valid.
CPF3CF2 E	Error(s) occurred during running of &1 API.
CPF3C1D E	Length specified in parameter &1 not valid.
CPF3C21 E	Format name &1 is not valid.
CPF3C3C E	Value for parameter &1 not valid.
CPF3C90 E	Literal value cannot be changed.
CPF9872 E	Program or service program &1 in library &2 ended. Reason code &3.

API Introduced: V4R2

[Top](#) | [Security APIs](#) | [Security Exit Programs](#) | [Digital Certificate Mgmt APIs](#) | [Network Security APIs](#) | [User Function Registration APIs](#) | [Validation List APIs](#) | [APIs by category](#)

NetWare Authentication Entry APIs

The NetWare Authentication Entry APIs provide a means that automatically logs you on to a server when you request a NetWare function (for example, the QNETWARE file system or NetWare administration commands). You can create authentication entries for each NetWare Directory Services (NDS) tree or NetWare 3.x server to which you are authorized. The entry identifies the tree or server, your name on that server, and (optionally) your password. The system saves the authentication entries as part of the user profile. When you request a NetWare function, the system attempts to start a connection to the server by using the data stored in the authentication entries.

Alternatively, you can explicitly start and end a connection to a server, such as when the system administrator has disabled storing passwords through the Retain Server Security Data (QRETSVRSEC) system value.

Note: To use these APIs, you need NetWare on iSeries. See [Netware on iSeries](#) in the Information Center for more information on this topic.

The NetWare Authentication Entry APIs are:

- [Add NetWare Authentication Entry](#) (QfpzAddNtwAutE) stores user authentication information that is used to access the specified server.
- [Change NetWare Authentication Entry](#) (QfpzChgNtwAutE) changes the authentication information in the specified authentication entry.
- [End NetWare Connection](#) (QfpzEndNtwCnn) ends a connection to a NetWare server.
- [List NetWare Authentication Entries](#) (QfpzListNtwAutE) returns a list of authentication entries in a user profile.
- [Remove NetWare Authentication Entry](#) (QfpzRmvNtwAutE) removes an authentication entry from the user profile.
- [Start NetWare Connection](#) (QfpzStrNtwCnn) establishes the caller as an authenticated user of the specified server and starts the connection with the server.
- [Verify Netware Authentication Entry](#) (QfpzVfyNtwAutE) returns a list of authentication entries for the specified user profile.

Add NetWare Authentication Entry (QfpzAddNtwAutE) API

Required Parameter Group:

1	Entry identifier data	Input	Char(*)
2	Length of entry identifier	Input	Binary(4)
3	Entry identifier format name	Input	Char(8)
4	Authentication entry data	Input	Char(*)
5	Length of authentication entry	Input	Binary(4)
6	Entry data format name	Input	Char(8)
7	Error code	I/O	Char(*)

Default Public Authority: *USE

Library Name/Service Program: QFPNTWE/QFPZAAPI

Threadsafe: No

The Add NetWare Authentication Entry (QfpzAddNtwAutE) API stores user authentication information that is used to access the specified server. This information can be used at a later time to start an authenticated connection to the server without requiring the user to enter the data.

Authorities and Locks

User Profile Authority

The user profile must be the current user profile, or the caller must have *USE and *OBJMGT authority to the user profile and *SECADM special authority.

Required Parameter Group

Entry identifier data

INPUT; CHAR(*)

The authentication entry to be added. The content and format of this structure are determined by the format name. See [Format of Authentication Entry Identifier](#) for a description of these formats.

Length of entry identifier

INPUT; BINARY(4)

The length of the entry identifier data structure.

Entry identifier format name

INPUT; CHAR(8)

The content and format of the authentication entry identifier data.

The possible format names follow:

[AUTE0100](#) NetWare Version 3.x server authentication entry identifier

[AUTE0200](#) NetWare Directory Services tree authentication entry identifier

See [Format of Authentication Entry Identifier](#) for a description of these formats.

Authentication entry data

INPUT; CHAR(*)

The authentication entry to be added. The content and format of this structure are determined by the format name. See [Format of Authentication Entry Data](#) for a description of these formats.

Length of authentication entry

INPUT; BINARY(4)

The length of the authentication entry data structure.

Entry data format name

INPUT; CHAR(8)

The content and format of the authentication entry input data. Each format corresponds to a type of authentication entry.

The possible format names follow:

[AUTD0100](#) NetWare Version 3.x server authentication entry data

[AUTD0200](#) NetWare Directory Services tree authentication entry data

See [Format of Authentication Entry Data](#) for a description of these formats.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see [Error Code Parameter](#).

Format of Authentication Entry Identifier

For details about the format of the authentication entries, see the following sections. For details about the fields in each format, see [Field Descriptions](#).

AUTE0100 Format

This format is used to identify a NetWare Version 3.x server authentication entry.

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to server name
4	4	BINARY(4)	Length of server name
8	8	CHAR(10)	User profile name
18	12	CHAR(6)	Reserved
		CHAR(*)	Server name

AUTE0200 Format

This format is used to identify a NetWare Directory Services tree authentication entry.

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to NDS tree name
4	4	BINARY(4)	Length of NDS tree name
8	8	CHAR(10)	User profile name
18	12	CHAR(6)	Reserved
		CHAR(*)	NDS tree name

Format of Authentication Entry Data

For details about the format of the authentication entries, see the following sections. For details about the fields in each format, see [Field Descriptions](#).

AUTD0100 Format

This format is used to specify the authentication entry data for a NetWare Version 3.x server authentication entry. This format must be used when entry identifier format AUTE0100 is used.

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to NetWare user name
4	4	BINARY(4)	Length of NetWare user name
8	8	BINARY(4)	Offset to password
12	C	BINARY(4)	Length of password
16	10	BINARY(4)	Reserved
		CHAR(*)	NetWare user name
		CHAR(*)	Password

AUTD0200 Format

This format is used to specify the authentication entry data for a NetWare Directory Services tree authentication entry. This format must be used when entry identifier format AUTE0200 is used.

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to NDS context
4	4	BINARY(4)	Length of NDS context
8	8	BINARY(4)	Offset to NetWare user name
12	C	BINARY(4)	Length of NetWare user name
16	10	BINARY(4)	Offset to password
20	14	BINARY(4)	Length of password
24	18	BINARY(4)	Reserved
		CHAR(*)	NDS context
		CHAR(*)	NetWare user name
		CHAR(*)	Password

Field Descriptions

Length of NDS context. The length, in bytes, of the NDS context.

Length of NDS tree name. The length, in bytes, of the NDS tree name.

Length of NetWare user name. The length, in bytes, of the NetWare user name.

Length of password. The length, in bytes, of the password.

Length of server name. The length, in bytes, of the server name.

NDS context. The directory context in which the user is defined.

NDS tree name. For NDS trees, the name of the tree to which the authentication entry applies.

NetWare user name. The NetWare user name that is used to authenticate the user to the server.

The following special value may be used:

**USRPRF* The NetWare user name is the same as the user profile name.

Offset to NDS context. The offset, in bytes, from the start of the input data area to the NDS context.

Offset to NDS tree name. The offset, in bytes, from the start of the input data area to the NDS tree name.

Offset to NetWare user name. The offset, in bytes, from the start of the input data area to the user name.

Offset to password. The offset, in bytes, from the start of the input data area to the password.

Offset to server name. The offset, in bytes, from the start of the input data area to the server name.

Password. The password that is used to authenticate the user to the server.

The following special values may be used:

- **NONE* The system does not need password information to authenticate the user.
- **STRNTWCNN* The system does not store password information in the authentication entry. Use the Start NetWare Connection (STRNTWCNN) command, with the correct password, to start a connection to a server.

Reserved. Set this field to binary zeros.

Server name. The name of the server to which the authentication entry applies.

User profile name. The name of the user profile to which the authentication entry is to be added.

You can use the following special values for the user profile name:

- **CURRENT* The current user profile.

Error Messages

Message ID	Error Message Text
CPF2204 E	User profile &1 not found.
CPF2217 E	Not authorized to user profile &1.
CPF24B4 E	Severe error while addressing parameter list.
CPF3C1D E	Length specified in parameter &1 not valid.
CPF3C21 E	Format name &1 is not valid.
CPF3C90 E	Literal value cannot be changed.
CPF3CF1 E	Error code parameter not valid.
CPF9872 E	Program or service program &1 in library &2 ended. Reason code &3.
FPE0211 E	Parameter length &1 not valid for field &2.
FPE0212 E	Field offset and length not within data.
FPE0216 E	Authentication entry already exists for &2.
FPE021F E	Data format &1 not valid with identifier format &2.
FPE0255 E	PASSWORD(*STRNTWCNN) required when QRETSVRSEC is 0.

[Top](#) | [Security APIs](#) | [APIs by category](#)

Change NetWare Authentication Entry (QfpzChgNtwAutE) API

Required Parameter Group:

1	Entry identifier data	Input	Char(*)
2	Length of entry identifier	Input	Binary(4)
3	Entry identifier format name	Input	Char(8)
4	Authentication entry data	Input	Char(*)
5	Length of authentication entry	Input	Binary(4)
6	Entry data format name	Input	Char(8)
7	Error code	I/O	Char(*)

Default Public Authority: *USE

Library Name/Service Program: QFPNTWE/QFPZAAPI

Threadsafe: No

The Change NetWare Authentication Entry (QfpzChgNtwAutE) API changes the authentication information in the specified authentication entry. The format that is specified for the authentication entry must correspond to the server type of the existing entry.

Authorities and Locks

User Profile Authority

The user profile must be the current user profile, or the caller must have *USE and *OBJMGT authority to the user profile and *SECADM special authority.

Required Parameter Group

Entry identifier data

INPUT; CHAR(*)

The authentication entry to be changed. The content and format of this structure are determined by the format name. See [Format of Authentication Entry Identifier](#) for a description of these formats.

Length of entry identifier

INPUT; BINARY(4)

The length of the entry identifier data structure.

Entry identifier format name

INPUT; CHAR(8)

The content and format of the authentication entry identifier data.

The possible format names follow:

[AUTE0100](#) NetWare Version 3.x server authentication entry identifier

[AUTE0200](#) NetWare Directory Services tree authentication entry identifier

See [Format of Authentication Entry Identifier](#) for a description of these formats.

Authentication entry data

INPUT; CHAR(*)

The changed authentication entry data. The content and format of this structure are determined by the format name. See [Format of Authentication Entry Data](#) for a description of these formats.

Length of authentication entry

INPUT; BINARY(4)

The length of the authentication entry data structure.

Entry data format name

INPUT; CHAR(8)

The content and format of the authentication entry input data. Each format corresponds to a type of authentication entry.

The possible format names follow:

[AUTD0100](#) NetWare Version 3.x server authentication entry data

[AUTD0200](#) NetWare Directory Services tree authentication entry data

See [Format of Authentication Entry Data](#) for a description of these formats.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see .

Format of Authentication Entry Identifier

For details about the format of the entry identifier data, see the following sections. For details about the fields in each format, see [Field Descriptions](#).

AUTE0100 Format

This format is used to identify a NetWare Version 3.x server authentication entry.

Offset		
--------	--	--

Dec	Hex	Type	Field
0	0	BINARY(4)	Offset to server name
4	4	BINARY(4)	Length of server name
8	8	CHAR(10)	User profile name
18	12	CHAR(6)	Reserved
		CHAR(*)	Server name

AUTE0200 Format

This format is used to identify a NetWare Directory Services tree authentication entry.

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to NDS tree name
4	4	BINARY(4)	Length of NDS tree name
8	8	CHAR(10)	User profile name
18	12	CHAR(6)	Reserved
		CHAR(*)	NDS tree name

Format of Authentication Entry Data

For details about the format of the authentication entries, see the following sections. For details about the fields in each format, see [Field Descriptions](#).

AUTD0100 Format

This format is used to specify the authentication entry data for a NetWare Version 3.x server authentication entry. This format must be used when entry identifier format AUTE0100 is used.

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to NetWare user name
4	4	BINARY(4)	Length of NetWare user name
8	8	BINARY(4)	Offset to password
12	C	BINARY(4)	Length of password
16	10	BINARY(4)	Reserved
		CHAR(*)	NetWare user name
		CHAR(*)	Password

AUTD0200 Format

This format is used to specify the authentication entry data for a NetWare Directory Services tree authentication entry. This format must be used when entry identifier format AUTE0200 is used.

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to NDS context
4	4	BINARY(4)	Length of NDS context
8	8	BINARY(4)	Offset to NetWare user name
12	C	BINARY(4)	Length of NetWare user name
16	10	BINARY(4)	Offset to password
20	14	BINARY(4)	Length of password
24	18	BINARY(4)	Reserved
		CHAR(*)	NDS context
		CHAR(*)	NetWare user name
		CHAR(*)	Password

Field Descriptions

Length of NDS context. The length, in bytes, of the NDS context.

Length of NDS tree name. The length, in bytes, of the NDS tree name.

Length of NetWare user name. The length, in bytes, of the NetWare user name.

Length of password. The length, in bytes, of the password.

Length of server name. The length, in bytes, of the server name.

NDS context. For NDS trees, the directory context in which the user is defined.

The following special value may be used:

**SAME* The value remains the same.

NDS tree name. For NDS trees, the name of the directory tree to which the authentication entry applies.

The selected NDS tree name must be the same as the NDS tree name of an existing NetWare Directory Services tree authentication entry.

NetWare user name. The NetWare user name that is used to authenticate the user to the server.

The following special values may be used:

**USRPRF* The NetWare user name is the same as the user profile name.

**SAME* The value remains the same.

Offset to NDS context. The offset, in bytes, from the start of the input data area to the NDS context.

Offset to NDS tree name. The offset, in bytes, from the start of the input data area to the NDS tree name.

Offset to NetWare user name. The offset, in bytes, from the start of the input data area to the NetWare user name

Offset to password. The offset, in bytes, from the start of the input data area to the password.

Offset to server name. The offset, in bytes, from the start of the input data area to the server name.

Password. The password that is used to authenticate the user to the server.

The following special values may be used:

- *NONE* The system does not need password information to authenticate the user.
- *STRNTWCNN* The system does not store the password information in the authentication entry. Use Start NetWare Connection (STRNTWCNN) command, with the correct password, to start a connection to a server.
- *SAME* The value remains the same.

Reserved. Set this field to binary zeros.

Server name. The name of the server to which the authentication entry applies.

The selected server name must be the same as the server name of an existing NetWare Version 3.x server authentication entry.

User profile name. The name of the user profile that contains the authentication entry.

You can use the following special value for the user profile name:

- *CURRENT* Use the current user profile.

Error Messages

Message ID	Error Message Text
CPF2204 E	User profile &1 not found.
CPF2217 E	Not authorized to user profile &1.
CPF24B4 E	Severe error while addressing parameter list.
CPF3C1D E	Length specified in parameter &1 not valid.
CPF3C21 E	Format name &1 is not valid.
CPF3C90 E	Literal value cannot be changed.
CPF3CF1 E	Error code parameter not valid.
CPF9872 E	Program or service program &1 in library &2 ended. Reason code &3.
FPE0211 E	Parameter length &1 not valid for field &2.

FPE0212 E Field offset and length not within data.
FPE0215 E Could not find authentication entry for &1.
FPE021F E Data format &1 not valid with identifier format &2.
FPE0255 E PASSWORD(*STRNTWCNN) required when QRETSVRSEC is 0.

API Introduced: V3R7

[Top](#) | [Security APIs](#) | [APIs by category](#)

End NetWare Connection (QfpzEndNtwCnn) API

Required Parameter Group:

1	Input data	Input	Char(*)
2	Length of input data	Input	Binary(4)
3	Format name	Input	Char(8)
4	Error code	I/O	Char(*)

Default Public Authority: *USE

Library Name/Service Program: QFPNTWE/QFPZAAPI

Threadsafe: No

The End NetWare Connection (QfpzEndNtwCnn) API ends a connection to a NetWare server. Connections to a server that was started from this iSeries server system, other iSeries servers, or workstations can be ended. Use the Work with NetWare Connections (WRKNTWCNN) command to view a list of connections.

Authorities and Locks

Special Authority

The connection must have been started by the current job, or the caller must have job control (*JOBCTL) special authority.

NetWare Authority

If this iSeries server did not start the connection being ended, the caller must have operator privileges for the server.

Note: To have operator privileges, the caller must have an authenticated connection to the server. The caller must be a NetWare user who is a member of the OPERATORS property for the server.

Required Parameter Group

Input data

INPUT; CHAR(*)

The input data that identifies the connections to be ended. The format name determines the format and content of this data. For detailed descriptions of the data's format and content, see [Input Data Formats](#). For detailed descriptions of the fields in this structure, see [Field Descriptions](#).

Length of input data

INPUT; BINARY(4)

The length of the input data structure.

Format name

INPUT; CHAR(8)

The format and content of the input data structure.

The following formats are supported:

[ENDC0100](#) End connections for the current job on the specified servers.

[ENDC0200](#) End the specified connection number on the specified server.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see [Error Code Parameter](#).

Input Data Formats

ENDC0100 Format

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to server name
4	4	BINARY(4)	Length of server name
8	8	BINARY(4)	Reserved
		CHAR(*)	Server name

ENDC0200 Format

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to server name
4	4	BINARY(4)	Length of server name
8	8	BINARY(4)	Connection number
12	C	BINARY(4)	Reserved
		CHAR(*)	Server name

Field Descriptions

Connection number. The connection number by which the connection is known on the server.

Length of server name. The length, in bytes, of the server name.

Offset to server name. The offset, in bytes, from the start of the input data to the server name.

Reserved. Set this field to binary zeros.

Server name. The name of the server. If format ENDC0100 is specified, the following special value may be used:

**ALL* End connections to all servers.

Error Messages

Message ID	Error Message Text
CPF24B4 E	Severe error while addressing parameter list.
CPF3C1D E	Length specified in parameter &1 not valid.
CPF3C21 E	Format name &1 is not valid.
CPF3C90 E	Literal value cannot be changed.
CPF3CF1 E	Error code parameter not valid.
CPF90FF E	*JOBCTL special authority required to do requested operation.
CPF9872 E	Program or service program &1 in library &2 ended. Reason code &3.
FPE0211 E	Parameter length &1 not valid for field &2.
FPE0212 E	Field offset and length not within data.
FPE021B E	Connection &1 on server &2 not found.
FPE0230 E	Connection type -1 must be single value.
FPE0231 E	Value &1 not valid for connection type.
FPE0232 E	User &1 not connected to server.
FPE023F E	Server operator privileges required.

API Introduced: V3R7

List NetWare Authentication Entries (QfpzListNtwAutE) API

Required Parameter Group:

1	Qualified user space name	Input	Char(20)
2	Entry identifier data	Input	Char(*)
3	Length of entry qualifier	Input	Binary(4)
4	Entry identifier format name	Input	Char(8)
5	Error code	I/O	Char(*)

Default Public Authority: *USE

Library Name/Service Program: QFPNTWE/QFPZAAPI

Threadsafe: No

The List NetWare Authentication Entries (QfpzListNtwAutE) API returns a list of authentication entries in a user profile. All entries may be returned, or only those entries that match specified criteria can be requested.

Authorities and Locks

User Profile Authority

The user profile must be the current user profile, or the caller must have *USE and *OBJMGT authority to the user profile and *SECADM special authority.

User Space Authority

*CHANGE

User Space Library Authority

*USE

User Space Lock

*EXCLRD

Required Parameter Group

Qualified user space name

INPUT; CHAR(20)

The user space that receives the information, and the library in which it is located. The first 10 characters contain the user space name, and the second 10 characters contain the library name.

You can use these special values for the library name:

**CURLIB* The job's current library
 **LIBL* The library list

Entry identifier data

INPUT; CHAR(*)

The authentication entries to be retrieved. The content and format of this structure are determined by the format name. See [Format of Authentication Entry Identifier](#) for a description of these formats.

Length of entry identifier

INPUT; BINARY(4)

The length of the authentication entry identifier structure.

Entry identifier format name

INPUT; CHAR(8)

The content and format of the authentication entry identifier data. Each format corresponds to a method of identifying an authentication entry.

The possible format names follow:

[AUTE0100](#) The NetWare Version 3.x server entry is identified by the server name.

[AUTE0200](#) The NetWare Directory Services tree entry is identified by the NDS tree name.

[AUTE0900](#) All authentication entries in a user profile are retrieved.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see [Error Code Parameter](#).

Format of Authentication Entry Identifier

For details about the format of the entry identifier data, see the following sections. For details about the fields in each format, see [Field Descriptions](#).

AUTE0100 Format

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to selected server name
4	4	BINARY(4)	Length of selected server name

8	8	CHAR(10)	User profile name
18	12	CHAR(6)	Reserved
		CHAR(*)	Selected server name

AUTE0200 Format

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to selected NDS tree name
4	4	BINARY(4)	Length of selected NDS tree name
8	8	CHAR(10)	User profile name
18	12	CHAR(6)	Reserved
		CHAR(*)	Selected NDS tree name

AUTE0900 Format

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	User profile name
10	A	CHAR(6)	Reserved

Format of Authentication Entry Lists

The authentication entry list consists of:

- A user area
- A generic area
- An input parameter section
- A header section
- A list data section:
 - Server authentication entry

For details about the user area and generic header, see [User Space Format for List APIs](#). For details about the remaining items, see the following sections. For detailed descriptions of the fields in the list that is returned, see [Field Descriptions](#).

When you retrieve list entry information from a user space, do not use the entry size that is returned in the generic header. Instead, use the displacement to next entry field that is returned in each list entry. If you do not use the displacement to next entry field, the results may not be valid. For examples of how to process

lists, see [Examples](#).

Input Parameter Section

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	User space name specified
10	A	CHAR(10)	User space library name specified
20	14	CHAR(8)	Format name specified
28	1C	BINARY(4)	Offset to identifier data specified
32	20	BINARY(4)	Length of identifier data specified
		CHAR(*)	Identifier data specified

Header Section

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	User space name used
10	A	CHAR(10)	User space library name used
20	14	CHAR(10)	User profile name used

Server Authentication Entry

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Displacement to next entry
4	4	BINARY(4)	Displacement to server specific data
8	8	CHAR(10)	Server type
18	12	CHAR(2)	Reserved
		CHAR(*)	Server-type specific data

NetWare 3.x Server Specific Data

If the server type is *NETWARE3, the format of the server-type specific data is as follows:

Offset		Type	Field
Dec	Hex		

0	0	BINARY(4)	Displacement to server name
4	4	BINARY(4)	Length of server name
8	8	BINARY(4)	Displacement to NetWare user name
12	C	BINARY(4)	Length of NetWare user name
		CHAR(*)	Server name
		CHAR(*)	NetWare user name

NetWare Directory Services Tree Specific Data

If the server type is *NDS, the format of the server-type specific data is as follows:

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Displacement to NDS tree name
4	4	BINARY(4)	Length of NDS tree name
8	8	BINARY(4)	Displacement to NDS context
12	C	BINARY(4)	Length of NDS context
16	10	BINARY(4)	Displacement to NetWare user name
20	14	BINARY(4)	Length of NetWare user name
		CHAR(*)	NDS tree name
		CHAR(*)	NDS context name
		CHAR(*)	NetWare user name

Field Descriptions

Displacement to NDS context. The displacement, in bytes, from the start of the list entry to the NDS context.

Displacement to NDS tree name. The displacement, in bytes, from the start of the list entry to the NDS tree name.

Displacement to NetWare user name. The displacement, in bytes, from the start of the list entry to the NetWare user name.

Displacement to next entry. The displacement, in bytes, from the start of the current list entry to the start of the next entry in the list.

Displacement to server name. The displacement, in bytes, from the start of the list entry to the server name.

Displacement to server specific data. The displacement, in bytes, from the start of the list entry to the server specific data.

Format name specified. The entry identifier format name that the caller of this API specifies.

Identifier data specified. The authentication entry identifier data that is specified when this API is called.

Length of identifier data specified. The length, in bytes, of the identifier data that is specified on the call to this API.

Length of NDS context. The length, in bytes, of the NDS context.

Length of NDS tree name. The length, in bytes, of the NDS tree name.

Length of NetWare user name. The length, in bytes, of the NetWare user name.

Length of selected NDS tree name. The length, in bytes, of the selected NDS tree name.

Length of selected server name. The length, in bytes, of the selected server name.

Length of server name. The length, in bytes, of the server name.

NDS context name. For NDS trees, the directory context in which the user is defined.

NDS tree name. For NDS trees, the name of the directory tree to which the authentication entry applies.

NetWare user name. The user name for which requests are made to the server.

Offset to identifier data specified. The offset, in bytes, from the start of the input parameter header to the identifier data that is specified on the call to this API.

Offset to selected NDS tree name. The offset, in bytes, from the start of the identifier data to the selected NDS tree name.

Offset to selected server name. The offset, in bytes, from the start of the identifier data to the selected server name.

Reserved. Set this field to binary zeros.

Selected NDS tree name. The name of the NDS tree for which authentication entries are to be listed. A generic name can be used.

The following special value may be specified:

**ALL* All NDS tree authentication entries.

Selected server name. The name of the server for which authentication entries are to be listed. A generic name can be used.

The following special value may be specified:

**ALL* All NetWare 3.x server authentication entries.

Server name. The name of the server to which the authentication entry applies.

Server type. The kind of server. The content and format of the server-specific data areas are dependent on the server type.

The following values may be returned:

**NETWARE3* The entry is for a NetWare Version 3.x server.

**NDS* The entry is for a NetWare Directory Services tree.

Server-type specific data. The name of the server and the user name that are used to start a connection to the server. The format and content of this data are dependent on the server type.

User profile name. The name of the user profile for which entries are to be listed.

The following special value may be specified:

**CURRENT* The current job's user profile.

User profile name used. The actual user profile name that is used for the authentication entries listed.

User space library name specified. The name that is specified for the library that contains the user space to receive the generated list.

User space library name used. The actual name of the library that is used to contain the user space that received the list.

User space name specified. The name that is specified for the user space that is to receive the generated list.

User space name used. The actual name of the user space that received the list.

Error Messages

Message ID	Error Message Text
CPF2204 E	User profile &1 not found.
CPF2217 E	Not authorized to user profile &1.
CPF24B4 E	Severe error while addressing parameter list.
CPF3C1D E	Length specified in parameter &1 not valid.
CPF3C21 E	Format name &1 is not valid.
CPF3C90 E	Literal value cannot be changed.
CPF3CAA E	List is too large for user space &1.
CPF3CF1 E	Error code parameter not valid.
CPF9801 E	Object &2 in library &3 not found.
CPF9802 E	Not authorized to object &2 in &3.
CPF9803 E	Cannot allocate object &2 in library &3.
CPF9872 E	Program or service program &1 in library &2 ended. Reason code &3.
FPE0211 E	Parameter length &1 not valid for field &2.
FPE0212 E	Field offset and length not within data.
FPE0213 E	Special value &1 not valid for field &2.

API Introduced: V3R7

[Top](#) | [Security APIs](#) | [APIs by category](#)

Remove NetWare Authentication Entry (QfpzRmvNtwAutE) API

Required Parameter Group:

1	Entry identifier data	Input	Char(*)
2	Length of entry identifier	Input	Binary(4)
3	Entry identifier format name	Input	Char(8)
4	Error code	I/O	Char(*)

Default Public Authority: *USE

Library Name/Service Program: QFPNTWE/QFPZAAPI

Threadsafe: No

The Remove NetWare Authentication Entry (QfpzRmvNtwAutE) API removes an authentication entry from the user profile.

Authorities and Locks

User Profile Authority

The user profile must be the current user profile, or the caller must have *USE and *OBJMGT authority to the user profile and *SECADM special authority.

Required Parameter Group

Entry identifier data

INPUT; CHAR(*)

The authentication entry to be removed. The content and format of this structure is determined by the format name. See [Format of Authentication Entry Identifier](#) for a description of these formats.

Length of entry identifier

INPUT; BINARY(4)

The length of the authentication entry identifier structure.

Entry identifier format name

INPUT; CHAR(8)

The content and format of the authentication entry identifier data. Each format corresponds to a method of identifying an authentication entry.

The possible format names follow:

[AUTE0100](#) The NetWare Version 3.x server entry is identified by the server name.

[AUTE0200](#) The NetWare Directory Services tree entry is identified by the NDS tree name.

[AUTE0900](#) All authentication entries are removed from a user profile.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see [Error Code Parameter](#).

Format of Authentication Entry Identifier

For details about the format of the entry identifier data, see the following sections. For details about the fields in each format, see [Field Descriptions](#).

AUTE0100 Format

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to server name
4	4	BINARY(4)	Length of server name
8	8	CHAR(10)	User profile name
18	12	CHAR(6)	Reserved
		CHAR(*)	Server name

AUTE0200 Format

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to NDS tree name
4	4	BINARY(4)	Length of NDS tree name
8	8	CHAR(10)	User profile name
18	12	CHAR(6)	Reserved
		CHAR(*)	NDS tree name

AUTE0900 Format

Offset		Type	Field
Dec	Hex		
0	0	CHAR(10)	User profile name
10	A	CHAR(6)	Reserved

Field Descriptions

Length of NDS tree name. The length, in bytes, of the NDS tree name.

Length of server name. The length, in bytes, of the server name.

NDS tree name. For *NDS tree entries, the name of the directory tree.

Offset to NDS tree name. The offset, in bytes, from the start of the input data area to the NDS tree name.

Offset to server name. The offset, in bytes, from the start of the input data area to the server name.

Reserved. Set this field to binary zeros.

Server name. For *NETWARE3 entries, the name of the server.

User profile name. The name of the user profile that contains the authentication entry.

You can use the following special value for the user profile name:

**CURRENT* The current user profile.

Error Messages

Message ID	Error Message Text
CPF2204 E	User profile &1 not found.
CPF2217 E	Not authorized to user profile &1.
CPF24B4 E	Severe error while addressing parameter list.
CPF3C1D E	Length specified in parameter &1 not valid.
CPF3C21 E	Format name &1 is not valid.
CPF3C90 E	Literal value cannot be changed.
CPF3CF1 E	Error code parameter not valid.
CPF9872 E	Program or service program &1 in library &2 ended. Reason code &3.
FPE0211 E	Parameter length &1 not valid for field &2.

FPE0212 E Field offset and length not within data.

FPE0215 E Could not find authentication entry for &1.

API Introduced:

[Top](#) | [Security APIs](#) | [APIs by category](#)

Start NetWare Connection (QfpzStrNtwCnn) API

Required Parameter Group:

1	Connection data	Input	Char(*)
2	Length of connection data	Input	Binary(4)
3	Connection data format name	Input	Char(8)
4	Error code	I/O	Char(*)

Default Public Authority: *USE

Library Name/Service Program: QFPNTWE/QFPZAAPI

Threadsafe: No

The Start NetWare Connection (QfpzStrNtwCnn) API establishes the caller as an authenticated user of the specified server. This API could be used to:

- Start a connection to a server for which a user has no authentication entry
 - Start a connection when the authentication entry has the password special value *STRNTWCNN
- An authentication entry may have the value *STRNTWCNN because the QRETSVRSEC system value does not allow retrieving security data such as passwords.
- Start a connection to a server by using a different NetWare user name than is specified in the authentication entry for that server

If an authentication entry for the server exists and contains a valid password and user name, the system starts a connection to the server when needed, and this API need not be used.

Connections may only be used by the specified user and job. The job may be either the current job (value 1 for the authorized job field) or any job (value 2 for the authorized job field) on the system. If any job is specified, all jobs that are running under the specified user profile can use the connection. If a connection for a user profile and job exists, that connection is used. Otherwise, an any-job connection for the user profile is used. A current-job connection might be used, for example, when a job uses a connection with a different NetWare user name than other jobs on the system. An any-job connection is required for certain functions, for example, printing to a NetWare print server.

NetWare backup services require a separate authentication. To support this, the connection type field specifies whether a normal login (*USER connection) or a backup services authentication (*SAVRST connection) is to be performed.

A user profile can only have one connection per job to a server (either NetWare 3.x server or a server within a NetWare Directory Services (NDS) tree) at any given time. Connections may be started to all servers within an NDS tree, for example, when copying from one server to another. If connections to multiple servers are open, operations that do not require a specific server use the first connection started.

Authorities and Locks

User Profile Authority

*USE

Required Parameter Group

Connection data

INPUT; CHAR(*)

The server and user name for the connection to be started. The content and format of this structure are determined by the format name. See [Format of Connection Data](#) for a description of these formats.

Length of connection data

INPUT; BINARY(4)

The length of the connection data structure.

Connection data format name

INPUT; CHAR(8)

The content and format of the input data. Several formats are provided. Each format corresponds to a type of server.

The possible format names follow:

[SVRC0100](#) Start a connection to a NetWare Version 3.x server.

[SVRC0200](#) Start a connection to a server in a NetWare Directory Services tree.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see [Error Code Parameter](#).

Format of Connection Data

For details about the format of the connection data, see the following sections. For details about the fields in each format, see [Field Descriptions](#).

SVRC0100 Format (NetWare Version 3.x Server)

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to server name

0	0	BINARY(4)	Offset to server name
4	4	BINARY(4)	Length of server name
8	8	BINARY(4)	Offset to NetWare user name
12	C	BINARY(4)	Length of NetWare user name
16	10	BINARY(4)	Offset to password
20	14	BINARY(4)	Length of password
24	18	BINARY(4)	Offset to connection type list
28	1C	BINARY(4)	Number of entries in connection type list
32	20	BINARY(4)	Authorized job
36	24	BINARY(4)	Connection idle time
40	28	CHAR(10)	User profile name
50	32	CHAR(6)	Reserved
		CHAR(*)	Server name
		CHAR(*)	NetWare user name
		CHAR(*)	Password
Note: The following field is repeated for each connection type requested.			
		BINARY(4)	Connection type

SVRC0200 Format (NetWare Directory Services Tree)

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to NDS tree name
4	4	BINARY(4)	Length of NDS tree name
8	8	BINARY(4)	Offset to server name
12	C	BINARY(4)	Length of server name
16	10	BINARY(4)	Offset to NDS context
20	14	BINARY(4)	Length of NDS context
24	18	BINARY(4)	Offset to NetWare user name
28	1C	BINARY(4)	Length of NetWare user name
32	20	BINARY(4)	Offset to password
36	24	BINARY(4)	Length of password
40	28	BINARY(4)	Offset to connection type list
44	2C	BINARY(4)	Number of entries in connection type list
48	30	BINARY(4)	Authorized job
52	34	BINARY(4)	Connection idle time
56	38	CHAR(10)	User profile name
66	42	CHAR(6)	Reserved
		CHAR(*)	NDS tree name
		CHAR(*)	Server name
		CHAR(*)	NDS context

		CHAR(*)	NetWare user name
		CHAR(*)	Password
Note: The following field is repeated for each connection type requested.			
		BINARY(4)	Connection type

Field Descriptions

Authorized job. The jobs authorized to use the connection.

The following values may be specified:

- 1 The connection can be used only by the *current job*. The connection ends when the current job is ended, or when the connection is ended by an end NetWare connection request.
- 2 The connection can be used by *any job* on the system that is running under the specified user profile. The connection must be explicitly ended by an end NetWare connection request.

Notes:

1. The QNETWARE file system requires a connection for the current job.
2. If no authentication entry exists, or the password in the authentication entry is *STRNTWCNN, printing functions require that a connection for any job (authorized job value is 2) be started.
3. If the authorized job value is 1 and user reclaims the QFPZAUT activation group (RCLACTGRP command), the connection ends.
4. For either authorized job value, you may use the connection idle time value to control when a connection ends.

Connection idle time. The idle time (in minutes) before a connection is closed by the system. Idle time is the time between subsequent requests. Valid values range from 1 minute through 9999 minutes.

The following special value may be specified:

- 1 There is no idle time. A connection is closed by the user, or it is closed when the job has ended (if the authorized job value is 1).

Connection type. The type of authentication to be performed. NetWare backup services require a separate authentication in addition to a normal user authentication.

The following values may be specified:

- 1 A normal user authentication is done. The user can use administrative and file system functions other than save and restore.
 - 2 Authentication to NetWare backup services is performed. This option requires that the appropriate NetWare Loadable Module software (TSA312.NLM, TSA410.NLM, or TSANDS.NLM, and SMDR.NLM) be loaded on the server.
- 1 Perform both user and backup services authentications. If -1 is specified, it must be the only connection type value specified.

Length of NDS context. The length, in bytes, of the NDS context.

Length of NDS tree name. The length, in bytes, of the NDS tree name.

Length of NetWare user name. The length, in bytes, of the NetWare user name.

Length of password. The length, in bytes, of the password.

Length of server name. The length, in bytes, of the server name.

NDS context. For NetWare Directory Services trees, the directory context in which the user is defined.

The following special value may be used:

**AUTE* Use the NDS context from the user profile authentication entry for this NDS tree.

NDS tree name. The name of the NetWare Directory Services tree to which the connection is to be started.

NetWare user name. The NetWare user name that is used to authenticate the user to the server.

The following special values may be used:

**USRPRF* Use the authorized OS/400 user profile name as the NetWare user name.

**AUTE* Use the NetWare user name from the user profile authentication entry for this server or NDS tree.

Number of entries in connection type list. The number of connection type values in the connection type list. At least one value must be specified.

Offset to connection type list. The offset, in bytes, from the start of the data area to the connection type values.

Offset to NDS context. The offset, in bytes, from the start of the data area to the NDS context.

Offset to NDS tree name. The offset, in bytes, from the start of the data area to the NDS tree name.

Offset to NetWare user name. The offset, in bytes, from the start of the data area to the NetWare user name.

Offset to password. The offset, in bytes, from the start of the data area to the password.

Offset to server name. The offset, in bytes, from the start of the data area to the server name.

Password. The password that is used to authenticate the user to the server.

The following special values may be used:

**AUTE* Use the password from the user profile authentication entry for this server or NDS tree.

**NONE* No password is used to authenticate the user.

Reserved. Set this field to binary zeros.

Server name. The name of the server to which the connection is to be started.

When you are connecting to a NetWare Version 3.x server, the server name must be specified.

When you are connecting to a NetWare Directory Services tree, the connection must be started on a server

within the tree.

Either the server name or one of the following special values must be specified:

**ANY* Use any server within the specified NDS tree.

**ALL* Start connections to all servers in the specified tree.

User profile name. The OS/400 user profile name that is authorized to use this connection.

The following special value may be used:

**CURRENT* Jobs running under the current user profile are authorized to use the connection.

Error Messages

Message ID	Error Message Text
CPF2144 E	Not authorized to &1 in &2 type *&3.
CPF2217 E	Not authorized to user profile &1.
CPF24B4 E	Severe error while addressing parameter list.
CPF3C1D E	Length specified in parameter &1 not valid.
CPF3C21 E	Format name &1 is not valid.
CPF3C90 E	Literal value cannot be changed.
CPF3CF1 E	Error code parameter not valid.
CPF9872 E	Program or service program &1 in library &2 ended. Reason code &3.
FPE0211 E	Parameter length &1 not valid for field &2.
FPE0212 E	Field offset and length not within data.
FPE0215 E	Could not find authentication entry for &1.
FPE021C E	Not able to contact server &1.
FPE0227 E	Server name *ANY or *ALL not allowed for server type.
FPE0230 E	Connection type -1 must be single value.
FPE0235 E	Error &2 connecting to server &3.
FPE0236 E	Value &1 not valid for authorized job.
FPE0237 E	Value &1 not valid for connection idle time.
FPE023C E	Server is not a &2 server. Server: &1.
FPE023D E	NDS tree not known to system. Tree: &1.
FPE023E E	Server &1 not found in tree &2.

API Introduced: V3R7

[Top](#) | [Security APIs](#) | [APIs by category](#)

Verify NetWare Authentication Entry (QfpzVfyNtwAutE) API

Required Parameter Group:

1	Entry identifier data	Input	Char(*)
2	Length of entry identifier	Input	Binary(4)
3	Entry identifier format name	Input	Char(8)
4	Error code	I/O	Char(*)

Default Public Authority: *USE

Library Name/Service Program: QFPNTWE/QFPZAAPI

Threadsafe: No

The Verify NetWare Authentication Entry (QfpzVfyNtwAutE) API verifies that the specified authentication entry can be used to connect to a server. The user name, password, and other data are sent to the server, where they are used to attempt to start an authenticated connection to the server. This API might be used, for example, to verify that the password is valid before submitting a batch job that would use this entry.

Authorities and Locks

User Profile Authority

The user profile must be the current user profile, or the caller must have *USE and *OBJMGT authority to the user profile and *SECADM special authority.

Required Parameter Group

Entry identifier data

INPUT; CHAR(*)

The server and user name for the connection to be started. The content and format of this structure are determined by the format name. See [Format of Authentication Entry Identifier](#) for a description of these formats.

Length of entry identifier

INPUT; BINARY(4)

The length of the entry identifier structure.

Entry identifier format name

INPUT; CHAR(8)

The content and format of the input data. Each format corresponds to a method of identifying an authentication entry.

The possible format names follow:

[AUTE0100](#) The NetWare Version 3.x server entry is identified by the server name.

[AUTE0200](#) The NetWare Directory Services tree entry is identified by the NDS tree name.

Error code

I/O; CHAR(*)

The structure in which to return error information. For the format of the structure, see [Error Code Parameter](#).

Format of Authentication Entry Identifier

For details about the format of the entry identifier, see the following sections. For details about the fields in each format, see [Field Descriptions](#).

AUTE0100 Format

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to server name
4	4	BINARY(4)	Length of server name
8	8	CHAR(10)	User profile name
18	12	CHAR(6)	Reserved
		CHAR(*)	Server name

AUTE0200 Format

Offset		Type	Field
Dec	Hex		
0	0	BINARY(4)	Offset to NDS tree name
4	4	BINARY(4)	Length of NDS tree name
8	8	BINARY(4)	Offset to server name
12	C	BINARY(4)	Length of server name
16	10	CHAR(10)	User profile name
26	1A	CHAR(6)	Reserved
		CHAR(*)	NDS tree name
		CHAR(*)	Server name

Field Descriptions

Length of NDS tree name. The length, in bytes, of the NDS tree name.

Length of server name. The length, in bytes, of the server name.

NDS tree name. For *NDS trees, the name of the directory tree.

Offset to NDS tree name. The offset, in bytes, from the start of the input data area to the NDS tree name.

Offset to server name. The offset, in bytes, from the start of the input data area to the server name.

Server name. For *NETWARE3 servers, the name of the server.

For *NDS servers, the name of the server on which to verify the authentication entry.

For *NDS servers, the following special value may be specified:

**ANY* Any server in the specified NDS tree.

Reserved. Set this field to binary zeros.

User profile name. The name of the user profile that contains the authentication entry.

You can use the following special values for the object name:

**CURRENT* The current user profile.

Error Messages

Message ID	Error Message Text
CPF2204 E	User profile &1 not found.
CPF2217 E	Not authorized to user profile &1.
CPF24B4 E	Severe error while addressing parameter list.
CPF3C1D E	Length specified in parameter &1 not valid.
CPF3C21 E	Format name &1 is not valid.
CPF3C90 E	Literal value cannot be changed.
CPF3CF1 E	Error code parameter not valid.
CPF9872 E	Program or service program &1 in library &2 ended. Reason code &3.
FPE0211 E	Parameter length &1 not valid for field &2.
FPE0212 E	Field offset and length not within data.

FPE0215 E Could not find authentication entry for &1.
FPE021C E Not able to contact server &1.
FPE0235 E Error &2 connecting to server &3.
FPE023C E Server is not a &2 server. Server: &1.
FPE023D E NDS tree not known to system. Tree: &1.
FPE023E E Server &1 not found in tree &2.

API Introduced: V3R7

[Top](#) | [Security APIs](#) | [APIs by category](#)