

# **POWER Systems Client Care Electronic Tools**

Firmware Level Recommendation Tool (FLRT)

Reporting & Inventory

Firmware & HMC Version Update

Regina Moliff rmoliff@us.ibm.com



## What is FLRT

- □ FLRT (Fix Level Recommendation Tool) is designed for System p servers running AIX on POWER6, POWER5/5+ and BLADE systems.
- □ FLRT is a health check tool used by customers to compare current system fix levels against recommendations from IBM.
- □ Product data is maintained in an XML database running on a Websphere based solution.
- Located at www14.software.ibm.com/webapp/set2/flrt



## Products currently supported

- System firmware for p6, p5+, p5 & Blade
- **HMC** 7.3, 6.1, 5.2, 5.1, 4.5
- **AIX** 6.1, 5.3, 5.2
- **Virtual I/O Server** 1.4, 1.3, 1.2, 1.1

- **HACMP** 5.4, 5.3, 5.2, 5.1
- **GPFS** 3.1, 2.3
- □ **CSM** 1.6, 1.5, 1.4




## Recommendation types and Features

- Recommendation types
  - ✓ "A OK" System is at or above recommendations
  - "Take action" IBM recommends an update to one or more products
  - Could not recommend. Read why and try another configuration

- Features
  - Single product or multiple product recommendations
  - Guidance on which product update to apply first
  - Help on how to determine current levels
  - Supports scripting for recommended updates
  - What If What if I were to update my firmware? Will I need to update my HMC too?

## FLRT Website - Current Release v2 (launched 12/4)





# **Order and Discovery**

FLRT usage

Fix level determination

Installation order

Scripting help

The FLRT assists AIX system administrators in formulating a maintenance plan for IBM System p servers. If a FLRT report makes update recommendations, apply any updates in the recommended order.

### Recommended installation order

Following is the recommended order for updating

- HMC
- Firmware
- 3 VIOS
- AIX 5L

After AIX 5L has been updated, HACMP, CSM, ar depends on CSM; therefore, it should be update FLRT usage

Fix level determination

The FLRT assists AIX system administrators in for p servers. It uses various code and fix levels to pro incompatibilities on your system.

## How to determine processor speed and firmwar

Use these instructions to determine the processo and the level of products installed on that system.

- Processor speed
- AIX
- Firmware
- HMC
- Virtual I/O Server

### Processor speed

Enter the following command to confirm the mode system:

Enter the following command to confirm the model number and processor speed of the

Example output:

System Model: IBM, 9117-570 Machine Serial Number: 104CAEC Processor Type: PowerPC POWER5 Number Of Processors: 3 Processor Clock Speed: 1502 MHz

Make a note of the System Model and the Processor Clock Speed.

Use the oslevel command to display the highest recommended technology level installed on your system. For example:

Example output:

Firmware

### Enter the following command:

lsmcode -c

Example output:

The current permanent system firmware image is SF240 219 The current temporary system firmware image is SF240 219

The system is currently booted from the temporary firmware image.

HMC version and release information can be viewed locally at an HMC console by bringing up the Help menu and clicking on About Hardware Managment Console. You can also view this information, either locally or from a remote WebSM client, by going to

Licensed Internal Code Maintenance -> HMC Code Update

and then reading the status section. From the command line, you can display the current code level by running the following command: # 1shmc -V

Example output:

version= Version: 6 Release: 1 0 HMC Build level 20060801.1 MH00781: Required fixes for V6R1.0 (08-03-2006) "."base version=V6.1.0

Virtual I/O Server The VIOS command line user interface provides the ioslevel command that display the VIOS version information.

Example output:

### High Availability Cluster Multi-processing

To determine the level installed on your server, enter the following command:

# lslpp -h cluster\*

### Cluster Systems Management

Enter the following command to display the version of CSM installed on your server. Note that version displayed does not necessarily indicate that CSM is configured or operational.

Use 1s1pp -h csm\* to list all the filesets installed for CSM \*, which may be at different levels (in a PTF configuration). For example, CSM 1.5.1.3 may have csm.core 1.5.1.3 and csm.server 1.5.1.2. but the overall level is considered 1.5.1.3.

**CSM Highly Available Systems Management** 

Enter the following command to determine the level of CSM-HA installed on your server: # 1slpp -h csm.ha\*

# 1slpp -1 | grep csm.hams

General Parallel File System

Enter the following command to determine the level of GPFS installed on your server # 1slpp -h gpfs\*

Example output:

Translate my page

6



#/bin/ksh Sample script using wget to gather product versions and query FLRT. # This current sample script provides commands for gathering MTM/AIX version/System Firmware. The rest of the product queries are samples which are commented out. Please provide additional samples through the feedback button at: http://www14.software.ibm.com/webapp/set2/sas/f/flrt/scripting.html REPORTNAME=`hostname` #Set all the values to empty, please do not modify this section: MTMVALUE="" GHZVALUE="" AIXVALUE="" SFIRMWAREVALUE="" HMCVALUE="" VIOSVALUE="" HACMPVALUE="" **GPFSVALUE=""** CSMVALUE="" CSMHAVALUE="" #Uncomment relevant product sections . # Determine the System Model MTMVALUE=\&mtm=`prtconf | grep "System Model" | cut -f 2 -d ,` # MHZ - processor speed. MHZVALUE=\&mhz=`prtconf | grep "Processor Clock Speed" | cut -f4 -d " "` # AIX service pack level. AIXVALUE=\&aix=`oslevel -s` # System firmware (booted) version SFIRMWAREVALUE=\&sfirmware=`Ismcode -r system | cut -f1 -d " " | cut -f2 -d":"` # HMC version requires a call to the HMC box. Using ssh is one way to do this. # This requires setup of ssh which is not discussed here. #HMC\_OUTPUT=`ssh -I userid hostname.domain.com lshmc -V > hmc.out` #HMC\_VERSION=`grep -i version hmc.out | cut -f 3 -d " "` #HMC\_RELEASE=`grep -i release hmc.out | cut -f 3 -d " "` #HMCVALUE=\&hmc=\$HMC VERSION.\$HMC RELEASE #VIOSVALUE=\&vios=`ioslevel` #HACMP version #HACMPVALUE=\&hacmp=`lslpp -L cluster.es.server.rte | grep cluster.es.server.rte | cut -f3 -d":"` #GPFS version #GPFSVALUE=\&gpfs=`lslpp -Lc csm.gpfs | grep csm.gpfs | cut -f3 -d":"` #CSMVALUE=\&csm=`/opt/csm/bin/csmconfig -V` #CSMHAVALUE=\&csmha=`lslpp -Lc csm.hams | grep csm.hams | cut -f3 -d":"` echo \$REPORTNAME ../wget-1.9/src/wget "http://www14.software.ibm.com/webapp/set2/flrt/query?format=text\$MTMVALUE\$MHZVALUE\$AIXVALUE\$SFIRMWAREVALUE\$HMCVALUE\$VIOSVALUE\$HACMPVALUE\$GPFSVALUE\$CSMVALUE\$CSMHAVALUE" -o getfirt.stdout -O getfirt.rpt cat getfirt.rpt



# Demo





# **Futures**





## Next Release - Version 3

- Support for more cluster products
  - Tivoli WorkloadScheduler (LoadLeveler)
  - Deep ComputingVisualization
  - Parallel Environment
  - Engineering & Scientific Subroutine Library

- Multi-system reports
  - Consolidated reporting
- Usability improvements
  - Highlight FLRTs many uses by driving customers to a task.
    - Do you want to verify your current system?
    - Do you want to run what-if scenarios?



# Questions????







