

Open Client Administrator Help

Getting started with Open Client

Open Client is an optional addition to FileNet Web Services. Without downloading or installing any FileNet software, Open Client users can access documents in Image Services (IS) and Content Services (CS) libraries through a web browser. A user can view a retrieved document in these ways:

- In the document's registered application, if the application is installed on the workstation.
- In the browser (for example, using the Acrobat Reader plug-in to view PDF documents).
- In the IDM Viewer. The administrator must enable the IDM Viewer using a site preference, and the user must download and install the viewer.
- In the Java Viewer. The administrator must enable the Java Viewer using a site preference. No download is necessary.

Open Client was developed using Microsoft's .NET technology.

About this Help

The Open Client Administrator's Help supplements the FileNet Web Services Administrator's Help and provides instructions on installing, configuring, and troubleshooting Open Client. It includes information on Process and eForms integration.

For general information on FileNet Web Services administration, such as adding libraries, setting FileNet Web Services preferences, setting up LDAP login, and defining stored searches, see the FileNet Web Services Administrator's Help.

What's new in this release?

The Open Client 4.0.1 release incorporates the following features:

- CS user rights are validated based on the value of the “Add Folder” property for the user when attempting to add a folder in the CS library. CS user rights are validated only after installing CS 5.4 HFP 2 (both at the server and client side). An error message is displayed in case a user does not have appropriate rights. An Admin user can add a folder in CS library even if there are no rights assigned to this user for adding a folder.
- You can use Open Client with .NET Framework 1.1 SP1 and some other application with .NET Framework 2.0 on the same server. This collocation configuration will not affect the working of Open Client. Open Client continues to work properly on the same machine if it is configured to use .NET Framework 1.1 SP1 using IIS management console. For more information regarding configuring Open Client with .NET Framework 1.1 SP1, refer to *Configure .NET Framework 1.1 SP1 and .NET Framework 2.0 Collocation Support* section on the [Install Open Client](#) page.
- System Manager allows FileNet to provide real-time and standards-compliant monitoring of all your FileNet servers. Level 1 System Manager integration with Open Client provides information such as Product Name, Version number, and static environmental data about Open Client. For capturing this information, the System Manager uses two major components: a Listener, which gathers data from applications, and a Manager, which provides users with the ability to view, save and export that data. You can view the system details of the FileNet Open Client server. For more information regarding System Manager Integration with Open Client, refer to [Configuring System Manager Listener](#) and [Setting System Manager Integration site preferences](#).
- The Java Viewer Quick Start feature provides a mechanism for initializing a Web browser, Java, and Java Viewer session. The background task required to initialize a Java Viewer session is done at the time when the Web browser is initialized, prior to the time when Java Viewer is actually required. This reduces the startup time of Java Viewer. This feature is supported on various Operating Systems, such as Microsoft 2000 Professional and XP. The only Web browser supported for this feature is Internet Explorer; future versions of Java Viewer may support additional Web browsers. The Quick Start feature is not enabled by default, you need to manually enable it. For more information regarding configuring the Java Viewer Quick Start feature, refer to [Configure the Java Viewer Quick Start Feature](#).
- The error page format is similar to rest of Open Client pages. Earlier, for any unforeseen exception a .NET error page was being displayed. An application level exception handler has been introduced to handle all the unforeseen exceptions. The user is given maximum amount of information about the error/exception that has occurred.

About Open Client installation

Installing Open Client involves running the Open Client Setup program from the software CD, specifying physical and virtual directories for web documents (the virtual directory is part of the URL), selecting the components to install, and allowing Setup to copy the software to the web server. You must have Administrator privileges to install Open Client.

Following installation, you must configure the software.

Silent installation and maintenance options are provided.

Note

The first time a user accesses an Open Client page, .NET compiles the page into machine language. Subsequently, this compilation occurs each time the web service restarts.

Open Client Requirements

Web server requirements

Open Client server and client requirements are published in the [IDM Desktop, Web Services, and Open Client Compatibility and Dependency](#) document. This document is commonly called the compatibility matrix. It is posted on the FileNet CSS web site when the software is released and updated as changes occur (for example, when third-party service packs are certified). Additional requirements for Process Integration with Open Client are published in the [Process Compatibility & Dependency](#) document on the FileNet CSS web site.

Web client requirements

Open Client provides a no-download web client based on .NET technology. The Open Client includes two viewers:

- The IDM Viewer, which requires a user download.
- The Java Viewer, which requires the workstation to have either (any version of) the Java Runtime Environment (JRE) or the Microsoft Java Virtual Machine (JVM). Note that Process Integration has specific JRE version requirements. If necessary, JRE 1.4.0 is automatically installed on a workstation the first time a user runs a Process Java applet, such as Process Designer, from the Open Client Process page. If you are not using Open Client with Process Integration, you must obtain a JRE from the [Sun web site](#) or another location. If you plan to add Process Integration at a later time, we recommend that you install JRE 1.4.0 on the workstations. **TIP** To download JRE 1.4.0 from the Sun web site, go to the "Archive releases" page. The JVM can be downloaded from FileNet's FTP site. See the readme file for details.

Web client requirements for Process Integration

Before running a Process Java applet on a web client, FileNet recommends installing a supported version of the Java Runtime Environment (JRE) on the client. To see if a supported version of the JRE is installed, go to Start, Settings, Control Panel, Java Plug-In. The JRE 1.4.0 setup package is available on Process 5.0 web server and JRE 1.4.2 setup package is available on Process 5.1 web server. The location of the JRE setup package in both the Process web server is `..\\FileNet\\IDM\\Web\\FnOpenClient\\eProcess\\Download` directory.

A web client cannot run multiple versions of the JRE. Any version other than the one used for Process integration must be uninstalled before accessing a Process applet.

JRE for Process 5.0 Integration

Process 5.0 requires either JRE 1.4.0 or 1.4.2. Other JRE versions are not supported.

- If JRE 1.4.0 exists, no actions are required prior to accessing the Process 5.0 applets.
- If JRE 1.4.0 exists, the Internet Explorer option on the Java Plug-In\\Browser tab must be unselected (not checked) prior to accessing the Process applets.
- If no JRE exists and the client is using Internet Explorer, JRE 1.4.0 will be downloaded automatically when the user first attempts an operation that requires the JRE.
- If no JRE exists and the client is using Netscape, either JRE 1.4.0 or 1.4.2 must be installed before accessing a Process applet. If you are using Netscape 6, make sure the Netscape option is selected.

JRE for Process 5.1 Integration

Process 5.1 requires JRE 1.4.2. Other JRE versions are not supported.

- If JRE 1.4.2 exists, the Internet Explorer option on the Java Plug-In\Browser tab must be unselected (not checked) prior to accessing the Process applets.
- If no JRE exists and the client is using Internet Explorer, JRE 1.4.2 will be downloaded automatically when the user first attempts an operation that requires the JRE.
- If no JRE exists and the client is using Netscape, the 1.4.2 must be installed before accessing a Process applet. If you are using Netscape 6, make sure the Netscape option is selected.

What Setup installs

During Open Client installation, you have a choice of a Typical installation, a Complete installation, or a Custom installation. All options include the Java Viewer.

Typical installation

For a typical installation, Setup installs Open Client.

Complete installation

For a complete installation, Setup installs Open Client and Process Integration.

Custom installation

With a custom installation, Setup allows you to select the components to install.

Install Open Client

To install Open Client on your system, you must perform the following two steps:

1. Install Microsoft .NET Framework.
2. Install Open Client from the FileNet Web Services software CD.
3. Install Open Client 4.0.1 from the FileNet Web Services software CD.
4. If .NET Framework 2.0 is installed on the server, then configure Open Client with .NET Framework 1.1 SP1 for collocation support.

Note that you must ensure the following while installing Open Client:

- Specify the destination location for the Open Client software or accept the default path.
- Specify the virtual directory name to appear as the customized Open Client URL.

Install .NET Framework

1. From the Microsoft web site, download a supported version of .NET Framework.
2. Install .NET Framework.
3. On Windows 2003, activate ASP.NET. (On Windows 2000, installing .NET automatically activates ASP.NET.)
 - a. In the IIS Control Panel, click Add/Remove Programs->Add/Remove Window Components to open the Windows Components Wizard Dialog Box.
 - b. Double-click the Application Server option and choose the ASP.NET option.

Install Open Client 4.0

Caution You can install Open Client 4.0 only with Web Services 4.0 and its patches.

1. Login as a user with Administrator privileges on the machine where you want to install the Open Client.
2. Insert the CD.
3. Open the Open Client folder.
4. Run **setup.exe**.
5. Choose the type of installation as shown below.

Types of Installation	Description
Complete	In case of Complete installation, Open Client 4.0 with Process Integration is installed along with the script, binary, and source files. For more information about installing eProcess Integration, refer to Install Open Client with Process 5.0 Integration or Install Open Client with Process 5.1 Integration .
Custom	<p>In case of Custom installation, you are prompted with two options, eProcess Integration and Development Tools as listed below.</p> <ol style="list-style-type: none">1. Selecting eProcess Integration option installs the Process Integration with Open Client 4.0 and copies the script and binary files to the destination folder. The eProcess Integration option is checked by default.2. Selecting the Development Tools option copies source files of Open Client 4.0 to the destination folder. Help for Developers will not be installed if Development Tools option is not selected while installing Open Client 4.0.

	<p>3. Selecting both the options will install script, binary and source files of both Process Integration and Open Client 4.0. If you do not select any of the options, then Open Client 4.0 is installed with the script and binary files but without Process Integration.</p> <p>For more information about installing eProcess Integration, refer to Install Open Client with Process 5.0 Integration or Install Open Client with Process 5.1 Integration.</p>
Typical	In case of Typical installation only the Open Client script and binary files will be copied to the destination folder. A typical installation is without Process Integration.

6. After successful installation, you will receive an installation confirmation message and a prompt to restart the machine.

Install Open Client 4.0.1

Open Client 4.0.1 can be applied on top of Open Client 4.0 installation and any of its 4.0.0-00x patches. In addition, Web Services 4.0.1 is a prerequisite for installing Open Client 4.0.1 successfully. Following are the steps for installing Open Client 4.0.1:

1. Login as a user with Administrator privileges on the machine where you have installed Open Client 4.0.
2. Insert the CD.
3. Open the Open Client folder.
4. Run the **OpenClient-4.0.1-000.exe** file on your machine.
5. The installation completes and you are prompted to click **Finish** to exit the Installation Wizard.
6. If .NET Framework 2.0 is installed on the server, then [configure Open Client with .NET Framework 1.1 SP1 for collocation support](#).
7. It is recommended to reboot the system after the installation completes.
8. After reboot, you need to [verify the installation](#).

Configure .NET Framework 1.1 SP1 and .NET Framework 2.0 Collocation Support

If .NET Framework 2.0 exists on the server, you need to configure Open Client with .NET Framework 1.1 SP1. Following are the steps for configuring Open Client with .NET Framework 1.1 SP1 using the IIS console.

1. If you are using Windows 2000, then **Start > Programs > Administrative Tools > Internet Service Manager**. If you are using Windows 2003, then **Start > Programs > Administrative Tools > Internet Information Services (IIS) Manager**.
2. Expand the Internet Information Server tree so that you can see your Web server's "**Default Web Site**".
3. Verify that the Open Client virtual directory you created during setup exists.
4. Right-click the Open Client virtual directory folder, and click **Properties**.
5. Click on the **ASP.NET** tab.
6. Choose the version of .NET Framework 1.1 SP1 from the drop down list.
7. Click **OK**.

Upgrade Open Client

The Setup program does not perform upgrades of Open Client. To upgrade Open Client from 3.3 to 4.0, you will save customizations, uninstall all FileNet software from the web server, upgrade third-party software as needed, install the 4.0 release, and then reinstate your customizations.

Upgrade Open Client

1. Back up all customizations.
2. If you are using a Windows 2000 server, install any required service pack.
3. Upgrade .NET Framework to a supported version.
4. If you are using Process for Open Client, upgrade the JRE to a supported version.
5. [Uninstall Open Client](#) and any integrations.
6. Uninstall Web Services using the procedure in the FileNet Web Services Administrator's Help.
7. Install FileNet Web Services 4.0.
8. Install Open Client 4.0 using one of the following procedures:
 - [Install Open Client](#)
 - [Install Open Client with Process 5.0 Integration](#)
 - [Install Open Client with Process 5.1 Integration](#)
9. Restore code customizations and recompile. See *Upgrading a Customized Application* in the topic "Best Practices for Customization" in the Open Client Developer's Guide.

Verify Open Client installation

When Open Client software installation is complete, use these steps to verify the installation.

To verify Open Client installation

1. If you are using Windows 2000, then **Start > Programs > Administrative Tools > Internet Service Manager**. If you are using Windows 2003, then **Start > Programs > Administrative Tools > Internet Information Services (IIS) Manager**.
2. Expand the Internet Information Server tree so that you can see your Web server's "**Default Web Site**".
3. Verify that the virtual directory you created during setup exists.
4. Using a browser, access your web site from another computer to confirm that it is working. For example, `http://<webservername>/<virtual directory>`.
5. Access each page to complete the .NET just-in-time compilation.

Setup log file

The Setup program records installation information in opclient.log. Setup places the log file in your WINNT directory.

You can use opclient.log to verify and troubleshoot an installation. If you need to contact FileNet customer support, the representative may ask for the opclient.log file for reference.

The log file contains the following information:

- The date and time the installation started and finished
- Information on the computer on which Open Client is installed, such as operating system and version, video card and monitor resolution, memory, system directory path, and disk drives
- Setup program activity
- A list of the components that Setup successfully installed
- Any errors or warnings

Silent installation

A silent installation suppresses messages and requires no user input. To install Open Client in quiet mode, create a recording session, then run the setup in silent mode.

To create a recording session

1. From the command line, enter the following, where /r indicates recording mode and /f1 indicates the name of the recording session file:

```
setup /r /f1"<filespec>"
```

For example, `setup /r /f1"c:\sessions\setup.iss"`

Note: The quotation marks are required.

2. Run the installation procedure.
3. You may also want to create an uninstall session. To create an uninstall session, use the same format. For example,

```
setup /r /f1"c:\sessions\uninstall.iss"
```

When this finishes, a maintenance menu is displayed. Select **Uninstall**.

To run setup in silent mode

On a machine on which Open Client has not been installed, enter the following on the command line, where /s indicates silent (quiet) mode:

```
setup /s /f1"<filespec>"
```

For example, `setup /s /f1"c:\sessions\setup.iss"`

Note: The quotation marks are required.

When Setup runs in silent mode, the Setup icon appears on the Task bar. This is the only indication that the install is running. No messages or dialog boxes appear.

Repair Open Client

Repair re-installs Open Client based on the settings used when it was first installed.

To repair Open Client

1. Select **Add/Remove Programs** from the Control Panel.
2. Select **FileNet Open Client**.
3. Click the **Change/Remove** button. The Maintenance Wizard appears.
4. Select **Repair** and follow the prompts to refresh the Open Client software from the installer's database.

Process Integration

Install Open Client with Process 5.0 Integration

You will install FileNet Web Services, Microsoft's .NET Framework, Open Client with Process Integration, and the Process Connectivity Bundle.

It is recommended that you accept all default paths.

Log on

Log on to the web server with Administrator privileges. Ensure that you use the same user account to login after each required reboot in the procedure.

Install FileNet Web Services

Install FileNet Web Services using the procedure in the FileNet Web Services Administrator's Help.

Install .NET Framework

1. From the Microsoft web site, download a supported version of .NET Framework.
2. Install .NET Framework.
3. On Windows 2003, activate ASP.NET. (On Windows 2000, installing .NET activates ASP.NET.)
 - a. In Control Panel of IIS, click Add/Remove Programs->Add/Remove Window Components to open the Windows Components Wizard Dialog Box.
 - b. Double-click the Application Server option and choose the ASP.NET option.

Install Open Client with Process Integration

1. Insert the FileNet Web Services software CD in the CD-ROM drive. Exit Setup if it starts automatically.
2. On the CD, open the \Open Client ExeZip folder, and double-click on setup.exe.
3. Click **Next**.
4. Click **Yes** to accept the license agreement.
5. Select "Anyone who uses this computer" to allow all users on this machine to administer Open Client, and then click **Next**. Select "For myself only" if you want to be the only user on this machine who can administer Open Client, and then click **Next**. This setting has no effect on web client access to Open Client and Process.
6. Accept the default installation folder, or click **Browse** to select a folder other than the default, and then click **Next**.
7. Enter the alias (IIS virtual directory) for Open Client. This becomes part of the URL used to access Open Client. For example, if you enter the alias OpenClient, the URL will be `http://<webserver>/OpenClient`.
8. Select **Complete** or **Custom** to install Open Client with Process Integration.

In case of Complete installation the source as well as the script files are copied to the destination machine.

In case of **Custom** installation, user is prompted with two options, eProcess Integration and Development Tools. The eProcess Integration option is checked by default.

Selecting eProcess Integration option installs the Process Integration with Open Client 4.0 and copies the script and binary files to the destination folder.

Selecting the Development Tools option copies source files of Open Client 4.0 to the destination folder. Help for Developers will not be installed if Development Tools option is not selected while installing Open Client 4.0.

Selecting both the options will install script, binary and source files of both Process Integration and Open Client 4.0.

If you do not select any of the options then Open Client 4.0 is installed without the script and binary files.

9. Click **Next**.
10. Restart machine to complete installation.
11. For Windows 2003 only, register the Java Viewer MIME type.
 - a. In IIS Manager, right-click on the computer name, choose Properties.
 - b. Click the MIME Types button.
 - c. Enter the extension v1, the name JavaViewer, and click OK.

Install the Process Connectivity Bundle

Install the Process Connectivity Bundle using the procedure [Installing the Process Connectivity Bundle](#) posted on the CSS web site.

Install Open Client with Process 5.1 Integration

You must install FileNet Web Services, .NET Framework, Open Client with Process Integration, and Process Java Applets and Connectivity (PJAC) 5.1.

Log on

Log on to the web server with Administrator privileges. Ensure that you use the same user account to login after each required reboot in the procedure.

Install FileNet Web Services

Install FileNet Web Services using the procedure in the FileNet Web Services Administrator's Help (skip if already installed).

Install .NET Framework

1. From the Microsoft web site, download a supported version of .NET Framework.
2. Install .NET Framework.
3. On Windows 2003, activate ASP.NET. (On Windows 2000, installing .NET activates ASP.NET.)
 - a. In Control Panel of IIS, click Add/Remove Programs->Add/Remove Window Components to open the Windows Components Wizard Dialog Box.
 - b. Double-click the Application Server option and choose the ASP.NET option.

Install Open Client with Process Integration

1. Insert the FileNet Web Services software CD in the CD-ROM drive. Exit from Setup if it starts automatically.
2. On the CD, open the \Open Client ExeZip folder, and double-click on setup.exe.
3. Click **Next**.
4. Click **Yes** to accept the license agreement.
5. Select "Anyone who uses this computer" to allow all users on this machine to administer Open Client, and then click **Next**. Select "For myself only" if you want to be the only user on this machine who can administer Open Client, and then click **Next**. This setting has no effect on web client access to Open Client and Process.
6. Accept the default installation folder, or click **Browse** to select a folder other than the default, and then click **Next**.
7. Enter the alias (IIS virtual directory) for Open Client. This becomes part of the URL used to access Open Client. For example, if you enter the alias OpenClient, the URL will be `http://<webserver>/OpenClient`.
8. Select **Complete** or **Custom** to install Open Client with Process Integration.

In case of Complete installation the source as well as the script files are copied to the destination machine

In case of Custom installation, user is prompted with two options, eProcess Integration and Development Tools. The eProcess Integration option is checked by default.

Selecting eProcess Integration option installs the Process Integration with Open Client 4.0 and copies the script and binary files to the destination folder.

Selecting the Development Tools option copies source files of Open Client 4.0 to the destination folder. Help for Developers will not be installed if Development Tools option is not selected while installing Open Client 4.0.

Selecting both the options will install script, binary and source files of both Process Integration and Open Client 4.0.

If you do not select any of the options then Open Client 4.0 is installed without the script and binary files.

9. Click **Next**.
10. Reboot the machine to complete the installation.
11. For Windows 2003 only, register the Java Viewer MIME type.
12. In IIS Manager, right-click on the computer name, and choose **Properties**.
 - a. Click the **MIME Types** button.
 - b. Enter the extension v1, the name JavaViewer, and then click **OK**.

Install Java Applets and Connectivity (PJAC)

Install PJAC 5.1 from the PJAC 5.1 CD.

The installation copies JRE 1.4.2 to the \download folder on the web server. A client workstation must have JRE 1.4.2 to run Process Java applets, and cannot have any additional version installed. If the JRE is not installed when the user starts a Process Java applet:

- For clients running Internet Explorer, the software automatically installs JRE 1.4.2.
- For clients running Netscape, the software prompts the user to install JRE 1.4.2.

Alternatively, you can install the JRE on client machines from the PJAC CD, make the JRE available to clients from a network drive, or instruct clients to download the JRE from another location. See [Open Client requirements](#) for more information on web client setup.

Add or remove Process Integration

You use the Open Client Setup program to install Process Integration and then you must also install either the 5.0 Process Connectivity Bundle or 5.1 Process Java Applets and Connectivity (PJAC). You can install Process Integration along with Open Client, or add Process Integration at a later time using Add/Remove Programs. You can also use Add/Remove Programs to uninstall Process Integration.

To add Process Integration to Open Client

1. Verify that you have Open Client and either the 5.0 Process Connectivity Bundle or 5.1 PJAC installed.
2. Select **Add/Remove Programs** from the Control Panel.
3. Select **FileNet Open Client**.
4. Click the **Change/Remove** button. The Maintenance Wizard appears.
5. Select **Modify** and follow the prompts to add Process Integration to Open Client.
6. If you have previously compiled the Open Client project without Process Integration installed, recompile the project.
7. Apply the latest Open Client and Process hot fix packs.

If you have already applied the latest Open Client hot fix pack, it is not necessary to reapply it after adding Process Integration.

To remove Process Integration from Open Client

1. Select **Add/Remove Programs** from the Control Panel.
2. Select **FileNet Open Client**.
3. Click the **Change/Remove** button. The Maintenance Wizard appears.
4. Select **Modify** and follow the prompts to remove Process Integration.
5. Optionally, uninstall PJAC using the instructions in the *Process for FileNet Image Manager Installation Guide* or [Uninstall the Process Connectivity Bundle](#).

Uninstall Open Client

We recommend that you uninstall software in the following order (reversing the order of installation):

1. Process applets and connectivity (either the 5.0 Process Connectivity Bundle or PJAC 5.1)
2. Open Client
3. FileNet Web Services

To uninstall Open Client

1. [Uninstall the 5.0 Process Connectivity Bundle](#) or uninstall PJAC 5.1 using the instructions in the *Process for FileNet Image Manager Installation Guide*.
2. Remove Process Integration for Open Client if it was installed.
3. Select **Add/Remove Programs** from the Control Panel.
4. Select **FileNet Open Client**.
5. Click the **Change/Remove** button. The Maintenance Wizard appears.
6. Select **Remove** and follow the prompts to uninstall Open Client.

NOTE If an error occurs telling you that the Open Client folder can't be deleted, reboot the server and go back to step 3.

7. Remove FileNet Web Services using the procedure in the FileNet Web Services Administrator's Help.
8. Optionally, remove the ODBC Data Sources if you will not use them to access CS libraries after the installation.

Note

The Uninstall Wizard removes all Open Client components but does not remove the Java Runtime Environment (JRE). You can uninstall the JRE using Add/Remove from the Control Panel.

About Open Client configuration

Open Client configuration consists of:

- Using IDM Configure to set the FileNet Web Services site preferences that apply to Open Client. These preferences are stored in the registry.
- Setting additional preferences for Open Client. These preferences are stored in SitePreferences.xml, which resides in the \Preferences subdirectory of the Open Client installation directory (by default, C:\FileNet\IDM\Web\FNOpenClient).
- Optionally, using FileNet Neighborhood to define the property columns that appear in Open Client.
- Modifying the web.config file, which resides in the Open Client installation directory, to [set the maximum size of a file you can add to a library](#).
- Modifying the machine.config file, a Microsoft .NET Framework configuration file, which resides in the .NET Framework installation directory.

Open Client users see all libraries configured for FileNet Web Services. All other preference settings are optional. Preferences and other configuration settings apply to all users who access the Open Client site.

See the FileNet Web Services Administrator's Help for information on adding libraries and setting preferences.

Authentications options

FileNet Web Services and Open Client support the same authentication methods: default logon, unified logon, and LDAP logon. For details and procedures related to authentication:

- See the topic "Authentication options" in the FileNet Web Services Administrator's Help.
- See the topic "About Authentication" in the IIS 5.0 Help.

To logon in any of the libraries in Open Client using unified logon, you need to perform following additional steps:

1. Open **machine.config** file from <OS install drive>:\WINNT\Microsoft.NET\Framework\v1.1.4322\CONFIG folder in any text editor.
2. Search for **<processModel** tag and modify the value of **userName** attribute from "machine" to "SYSTEM".
3. Save the **machine.config** file.
4. Click **Start ->Run**.
5. Type **iisreset /restart** in the **Run** dialog box and click **OK**.
6. Open <OS install drive>:\WINNT\Microsoft.NET\Framework\v1.1.4322\Temporary ASP.NET Files folder.

Note: The Temporary ASP.NET Files folder includes a folder with the same name as of the Open Client virtual directory.

7. Delete the folder named with your virtual directory.
8. Open <OS install drive>:\WINNT\Microsoft.NET\Framework\v1.1.4322 folder.
9. Select and right click **Temporary ASP.NET Files** and select **Properties** from shortcut menu.
10. From the **Security** tab add the domain user(s) for which unified logon needs to be enabled.

Note: Skipping this step might lead to "Access denied..." error.

11. For each added user, make sure that all check boxes except **Full Control** under **Allow** column are selected.
12. Click **Apply** and **OK**.

Configure the folder view

You can configure the folder view visible to Open Client users by specifying the number of rows or columns that are displayed.

To set the number of rows displayed

1. From a text or XML editor, open the SitePreferences.xml file, located in the Preferences subdirectory of your Open Client installation directory.
2. Locate the following XML section and replace the parameter, shown in boldface in the example below, with the new value:

```
<setting name="NumberOfRows"
  label="Number of Rows"
  description="Number of Rows">
  <value default="10" type="integer">7</value>
  <uiType>TextBox</uiType>
  <minimum>1</minimum>
  <maximum>30</maximum>
  <visible>true</visible>
</setting>
```

To set the number of columns displayed

1. From a text or XML editor, open the SitePreferences.xml file, located in the Preferences subdirectory of your Open Client installation directory.
2. Locate the following XML section and replace the parameter, shown in boldface in the example below, with the new parameter:

```
<setting name="NumberOfColumns"
  label="Number Of Columns"
  description="Number of columns">
  <value default="10" type="integer">4</value>
  <uiType>TextBox</uiType>
  <minimum>1</minimum>
  <maximum>30</maximum>
  <visible>true</visible>
</setting>
```

Set up searches for Open Client users

By default, a predefined search, called Simple Search, is available to FileNet Web Services and Open Client users. As the administrator, you can modify or delete Simple Search and create additional searches using the IDM Find application, which is installed on the web server with FileNet Web Services. See "Save a stored search" and "Save a search template" in the IDM Desktop User's Help for information on creating and saving searches using IDM Find. Go to Start>Programs>FileNet IDM to start IDM Find and the IDM Desktop User's Help.

A search appears on Open Client's Search page when it is saved in a particular folder in the local search path on the web server. The default local search path for Open Client is the installation folder, C:\FileNet\IDM or equivalent. Searches stored in this path are available to users of both Open Client and FileNet Web Services. See "Create stored searches and search templates" in the FileNet Web Services Administrator's Help for information on making searches available to FileNet Web Services Clients. You can share searches with FileNet Web Services clients by using the default local search path or you can [set an Open Client site preference to establish a different local search path for Open Client searches](#).

When you add a library, IDM Configure creates an \IS or \CS folder, if the folder doesn't already exist, and a folder for the library.

Folder path and name	Contains searches available to users while logged on to...
<local search path>\IS	Any IS library
<local search path>\CS	Any CS library
<local search path>\IS\Default IMS <IS library> FileNet	<IS library>
<local search path>\CS\<CS library> <host>	<CS library>

For example, if you install both FileNet Web Services and Open Client to the default locations, then add an IS library CorpIS and a CS library CorpCS, IDM Configure creates the folders listed below:

- C:\FileNet\IDM\IS
- C:\FileNet\IDM\IS\DefaultIMS CorpIS FileNet
- C:\FileNet\IDM\CS
- C:\FileNet\IDM\IS\CorpCS <host server>

If you change the default search path for Open Client, you will have to create these folders in that path.

The colons that normally separate the three parts of an IS library's name are replaced in the folder name by spaces. Similarly, the caret (^) that typically separates the two parts of a CS library's name are replaced in the folder name by a space, as in CorpCS LibServer.

Enable adding large documents

By default, four megabytes is the largest file that a user can add to a library. To allow users to add documents larger than four megabytes, you can specify another maximum size, up to two gigabytes.

To enable adding large documents

1. Open the web.config file, which is located in the Open Client installation directory, in a text or XML editor.
2. In the <system.web> section, add a line with a maxRequestLength value to override the default, and save the file. For example, to allow files up to eight megabytes, add the following line:

```
<httpRuntime maxRequestLength="8192" />
```

For more information see <http://support.microsoft.com/default.aspx?scid=kb;en-us;Q295626>.

Set memory limit

If the ASPNET_WP process restarts due to heavy usage, you can change the memory limit to extend the longevity of the process. The memory limit specifies the maximum memory size, as a percentage of total system memory that a process can consume before ASP.NET launches a new process and reassigns existing requests. By default, this parameter is set to 60%. This means that once the web server uses 60% of the physical memory, the ASPNET_WP process restarts with more available memory. If you increase the memory limit, the recommended maximum value is 80%.

To set the memory limit

1. From a text or XML editor, open the machine.config file, which is located in .NET Framework installation directory.
2. Locate the <processModel> section and change the memory limit value, shown in boldface in the example below, with a new value:

```
<processModel enable="true"
  timeout="Infinite" idleTimeout="Infinite"
  shutdownTimeout="0:00:05"
  requestLimit="Infinite" requestQueueLimit="5000"
  restartQueueLimit="10" memoryLimit="60"
  webGarden="false"
  cpuMask="0xffffffff" userName="machine"
  password="AutoGenerate"
  logLevel="Errors" clientConnectedCheck="0:00:05"
  comAuthenticationLevel="Connect"
  comImpersonationLevel="Impersonate"
  responseRestartDeadlockInterval="00:09:00"
  responseDeadlockInterval="00:03:00"
  maxWorkerThreads="25" maxIoThreads="25" />
```

Terminal Services

Users can access Open Client and the Java Viewer via Microsoft Terminal Services. Users cannot run the IDM Viewer via Terminal Services nor can they use FileNet Web Services Application Integration. For a more detailed discussion, ask your FileNet representative for the Technical Brief titled "FileNet Open Client Support of Microsoft Windows Terminal Services" (available on FileNet's internal eXtra site).

To run the Java Viewer via Terminal Services, the site administrator must add the following code to the FnOpenClient project and recompile. Failure to make these changes can lead to Java Viewer image and annotation cache contention.

To modify code to use Java Viewer via Terminal Services

1. In the second JavaScript block of the **FnJavaViewHelper.js** page add the following Java script:

```
strDocWrite+='<param name="CachePath" value="<%=getCachePath()%>">';
```

2. In the FnJavaView class of the **fnjavaview.aspx.vb** file, add the following function. Please note that the aCachePath string value can contain a directory path of the administrator's choosing. The current user's login name is appended to the end of this directory path so that it has a unique value for each user.

```
' Public Function getCachePath()  
  
' Purpose: Gets a cache path name to use as the alternate Java Viewer cache  
path. Note the following:  
  
    -A forward slash must be used for directory separators.  
  
    -The ' cachePath parameter is recognized only on Windows  
platforms.  
  
' Parameters: None  
  
' Throws: None  
  
Public Function getCachePath() As String  
  
Dim aCachePath As String  
  
aCachePath = "c:/CACHE_DIRECTORY_STRUTURE_OF_CHOICE_HERE/" + getUserId()  
  
Return aCachePath  
  
End Function
```

Configure viewers

Open Client installation makes both the IDM Viewer and the Java Viewer available in the client interface by default. You can:

- Enable or disable the Java Viewer
- Configure the Java Viewer Magnifier to remain open
- Enable or disable the IDM Viewer

Enable or disable viewers

When Open Client is installed, both the IDM Viewer and Java Viewer are available in the client interface by default. The IDM Viewer must be manually downloaded to each client. If a user selects the IDM Viewer and it is not yet installed, download instructions are displayed.

- If you have not installed Process Integration, you can enable one or both of the viewers.
- If you have installed Process Integration, you can use only one viewer. If both viewers are enabled in the preferences file, Java applets use the IDM Viewer.

Note: You must restart the Open Client application for this change to go into effect. Also, client users will not see the change until they start a new browser session.

To enable or disable a viewer

1. From a text or XML editor, open the SitePreferences.xml file, located in the Preferences subdirectory of your Open Client installation directory.
2. Locate the parameter value, shown in boldface in the example below, for the viewer you want to enable or disable, and change it to "False" to disable or "True" to enable:

```
<subsystem name="Viewing" label="Viewing"
  description="Viewing"
  visible="true">
  <category name="IDMViewer" label=" IDM Viewer"
    description="IDM Viewer"
    visible="true">
    <setting name="IsEnabled"
      label="Is IDM Viewer enabled"
      description="Is IDM Viewer enabled">
      <value default="True" type="string">True</value>
      <options>
        <option label="True">True</option>
        <option label="False">False</option>
      </options>
      <uiType>DropDownList</uiType>
      <minimum>
      </minimum>
      <maximum>
      </maximum>
      <visible>true</visible>
    </setting>
  </category>
  <category name="JavaViewer"
    label=" Java Viewer"
    description="Java Viewer" visible="true">
    <setting name="IsEnabled"
      label="Is Java Viewer enabled"
      description="Is Java Viewer enabled">
      <value default="True" type="string">True</value>
      <options>
        <option label="True">True</option>
        <option label="False">False</option>
      </options>
      <uiType>DropDownList</uiType>
      <minimum>
      </minimum>
      <maximum>
      </maximum>
```

```
        <visible>true</visible>
    </setting>
</category>
</subsystem>
```


Configure the Java Viewer Magnifier

You can configure the Java Viewer Magnifier to:

1. Open in a window external to the document window
2. Remain open when additional documents are opened

To configure the Magnifier to open in an external window

1. Open the **FnJavaViewHelper.js** file.
2. Add the following line in the section where JavaScript document calls are made:

```
strDocWrite+='<param name="externalMagnifier" value="true">';
```

The default mode is "false". In the default mode, the Magnifier window appears within the display area when a user clicks the Magnifier button.

To configure the Magnifier to remain open

1. Open the **FnJavaViewHelper.js** file.
2. Add the following line in the section where JavaScript document calls are made:

```
strDocWrite+='<param name="magnifierPersistent" value="true">';
```

When this parameter is set to "true", the Magnifier window reappears in its last form (same size, position, and magnitude) when the user opens a new document. The default mode is "false," which hides the Magnifier window when the user opens a new document, requiring the user to manually display it each time. If users repeatedly magnify the same image area in a set of documents, set this parameter to "true" to keep the Magnifier window open while paging through images.

Configure the Java Viewer File Options

You can configure the Java Viewer right-click File Options to appear:

1. enabled, or
2. disabled

To enable the File options

1. Open the **FnJavaViewHelper.js** file.
2. Add the following line in the section where JavaScript document calls are made:

```
strDocWrite+='<param name="fileMenuOpen" value="true">';
```

The default mode is "true". In the default mode, the File options, Open File and Open URL, appear enabled for users.

To disable the File options

1. Open the **FnJavaViewHelper.js** file.
2. Add the following line in the section where JavaScript document calls are made:

```
strDocWrite+='<param name="fileMenuOpen" value="false">';
```

The default mode is "true". If you set it to "false", the Open File and Open URL functions under the File option will appear disabled for users.

Configure the Java Viewer Quick Start Feature

You can configure the Quick Start feature so that it appears as a menu option in the Preferences context menu in Java Viewer. Following are the steps to configure the Quick Start feature:

To enable the Quick Start feature

1. Check the availability of the **quickstart.htm** file in the `..\FileNet\IDM\Web\FNOpenClient\FNJavaV1` files folder.
2. Navigate to the `..\FileNet\IDM\Web\FNOpenClient\Util\JS` folder.
3. Open the **FnJavaViewHelper.js** file.
4. Add the highlighted code line to the file as shown in the code segment below.

```
function renderAppletPlugin()  
{  
  
    strDocWrite='<applet CODEBASE="'+ jViewerPath + '"';  
    strDocWrite+=archiveTag;  
    strDocWrite+='CODE="ji.applet.jiApplet.class" NAME="viewONE" ID="viewONE";  
    ..  
    ..  
    ..  
    strDocWrite+='<param name="quickstartURL" value="quickstart.htm">';  
    ..  
    ..  
    ..  
    strDocWrite+='</applet>';  
    document.write(strDocWrite);  
  
}
```

5. Save and close the file.

Enabling the Quick Start feature will add an icon within the System tray (bottom right of the Windows Desktop) and a menu item “FileNet JavaView QuickStart for Internet Explorer” under Start->Programs->Startup menu on the client desktop. After enabling Quick Start, if the machine is rebooted, the Quick Start feature remains enabled. Disabling the Quick Start feature will remove the Quick Start icon from the System tray and the menu item “FileNet JavaView QuickStart for Internet Explorer” from the Start->Programs->Startup menu.

For information regarding the known issues related to Java Viewer Quick Start feature, refer to [Release Notes Open Client 4.0.1](#) under *Product Documentation* on the CSS Website.

Set up Process

After installing Process for Open Client, you must complete the following tasks to enable Process activity:

- Start Process Services on the workflow server if it is not already running. For more information, see "Starting and stopping Process Service" in the Help for Task Manager.
- Start the Pooled Process Manager (PPM) on the Process Engine. For more information, see "About the Pooled Process Manager (PPM)" in the Help for PPM Administrators.
- Start one or more routers on the web server. For more information, see "About the Process Router" in the Help for Task Manager.
- For each router you started, initialize the corresponding isolated region. For more information, see "Initialize an isolated region" in the Help for Process Configuration Console.

The Process preferences allow you to:

- Specify the milestone level visible to workflow participants
- Designate the default router that users access when logging in to the workflow server
- Designate the default RMI port on which routers run
- Make routers running on additional RMI ports available to users at workflow server login

In addition, you can use various configuration options within Process to customize your Process application. For example, you can set up email notification of workflow activity or enable automatic workflow launching. For details see "About Configuration" in Help for Process Administrators. You can also create work queues to hold work that can be completed by one of multiple users rather than by a specific user. See "Configuring work and user queues" in Help for Process Configuration Console for details.

Be sure to also set the Documentation server preference to enable access to the Help for Process.

eForms integration

eForms is an optional add-on to FileNet Web Services. Installation of eForms creates a new Open Client preference "IS EFORMS INSTALLED" in the new eForms preference subsystem.

- When the preference is set to True (the default when installed), Open Client opens eForms documents in the eForms application.
- When the preference is set to False, eForms documents open in the workstation's registered application for XML files. Typically, opening an XML file displays raw XML in the browser.

Uninstalling the eForms software removes the preference.

Configure System Manager Listener

The Listener can be configured using the PchConfig.properties configuration file. This file is available in the IDM installation directory. The Listener provides default values for all its configuration parameters. If you wish to override these defaults, then you can edit the configuration file that will be read when the Listener object is instantiated. The default port used by a Listener is 32775. For cases where only few ports are enabled for communication, a different port for the Listener can be assigned using the configuration file. In addition, if more than one Listener-enabled applications are running on the same computer, only the first one of them, called the primary Listener, will be able to bind successfully to that particular port. Any secondary Listeners will fail to get that port, in which case, they shall bind to a different port, then contact the primary Listener and inform it of the port they have chosen. You can configure this secondary Listener using the secondary_port parameter in the configuration file.

There are four possible properties that can be configured using this file, listed in the following table:

Property Name	Default	Description
port_number	32775	The primary TCP port number on which the Listener will listen for connections from Managers. It would require changing if another service is already using this port.
secondary_port	OS defined	The first Listener on a host will acquire the Listener port (defined by port_number); others will by default bind to OS-defined ports. If this configuration parameter is specified, then secondary Listeners will instead try this port number, then that plus 1, plus 2, and so on, until they successfully bind to a port.
output_interval	900	Specifies the aggregation interval in seconds.
output_count	96	Specifies the maximum number of summary blocks that will be written to the summary log before it is closed and a new one opened. The default configuration provides for 24 hours' worth of data to be written to a single file, and so between 24 and 48 hours' history will be available at any given time.

To set the System Manager Integration Listener properties

1. From a text editor, open the **PchConfig.properties** file, located in the **..\FileNet\IDM** installation directory.
2. Replace the parameter(s) as shown in boldface in the example below, with the new value:

```
port_number=32775
secondary_port=
output_interval=900
output_count=96
```

Note

To view the data captured by FileNet System Manager Listener, you need to install and configure the FileNet System Manager Dashboard monitoring tool. For information regarding installing and configuring the FileNet System Manager Dashboard tool, refer to FileNet System Manager Dashboard help.

Set site preferences

You can set site preferences in two ways:

- Some [FileNet Web Services preferences](#) affect Open Client. You can set these using the IDM Configure application on the web server.
- Additional Open Client preferences can be set by editing SitePreferences.xml that resides in the \Preferences subfolder of the Open Client installation directory.

In the SitePreferences.xml file and in this Help system, Open Client preferences are organized into subsystems and categories as shown in the reference table below. Preference changes take effect after restarting the Open Client application.

Subsystems	Categories	Preferences	Values
General	Search	Local search path	Path
		Execute stored search on open	Yes or No
	Security	Change expired IS password	Yes or No
		Default web mode	Browse or Search
	Cache Management	Cache duration	0 to 60 minutes
		Enable folder content caching	True or False
	System Manager	System Manager Integration	Yes or No
User Interface	Folder View Settings	Number of rows	1 to 30
		Number of columns	1 to 30
	List View Settings	Deselect on page change	Yes or No
		Number of rows	Yes or No
Documents	Properties	Clear custom properties on document class change	Yes or No
		Maximum number of CVL elements to retrieve	1 to 7500
	List View Settings	Display ID column	Yes or No
		Display configured columns	Yes or No
	Add Checkin Wizard	Show Index Content	Yes or No

Process	Toolbar Settings	Index Content	Use Library Default	
		Set document title to file name	Yes or No	
	Email Preferences	Delayed toolbar status check	Yes or No	
		Use page1 extension	Yes or No	
		Search registry	Yes or No	
	General	Default file extension	String	
		Milestone level	1 to 99	
		Update queue after processing step	Yes or No	
		User list cache refresh rate	0-999	
	Routers	Display exposed data fields	Yes or No	
JRE Setup		Default router name	Name of a router	
	Port numbers	Router port numbers		
	JRE Version	True or False JRE version 1.4.0 must be specified for Process 5.0, and JRE version 1.4.2 for Process 5.1. Default is 1.4.2.		
Viewing	IDM Viewer	JRE Executable	Filename of JRE executable. Default is j2re-1_4_2-windows-i586.exe.	
		Java Viewer	Is IDM Viewer enabled	Yes or No
	Is Java Viewer enabled		Yes or No	
	Digital Signature		Document Class Name	
	Native Application	Print View option	View Only, Print Only, and Print/View	
		Use Print View option	Yes or No	
		Auto save annotations	Yes or No	
		Send Visio files as attachment	Yes or No	
	Documentation	Documentation Server		
			Documentation Server	URL
eForms	eForms			
		Is eForms installed	Yes or No	

Supported FileNet Web Services preferences

The following FileNet Web Services preferences apply to Open Client. For a description of each of these preferences, see the Preference Guide in the FileNet Web Services Administrator's Help.

Add, check in, retrieve

- Checksum new IS document
- Checksum retrieved IS documents
- Use server notification for IS document migration
- IS document migration timeout (seconds)

Local caching

- Cache directory
- Maximum cache size (MB)
- Maximum cached documents (K)
- Configure NT credentials for cache

Prefetching

- Prefetch to server cache

LDAP settings

- Enable LDAP for the whole website
- Server name
- Distinguished name/User principal name
- Port number
- Server type

IS libraries

- Service
- System type
- Use operating system credentials for login
- Alternate IS page cache

CS libraries

- Service
- System type
- Use operating system credentials for login
- Active requests per user
- Active requests per guest
- Guest user name

- Enable timeouts
- Active request timeout
- Inactive session timeout
- Inactive user timeout
- Enable direct document access

Set Open Client site preferences

To set Open Client site preferences, edit SitePreferences.xml. The file resides in the Preferences folder in the Open Client installation directory.

General site preferences

General site preferences allow you to set the local search path.

Search

Local search path

Preference	Local search path
Description	Defines the main directory for local searches.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the LocalSearchPath value.
Applies to	Open Client
Possible values	Any valid path. Default is C:\FileNet\IDM.
API	No
Exportable	No

To change the default search path

1. Open the SitePreferences.xml file in a text or XML editor.
2. Locate the following XML section and replace the path, shown in boldface in the example below, with the new local search path:

```
<category name="Search"
  label="Search"
  description="Search" visible="true">
  <setting name="LocalSearchPath"
    label="Local Search Path"
    description="Main directory for local searches">
    <value default="C:\FileNet\IDM"
      type="string">C:\FileNet\IDM</value>
    <uiType>TextBox</uiType>
    <visible>true</visible>
  </setting>
</category>
```

Execute stored search on open

Preference	Execute stored search on open
Description	When set to Yes, bypasses the page with Find and Find Count buttons.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the ExecuteStoredSearchOnOpen value.
Applies to	Open Client
Possible values	Yes or No. The default is No.
API	No
Exportable	No

By default, when a user opens a stored search, the user can click Find to execute the search or click Find Count to count the number of matches that the search would find.

Security

Change expired IS password

Preference	Changed expired IS password
Description	When set to Yes, allows an IS user to change an expired password.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the OpenClientChangeExpiredPassword value.
Applies to	Open Client
Possible values	Yes or No. The default is No.
API	No
Exportable	No

Administrator must configure the Password Renewal Days settings under Default security settings in IS to allow changing of the expired password.

Login

Default web mode

Preference

Description

How to set

Applies to

Possible values

API

Exportable

Default web mode

Specifies which page, Browse or Search, users see after logging on.

In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DefaultWebMode value.

Open Client

Browse or Search. The default is Browse.

No

No

Cache Management

Cache duration

Preference	Cache duration
Description	How long to keep items in cache
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the CacheDuration value.
Applies to	Open Client
Possible values	0 to 60 minutes. The default is 5.
API	No
Exportable	No

Enable folder content caching

Preference	Enable folder content caching
Description	When set to yes, caches folder content
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the EnableFolderContentCaching value.
Applies to	Open Client
Possible values	True or False. The default is True.
API	No
Exportable	No

System Manager Integration

System Manager Integration

Preference	System Manager Integration
Description	To be used for enabling System Manager Integration in Open Client
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the SystemManagerIntegration value.
Applies to	Open Client
Possible values	Yes or No. The default is No.
API	No
Exportable	No

To change the default System Manager settings

1. Open the **SitePreferences.xml** file in a text or XML editor.
2. Locate the following XML section in the file:

```
< subsystem name = " GeneralSitePreferences " label = " General Site Preferences "
description = " Open Client Site Preferences "
```

3. Copy and paste the following code segment in the file as shown below. This will create a new category **SystemManagerIntegration** under the **GeneralSitePreferences** subsystem.

```
<category name="SystemManagerIntegration" label="System Manager Integration"
description="System Manager Integration" visible="true">
<setting name="EnableSystemManagerIntegration" label="Enable System Manager Integration"
description="Enables System Manager Integration">
<value default="No" Type="string">No</value>
<options>
<option label="Yes">Yes</option>
<option label="No">No</option>
</options>
<uiType>DropDownList</uiType>
<visible>true</visible>
</setting>
</category>
```

4. To enable the System Manager Integration, you can now change the value "No" as shown in boldface in the code segment below, with the value "Yes":

```
<category name="SystemManagerIntegration" label="System Manager Integration"
description="System Manager Integration" visible="true">
<setting name="EnableSystemManagerIntegration" label="Enable System Manager Integration"
description="Enables System Manager Integration">
<value default="No" Type="string">No</value>
<options>
<option label="Yes">Yes</option>
<option label="No">No</option>
</options>
<uiType>DropDownList</uiType>
<visible>true</visible>
</setting>
</category>
```

5. Reset IIS to apply the FileNet System Manager Integration settings.

User Interface

The user interface site preferences allow you to set the number of rows and columns visible in a folder view.

Folder View Settings

Number of rows

Preference

Description

How to set

Applies to

Possible values

API

Exportable

Number of rows

Determines the number of rows visible to users on the Folder View page.

In the <installation_directory> /Preferences/SitePreferences.xml file, edit the NumberOfRows value.

Open Client

1 to 30. The default is 7.

No

No

Number of columns

Preference

Description

How to set

Applies to

Possible values

API

Exportable

Number of columns

Determines the number of columns on the Folder View page.

In the <installation_directory> /Preferences/SitePreferences.xml file, edit the NumberOfColumns value.

Open Client

1 to 30. The default is 4.

No

No

List View Settings

Deselect on page change

Preference	Deselect on page change
Description	When set to yes, Open Client discards information associated with a selected item when a user displays a different page of a list view.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DeselectOnPageChange value.
Applies to	Open Client
Possible values	Yes or No. The default is No.
API	No
Exportable	No

By default, when a user selects a document from a list view that spans several pages, the software remembers the selection and the toolbar state (which buttons are enabled) for that document until the user makes a different selection. The user can, for example, select a document on the first page of a list view, look at other list view pages, then return to the first page without losing the selection or the toolbar state.

When this preference is set to No, the selection and the toolbar state are lost when a user goes to another page of a list view. This setting may improve performance.

Number of rows

Preference	Number of rows
Description	Determines the number of rows visible to users on the List View page.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the NumberOfRows value.
Applies to	Open Client
Possible values	1 to 30. The default is 10.
API	No
Exportable	No

Documents

The preferences in the Documents category allow you to:

- Clear custom properties on document class change
- Set the maximum number of CVL elements to retrieve
- Show or hide the document ID column in document lists
- Display the property columns configured for FileNet Web Services

Select a preference from the Contents for more information

Properties

Clear custom properties on document class change

Preference	Clear custom properties on document class change
Description	When set to yes, Open Client clears custom properties when the user selects a different document class while adding or modifying the properties of a CS document.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the ClearCustomPropertiesOnDCChanges value.
Applies to	Open Client
Possible values	Yes or No. The default is Yes.
API	No
Exportable	No

This applies to CS only.

To change the default value of Clear Custom Properties:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of ClearCustomPropertiesOnDCChanges.

```
<category name="Properties" label="Properties Settings" description="Properties
settings" visible="true">
  <setting name="ClearCustomPropertiesOnDCChanges" label="Clear custom
properties on document class change" description="Clears the custom
properties whenever the document class is changed.">
    <value default="Yes" type="string">Yes</value>
    <uiType>DropDownList</uiType>
    <options>
      <option label="Yes">Yes</option>
      <option label="No">No</option>
    </options>
    <visible>true</visible>
  </setting>
</category>
```

Maximum number of CVL elements to retrieve

Preference	Maximum number of CVL elements to retrieve
Description	Limits the number of elements retrieved for a CVL (controlled value list).
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the MaxCVLElementsRetrieval value.
Applies to	Open Client
Possible values	1 to 7500. The default is 2500.
API	No
Exportable	No

A CVL is a menu of items from which a user can select property values for a CS document. A CVL can have any number of elements. Limiting the number may improve performance. However, be aware that users get no indication that a CVL has missing elements (no "More" button appears at the end of the list).

To change the default value of Max CVL elements retrieval:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of MaxCVLElementsRetrieval.

```
<category name="Properties" label="Properties Settings" description="Properties settings" visible="true">
  <setting name="MaxCVLElementsRetrieval" label="Max CVL elements retrieval"
description="Maximum number of CVL elements to retrieve.">
    <value default="2500" type="string">2500</value>
    <uiType>TextBox</uiType>
      <minimum>1</minimum>
      <maximum>7500</maximum>
    <visible>true</visible>
  </setting>
</category>
```

Add/Check-In Wizard Settings

Show Index Content checkbox in the Add/Check-In Wizard Settings

Preference	Show Index Content checkbox in the Add/Check-in Wizard Settings.
Description	When set to yes, Open Client displays a checkbox for Index Content in the Add/Check-In Wizard settings.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the ShowIndexContent value.
Applies to	Open Client
Possible values	Yes or No. The default is Yes.
API	No
Exportable	No

This applies to CS library only.

To change the default value of Show Index Content:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of ShowIndexContent.

```
<category name="AddCheckinWizard" label="Add / Check-In Wizard Settings"
description="Add / Check-In Wizard Settings" visible="true">
  <setting name="ShowIndexContent" label="Show Index Content"
description="Show Index Content">
    <value default="No" type="string">Yes</value>
    <uiType>DropDownList</uiType>
    <options>
      <option label="Yes">Yes</option>
      <option label="No">No</option>
    </options>
    <visible>true</visible>
  </setting>
</category>
```

Index Content

Preference	Index the document for content searching.
Description	When set to Index, Open Client indexes the document for content searching.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the IndexContent value.
Applies to	Open Client
Possible values	Use Library Default, Index, Do not Index.
API	No
Exportable	No

The default value for the Index Content would be the same as library settings. Applies to CS library only.

To change the default value of Index Content:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of IndexContent.

```
<category name="AddCheckinWizard" label="Add / Check-In Wizard Settings"
description="Add / Check-In Wizard Settings" visible="true">
  <setting name="IndexContent" label="Index Content" description="Index Content">
    <value default="Use Library Default" type="string">Use Library
Default</value>
    <uiType>DropDownList</uiType>
    <options>
      <option label="Use Library Default">Use Library Default</option>
      <option label="Index">Yes</option>
      <option label="Do not index">No</option>
    </options>
    <visible>true</visible>
  </setting>
</category>
```

Set document title to file name

Preference	Set Document Title
Description	Setting this preference value to "Yes" will set the document title to the file name.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the SetDocTitleToFileName value.
Applies to	Open Client
Possible values	Yes or No. Default is No.
API	No
Exportable	No

To change the default preference value of SetDocTitleToFileName

1. Open the SitePreferences.xml file in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of SetDocTitleToFileName:

```
<category name="AddCheckinWizard"
  label="Add / Checkin Wizard"
  description="Add / Checkin Wizard" visible="true">
  <setting name="SetDocTitleToFileName"
    label="Set Document Title To FileName"
    description="Set Document Title To FileName">
    <value default="No"
      type="string">No</value>
  <uiType>DropDownList</uiType>
    <options>
      <option label="Yes">Yes</option>
      <option label="No">No</option>
    </options>
    <visible>true</visible>
  </setting>
</category>
```

List View Settings

Display additional states

Preference	Display Additional States
Description	When set to Yes, shows the additional document states such as annotated, published, external, compound document and replica in the browse and search result pages.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DisplayAdditionalStates value.
Applies to	Open Client
Possible values	Yes or No
API	No
Exportable	No

To change the default value of Display Additional States:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of DisplayAdditionalStates.

```
<category name="ListViewSettings" label="List View Settings" description="List
View Settings" visible="true">
    <setting name="DisplayAdditionalStates" label="Display Additional
States" description="Display Additional States">
        <value default="No" type="string">No</value>
        <uiType>DropDownList</uiType>
        <options>
            <option label="Yes">Yes</option>
            <option label="No">No</option>
        </options>
        <visible>true</visible>
    </setting>
</category>
```

Display ID column

Preference	Display ID column
Description	When set to Yes, shows the document ID in the first column of a list view.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DisplayIdColumn value.
Applies to	Open Client
Possible values	Yes or No
API	No
Exportable	No

Set this preference to No when you enable the Display configured columns preference to avoid displaying two ID columns.

To change the default value of Display ID Column:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of DisplayIdColumn.

```
<category name="ListViewSettings" label="List View Settings" description="List View Settings" visible="true">
  <setting name="DisplayIdColumn" label="Display ID column" description="Display ID column when Yes">
    <value default="Yes" type="string">No</value>
    <uiType>DropDownList</uiType>
    <options>
      <option label="Yes">Yes</option>
      <option label="No">No</option>
    </options>
    <visible>true</visible>
  </setting>
</category>
```

Display configured columns

Preference	Display configured columns
Description	When set to yes, displays the property columns configured for FileNet Web Services
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DisplayConfiguredColumns value.
Applies to	Open Client
Possible values	Yes or No. The default is No.
API	No
Exportable	No

The web administrator can configure property columns for each library using FileNet Neighborhood. These property columns are then displayed for FileNet Web Services clients. See the topic "Customize FileNet Neighborhood" for instructions.

The Open Client administrator can display these configured columns to Open Client users. Note the following:

- If you set this preference to Yes, set the **Display ID column** preference to No. Otherwise, the list view will show two ID columns.
- Open Client does not honor column width or alignment. Columns size themselves to accommodate the longest value and all properties are left-aligned.
- Search results shows the columns configured in the search.
- Open Client document lists do not show document state icons (annotations, checked out, etc.)
- If you set this preference to Yes, but no property columns have been configured for FileNet Web Services clients, the Open Client default columns remain in effect.

Display LDAP full name

Preference	Display LDAP Full Name
Description	Setting this preference value to "Yes" will display the LDAP full name of the user instead of User ID.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DisplayLDAPFullName value.
Applies to	Open Client
Possible values	Yes or No. Default is No.
API	No
Exportable	No

The default preference value is "No", setting it to "Yes" will display the LDAP full name instead of User ID.

To change the default value of LDAP full name:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of DisplayLDAPFullName.

```
<category name=" ListViewSettings " label=" ListViewSettings " description="
ListViewSettings ">
    <setting name="DisplayLDAPFullName" label="Display LDAP Full Name"
description="Display the LDAP Full Name when Yes">
        <value default="No" type="string">No</value>
        <uiType>DropDownList</uiType>
        <options>
            <option label="Yes">Yes</option>
            <option label="No">No</option>
        </options>
        <visible>true</visible>
    </setting>
</category>
```

Document Icon Default Action

Preference	Document Icon Default Action
Description	Sets the default action on Document Icon click.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DocumentIconDefaultAction value.
Applies to	Open Client
Possible values	Open, JavaView, and IDMView
API	No
Exportable	No

If the default value is set to Java Viewer or IDM Viewer and for any document the Java Viewer or IDM Viewer is not supported, then the document is opened in native application.

To change the default value of Document Icon Default Action:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of DocumentIconDefaultAction.

```
<category name="ListViewSettings" label="List View Settings" description="List
View Settings" visible="true">
<setting name="DefaultDocumentAction" label="Document Icon Default Action"
description="Document Icon Default Action">
  <value default="Open" type="string">Open</value>
  <uiType>DropDownList</uiType>
  <options>
    <option label="Open">Open</option>
    <option label="JavaView">JavaView</option>
    <option label="IDMView">IDMView </option>
  </options>
  <visible>true</visible>
</setting>
</category>
```

Toolbar Settings

Delayed toolbar status check

Preference	Delayed Toolbar Status Check
Description	Setting this preference value to "Yes" will delay the toolbar status check operation for performance benefits.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DelayedToolbarStatusCheck value.
Applies to	Open Client
Possible values	Yes or No. Default is Yes.
API	No
Exportable	No

To change the default preference value of DelayedToolbarStatusCheck

1. Open the SitePreferences.xml file in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of DelayedToolbarStatusCheck:

```
<subsystem name="UserInterface"
  label="User Interface"
  description="User Interface Preferences" visible="true">
  <category name="ToolbarSettings"
    label="Toolbar Settings"
    description="Toolbar Settings" visible="true">
    <setting name="DelayedToolbarStatusCheck"
      label="Delayed Toolbar Operation Status Check"
      description="Delayed Toolbar Operation Status Check">
      <value default="Yes" type="string">Yes</value>
      <uiType>DropDownList</uiType>
      <options>
        <option label="Yes">Yes</option>
        <option label="No">No</option>
      </options>
      <visible>true</visible>
    </setting>
  </category>
</subsystem>
```

Email Preferences

Use page1 extension

Preference	Use Page1 Extension
Description	When set to yes, the extension of first attached page is used as the extension for the subsequent pages attached in the mail.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the UsePage1Extension value.
Applies to	Open Client
Possible values	Yes or No. Default is No.
API	No
Exportable	No

The UsePage1Extension value when set to 'No', the default .FNI extension is used for the attached pages.

To change the default preference value of UsePage1Extension :

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of UsePage1Extension:

```
<category name =" EmailPreferences" label ="Email Preferences"
description ="IS document attachment email preferences" visible ="true">
  <setting name ="UsePage1Extension" label ="Use Page 1 Extension" description
="Use Page 1 Extension for other pages">
    <value default ="No" type ="string">No</value>
    <uiType> DropDownList </uiType>
    <options>
      <option label ="No">No</option>
      <option label ="Yes">Yes</option>
    </options>
  </setting>
</category>
```

Search registry

Preference	Search Registry
Description	When set to 'Yes', Open Client searches the registry for the file extension of the first page attached. This is done only if the F_DOCFORMAT property of the document has MIME TYPE but no file extension.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the SearchRegistry value.
Applies to	Open Client
Possible values	Yes or No. Default is No.
API	No
Exportable	No

To change the default preference value of SearchRegistry:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of SearchRegistry:

```
<category name = " EmailPreferences" label = "Email Preferences"
  description = "IS document attachment email preferences" visible = "true">
  < setting name = " SearchRegistry " label = "Search Registry" description
="Search Registry for Extension">
    <value default = "No" type = "string">No</value>
    <uiType>DropDownList</uiType>
    <options>
      <option label = "No">No</option>
      <option label = "Yes">Yes</option>
    </options>
  </setting>
</category>
```

Default file extension

Preference	Default File Extension
Description	Specifies the default file extension for page 1 when F_DOCFORMAT property does not have a file extension and no file extension is found in the registry for the specified MIME type.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DefaultFileExtension value.
Applies to	Open Client
Possible values	String
API	No
Exportable	No

To change the default preference value of DefaultFileExtension:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of DefaultFileExtension:

```
<category name =" EmailPreferences" label ="Email Preferences"
  description ="IS document attachment email preferences" visible ="true">
  <setting name ="DefaultFileExtension" label ="Default File Extension"
description ="Default File Extension">
    <value default ="FNI" type ="string">FNI</value>
    <uiType>TextBox</uiType>
  </setting>
</category>
```

Process

Using the Process preferences, you can set the milestone level, specify a default Process router, enter available RMI port numbers for Process routers, and specify the default RMI port. Be sure to also set the Documentation server preference to enable access to the Help for Process.

General

Milestone level

Preference	Milestone level
Description	Using the Milestone Level preference, you can set the maximum milestone level to display in open work items and in launched workflows. For example, if the site preference is set to 5, reached milestones of levels 1, 2, 3, 4, and 5 will be visible.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the Milestone Level value.
Applies to	Process
Possible values	1-99 Default value: 1
API	No
Exportable	No

Using the Milestone Level preference, you can set the maximum milestone level to display in open work items and in launched workflows. For example, if the site preference is set to 5, reached milestones of levels 1, 2, 3, 4, and 5 will be visible. Acceptable values are between 1 and 99.

To set the milestone level

1. From a text or XML editor, open the SitePreferences.xml file, located in the Preferences subdirectory of your Open Client installation directory.
2. Locate the following XML section and replace the milestone value, shown in boldface in the example below, with the new value:

```
<setting name="MilestoneLevel" label="Milestone Level"
  description="Maximum milestone level to display">
  <value default="1" type="string">1</value>
  <uiType>TextBox</uiType>
  <minimum>1</minimum>
  <maximum>99</maximum>
  <visible>true</visible>
</setting>
```

Update queue after processing step

Preference	Update queue after processing step
Description	When set to Yes, updates the workflow queue after each processing step.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the UpdateQueueAfterProcessingStep value.
Applies to	Open Client
Possible values	Yes or No.
API	No
Exportable	No

You might improve performance by disabling automatic queue updates. After you disable automatic queue updates, only the actions listed in the table below will update the queue:

Queue	Actions that update the queue
Inbox	Complete, Reassign, or Return
Tracker	Delete
Work queue	Complete, Reassign, Move to Inbox

User list cache refresh rate

Preference	User list cache refresh rate
Description	Sets the interval between refreshes of the Process user cache
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the UserListCacheRefreshRate value.
Applies to	Open Client
Possible values	0-999, 10 is the default, 0 disables refreshing
API	No
Exportable	No

Set this preference to a nonzero value to refresh the cache of Process users without restarting the web server.

Display exposed data fields

Preference	Display Exposed Data Fields
Description	Setting this preference value to "Yes" will trigger the Inbox of User Queues and Public Work Queues to display the exposed data fields. You can configure the exposed data fields from the Results Option tab of the Filter control only if the preference value is set to "Yes".
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DisplayExposedDataFields value.
Applies to	Process
Possible values	Yes or No. Default is No.
API	No
Exportable	No

To set the value for display exposed data fields:

1. Open the SitePreferences.xml file, located in the Preferences subdirectory of your Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of DisplayExposedDataFields:

```
<category name="General"
  label="General" description="General">
  <Setting name="DisplayExposedDataFields"
    label="Display Exposed Data Fields"
    description = "Triggers the inbox user queues and public work
queues to display the exposed data fields.">
    <Value default="No" type="string">No</value>
    <Options>
      <Option label="Yes">Yes</option>
      <Option label="No">No</option>
    </options>
    <uiType>DropDownList</uiType>
    <visible>true</visible>
  </setting>
</category>
```

Routers

Default router name

Preference	Default router name
Description	Defines the default router to use when logging in to the workflow server.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit Default Router Name value.
Applies to	Process
Possible values	Any valid server name Default value: vwrouter
API	No
Exportable	No

You can specify the default router to use when logging in to the workflow server. When the Open Client is installed, the default router name is "vwrouter."

To set the default router name

1. From a text or XML editor, open the SitePreferences.xml file, located in the Preferences subdirectory of your Open Client installation directory.
2. Locate the following XML section and replace the default router name, shown in boldface in the example below, with the new default router name:

```
<category name="Routers"
  label="Routers"
  description="eProcess routers" visible="true">
  <setting name="DefaultRouterName"
    label="Default Router Name"
    description="Router name to use as default">
    <value default="vwrouter"
      type="string">vwrouter</value>
    <uiType>TextBox</uiType>
    <visible>true</visible>
  </setting>
  <setting name="Ports"
    label="Port Numbers"
    description="List of router port numbers">
    <value default="1099" type="integer">1099</value>
    <options>
      <option label="1099">1099</option>
    </options>
    <uiType>DropDownList</uiType>
    <visible>true</visible>
  </setting>
</category>
```

Port numbers

Preference	Port numbers
Description	The default port and the ports on which Process RMI routers run
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the Port Numbers value.
Applies to	Process
Possible values	Any valid port number above 1024 Default value: 1099
API	No
Exportable	No

Typically, use 1099 for Process 5.0 and 32771 for Process 5.1.

To set the default RMI port

1. From a text or XML editor, open the SitePreferences.xml file, which is located in the Preferences subdirectory of your Open Client installation directory.
2. Locate the following XML section and change the port number, shown in boldface in the example below, to the desired port number. Note that the number must be greater than 1024.

```
<category name="Routers"
  label="Routers"
  description="eProcess routers" visible="true">
  <setting name="DefaultRouterName"
    label="Default Router Name"
    description="Router name to use as default">
    <value default="vwrouter" type="string">vwrouter</value>
    <uiType>TextBox</uiType>
    <visible>true</visible>
  </setting>
  <setting name="Ports"
    label="Port Numbers"
    description="List of router port numbers">
    <value default="1099" type="integer">1099</value>
    <options>
      <option label="1099">1099</option>
    </options>
    <uiType>DropDownList</uiType>
    <visible>true</visible>
  </setting>
</category>
```

To add RMI ports

1. From a text or XML editor, open the SitePreferences.xml file, located in the Preferences subdirectory of your Open Client installation directory.
2. Locate the following XML section. For each port you want to add:
 - Duplicate the boldface line and paste the copy between the boldface line and the </options> line.
 - In the copy, change both occurrences of the port number to the desired number. Note that the number must be greater than 1024. In the example below, the red text adds port 3277.

```
<Category name="Routers"
  label="Routers"
  description="eProcess routers" visible="true">
```

```

<setting name="DefaultRouterName"
  label="Default Router Name"
  description="Router name to use as default">
  <value default="vwrouter" type="string">vwrouter</value>
  <uiType>TextBox</uiType>
  <visible>true</visible>
</setting>
<setting name="Ports"
  label="Port Numbers"
  description="List of router port numbers">
  <value default="1099" type="integer">1099</value>
  <options>
    <option label="1099">1099</option>
    <option label="3277">3277</option>
  </options>
  <uiType>DropDownList</uiType>
  <visible>true</visible>
</setting>
</category>

```

Note

The list of RMI ports should only include ports on which you run routers for this web application. To remove a port, delete its line in the options list. Be sure the designated default port is in the list.

JRE Setup

JRE Version

Preference	JRE Version
Description	Enables you to set the current installed JRE version according to the Process connectivity.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the JREVersion value.
Applies to	Process
Possible values	JRE version 1.4.0 must be specified for Process 5.0, and JRE version 1.4.2 for Process 5.1. Default is 1.4.2.
API	No
Exportable	No

To set the value for JRE Version:

1. Open the SitePreferences.xml file, located in the Preferences subdirectory of your Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of JREVersion:

```
<category name="JRESetup" label="JRE Setup" description="eProcess JRE Setup"
visible="true">
<setting name="JREVersion" label="JRE Version" description="eProcess JRE Version">
<value default="1.4.2" type="string">1.4.2</value>
    <uiType>TextBox</uiType>
<visible>true</visible>
</setting>
</category>
```

JRE Executable

Preference	JRE Executable
Description	Enables you to set the executable file for JRE.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the JREexecutable value.
Applies to	Process
Possible values	Filename of JRE executable. Default is j2re-1_4_2-windows-i586.exe.
API	No
Exportable	No

To set the value for JRE executable:

1. Open the SitePreferences.xml file, located in the Preferences subdirectory of your Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of JREexecutable:

```
<category name="JRESetup" label="JRE Setup" description="eProcess JRE Setup"
visible="true">
  <setting name="JREexecutable" label="JRE Executable" description="eProcess
JRE Executable">
    <value default="j2re-1_4_2-windows-i586.exe" type="string">j2re-1_4_2-
windows-i586.exe</value>
    <uiType>TextBox</uiType>
    <visible>true</visible>
  </setting>
</category>
```


Viewing

The Viewer preferences allow you to choose which viewers are available to Open Client users and, if Process is installed, which viewer is available on Java step processor pages. When Open Client is installed, both the IDM Viewer and Java Viewer are enabled by default.

Note: Only one viewer can be available in the Java step processor, even if both viewers are enabled. If Process is installed, see [Is Java Viewer enabled](#) for further details on which viewer is available to Java step processor users.

IDM Viewer

Is IDM Viewer enabled

Preference

Description

Is IDM Viewer enabled

Defines whether the IDM Viewer is available to users. The IDM Viewer must be manually downloaded to each client. If a user selects the IDM Viewer without installing it first, download instructions are displayed.

How to set

In the <installation_directory> /Preferences/SitePreferences.xml file, edit the Is IDM Viewer Enabled value.

Applies to

Open Client

Possible values

True or False. The default is True.

API

No

Exportable

No

Java Viewer

Is Java Viewer enabled

Preference	Is Java Viewer enabled
Description	Defines whether the Java View is available to users.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the Is Java Viewer Enabled value.
Applies to	Open Client
Possible values	True or False. The default is True.
API	No
Exportable	No

Note

If Process is installed and a user opens a viewer from within the Java step processor, the Java Viewer is used only if this preference is set to "True" and the "Is IDM Viewer enabled" preference is set to "False". If both viewer preferences are set to "True", the IDM Viewer is used.

Digital signatures

Preference	Digital signatures
Description	Setting this preference defines the document class name for Digital Signature to be used as an Image Stamp.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the DigitalSignatures value.
Applies to	Open Client
Possible values	Document Class Name
API	No
Exportable	No

To set the value for DigitalSignatures:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor, .
2. Locate the following XML section and replace the value (appears in bold below) of DigitalSignatures:

```
<category name="JavaViewer" label="Java Viewer" description="Java Viewer"
visible="true">
    <setting name ="DigitalSignatures" label ="Digital Signatures"
        description ="Doc Class For Digital Signatures">
        <value default ="DigitalSignatures" type ="string"> DigitalSignatures
</value>
        <uiType>
            DropDownList
        </uiType>
        <visible>
            true
        </visible>
    </setting>
</category>
```

Print View Option

Preference	Print View Option
Description	Print View Option enables a user to set the View Only, Print Only, or Print/View option for the sticky note annotations. Setting this preference will specify the print/view value.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the PrintViewOption value.
Applies to	Open Client
Possible values	View Only, Print Only, and Print/View. Default is Print/View.
API	No
Exportable	No

To set the value for PrintViewOption:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of PrintViewOption:

```
<category name="JavaViewer" label="Java Viewer" description="Java Viewer"
visible="true">
    <setting name="PrintViewOption" label="Print View Option"
description="Print View Option For Sticky Note Anotations">
        <value default="3" type="integer">3</value>
        <options>
            <option label="View Only">1</option>
            <option label="Print Only">2</option>
            <option label="Print/View">3</option>
        </options>
        <uiType>DropDownList</uiType>
        <visible>true</visible>
    </setting>
</category>
```

Use Print View Option

Preference	Use Print View Option
Description	This preference allows you to enable or disable the Print View Option.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the UsePrintViewOption value.
Applies to	Sticky Notes
Possible values	Yes or No. Default is No.
API	No
Exportable	No

To set the value for UsePrintViewOption:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of UsePrintViewOption:

```
<category name="JavaViewer" label="Java Viewer" description="Java Viewer"
visible="true">
  <setting name="UsePrintViewOption" label="Use Print View Option"
description="Use Print View Option">
    <value default="No" type="String">Yes</value>
    <options>
      <option label="No">No</option>
      <option label="Yes">Yes</option>
    </options>
    <uiType>DropDownList</uiType>
    <visible>true</visible>
  </setting>
</category>
```


Auto save annotations

Preference

Auto save annotations

Description

Determines whether annotations are saved or discarded if a user closes the JavaView window before saving annotations. If set to yes, automatically saves annotations. If set to no, discards annotations.

How to set

In the <installation_directory> /Preferences/SitePreferences.xml file, edit the AutoSaveAnnotations value.

Applies to

JavaView users with a JRE Java environment only. JavaView users with a JVM Java environment are prompted to save or discard annotations when closing the JavaView window.

Possible values

Yes or No. The default is No.

API

No

Exportable

No

Native Application

Send Visio files as attachment

Preference	Send Visio Files as Attachment
Description	When set to Yes, MS Visio files are sent as attachment and opens in a separate MS Visio application.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the SendVisioFilesAsAttachment.
Applies to	Open Client
Possible values	Yes or No. Default is No.
API	No
Exportable	No

You need to change the default value, only when MS Visio 2002 is installed.

To change the default value of SendVisioFilesAsAttachment:

1. Open the SitePreferences.xml file, located under the Preferences sub directory of the Open Client installation directory, in a text or XML editor.
2. Locate the following XML section and replace the value (appears in bold below) of SendVisioFilesAsAttachment.

```
<category name="NativeApplication" label="Native Application"
description="Native Application">
  <setting name="SendVisioFilesAsAttachment" label="Send Visio Files As
Attachment" description="Send Visio Files As Attachment">
    <value default="No" type="string">No</value>
    <options>
      <option label="Yes">Yes</option>
      <option label="No">No</option>
    </options>
    <uiType>DropDownList</uiType>
    <visible>true</visible>
  </setting>
</category>
```

Documentation

Documentation server

Preference	Documentation server
Description	Identifies the documentation server for Process Help.
How to set	In the <installation_directory> /Preferences/SitePreferences.xml file, edit the ServerURL value.
Applies to	Open Client with 5.1 Process Integration
Possible values	The value consists of a server name, a forward slash, and a site name (for example, "docserver/ProcessHelp").
API	No
Exportable	No

Process documentation is installed as a web site and accessed via the URL configured using this preference. You can set the URL for the documentation server while installing PJAC or edit SitePreferences.xml at a later time.

eForms

Is eForms installed

Preference	Is eForms installed
Description	Yes when eForms is installed
How to set	Install or uninstall eForms
Applies to	Open Client
Possible values	Yes. When eForms is not installed, the preference does not exist.
API	No
Exportable	No

Installation of eForms creates this preference, and removing eForms deletes the preference.

Administration

Administration topics provide information on:

- How to view support information
- How to delete temporary files

See the FileNet Web Services Administrator's Help for more administration information.

View support information

To view support information

1. From the Windows **Start** menu, select **Settings > Control Panel > Add/Remove Programs**.
2. In the **Currently Installed Programs** list, click on **FileNet Open Client**.
3. Click on **Support Information** to open the Support Info window.

Delete temporary files

When a user adds a document to a library, the document is placed in a temporary folder on the web server:

```
%Temp%\FileNet\<Session ID>
```

If the user logs off normally, this temporary folder is removed. However, the temporary files are not removed if the user closes the browser without logging off. You may wish to delete these temporary folders as part of your periodic server maintenance.

General Info

Glossary

This glossary defines important terms used throughout Open Client.

[A](#) [B](#) [C](#) [D](#) [E](#) [F](#) [GHI](#) [JKL](#) [MN](#) [O](#) [P](#) [QR](#) [S](#) [TUV](#) [W](#) [XYZ](#)

A

access rights

For a CS library, the security settings that control a user's access to libraries, documents, folders, stored searches, and search templates. Five levels define the access rights that can be assigned to users or groups: None, Viewer, Author, Owner, and Admin.

For an IS library, the security settings that control a user's access to documents, folders, and annotations. Three access rights, read, write, and append/execute, each assigned to one and only one group for an item, constrain what users can do.

authentication

The process of verifying a user name and password at login time against a designated authority.

authorization

The process of establishing the access rights (also called permissions) for a user.

[Return to Top](#)

B

browse

To navigate through a folder structure.

[Return to Top](#)

C

cache

A temporary storage location on magnetic disk. An IS server has server cache, reserved space on the server for documents retrieved from optical disk. When you retrieve a document, the document moves from optical disk to server cache to local cache.

check in

An operation that returns a checked out document to a library, completing the creation of a new version. While checked out, a document is locked so that no other user can modify it. A checkin unlocks the document.

check out

An operation that copies a document to your local hard disk for editing. It also locks the document in the library. No other user can modify a checked-out document.

commit, committal

A committed document is one that has been saved to an IS library. The last step in the process of creating an IS document, committal writes the document to a storage library and updates the property database.

Content Services (CS)

Server software and utilities for document management and version control.

CVL (controlled vocabulary list)

A list of acceptable values for a property field. The CS system administrator defines the list.

[Return to Top](#)

D

default group

Every CS user belongs to a default group. The system administrator assigns this group when defining your user account. At login time, if you don't specify a group, you log in as a member of this default group.

document type

For IS libraries only, the document type (F_DOCTYPE) indicates the page type of a document. Possible values are IMAGE, FORM, TEXT, MIXED, or OTHER. The document format (F_DOCFORMAT) indicates the file extension.

document

A set of image pages or other electronic files stored in a library and associated with a document ID and a set of properties. A CS document can include multiple versions.

document class

The system administrator defines document classes. A document class is a system property that specifies a type of document. Typically, a document class is a category like Invoices. When you add a document to a library, you must choose a document class. The document class determines:

- Which user properties apply to the document. User properties are values such as account numbers and names.
- For an IS document, the default access rights. These determine who can see, modify, add annotations to, and delete the document. (Access rights for a CS document are derived from the user profile of the user who adds the document.)

- For an IS document, disposition properties. For documents in the IS library, these determine when the document becomes eligible for disposal by archiving or deletion.

You can modify the document class of a CS document but not of an IS document

document ID (Item ID)

Each document in a library has a document ID that is unique within the library and cannot be modified.

- A CS document ID is a nine-digit number. When searching for document IDs, you can use wild cards, ? and *, in the search condition.
- IS document IDs begin at 100000. You cannot use wild cards when searching for IS document IDs.

[Return to Top](#)

E

Process Administrator

An Open Client application used by administrators to search and view workflows, edit workflow data and properties, and manage workflows.

Process Configuration Console

An Open Client application used to configure the workflow database and environment.

Process Designer

An Open Client application used to create and modify workflow definitions.

Process Tracker

An Open Client application used to monitor, manage, and modify workflows to which you have been assigned as a tracker.

external document

A document with properties but no content. Typically, an external document is used to track physical items such as artwork or video tapes.

[Return to Top](#)

F

FileNet imaging formats

FileNet imaging formats are supported natively by the IDM Viewer. These formats include FileNet proprietary banded and tiled images, TIFF 6.0 (mono FAX Group III, FAX Group IV, Packbits, uncompressed; color—4-, 8-, and 24-bit—Packbits, uncompressed) images, multipage TIFF images, BMP (Windows and OS/2, RLE4, RLE8,

and RGB/uncompressed) images, JPEG images, and DIB images. The document property F_DocType is set to IMAGE for all of these image formats. In addition, FileNet imaging formats include FileNet forms (F_DocType is FORM), COLD documents without background images and fax journals (F_DocType is TEXT), and COLD documents with background images (F_DocType is MIXED).

folder

A folder is a container. A folder can contain subfolders and documents. A CS folder can also contain references to stored searches.

folder name

At any level, an IS folder name can have up to 18 characters (no spaces are allowed), and a CS folder name can have up to 32 characters (any valid Windows folder name is allowed). For any library, a folder path and name cannot exceed 152 characters in all.

[Return to Top](#)

GHI

group

A group of one or more users and other groups. The system administrator creates user and group accounts. A user can belong to any number of groups. Membership in groups determines a user's access rights.

On IS libraries, your access rights determine what you can do with folders, documents, and annotations.

On CS libraries, your access rights determine what you can do with folders, documents, versions, and properties. The system administrator assigns each user to both a group and a default group. A user logs on as a member of one group. This membership determines the access rights for the session. Once you are logged on you cannot change the group name in the current session. The only way to change the group is to log out and then log in with a different group name.

host machine

The name of the computer that runs the CS library software. A host can be configured with multiple libraries.

Image Services (IS)

Server software and utilities for imaging, document storage, and retrieval.

index (or indexing)

For CS documents, indicates whether the version is currently indexed for content search.

item ID (Document ID)

See document ID.

[Return to Top](#)

JKL

launch

To begin the process specified in a workflow definition.

library

A library is a document management system. Both FileNet Image Services systems and FileNet Content Services systems are called libraries.

A storage library is another type of library. It is always identified as a storage library. IS supports both optical storage libraries (OSARs) and magnetic storage libraries (MSARs).

[Return to Top](#)

MN

name

An identifier for a library, system component (such as a printer), folder, or other object. For a CS document, the name is the document title. For a CS document, the name can be the document ID or a selected property.

[Return to Top](#)

O

original document

An original document is a document stored in a CS source library. This document is copied to replicated folders in participating CS libraries using Replication Services.

original library

An original library is a CS library that contains the source folders and documents that are replicated to participating libraries in Replication Services.

[Return to Top](#)

P

participant

A user or group assigned to process work at one or more steps in a workflow.

password

IS library passwords can range in length from 6 to 16 characters, but only the first eight characters are checked. CS library passwords can range in length from 1 to 32 characters. Your network administrator can assign a password of eight characters maximum for logging on to an IS library, or of 32 characters maximum for logging on to a CS library. In addition, all passwords are case-sensitive. If you do not have a password, leave the password field blank.

property

A piece of information associated with an object. For example, Document Title is a document property. Your access rights determine whether you can view and modify properties.

[Return to Top](#)

QR

queue

A workflow database structure that holds work items. There are three queue types: user queues, work queues, and system queues.

replicated folder

A folder in a target library in Replication Services. Replicated documents are filed in this folder.

replication

Replication Services is an optional server feature that automatically copies documents and their properties from a CS source library to one or more CS target libraries.

routing

The part of a workflow definition that orders a series of steps.

[Return to Top](#)

S

search

For Open Client users, to execute a stored search or search template to locate documents. You can search for a document based on its properties, its content, or both.

For Process Administrator users, to search for workflows, work items, workflow events, and workflow statistics.

search template

A search that allows the Open Client user to enter or change values at run time. Search templates appear on the Search page.

security

The rules that allow and limit access to computers and data.

step

A stage in a workflow where a distinct, well-defined activity takes place. Each step on a workflow map represents a specific activity or task in the business process described by the map.

step processor

An application that provides information and resources to a participant for a workflow step.

stored search

A ready-to-execute search. Instead of entering or modifying search criteria as in a search template, you simply execute the stored search.

[Return to Top](#)

TUV

target libraries

Target libraries are participating libraries in Replication Services. These libraries contain replicated folders that store documents copied from the original library.

tracker

A workflow participant who is designated to monitor the progress of a workflow. If necessary, the tracker can modify workflow steps and properties.

user name

Your user name identifies you to the FileNet system. A CS user name can contain a maximum of 39 characters; an IS user name can contain a maximum of 19 characters. This name is assigned by your network administrator, the person who controls access rights to the FileNet library and, for CS libraries, access to specific documents. For IS libraries, the user name is case sensitive.

version

A specific draft of a document stored in the CS library. Each time a document is checked out and checked in, the library creates and stores a new version of the document.

version number

Uniquely identifies the version of the document.

virtual folder

An IS folder displayed by Open Client that does not actually exist in the library. WorkForce Desktop allows users to assign multilevel names to folders. Because of this, a user can assign a name like /aaaa/bbbb to a folder without first creating the /aaaa folder. This nonexistent folder /aaaa is a virtual folder. To build the folder tree, Open Client displays virtual folders as needed to provide access to subfolders.

A virtual folder has no properties, cannot contain documents, but always has at least one subfolder. You can create subfolders below a virtual folder.

W

wizard

An interactive utility that steps you through a complex task, such as adding a document to a library.

work item

The collection of data and references to the system information necessary for processing the data. The smallest component of work to be done in a workflow.

workflow

Work performed by two or more individuals or resources, serially or in parallel, to accomplish a business process.

workflow author

A person who creates workflow definitions (steps and routing) to complete business processes.

workflow definition

An electronic representation of the activities and resources required to complete a business process. A workflow definition tells the Process software how to route work to participants.

workflow map

A graphical representation of a workflow that shows the sequences of steps needed to complete a business process. A step represents an activity. Routes between the steps indicate one or more possible processing paths.

WorkFlo Services

Back-end workflow server software and utilities that provide workflow functionality.

work queue

A list of work items that can be completed by any one of a number of users, or work items that can be completed by an automated process.

Contact FileNet

Visit the FileNet website

Visit the [FileNet website](#) for information on the corporation, its products, Global Learning Services, Professional Services, customer applications, and user groups.

Send documentation feedback

We welcome your [comments on Open Client documentation](#).

License Agreement

READ THIS NOTICE CAREFULLY, THE SOFTWARE IS THE PROPRIETARY INTELLECTUAL PROPERTY OF FILENET CORPORATION AND IS SUBJECT TO THE MINIMUM TERMS AND CONDITIONS SET FORTH BELOW. THESE TERMS AND CONDITIONS MAY BE SUPERCEDED BY THE TERMS AND CONDITIONS OF THE SOFTWARE LICENSE ENTERED INTO BY YOUR EMPLOYER FOR THE USE OF FILENET SOFTWARE. BY USING THE SOFTWARE, YOU ACKNOWLEDGE IT IS FILENET PROPRIETARY INTELLECTUAL PROPERTY AND THAT A VALID SOFTWARE LICENSE WITH FILENET CORPORATION IS APPLICABLE. THEREFORE AT A MINIMUM, YOU AGREE TO BE BOUND BY THE FOLLOWING FILENET END USER SOFTWARE LICENSE TERMS AND CONDITIONS (HEREINAFTER "Agreement"):

1. Definition of Software

The software consists of software owned by FileNet, as well as software owned by certain third party providers ("Third Party Providers"). Each software product includes any documentation relating to or describing such software, such as, logic manuals, flow charts, reference materials, and improvements or updates provided by FileNet (software and documentation collectively called "Software").

2. Grant of License

A. Each Software product, including any documentation relating to or describing such Software, such as, but not limited to, logic manuals, flow charts and improvements or updates provided by FileNet (collectively called "Software"), is furnished to End User under a personal, non-exclusive, nontransferable license solely for End User's own internal use in compliance with this License and all applicable laws and regulations. End User agrees that this License does not permit End User to: (1) use the Software for a service bureau application or (2) rent, lease, or sublicense the Software; (3) modify or remove any proprietary notices; or (4) transfer the Software without prior written consent from FileNet. The Software is licensed to the End User, not sold.

B. The Software may only be copied, in whole or in part (with the proper inclusion of FileNet's copyright notice and any other proprietary notice and/or trademarks on such Software), as may be necessary and incidental for archival purposes or to replace a worn or defective copy.

C. Title to and ownership of the Software and any portions (or any modifications, translations, or derivatives thereof, even if unauthorized) and all applicable rights in patents, copyrights and trade secrets in the Software shall remain exclusively with FileNet and its licensors, if any. Software provided hereunder is valuable, proprietary, and unique, and End User agrees to be bound by and observe the proprietary nature thereof as provided herein. End User agrees to take diligent action to fulfill its obligations hereunder by instruction or agreement with its employees or agents (whose confidentiality obligations shall survive termination of employment or agency) who are permitted access to the Software. Access shall only be given on a need-to-know basis. Except as set forth in this Agreement or as may be permitted in writing by FileNet, End User shall not use, provide or otherwise make available the Software or any part or copies thereof to any third party. End User shall not reverse engineer, decompile or disassemble the Software or any portion thereof, nor otherwise attempt to create or derive the source code. End User acknowledges that unauthorized reproduction, use, or disclosure of the Software or any part thereof may cause irreparable injury to FileNet and/or its licensors, who may therefore be entitled to injunctive relief to enforce these license restrictions, in addition to any other remedies available at law, in equity, or under this Agreement. Further, the trademarks are owned by the respective trademark holder.

D. FileNet agrees that End User's affiliates (business entities of which End User owns or controls more than fifty {50%} percent of the voting rights or the controlling body of the business entity) may use the Software; provided that prior to any affiliate's use of the Software: (i) End User accepts responsibility for the acts or omissions of such affiliates as if they were End User's acts or omissions; (ii) End User shall indemnify FileNet against losses or damages suffered by FileNet arising from breach of this Agreement

by any such affiliate; and (iii) such use shall not constitute an unauthorized exportation of the Software or documentation under U.S. Government laws and regulations.

3. **Termination.** FileNet shall have the right to terminate End User's license if End User fails to pay any and all required license fees or otherwise fails to comply with these license terms and conditions. Upon expiration of the license term or upon notice of such termination, End User shall immediately return or destroy the Software and all portions and copies thereof as directed by FileNet and, if requested by FileNet, shall certify in writing as to the destruction or return of the same. All confidentiality and non-disclosure obligations herein shall survive termination.

4. Limited Warranty

A. FileNet warrants that it has good and clear title to or has the right to sublicense the Software being licensed hereunder, free and clear of all liens and encumbrances.

B. FileNet warrants for a period of one year from the Shipment Date, Software used in a manner for which it was designed will perform the functions described in the applicable FileNet documentation supplied at the time of delivery provided that, (i) Software is continuously subject to a FileNet Software Support contract, (ii) any substantial nonconformance is reproducible, and (iii) the substantial nonconformance is not caused by third party software or hardware not specified in FileNet's documentation or not expressly authorized in advance by FileNet. FileNet's sole obligation and liability hereunder shall be to use reasonable efforts to remedy any material non-conformance which is reported to FileNet in writing within the warranty period.

C. End User accepts sole responsibility for, system configuration, design and requirements, selection of the software for the intended results, modifications, changes or alterations.

D. THERE ARE NO OTHER WARRANTIES, EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NONINFRINGEMENT WITH RESPECT TO THIS AGREEMENT, THE AGREEMENT, OR THE SOFTWARE LICENSED HEREUNDER. FILENET DOES NOT WARRANT THAT THE OPERATION OF THE SOFTWARE WILL BE UNINTERRUPTED, THAT THE SOFTWARE IS ERROR-FREE, OR THAT ALL ERRORS CAN BE CORRECTED.

5. **Export.** End User agrees that the Products purchased hereunder will not be exported directly or indirectly, separately or as part of any system, without first obtaining a license from the U.S. Department of Commerce or any other appropriate agency of the U.S. Government, as required.
6. **Restrictions on Use.** End User acknowledges that one of FileNet's Third Party Providers provides application integration software as part of the Software (the "Integration Software"). End User agrees to use the Software solely as follows: (i) FileNet's workflow or content management software will be the triggering source and/or the destination of the transaction managed by the Integration Software; (ii) FileNet's workflow or content management functionality must be a necessary part of the transaction managed by the Integration Software such that without such FileNet functionality, the transaction managed by the Integration Software could not process; (iii) the Software will not be used or configured in such a way as to only provide the functionality that the Integration Software provides; and (iv) all derivative works of the Software made by or for End User are subject to the foregoing restrictions.
7. **Choice of Law.** The laws of the State of California will govern the construction and operation of this Agreement without regard to the conflict of laws provisions thereof.
8. **U.S. Government Restricted Rights.** The Software is Commercial Software and the Software and Documentation are provided with Restricted Rights. Use, duplication or disclosure by the Government is subject to restrictions as set forth in paragraph (c) (1) (ii) of the Rights in Technical Data and Computer Software Clause at DFARS 252.227-7013 or subparagraphs (c) (1) and (2) of the Commercial Computer Software-Restricted Rights at 48 CFR 52.227-19, as applicable. Contractor/manufacturer is FileNet Corporation, 3565 Harbor Blvd., Costa Mesa, California 92626.

Notices

This document contains information proprietary to FileNet Corporation (FileNet). Due to continuing product development, product specifications and capabilities are subject to change without notice. You may not disclose or use any proprietary information or reproduce or transmit any part of this document in any form or by any means, electronic or mechanical, for any purpose, without written permission from FileNet.

FileNet has made every effort to keep the information in this document current and accurate as of the date of publication or revision. However, FileNet does not guarantee or imply that this document is error free or accurate with regard to any particular specification. In no event will FileNet be liable for direct, indirect, special incidental, or consequential damages resulting from any defect in the documentation, even if advised of the possibility of such damages. No FileNet agent, dealer, or employee is authorized to make any modification, extension, or addition to the above statements.

FileNet may have patents, patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this document. The furnishing of this document does not provide any license to these patents, trademarks, copyrights, or other intellectual property.

Open Client Help systems incorporate Deva Tools™, a product of Deva Associates LLC. Deva Associates assumes no liability for any claim that may arise regarding this incorporation. Deva Tools is a trademark of Deva Associates. Copyright © 2001 Deva Associates LLC. All rights reserved.

This product incorporates Outside In® (8.1.0) Conversion Technologies, a product of Stellent, Inc.™ Stellent, Inc. assumes no liability for any claim that may arise regarding this incorporation. In addition, FileNet disclaims all warranties, both express and implied, arising from the use of Outside In Conversion Technologies. Copyright © 1991-2006 Stellent, Inc., Chicago. All rights reserved.

JavaView incorporates viewONE image viewing and annotations technology developed and copyrighted by Daeja Image Systems. Daeja Image Systems assumes no liability for any claim that may arise regarding this incorporation. viewONE is a trademark or registered trademark of Daeja Image Systems. Copyright (c) 2006 Daeja Image Systems, www.daeja.com. All rights reserved.

FileNet and ValueNet are registered trademarks of FileNet Corporation. FileNet P8 and FileNet Workplace are trademarks of FileNet Corporation. All other company or product names referenced in this release may be trademarks or registered trademarks of their respective owners.

FileNet is a registered trademark of FileNet Corporation.

All other product and brand names are trademarks or registered trademarks of their respective companies.

Due to continuing product development, product specifications and capabilities are subject to change without notice.

Copyright © 1998, 2006 FileNet Corporation. All rights reserved.

FileNet Corporation
3565 Harbor Boulevard
Costa Mesa, California 92626
800.FILENET (345.3638)
Outside the U.S., call:
1.714.327.3400
www.filenet.com

Filename: Open_Client_Admin_Help.doc
Directory: E:\My Documents 2\General\OC\ahi350\ahi350 ui
Template: D:\Documents and Settings\sdudeja\Application
Data\Microsoft\Templates\Normal.dot
Title: Getting started with Open Client
Subject:
Author: mdua
Keywords:
Comments:
Creation Date: 7/3/2007 12:01:00 PM
Change Number: 3
Last Saved On: 7/3/2007 12:47:00 PM
Last Saved By: sdudeja
Total Editing Time: 5 Minutes
Last Printed On: 7/3/2007 12:47:00 PM
As of Last Complete Printing
Number of Pages: 127
Number of Words: 19,076 (approx.)
Number of Characters: 110,644 (approx.)