

IBM Security Verify Access  
Version 10.0.3  
December 2021

*Product overview*





---

# Contents

<b>Accessibility features for Security Verify Access.....</b>	<b>v</b>
<b>Chapter 1. Documentation for getting started.....</b>	<b>1</b>
<b>Chapter 2. What's new in this release.....</b>	<b>3</b>
<b>Chapter 3. Product requirements.....</b>	<b>7</b>
<b>Chapter 4. Documentation for an activation level.....</b>	<b>9</b>
<b>Chapter 5. Secure deployment considerations.....</b>	<b>11</b>
<b>Chapter 6. Upgrading to the current version.....</b>	<b>13</b>
<b>Chapter 7. APARs fixed in this version.....</b>	<b>17</b>
<b>Chapter 8. Compatibility with earlier versions of the product.....</b>	<b>19</b>
<b>Chapter 9. Known limitations.....</b>	<b>21</b>
<b>Chapter 10. Security Verify Access appliance FRU/CRU documentation.....</b>	<b>25</b>
Disk Drive Assembly Replacement Instructions.....	25
Replacing a storage drive assembly.....	25
Fan Assembly Replacement Instructions.....	27
Replacing a fan assembly.....	27
Network Interface Module Replacement Instructions.....	28
Replacing a failed network interface module.....	28
Power Supply Replacement Instructions.....	30
Identifying a failed power supply.....	30
Replacing a failed power supply.....	32
<b>Chapter 11. Supporting content.....</b>	<b>35</b>
<b>Chapter 12. Language support overview.....</b>	<b>37</b>
<b>Index.....</b>	<b>39</b>



## Accessibility features for Security Verify Access

---

Accessibility features assist users who have a disability, such as restricted mobility or limited vision, to use information technology content successfully.

### Accessibility features

Security Verify Access includes the following major accessibility features:

Accessibility features
Supports interfaces commonly used by screen readers. This feature applies to applications on Windows operating systems only.
Can be operated by using only the keyboard.
Allows the user to request more time to complete timed responses.
Supports customization of display attributes such as color, contrast, and font size.
Communicates all information independently of color.
Supports interfaces commonly used by screen magnifiers. This feature applies to applications on Windows operating systems only.
Allows the user to access the interfaces without inducing seizures due to photosensitivity.

Security Verify Access uses the latest W3C Standard, [WAI-ARIA 1.0](http://www.w3.org/TR/wai-aria/) (<http://www.w3.org/TR/wai-aria/>), to ensure compliance to [US Section 508](http://www.access-board.gov/guidelines-and-standards/communications-and-it/about-the-section-508-standards/section-508-standards) (<http://www.access-board.gov/guidelines-and-standards/communications-and-it/about-the-section-508-standards/section-508-standards>), and [Web Content Accessibility Guidelines \(WCAG\) 2.0](http://www.w3.org/TR/WCAG20/) (<http://www.w3.org/TR/WCAG20/>). To take advantage of accessibility features, use the latest release of your screen reader in combination with the latest web browser that is supported by this product.

The Security Verify Access online product documentation in IBM® Knowledge Center is enabled for accessibility. The accessibility features of IBM Knowledge Center are described at <https://www.ibm.com/support/knowledgecenter/help?view=kc#accessibility>.

### Keyboard navigation

This product uses standard navigation keys.

### Interface information

The Security Verify Access user interfaces do not have content that flashes 2 - 55 times per second.

The Security Verify Access web user interfaces and the IBM Knowledge Center rely on cascading style sheets to render content properly and to provide a usable experience. The application provides an equivalent way for low-vision users to use a user's system display settings, including high-contrast mode. You can control font size by using the device or web browser settings.

The Security Verify Access web user interface includes WAI-ARIA navigational landmarks that you can use to quickly navigate to functional areas in the application.

## **Related accessibility information**

In addition to standard IBM help desk and support websites, IBM has established a TTY telephone service for use by deaf or hard of hearing customers to access sales and support services:

TTY service 800-IBM-3383 (800-426-3383) (within North America)

## **IBM and accessibility**

For more information about the commitment that IBM has to accessibility, see [IBM Accessibility](http://www.ibm.com/able) ([www.ibm.com/able](http://www.ibm.com/able)).

---

## Chapter 1. Documentation for getting started

The IBM Knowledge Center provides documentation that can help you get started with the IBM Security Verify Access product.

IBM Security Verify Access is available from Passport Advantage. You can use this distribution to either configure a new deployment or upgrade a previous version of the product.

1. If you are upgrading from a previous version of IBM Security Verify Access for Web 8.\*, IBM Security Verify Access for Mobile 8.\*, or IBM Security Verify Access 9.0 be sure to review [Chapter 6, “Upgrading to the current version,”](#) on page 13. If applicable, you must complete these steps before you configure the product.
2. See [Product activations overview](#) to review the features you can use when you activate the Security Verify Access Platform, the Advanced Access Control Module, or the Federation Module.
3. Configure the appliance by using the instructions in [Getting Started](#).
4. Complete the initial setup of your Security Verify Access appliance deployment by following the instructions in [Initial configuration](#).
5. (Advanced Access Control Module only) Complete the initial setup of this module by following the instructions in [Getting Started with Advanced Access Control](#).

Security Verify Access Platform includes an optional Java ADK, available for download. To install the Java ADK, see [Intalling IBM Security Verify Access Runtime for Java](#).

See [Administering Web Reverse Proxy](#) for instructions on how to use the local management interface on the appliance to configure and administer Security Verify Access Platform.





---

## Chapter 2. What's new in this release

IBM Security Verify Access provides new features and extended functions for Version 10.0.3.

### Verify Access Platform

- WebSEAL request log

It is now possible to include the HTTP response status code, received from the junctioned server, in the request log. See [Customizing the HTTP log request](#).

- WebSEAL virtual host junctions

It is now possible, when creating a virtual host junction, to specify host name aliases which are used when matching the host header from a request to the virtual host junction. See [Creation of a virtual host junction](#).

- WebSEAL EAI Error Text

A new HTTP header, which contains an error message, can now be set by an EAI application to be included in WebSEAL generated error responses. See [External authentication interface HTTP header reference](#).

- Default SSL Personal Certificates

It is no longer possible to set a default personal certificate in an SSL certificate key file. This could potentially impact the WebSEAL instances and the Distributed Session Cache if no server key label has been specified in the configuration. In this instance the first key found within the SSL certificate key file will be used.

- WebSEAL junction status application

WebSEAL now contains an embedded application which can be used to display the status of hosted junctions. See [Junction Status REST API](#).

- Policy Server audit log forwarding

Remote Syslog forwarding capabilities has been added for policy server log files. These log files can now be collected by a remote logging server where they can be centrally managed. To set up a remote syslog server for IBM Security Verify Access. See [Forwarding logs to a remote syslog server](#).

- Container Enhancements

- It is now possible to specify a snapshot identifier so that the same volume can be used to host multiple environments.
- It is now possible to specify, using the **CONFIG\_SERVICE\_URL** environment variable, multiple endpoints to which the configuration container will publish the snapshot.

See [Docker Image for Security Verify Access](#).

- LMI basic authentication header caching

An internal cache has been added to the LMI for basic authentication (BA) headers to help improve authentication speeds in a DevOps environment. The lifetime of entries within the cache is managed by the 'baSessionTimeout' administrator setting. See [Configuring administrator settings](#).

- Kubernetes Operator

A Kubernetes operator is now available which can be used to manage the lifecycle of lightweight Docker worker containers in a Kubernetes environment. See [Kubernetes Operator](#).

- Java Runtime update

The underlying Java runtime which is used by the Local Management Interface and the Federation/Advanced Access Control runtime has been updated. As a result of this update:

- The SSLv3 protocol is no longer supported.
- The `java.enable.ibmjceplus` and `java.disable.fips.provider` advanced tuning parameters are no longer required and are ignored.
- The `lmi.jvm.option.*` and `runtime_profile.jvm.option` advanced tuning parameters, used to set custom Java runtime environment options, are still supported but the JVM options themselves may have changed. If the Java runtime environment has been customized using these advanced tuning parameters, the IBM support team should be contacted to provide alternative values.
- The `lmi.javasecurity_option.*` and `runtime_profile.javasecurity_option` advanced tuning parameters are no longer supported.
- A [Luna Safenet HSM device](#) can no longer be used to protect SAML 2.0 operations in the federation runtime. This includes the SAML 2.0 federated SSO protocol, and the inclusion of the SAML 2.0 token module in a trust chain of the Security Token Service. You should instead use software key storage, or an alternative supported HSM device.
- In order for the Java runtime to be able to view and access signer certificates the `CKA_TRUSTED` attribute on the certificate must now be set to `'true'`. Refer to the vendor documentation for the HSM device which is in use for instructions on how to set this attribute on the signer certificates.

- Web Reverse Proxy Certificate Validation

It is now possible to perform CN and Subject Alternative Name validation on certificates which are provided by Junctioned servers using the junction server hostname. See [Matching the common name \(CN\) and subject alternative name \(SAN\)](#).

- Multi-Instance rate limiting

Rate limiting data can now be distributed across multiple web reverse proxy instances by using a Redis database. See [Multi-instance Rate Limiting](#).

## **Advanced Access Control (AAC)**

- Embedded Cloud Identity API calls in an Info Map mechanism

There is a new Java class `CiClientV2` available to make Cloud Identity (CI) API calls in InfoMap mechanisms. The JavaDoc for the new client is available on the appliance from: **System > Secure Settings > File Downloads > access\_control folder > doc folder > ISAM-Javadoc.zip**. The fullname for the new client is `com.ibm.security.access.ciclient.CiClientV2`. See [Embedded Cloud Identity API calls in an InfoMap mechanism](#).

- Support for Kubernetes secrets in mapping rules in container deployments

It is now possible to retrieve Kubernetes secrets from within a mapping rule. Secrets can be retrieved by using the authentication details of the service account used to deploy the Verify Access runtime container. See the [JavaScript whitelist](#).

- Support for Silent Push Notifications

IBM Security Verify Access now supports silent push notifications for IBM Verify. See [Push notification registration](#).

- Bulk Import and Export of Mapping Rules

Advanced Access Control or Federation mapping rules can now be managed with bulk operations that allow multiple mapping rules to be imported or exported in a zip file. See [Managing JavaScript Mapping Rules](#).

- Adding Mapping Rules and Template Files to Generated Support Files

Advanced Access Control or Federation mapping rules and template files can now be included in generated support files. See [Managing Support Files](#).

- Command Line Configuration

It is no longer possible to use the command line to configure WebSEAL to act as a point of contact for Advanced Access Control. The corresponding Local Management Interface web service should be used instead. See [Authentication and Context based access configuration for a reverse proxy instance](#).

- SCIM Custom Schema Extensions

Custom attributes can now be added to SCIM User payloads with Custom Schema Extensions. See [Custom Schema Extensions](#).

- Managing Access Control Policy Attachments

When viewing the list of Access Control Resources, if a previously published resource has been modified such that the rba-pop POP has been removed from the protected resource, the resource will now show that a new publish is required. For details on managing access control. See [Managing Access Control Policy Attachments](#).

- How To FIDO Scenario

The scenario wizard is now updated to allow for the configuration of the How To FIDO policy. See [Scenarios](#).

- MMFA Transaction Archival Thread

The clean-up and archival of the MMFA Transaction database tables has been moved to a new clean-up thread. See [Advanced Configuration Properties](#).

- New FIDO2 WebAuthn Registration Mechanism

Users can now register FIDO2/WebAuthn devices by using the Authentication Service with the new Registration Mechanism. See [Configuring a FIDO2/WebAuthn registration mechanism](#). This mechanism is added to enable the How to FIDO Scenario.

## **Federation**

- SAML2.0 Mapping Rule utility

It is now possible to configure SAML2.0 assertion attribute(s) to be encrypted with a mapping rule.

- SAML 2.0 Scoping support

SAML2.0 Authentication request can now be modified to add scoping element with a new mapping rule of the category SAML\_2\_0\_AUTHN\_REQ. Its applicable to service provider federation and partner only. See [SAML 2.0 service provider worksheet](#).



---

## Chapter 3. Product requirements

You can view Software Product Compatibility Reports that list the system requirements and appliance specifications for the product.

The reports provide current information about hardware and software support and requirements for IBM Security Verify Access.

- System requirements for hardware appliance:
  - Prerequisite software, including supported databases, user registries, and browsers
  - Appliance specifications such as disk size, memory, network ports, physical characteristics, and electrical and environmental parameters
- System requirements for the virtual appliance:
  - Supported hypervisors, databases, user registries, and browsers
  - Disk space and memory requirements for virtual images

To view the reports, see [Software Product Compatibility Reports](#).

You can also view the specifications of the hardware and virtual appliance in the following Technotes:

- [Hardware appliance specifications](#)
- [Virtual appliance specifications](#)

### WebSEAL client support

When acting as a reverse proxy, WebSEAL generally supports clients that conform to the HTTP 1.1 standard as defined by RFC 2616 and the HTTP/2 standard as defined by RFC 7540. The preceding statement is not a comprehensive statement of support. WebSEAL relies on a number of client characteristics that are either not defined or are loosely defined by RFC 2616 and RFC 7540. Examples of such characteristics include, but are not limited to:

- Cookie management
- SSL support
- Concurrency of multiple connections

Widely used browsers such as Firefox, Chrome, Safari, and Internet Explorer support such characteristics during typical use.

The extension of browser capabilities that modify these characteristics can, however, introduce compatibility problems with WebSEAL. The same is true of other client types, such as mobile applications or rich clients. Compatibility complications that cannot be resolved through modification of the environment or configuration of the WebSEAL product are not supported.



## Chapter 4. Documentation for an activation level

IBM Security Verify Access uses the listed activation levels, depending on the modules you purchase. Use the information in the tables to determine which topics to start with in the documentation.

### Security Verify Access Supporting Components

No activation key is required for these functions.

*Table 1. Security Verify Access Supporting Components functions and topic links*

Function	Topic
Appliance Management: Local Management Interface	<a href="#">Appliance Management</a>
Appliance Management: REST APIs	<a href="#">REST API documentation</a>
Policy Server	<a href="#">Policy server administration tasks</a>
Embedded LDAP server	<a href="#">Embedded LDAP server management</a>
Authorization Server	<a href="#">Authorization servers</a>

### Security Verify Access Platform

An activation key is required for these functions.

*Table 2. Security Verify Access Platform functions and topic links*

Function	Topic
Web Reverse Proxy	<a href="#">Web Reverse Proxy configuration and Web Reverse Proxy administration</a>
Load Balancer	<a href="#">Front-end load balancer</a>
X-Force threat protection	<a href="#">Configuring web application firewall</a>
Distributed Session Cache	<a href="#">Distributed session cache</a>

### Advanced Access Control Module

This module is an add-on feature that requires an activation key.

*Table 3. Advanced Access Control functions and topic links*

Function	Topic
Authentication	<a href="#">Authentication</a>
OAuth 2.0 API protection	<a href="#">Configuring API protection</a>
Context-based access	<a href="#">Overview of context-based access</a>
Device fingerprinting	<a href="#">Device fingerprints</a>
Device registration	<a href="#">Consent-based device registration</a>
HOTP and TOTP Key Manager	<a href="#">Managing OTP secret keys</a>
Fine-grained authorization/XACML 2.0	<a href="#">Access control policies</a>
Runtime security services	<a href="#">Runtime security services external authorization service</a>

Table 3. Advanced Access Control functions and topic links(continued)

Function	Topic
Policy distribution (Policy administration point)	<a href="#">Risk management overview</a>

## Federation Module

This module is an add-on feature that requires an activation key.

Table 4. Federation functions and topic links

Function	Topic
SAML 2.0 Federations	<a href="#">SAML 2.0 federations</a>
Open ID Connect Federations	<a href="#">OpenID Connect Federations</a>
Module chains	<a href="#">Manage module chains</a> and <a href="#">Configuring STS modules</a>

## Related information

[Product activations overview](#)



---

## Chapter 5. Secure deployment considerations

When you deploy the IBM Security Verify Access appliance, consider the following points.

- The Security Verify Access embedded user registry should only be used in the following scenarios:
  - Proof of Technology deployments
  - Deployments with a low number of Security Verify Access users (< 5000)
  - When using federated directories with the Security Verify Access basic user feature
- Choose the suitable Security Verify Access user authentication mode for your environment.
  - Use basic user for all scenarios unless GSO lock-box, user based ACLs, or account-valid/password-valid features are required.
  - Only use the full user model if basic user is not suitable. Basic user only supports minimal mode.
- The appliance has management and application interfaces. Network separation between the management and application interfaces must be maintained.
- Any Security Verify Access web reverse proxies that are hosted in the corporate DMZ network zone should be configured as restricted nodes.
- The Security Verify Access appliance that hosts the Policy Server component should be hosted in a secure network zone and not exposed to the internet.
- If the embedded user registry is used, it should be hosted on the same appliance as the Security Verify Access Policy Server in a secure network zone. The embedded user registry port (636) should not be routable from the internet.
- Security Verify Access clustering is recommended to provide a highly available solution. Two Security Verify Access appliances performing the primary and secondary roles respectively should be used. These should be hosted in the secure network zone with Security Verify Access runtime replication enabled.
- If advanced authentication/authorization is required, the Security Verify Access authentication service in the Advanced Access Control (AAC) component should be used. This should be hosted on the Security Verify Access primary and secondary appliances in the secure network zone. This service should not be routable from the internet.
- Second factor or multi-factor authentication should be considered to increase assurance of user identity.
- Enable Network Time Protocol (NTP) on all appliances to synchronize the time correctly. This is to ensure that the appliance works correctly with distributed components.
- Do not use self-signed certificates for any public facing services. Always obtain certificates issued by an appropriate certificate authority.
- All non-TLS communication should be disabled:
  - Only use port 636 for LDAP communication.
  - Only use HTTPS 443 application interfaces.
  - Only use TLS for junction communication.
- Enable the Security Verify Access Web Application Firewall (WAF) feature on all appliances hosting the Security Verify Access reverse proxy.
- Session affinity should be enabled between all Security Verify Access components for performance and scalability reasons.
- The Security Verify Access Distributed Session Cache (DSC) or failover cookie should be used to provide a highly available solution across multiple reverse proxy instances.
- If the DSC is deployed, it should be hosted in the secure network zone.

- Configure the reverse proxy cookie jar feature to prevent application cookies from being returned to clients unnecessarily.
- Connection pooling for junctions should be enabled to optimize performance of the solution. This capability is disabled by default.
- FIPS should be enabled if appropriate.
- Enable these security headers in the reverse proxy configuration:
  - **strict-transport-security**
  - **content-security-policy**
- Minimize access to unauthenticated resources using standard Security Verify Access ACL policy.
- Host the Security Verify Access runtime database on an external Database. This database is used for federation and/or AAC features. The runtime database should be hosted in a secure network zone and should not be routable from the internet.
- Use a highly available solution for the external Security Verify Access runtime database. This service is critical to Security Verify Access operation.
- Best practice is to use the Security Verify Access REST APIs for automated deployment to allow:
  - Rapid recovery
  - Consistent and repeatable deployment configuration
- Don't use Basic Authentication (BA) for authentication to Security Verify Access REST APIs when automating deployment and management of the Security Verify Access appliance. Certificate authentication should be used.
- Standard network security guidelines should be applied. Network access and administrative credentials to the appliance should only be available to authorized administrators on appropriate networks.
- Minimize on-board storage of logs by configuring remote syslog to store log and audit archives in a protected network zone. A separate logging server/service should be used to store logs.
- An appropriate patch process should be implemented to:
  - Subscribe to, and monitor IBM support site for Security Verify Access appliance patches
  - Apply all patches promptly when released
- Set the **sps.setCookiesAsSecure** parameter to Secure to flag the cookies set by Security Verify Access.

---

## Chapter 6. Upgrading to the current version

Complete this task if you are upgrading an existing Security Verify Access for Web, Security Verify Access for Mobile, or Security Verify Access installation to the current version.

### Before you begin

#### Important:

See [IBM Security Verify Access Upgrade Paths](#).

When you upgrade a cluster, upgrade the primary master first and do not upgrade the remaining cluster nodes until the primary master finishes upgrading and is operational.

In the case where one of the non-primary nodes is upgraded when the primary master is not available, upon upgrade completion the node will be in a non-operational state. To rectify this problem, remove the non-operational node from the cluster and then re-add it. This approach will ensure that the configuration and database replication returns to a working state.

If you are installing the virtual appliance for the first time, download the .iso image and follow the installation instructions in the [IBM Security Verify Access Virtual Appliance](#).

Review the following tasks and complete the tasks that are appropriate to your environment:

#### Clear the browser cache

As part of the upgrade process, clear your browser cache to reduce the likelihood of encountering issues with cached items.

#### USB drive for an update

If you use a USB drive for an update, it must be formatted with a FAT file system.

#### Risk engine reports

Any risk engine reports that you generated before you begin the upgrade task are not preserved. Export copies of the risk reports and save them locally by completing the following steps:

1. Log in to the local management interface.
2. Click **Monitor > Application Log Files**.
3. Expand **access\_control** and select the risk reports to export.
4. Click **Export** and save the files.

### Procedure

Choose one of the following upgrade methods and complete the steps:

#### Use the online update server.

- a. Meet the following conditions:
  - A valid license is installed on the appliance.
  - The appliance has network connectivity to the online update server.
- b. Log in to the local management interface. If you are upgrading a cluster, log in to the local management interface of the primary master first.
- c. Select **System > Updates and Licensing > Available Updates**.
- d. Click **Refresh**.
- e. Select the firmware update.
- f. Click **Install**. The firmware update might take a long time to complete, depending on the bandwidth that is available to the appliance. After the update is successfully applied, the appliance automatically restarts.

- g. If you use any external databases, download the **dbupdate9.zip** file from **File Downloads** area of the appliance and upgrade the external databases.
- h. If you are upgrading a cluster, complete the following steps:
  - i) Repeat steps “1.b” on page 13 through “1.f” on page 13 on each node in the cluster starting with the secondary master.  
**Note:** If you use internal databases, do not subsequently reboot the primary master until the secondary master has been upgraded.
  - ii) Wait for the cluster to synchronize. The firmware for each appliance in the cluster is now upgraded and the cluster is operational.

**Note:** Although the secondary master remains present and the embedded runtime database fails over to the secondary master when the primary master is down during the migration, you cannot avoid down time by leveraging this failover mechanism. This is due to the fact that the database changes made to the secondary master while the primary master is being migrated will likely be discarded and replaced by the upgraded databases from the primary master after it begins operating again after the migration.

**Use the local management interface for a single appliance *not* in a cluster.**

- a. Download the .pkg file.
- b. Log in to the local management interface.
- c. Select **System > Updates and Licensing > Available Updates**.
- d. Click **Upload**. The **New Update** window opens.
- e. Click **Select Update**.
- f. Browse to the .pkg file.
- g. Click **Open**.
- h. Click **Save Configuration**. The upload process might take several minutes.
- i. Select the new firmware and click **Install**. The installation of the new firmware takes a few minutes. After the update is successfully applied, the appliance restarts automatically.

**Use the local management interface for a cluster of appliances.**

- a. Download the .pkg file.
- b. Log in to the local management interface of the primary master.
- c. Upload and install the firmware .pkg file on the primary master. This step includes the automatic restart of the appliance.  
**Note:** If you use internal databases, do not subsequently reboot the primary master until the secondary master has been upgraded.
- d. If you use any external databases, download the dbupdate9.zip file from **File Downloads** area of the primary master and upgrade the external databases.
- e. Upload and install the firmware .pkg file on each node in the cluster starting with the secondary master if present.
- f. Wait for the cluster to synchronize. The firmware for each node in the cluster is now upgraded and the cluster is operational.

**Note:** Although the secondary master remains present and the embedded runtime database fails over to the secondary master when the primary master is down during the migration, you cannot avoid down time by leveraging this failover mechanism. This is due to the fact that the database changes made to the secondary master while the primary master is being migrated will likely be discarded and replaced by the upgraded databases from the primary master after it begins operating again after the migration.

**Use a USB drive. (Only for upgrading a hardware appliance.)**

- a. Download the .pkg file.

- b. Copy the firmware update from the .pkg file to a USB flash drive.
- c. Insert the USB flash drive into the hardware appliance.
- d. Log in to the appliance console as admin or use Secure Shell.
- e. Type updates and press Enter.
- f. Type install and press Enter.
- g. Select the following options:
  - i) Type 1 for a firmware update.
  - ii) Type 1 to install the update from a USB drive.
  - iii) Type YES to confirm that the USB drive is plugged into the appliance.
  - iv) Type the index number to select the appliance firmware from the list.
  - v) Type YES to confirm the update and start the update process.

**Note:** The firmware update takes a few minutes to complete and the appliance automatically restarts.

## **What to do next**

- If you are using an external database to store the runtime or configuration data, you also need to update the database schema. This can be achieved by downloading the database update utility from the appliance and running this utility against the external database. For more details, see [Upgrading external databases with the dbupdate tool \(for appliance at version 9.0.0.0 and later\)](#).
- If you are upgrading an existing appliance, your Security Verify Access Platform is ready to use.
- If you are upgrading an existing Security Verify Access for Mobile appliance or Advanced Access Control module to the current version, continue with the [Upgrading configuration](#) instructions.
- If you are upgrading an existing Federation module to the current version, continue with the [Upgrading configuration](#) instructions.



## **Chapter 7. APARs fixed in this version**

Several APARs were fixed with this version of the product.

For the latest list, see [APARs fixed by IBM Security Verify Access version 10.0.3](#).





---

## Chapter 8. Compatibility with earlier versions of the product

IBM Security Verify Access V10.0.\* is compatible with previous versions of Security Verify Access for Web, Tivoli Access Manager for e-business, Security Access Manager for Web, Security Access Manager for Mobile, and Security Verify Access for Mobile.

The Version 10.0.\* policy server can communicate with some previous versions of Security Access Manager for Web, Tivoli Access Manager for e-business, and Security Verify Access for Mobile. The following compatibility with earlier versions is supported:

- Policy server compatibility with servers in prior versions
- Compatibility with single sign-on targets
- Limited compatibility with earlier versions for session management

### **Compatibility with single sign-on targets**

IBM Security Verify Access maintains compatibility with earlier versions for all single sign-on information that is sent over HTTP to applications behind WebSEAL junctions. Applications that are written to use single sign-on information that is supplied by previous versions of the product can use the same information that is provided by Version 10.0.\*.

This compatibility applies to both custom applications and IBM applications such as the Trust Association Interceptor. The Trust Association interface is a service provider API that enables the integration of third-party security service (for example, a reverse proxy) with WebSphere Application Server. Security Verify Access, version 10.0.\*, is compatible with all versions of the Trust Association Interceptor.



---

## Chapter 9. Documentation updates for known limitations

You can view the known software limitations, problems, and workarounds on the IBM® Security Verify Access Support site.

The Support site describes not only the limitations and problems that exist when the product is released, but also any additional items that are found after product release. As limitations and problems are discovered and resolved, the IBM Software Support team updates the online knowledge base. By searching the knowledge base, you can find workarounds or solutions to problems that you experience.

Also, check the [Troubleshooting](#) topics.

### Known limitations for Security Verify Access

#### A system error is displayed briefly when the Mozilla Firefox browser is refreshed.

When you use the Mozilla Firefox browser to access the local management interface, sometimes a system error is displayed briefly during a browser refresh.

This error is displayed because the browser refresh causes an XMLHttpRequest (XHR) request to be canceled before the request finishes. The error does not indicate impact to normal operations and can be ignored.

#### Unable to remove local users or groups from authorization roles with Mozilla Firefox on Mac OS X.

When you use the local management interface through a Mozilla Firefox browser version on a Mac OS X system, you might not be able to remove a user or group from an authorization role.

On the **Management Authorization** page of the local management interface, when you click **Edit**, the **Edit Local Members** window is displayed. To remove a user or group, normally you uncheck the check box for that user or group and then click **OK** to save the changes. However, if you use Firefox on Mac OS X to complete such operation, the browser does not properly recognize the change and does not display any error messages. The user or group list remains unchanged after you click **OK**.

To avoid such issue on Mac OS X, you have two options:

- Use a different browser to access the local management interface.
- Use the REST API. See the [REST API documentation](#) and browse to **Manage: System Settings > System Settings > Management Authorization > Updating an authorization role**.

#### Lower throughput observed with certificate revocation list enabled

Enabling certificate revocation list (CRL) validation might result in a lower throughput from the system. If your certificate does not have a CRL, you might want to disable CRL checking by using the advanced configuration parameter **kess.crlEnabled**. Alternatively, you might want to reduce the frequency of CRL checking by using the advanced configuration parameter **kess.crlInterval**.

#### Client certificate authentication for federated directories is not supported for UsernameTokenSTSModule

When you configure a federated directory, do not select a client certificate.

#### In rare circumstances, an OAuth access token validation might fail.

These instances have been observed very shortly after a restart of the Advanced Access Control runtime server. The symptoms and conditions include:

1. Restart the Advanced Access Control runtime server.
2. Execute an OAuth flow, such as the Resource Owner Password Credential flow, to obtain a valid access and refresh token pair.
3. Attempt to use the access token to access a resource that is protected by the API Definition associated with the OAuth client that has been granted the access token.

Step 3 has been observed to fail on some rare occasions. The cause is due to delayed restart initialization of some internal Advanced Access Control runtime components. Normal successful processing has been observed when the request for the protected resource in step 3 is resubmitted.

### Junction type for Security Verify Access Oracle PeopleSoft PeopleTools integration

When you access the PeopleSoft Workcenter Dashboard via WebSEAL using a standard junction type, the dashboard is not displayed correctly. The browser issues a message "Only secure content is displayed" with a button "Show all content". When this button is clicked, an Oracle authentication login panel is displayed.

Note that the full URI of the server is used instead of just the junction name. Because the content contains an absolute address that WebSEAL cannot filter when a standard junction type is used, for example:

```
<DIV id="ptasjs1"> http://hostaddress/cs/path/cache
/PT_PORTAL_UTIL_JS_MIN_1.js</DIV>
```

In this case, a virtual host junction type must be adopted to negate the limitations associated with the use of standard junction script filtering.

### Tooltips display issue

Tooltips might not display if you use the keyboard (for example, the Tab key) to navigate to a field. Tooltips are displayed properly when you use a mouse to navigate to the field.

### Creating PIP resource when the server connection for database and LDAP is not available returns the wrong response.

For example, when you use the following command:

```
curl -k -b whatigtot -s -S --ciphers "DES-CBC3-SHA" -X "POST" -H
"Accept:application/json" -H "Content-Type: application/json" --data-
binary "{\"name\":\"tldap1234\",\"description\":\"\"attributes\":[{\"name
\":\"trusteer.pinpoint.csid\",\"selector\":\"wrongtestLdap\"}]}\"type\":
\"LDAP\",\"predefined\":false,\"properties\":[{\"datatype\":\"String\",
\"readOnly\":false,\"sensitive\":false,\"value\":\"objectclass=abc\", \"key
\":\"searchBaseDN\"},{\"datatype\":\"String\", \"readOnly\":false,\"sensitive
\":false,\"value\":\"cn=*\", \"key\":\"searchFilter\"},{\"datatype\":\"String
\", \"readOnly\":false,\"sensitive\":false,\"value\":\"0cdebb0c-49d9-4179-
a47a-52f759a4ff57\", \"key\":\"dataSource\"}]}" --user admin:admin -D
whatigtot "https://{appliance_host}/iam/access/v8/pips/"
```

The expected response is as follows:

```
HTTP/1.1 400 Bad Request
```

But the actual response is as follows:

```
HTTP/1.1 201 Created
```

### The error message "illegal character" when you modify an SSO rule is always displayed in English.

The error message "illegal character" is always displayed in English no matter which locale your browser uses.

### Audit events cannot be sent to the remote syslog server if certain information is not provided.

If you choose to send the audit events to a remote machine, you must specify the correct details on the Audit Configuration page for host, port, protocol, and certificates. Otherwise, the audit events cannot be sent to the remote machine.

### Attribute sources that are being used by a federation or partner is deletable.

Users can accidentally delete attribute sources that are in use by a federation or partner. Such operation causes errors to the federation. You must ensure that an attribute source is not in use before you delete it.

**Federation Module: The email address name ID format requires a mapping rule**

If you use an email address name ID format in a SAML 2.0 federation, you must set the type of STS Universal User attribute, whose name is "name", to:

```
"urn:oasis:names:tc:SAML:1.1:nameid-format:emailAddress"
```

You can accomplish this by using a mapping rule. Following is an example:

```
// Get the current principal name.
var principalName = stsuu.getPrincipalName();
// Set the type of principal name attribute "name" to
// "urn:oasis:names:tc:SAML:1.1:nameid-format:emailAddress".
stsuu.addPrincipalAttribute(new Attribute("name",
"urn:oasis:names:tc:SAML:1.1:nameid-format:emailAddress", principalName));
```

**Personal certificates are not included in the list of selections when you choose certificates to use for encryption or signature validation with the SAML 2.0 partner management GUI**

If you use the local management interface to choose certificates to be used for encryption or signature validation, only signer certificates are available for selection. Personal certificates are not included in the list of selections. A work-around is to use the REST API for such operations.

**Federation module: The RSA-OAEP key encryption algorithm is not supported with HSM keys**

IBM Security Verify Access does not support decryption of SAML 2.0 messages using the RSA Optional Asymmetric Encryption Padding (RSA-OAEP) key transport algorithm with Hardware Security Module (HSM) keys. The RSA-OAEP algorithm is supported with software (non-HSM) keys. For more information on RSA-OAEP, see <http://www.w3.org/2001/04/xmlenc#rsa-oaep-mgf1p>.

**The upgrade from Security Access Manager 8.0, 8.0.0.1, and 8.0.0.2 does not correctly migrate the authentication module policies for Security Verify Access for Mobile.**

The work-around is to create the default set of authentication policies with the local management interface or REST API.

The following link creates a customized query of the live Support knowledge base for items specific to IBM® Security Verify Access, Version 10.0, and its fix packs.

[IBM Security Access Manager technical documents](#)

You can also create your own search query on the IBM Support Portal. For example:

1. Go to the IBM Support Portal:<http://www.ibm.com/support/entry/portal/support>
2. In the **Search** field, enter: Verify Access.

**Identity Provider and Service Provider is not recommended to be configured as partners on the same appliance or on the same external HVDB**

Identity Provider and Service Provider is not recommended to be configured as partners on the same appliance or on the same external HVDB. This might lead to several features not functioning correctly. The following problems (but not limited to) might be encountered:

- HTTP Artifact binding SAML single sign flows does not work due to key conflict in storing the messages in runtime database.
- The STS chain mapping created internally for Identity Provider and Service Provider will have identical 'issuer' and 'applies to' which can lead to unexpected behavior during runtime flow.
- Leads to database contention as the DMAP entries could be inserted or modified simultaneously by Identity provider and Service provider.

It is recommended that the Identity Provider and Service Provider that are partners reside in separate appliances configured with separate external HVDB.

**Synchronization of WebSEAL data is unable to handle deleted junctions**

The current WebSEAL sync functionality is designed to pick up new entries or junctions and modifications to existing entries or junctions. However, it is currently unable to detect a deleted junction or entry. This limitation applies to both configuration entries and junctions.

### **Local management interface (LMI) session timeouts**

LMI sessions expire after the duration of time that is specified by the **Session Timeout** field on the **Administrator Settings** page. When a session timeout occurs, you are automatically logged out and any unsaved data on the current page is lost.

Save your configuration updates in the LMI regularly to avoid data loss in the event of a session timeout.

### **PAM Support**

The Web Application Firewall capability will reach end of service on 31st December, 2022. After this date, no further updates will be made available. Customers can continue to use the capability on an as-is basis, and support will be available for general information and existing functionality only. There will be no defect support available.

# Chapter 10. Security Verify Access appliance FRU/CRU documentation

Read the IBM Security Verify Access Field Replacement Unit (FRU) parts and Customer Replacement Unit (CRU) parts documentation before you replace the relevant parts.

## Disk Drive Assembly Replacement Instructions

This document helps you to complete the following tasks:

- Remove a failed disk drive and replace it with a new disk drive
- Verify that the new disk drive is working correctly

**Important:** Before you proceed with these instructions, review the *IBM Systems Safety Notices* provided in the *IBM Media Terms and Conditions CD* that is included with your appliance model.

**Note:** The illustrations in this document might differ slightly from your appliance model.

### Supported appliances

The instructions in this document support IBM Security Verify Access (IBM Part Number: 01LK905).

## Replacing a storage drive assembly

### Before you begin

You must have a replacement storage drive assembly before you remove and replace the failed assembly.

### About this task

#### Identifying the storage drive assembly

The front panel of the appliance contains the storage drive assembly, as highlighted in yellow in the following figure:





Figure 1. Location of the storage drive assembly on the front of the appliance

### Procedure

1. Shut down the appliance by using the local management interface (LMI) or the command-line interface (CLI).
2. Unplug all of the power cords that are attached to the appliance.
3. Press the release button on the right side of the storage drive assembly to release the assembly lock.

4. Pull the drive handle lever to the left to pull the storage drive assembly from the drive bay, as shown in the following figure:



*Figure 2. Removing the storage drive assembly from the drive bay*

5. Place the new storage drive assembly in the drive bay.
6. Push the storage drive assembly into the drive bay until the lever locks into place.

### **What to do next**

Turn on the appliance, and then reimage it.

**Important:** You must reimage the appliance after you replace the storage drive. If you do not reimage the appliance, the appliance can become inoperable.



## Fan Assembly Replacement Instructions

Use these instructions to complete the following tasks:

- Remove a failed fan module from the appliance and replace it with a new one
- Verify that the new fan module is working correctly

**Important:** Before you proceed with these instructions, review the *IBM Systems Safety Notices* provided in the *IBM Media Terms and Conditions CD* that is included with your appliance model.

**Note:** The illustrations in this document might differ slightly from your appliance model.

### Supported appliances

The instructions in this document support IBM Security Verify Access (IBM Part Number: 01LK905).

## Replacing a fan assembly

### Before you begin

You must have the applicable replacement fan assembly before you can remove and replace the failed fan assembly.

### About this task

#### Identifying a failed fan assembly

The back panel of the appliance contains four user-accessible fan modules, as highlighted in yellow in the following figure:




Figure 3. Location of the fan modules on the back of the appliance

During normal operation, the LED for the fan module is not illuminated. If one of the fan modules experiences a failure, the LED for the failed fan module is illuminated in amber.

### Procedure

1. Pinch the orange retention clip on the fan module to release the fan assembly from the chassis.

2. Pull the fan assembly out of the chassis, as shown in the following figure:




Figure 4. Removing a fan assembly from the back of the appliance

3. Slide the replacement fan assembly into the fan assembly bay. Make sure the fan assembly is secured in the chassis.

## Results

The fan module LED is not illuminated in amber and the fan starts to circulate air.

## Network Interface Module Replacement Instructions

---

This document helps you to complete the following tasks:

- Remove a failed network interface module and replace it with a new network interface module
- Verify that the replacement network interface module is working correctly

**Best practice:** Replace a failed network interface module as soon as possible.

**Important:** Before you proceed with these instructions, review the *IBM Systems Safety Notices* provided in the *IBM Media Terms and Conditions CD* that is included with your appliance model.

**Note:** The illustrations in this document might differ slightly from your appliance model.

### Supported appliances

The instructions in this document support IBM Security Verify Access (IBM Part Number: 01LK905).

## Replacing a failed network interface module

### About this task

#### Identifying the network interface module

The front panel of the appliance contains the network interface modules, as highlighted in yellow in the following figure:




Figure 5. Location of the network interface modules on the front of the appliance

## Procedure

1. Turn off the appliance by using the local management interface (LMI) or the command-line interface (CLI).
2. Unplug all of the power cords that are attached to the appliance.
3. Grasp the blue latch on the front of the appliance and pull it toward you.
4. Pull the lever on the failed module toward you, and then pull module from the chassis, as shown in the following figure:




Figure 6. Removing a network interface module from the front of the appliance

5. Set aside the failed module.



**Attention:** As you unpack the replacement module, make sure that you do not touch the gold connectors on the back of the module, and do not let the gold connectors come in contact with the packing material. In addition, do not let these gold connectors touch the appliance while you are inserting the replacement module into the chassis. The gold connectors are extremely fragile and can be damaged if they touch anything.

6. Unpack the replacement module.
7. Carefully align the replacement module with the chassis, and then push the module into the chassis until the module is in place.
8. Push the blue latch on the front of appliance into place.
9. Plug in all of the power cords that are attached to the appliance.
10. Turn on the appliance by pressing the power button on the front.
11. Verify that the LCD panel on the front of the appliance is illuminated.

## What to do next

Check whether the new module is working correctly by logging in to the appliance LMI and verifying that the new module was recognized by the appliance.

## Power Supply Replacement Instructions

---

This document helps you to complete the following tasks:

- Identify a failed power supply
- Remove the failed power supply and replace it with a new power supply
- Verify that the replacement power supply is working correctly

**Best practice:** Replace a failed power supply as soon as possible.

**Important:** Before you proceed with these instructions, review the *IBM Systems Safety Notices* provided in the *IBM Media Terms and Conditions CD* that is included with your appliance model.


**Note:** The illustrations in this document might differ slightly from your appliance model.

### Supported appliances

The instructions in this document support IBM Security Verify Access (IBM Part Number: 01LK905).



**CAUTION:** The power control button on the device and the power switch on the power supply do not turn off the electrical current supplied to the device. The device also might have more than one power cord. To remove all current from the device, ensure that all power cords are disconnected from the power source.



**CAUTION:** Never remove the cover on a power supply or any part that has the following label attached.



Hazardous voltage, current, and energy levels are present inside any component that has this label attached. There are no serviceable parts inside these components. If you suspect a problem with one of these parts, contact a service technician.

## Identifying a failed power supply

The power supply unit uses an LED that indicates whether the unit is working as expected. The location of the LED is shown in the following figure:




Figure 7. Power supply LED

The following table indicates the potential problems that can occur with the power supply:

<i>Table 5. Power supply LED combinations for detecting potential problems</i>	
<b>Power supply condition</b>	<b>LED state</b>
Normal work	Green
No AC power to all the power supplies	Off
AC present / Only 12VSB on (PS off) or PS in CR state	1 Hz Blink Green
AC cord unplugged with a second power supply in parallel still with AC input power	0.5 Hz Blink Green
Power supply warning events where power supply continues to operate: high temp, high power, high current, slow fan	1 Hz Blink Red
Power supply critical event causing a shutdown, failure, OCP, OVP, Fan Fail	Red

## Replacing a failed power supply

### Before you begin

When you replace a failed power supply, do not unplug the power supply unit that is working. This action disrupts service to the appliance.

### Procedure

1. Remove the failed power supply from the power supply bay by pinching the side clip and pulling the failed power supply from the bay, as shown in Figure 2.

#### Important:

During normal operation, each power supply bay must contain either a power supply or a power supply blank for proper cooling.





Figure 8. Removing the power supply from the back of the appliance

2. Slide the AC power supply into the bay until the retention latch clicks into place. Make sure that the power supply connects firmly to the power supply connector.
3. Connect the power cord for the new AC power supply to the power cord connector on the power supply. The AC power supply connectors on the back of the appliance are shown in the following figure:



## Power cord connectors

*Figure 9. Identifying the power cord connectors*

4. Route the power cord through the power supply handle and through any cable clamps on the back of the appliance to prevent the power cord from being accidentally pulled out when you slide the appliance into and out of the rack.
5. Connect the power cord to a properly grounded electrical outlet.

### What to do next

Make sure that the AC power LED and the DC power LED on the AC power supply are illuminated, which indicates that the power supply is operating correctly. The two power LEDs are to the left of the power cord connector.





## Chapter 11. Supporting content

Use these resources to better understand the product.

**IBM Security Verify Access product page**

<https://www.ibm.com/products/verify-access>

**IBM Security Learning Academy**

<https://www.securitylearningacademy.com/local/navigator/index.php?level=iaam01>

**The IBM Security YouTube Channel**

<https://www.youtube.com/user/IBMSecuritySolutions>

**The IBM Security Support YouTube Channel**

<https://www.youtube.com/channel/UCIYjTJjvRaolva6tiYU4Cg>

**IBM Support Community Forums**

<https://www.ibm.com/mysupport/s/forumshome>

**IBM Security Community for Identity and Access Management (IAM)**

<https://community.ibm.com/community/user/security/communities/community-home?CommunityKey=e7c36119-46d7-42f2-97a9-b44f0cc89c6d>



## Chapter 12. Language support overview

IBM Security Verify Access software is translated into the following languages:

- Brazilian Portuguese
- Czech
- Chinese (Simplified)
- Chinese (Traditional)
- French
- German
- Hungarian
- Italian
- Japanese
- Korean
- Polish
- Spanish
- Russian

**Note:** The translations for these languages are pre-installed on the IBM Security Verify Access appliance. A language can be selected by using the **Language** drop-down list in the appliance dashboard LMI menu.



---

# Index

## A

accessibility features for this product [v](#)  
APARs fixed [17](#)

## D

documentation updates [21](#)

## F

fixes  
APARs [17](#)

## G

getting started [1](#)

## K

known limitations [21](#)

## N

new features [3](#)

## S

Security Verify Access  
features [3](#)

## V

Verify Access  
features [3](#)

## W

what's new [3](#)





